

# **Connecting Systems Using Reactive Network Configuration in Oracle® Solaris 11.1**

Copyright © 2011, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

---

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

# Contents

---

<b>Preface</b> .....	7
<b>1 Reactive Network Configuration (Overview)</b> .....	9
Highlights of Profile-Managed Network Configuration .....	10
What Is Reactive Network Configuration? .....	11
When to Use Reactive Network Configuration .....	11
Network Profiles and Types .....	11
Description of an NCP .....	12
Description of a Location Profile .....	14
Description of an ENM .....	15
Description of a Known WLAN .....	16
Profile Activation Policy .....	17
NCP Activation Policy .....	17
Location Activation Selection Criteria .....	19
Profile Configuration Tasks .....	22
How Reactive Network Profiles Work .....	24
How Reactive Networking Works With Other Oracle Solaris Networking Technologies .....	25
SMF Network Services .....	26
Network Configuration Security and Authorizations .....	26
Authorizations and Profiles Related to Network Configuration .....	27
Authorizations Required to Use the User Interfaces .....	27
Where to Find Network Configuration Tasks .....	29
<b>2 Creating and Configuring Reactive Network Profiles (Tasks)</b> .....	31
Configuring Profiles by Using the <code>netcfg</code> Command .....	32
<code>netcfg</code> Interactive Mode .....	32
<code>netcfg</code> Command-Line Mode .....	34

netcfg Command-File Mode .....	34
netcfg and netadm Subcommands .....	35
netcfg Subcommands .....	35
netadm Subcommands .....	37
Creating User-Defined Profiles .....	39
Creating an NCP .....	41
Creating a Location Profile .....	48
Creating an ENM Profile .....	54
Creating a Known WLAN Profile .....	57
Setting and Changing Property Values for a Profile .....	60
▼ How to Interactively Set Property Values .....	61
Listing Profile Configuration Information on a System .....	63
Listing All of the Profile Configuration Information on a System .....	63
Listing All Property Values for a Specific Profile .....	65
Obtaining the Value of a Specific Property .....	65
Viewing and Changing Property Values by Using the walprop Subcommand .....	68
Enabling and Disabling Profiles .....	69
<b>3 Administering Your Reactive Network Configuration (Tasks) .....</b>	<b>73</b>
Switching Between Fixed and Reactive Network Configurations .....	74
▼ How to Switch From Reactive Network Configuration to Fixed Network Configuration .	74
▼ How to Switch From Fixed Network Configuration to Reactive Network Configuration .	75
Displaying Information About Profile States .....	75
Displaying the Current State of a Profile .....	76
Displaying Auxiliary State Values .....	77
Exporting and Restoring a Profile Configuration .....	77
Restoring a User-Defined Profile .....	81
Removing Profiles .....	81
Performing a Wireless Scan and Connecting to Available Wireless Networks .....	83
Troubleshooting Reactive Network Configuration Issues .....	84
Monitoring the Current State of All Network Connections .....	84
Troubleshooting Network Interface Configuration Issues .....	85
<b>4 Using the Network Administration Graphical User Interface .....</b>	<b>87</b>
Introduction to the Network Administration Graphical User Interface .....	88

Accessing the Network Administration GUI From the Desktop .....	88
Differences Between the Network Administration GUI and the Network CLI .....	89
Functional Components of the GUI .....	90
Interacting With Reactive Network Profiles From the Desktop .....	92
Checking the Status of Your Network Connection .....	92
Controlling Network Connections From the Desktop .....	94
Joining and Managing Favorite Wireless Networks .....	96
▼ How to Join a Wireless Network .....	97
Managing Favorite Networks .....	98
Managing Network Profiles .....	99
About the Network Preferences Dialog .....	99
Viewing Information About Network Profiles .....	101
Adding or Removing a Network Profile .....	102
Editing Network Profiles .....	102
Working With Priority Groups .....	104
Creating and Managing Locations .....	105
Editing Locations .....	108
About External Network Modifiers .....	109
About the Network Modifiers Dialog .....	109
▼ How to Add a Command-Line ENM .....	110
<b>Index</b> .....	<b>113</b>



# Preface

---

Welcome to *Connecting Systems Using Reactive Network Configuration in Oracle Solaris 11.1*. This book is a part of the series *Establishing An Oracle Solaris 11.1 Network* that cover basic topics and procedures to configure Oracle Solaris networks. This book assumes that you have already installed Oracle Solaris. You should be ready to configure your network or ready to configure any networking software that is required on your network.

---

**Note** – This Oracle Solaris release supports systems that use the SPARC and x86 families of processor architectures. The supported systems appear in the *Oracle Solaris OS: Hardware Compatibility Lists*. This document cites any implementation differences between the platform types.

---

## Who Should Use This Book

This book is intended for anyone responsible for administering systems that run Oracle Solaris, which are configured in a network. To use this book, you should have at least two years of UNIX system administration experience. Attending UNIX system administration training courses might be helpful.

## Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Description	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
<b>AaBbCc123</b>	What you type, contrasted with onscreen computer output	<code>machine_name%</code> <b>su</b> Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . <i>A cache</i> is a copy that is stored locally. Do <i>not</i> save the file. <b>Note:</b> Some emphasized items appear bold online.

## Shell Prompts in Command Examples

The following table shows the default UNIX system prompt and superuser prompt for shells that are included in the Oracle Solaris OS. Note that the default system prompt that is displayed in command examples varies, depending on the Oracle Solaris release.

TABLE P-2 Shell Prompts

Shell	Prompt
Bash shell, Korn shell, and Bourne shell	\$
Bash shell, Korn shell, and Bourne shell for superuser	#
C shell	<code>machine_name%</code>
C shell for superuser	<code>machine_name#</code>

# Reactive Network Configuration (Overview)

---

Reactive network configuration (formerly known as Network Auto-Magic (NWAM)) simplifies basic network configuration by automatically addressing basic Ethernet and WiFi configurations. The basic network configuration includes connecting to wired or wireless network at startup and displaying notifications about the status of your currently active network connection from the desktop. Reactive or automatic network configuration also simplifies some of the more complex networking tasks, such as the creation and management of system-wide network profiles, for example, the configuration of naming services, IP Filter, and IP Security (IPsec), all of which are features of Oracle Solaris.

This chapter provides background information about reactive network configuration. A detailed description of the profiles that the system uses to simplify and automate network configuration is also provided.

This chapter covers the following topics:

- “Highlights of Profile-Managed Network Configuration” on page 10
- “What Is Reactive Network Configuration?” on page 11
- “When to Use Reactive Network Configuration” on page 11
- “Network Profiles and Types” on page 11
- “Profile Activation Policy” on page 17
- “Profile Configuration Tasks” on page 22
- “How Reactive Network Profiles Work” on page 24
- “How Reactive Networking Works With Other Oracle Solaris Networking Technologies” on page 25
- “SMF Network Services” on page 26
- “Network Configuration Security and Authorizations” on page 26
- “Where to Find Network Configuration Tasks” on page 29

This chapter is intended for users and system administrators who have an understanding of basic networking concepts, as well as some experience managing network configuration by using traditional networking tools and commands. If you are ready to use reactive network

configuration to manage your network configuration, skip to [Chapter 2, “Creating and Configuring Reactive Network Profiles \(Tasks\)”](#)

For basic information about administering network interfaces in Oracle Solaris, see [Configuring and Administering Oracle Solaris 11.1 Networks](#) and [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

## Highlights of Profile-Managed Network Configuration

In Oracle Solaris 11, network configuration is based on profiles. A system's network configuration is managed by a specific network configuration profile (NCP) and a corresponding Location profile. For a fuller description of profile-managed network configuration, see “[Network Configuration Profiles](#)” in [Introduction to Oracle Solaris 11 Networking](#).

---

**Note** – For network configuration, the principal profile types are NCPs, Location profiles, external network modifiers (ENMs), and known wireless local area networks (known WLANs). Of these types, the main profile type is the NCP. For more information about network profile types, see “[Network Profiles and Types](#)” on page 11.

---

The highlights of profile-based network configuration follow:

- Only one pair of NCP and Location profiles can be active at one time to manage a system's network configuration. All other existing NCPs on the system are non-operational.
- The active NCP can be either reactive or fixed. With a reactive profile, the system monitors the network configuration to adapt to changes in the system's network environment. With a fixed profile, the network configuration is instantiated but not monitored.
- The values of the different properties of an NCP constitute a policy that governs how the profile manages the network configuration.
- Changes to the NCP's properties are immediately implemented as new property values, which become part of the profile's policy that manages the network configuration.

If your system is configured for fixed networking, then the active NCP that manages its network configuration is `DefaultFixed`. This profile is generated by the operating system (OS) and is the only fixed profile on the system. A system does not support multiple fixed profiles. For more information, see [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

The conceptual information, procedures, and examples in this book relate to reactive network configuration where multiple NCPs can be created and configured but only one profile can be active at a time on the system.

## What Is Reactive Network Configuration?

In reactive network configuration, the system automatically adapts to any change in network condition and network configuration without requiring manual reconfiguration. For example, if your wired network interface becomes unplugged or if a new wireless network becomes available, the system adapts accordingly. With the primary focus on mobility, a reactive configuration policy allows the system's configuration to be changed dynamically, in response to different network events or at a user's request.

The system's network configuration is organized into profiles. Profiles are either reactive or fixed. A reactive profile includes properties that determine when the profile or its components should be enabled. These properties enable the profile to be applied dynamically by the network management daemon, `nwamd`. For information about fixed network configuration and the distinction between fixed network and reactive network configuration, see [“What Is Fixed Network Configuration?”](#) in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1*.

## When to Use Reactive Network Configuration

Reactive network configuration is a valuable feature for users of laptop models and systems that require frequent changes in their network environment and connection methods. You can set up user-defined profiles that enable you to connect to networks in a variety of settings, for example, at the office, at home, or on the road. In addition, the network administration graphical user interface (GUI) (formerly known as the NWAM GUI) makes the setting up of static IP configurations and connections to WiFi networks much easier than traditional networking tools and commands. Reactive network profiles can be configured to adapt to changes in your network environment, such as the loss of Ethernet connectivity or the addition or removal of a network interface card (NIC).

## Network Profiles and Types

The system manages network configuration by storing preferred property values in the form of profiles. These property values determine how a network is configured and when its components need to be configured depending on current network conditions. The reactive profiles implementation is a primary component of reactive network configuration. The two primary network profile types are the NCP and the Location profile. Exactly one NCP and one Location profile must be active on the system at all times.

The following are the profile types and configuration objects that comprise the system's network configuration:

- **Network configuration profiles (NCPs)**

An NCP specifies the configuration of network links and interfaces. The system always defines an NCP called the `Automatic` NCP. This profile is the default reactive NCP. The `Automatic` NCP is created and maintained by the system and cannot be modified or removed. You can also create additional user-defined NCPs, as needed. For a complete description of the `Automatic` and user-defined NCPs, see [“Description of the Automatic and User-Defined NCPs” on page 13](#). For a complete description of an NCP, see [“Description of an NCP” on page 12](#).

- **Network configuration units (NCUs)**

NCUs are the individual configuration objects that contain all of the properties that define an NCP. There are two types of NCUs: a link NCU and an interface NCU. Each NCU represents a physical link or an interface and contains properties that define the configuration for that link or interface. For a complete description of an NCU, see [“Description of an NCU” on page 14](#).

- **Location profiles**

The Location profile is one of the two primary profile types that make up the system's network configuration. The Location profile specifies the system-wide network configuration, for example, the naming services, the domain, the IP Filter configuration, and the IPsec configuration. There are both system-defined and user-defined locations. For a complete description of the Location profile, see [“Description of a Location Profile” on page 14](#).

- **External network modifiers (ENMs)**

ENMs are profiles that are used to manage applications that create their own network configuration, which is external to the configuration managed by the system, for example, a VPN application. The network management daemon, `nwamd`, enables or disables an ENM, depending on the conditions that are specified as a part of the ENM. For a complete description of an ENM, see [“Description of an ENM” on page 15](#).

- **Known WLANs**

Known WLAN profiles store information about wireless networks that are known to your system. The system uses this information while configuring wireless links automatically to determine the order in which connections to available wireless networks are attempted and to find key information for protected wireless networks. For a complete description of known WLANs, see [“Description of a Known WLAN” on page 16](#).

## Description of an NCP

An NCP defines the network configuration of a system. The NCUs that make up an NCP specify how to configure the various network links and interfaces as well as the conditions

under which that link or interface should be brought up. All NCPs have a management - type property that determines how the profiles are managed. The possible values for this property are fixed and reactive.

NCUs that define the reactive NCP include property values that describe the conditions under which each NCU should be enabled. The system's network uses the properties and conditions that are specified for each NCU to enforce the NCP activation policy. For information about the NCP activation policy, see [“Profile Activation Policy” on page 17](#).

The system defines one reactive NCP: the Automatic NCP. You can also create additional user-defined reactive NCPs.

Fixed NCPs are also managed by the network management daemon. However, their configuration is always applied when the fixed NCP is enabled and is not altered by the system while the NCP remains active. There is only one fixed NCP on the system, the DefaultFixed NCP. For more information about the fixed NCP, see [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

## Description of the Automatic and User-Defined NCPs

The Automatic NCP is a system-defined profile that is made up of one link NCU and one interface NCU for each physical link that is present on the system. For information about NCUs, see [“Description of an NCU” on page 14](#). The content of the Automatic NCP changes if network devices are added or removed. However, the configuration preferences that are associated with the Automatic NCP cannot be edited.

The Automatic NCP utilizes dynamic host configuration protocol (DHCP) and address autoconfiguration to obtain IP addresses for the system. This profile also implements an NCU activation policy in this NCP that favors wired links over wireless links and that plumbs both IPv4 and IPv6 on each enabled link. If the specification of an alternate IP configuration policy or an alternate link selection policy is required, you can create additional user-defined NCPs on your system. The Automatic NCP changes dynamically when a new link is inserted or removed from the system. All NCUs that correspond to the inserted or removed link are also added or removed at the same time. The profile is updated automatically by the network management daemon.

User-defined NCPs are created and managed by the user. You must explicitly add and remove NCUs from the specified profile. You can create NCUs that do not correlate to any link that is currently present on the system. You can also remove NCUs that do not correlate to any link that is present on the system. In addition, you can determine the policy for the user-defined NCP. For example, you can allow multiple links and interfaces to be enabled on the system at a given time, as well as specify different dependency relationships between NCUs and static IP addresses.

For step-by-step instructions about creating a user-defined NCP and adding and removing NCUs to and from this NCP, see [“Creating an NCP” on page 41](#).

## Description of an NCU

NCUs are the individual configuration objects that make up an NCP. NCU represents a physical link or an interface on a system. The process of configuring a user-defined NCP includes creating NCUs that specify how each link and interface must be configured. For NCUs in a reactive NCP, the conditions under which each link or interface should be configured must also be specified.

There are two types of NCUs:

- **Link NCUs**

Link NCUs, for example, physical devices, are Layer 2 entities in the Open Systems Interconnection (OSI) model.

- **Interface NCUs**

Interface NCUs, specifically, IP interfaces, are Layer 3 entities in the OSI model.

Link NCUs represent datalinks. There are several different classes of datalinks:

- Physical links (Ethernet or WiFi)
- Tunnels
- Aggregations
- Virtual local area networks (VLANs)
- Virtual network interface cards (VNICs)

For more information about how to configure virtual NICs to create virtual networks, see [Using Virtual Networks in Oracle Solaris 11.1](#).

## Description of a Location Profile

A Location profile provides additional networking details after the basic IP connectivity has been established. Locations contain network configuration information that is comprised of a set of properties that relate to network configuration on a system-wide level.

A Location profile consists of certain network configuration information, for example, a naming service and firewall settings, that are applied together, when required. Also, because a location does not necessarily correspond to a physical location, you can set up several Location profiles to meet different networking needs. For example, one location can be used when you are connected to the company intranet. Another location can be used when you are connected to the public Internet by using a wireless access point that is located in your office.

Each Location profile contains properties that define the location activation selection criteria. For information about the location activation criteria, see [“Location Activation Selection Criteria” on page 19](#).

By default, three Location profiles are predefined by the system:

- **NoNet**

The **NoNet** location has very specific activation conditions. This profile is applied to a system when no local interfaces have an assigned IP address. You can modify the **NoNet** location after it is enabled on your system for the first time. A read-only copy of the original **NoNet** location is stored on the system, in case you want to restore the default settings for this location.

- **Automatic**

The **Automatic** location is enabled if there are networks available, but no other Location profile supersedes it. You can modify the **Automatic** location after it has been enabled on your system for the first time. A read-only copy of the original **Automatic** location is stored on the system, in case you want to restore the default settings for this location.

---

**Note** – The **Automatic** location should not be confused with the **Automatic NCP**. The **Automatic** location is a Location profile type that defines system-wide network properties after the initial network configuration of a system takes place. The **Automatic NCP** specifies link and interface network configuration on a system.

---

- **DefaultFixed**

The **DefaultFixed** location is enabled if the **DefaultFixed NCP** is active and at least one interface is configured with an IP address. The system updates the **DefaultFixed** location to reflect the changes made to relevant Service Management Facility (SMF) properties while the location is active. You must not modify the **DefaultFixed** location directly. For more information about fixed network configuration, see [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

User-defined locations are profiles that you create with values that you specify for the system-wide network configuration. User-defined locations are identical to system-defined locations, except that a user-defined location is configured with values that you set, but system-defined locations have preset values.

For more information about creating user-defined locations, see [“Creating a Location Profile” on page 48](#).

## Description of an ENM

ENMs enable you to specify when applications or scripts, for example, a VPN application, should perform their own network configuration external to the configuration specified in the NCP and Location profiles. ENMs can also be defined as services or applications that directly modify your network configuration when they are enabled or disabled. You can specify the conditions under which an ENM should be enabled or disabled. You can also enable or disable

an ENM manually. Unlike an NCP or a Location profile, where only one of each profile type can be active on the system at any given time, multiple ENMs can potentially be active on the system at the same time. The ENMs that are active on a system at any given time are not necessarily dependent on the NCP or Location profile that is also enabled on the system at the same time.

Although there are several external applications and services for which you can create an ENM, the obvious example is the VPN application. After you install and configure VPN on your system, you can create an ENM that automatically enables and disables the application under the conditions that you specify.

---

**Note** – Reactive network configuration cannot automatically detect external applications that are capable of directly modifying the network configuration on a system. To manage the activation or deactivation of a VPN application, or any external application or service, you must first install the application, then create an ENM for it by using either the command-line interface (CLI) or the network administration GUI.

---

Persistent information about any network configuration that is performed by an ENM is not stored or tracked by the system in exactly the same way as information about an NCP or a Location profile is stored. However, reactive network configuration is capable of noting an externally initiated network configuration. Based on any configuration changes that are made to the system by an ENM, reactive network configuration reevaluates which Location profile should be active, and subsequently enables that location. For example, switching to a location that is enabled conditionally when a certain IP address is in use. If the `svc:/network/physical:default` service is restarted at any time, the network configuration that is specified by the active NCP is reinstated. ENMs are restarted as well, possibly tearing down and re-creating the network configuration in the process.

For information about creating and modifying the properties of an ENM, see [“Creating an ENM Profile” on page 54](#).

## Description of a Known WLAN

Known WLAN profiles store information about wireless networks, enabling NCPs to automatically configure wireless interfaces based on the configuration information of wireless networks that you connect to from your system.

Known WLAN profiles provide details about WLANs that might be connected to automatically. For example, each profile contains a priority value, which determines the order of preference for different wireless networks to be connected when two or more known networks are available. A profile with a lowest number as its priority value has the highest priority. When an NCP includes a wireless link to be enabled, the Known WLAN profile list is examined. If a wireless network that has a Known WLAN profile is available, the wireless link is automatically connected to that WLAN. If two or more known networks are available, the

wireless network that has the highest priority (lowest number) is connected to the WLAN. The most recent wireless network that a wireless link is connected to (by explicit user action) is added to the top of the Known WLAN list, and that network becomes the new highest priority wireless network. This means that more recently connected WLANs are preferred over WLANs that you had connected to earlier. Known WLANs do not share the same priority at any point of time. If a new WLAN is added to the list with the same priority value as an existing WLAN, the existing entry is shifted to a lower priority value. Subsequently, the priority value of all other WLANs in the list is dynamically shifted to a lower priority value.

One or more key names can also be associated with a known WLAN. *Key names* enable you to create your own keys by using the `dladm create-secobj` command. You can then associate these keys with WLANs by adding the secure object names to the known WLAN keyname property. For more information, see the `dladm(1M)` man page. For more information about working with datalinks using the `dladm` command, see [Chapter 3, “Working With Datalinks,” in \*Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1\*](#).

For more information about using the command-line utilities to manage WLANs, see [“Performing a Wireless Scan and Connecting to Available Wireless Networks” on page 83](#).

## Profile Activation Policy

Reactive network configuration enables you to specify the NCP activation policy for reactive NCPs. This policy describes when NCUs are enabled. Each Location profile also contains properties that define the activation criteria.

NCUs, Location profiles, and ENMs have an `activation-mode` property. The allowable values for each profile type differ. In addition, how the `activation-mode` property is validated differs for each profile type, as do the conditions under which each profile is enabled.

---

**Note** – The `activation-mode` property for the NCU can be either set to `manual` or `prioritized`. The `activation-mode` property for the Location profile can be set to `manual`, `conditional-any`, `conditional-all`, or `system`.

---

## NCP Activation Policy

The NCP activation policy is enforced through the use of properties and conditions that can be specified for each NCU. Examples of policy that you might specify include: “prefer wired connections over wireless connections” or “activate one interface at a time.” How and when NCPs are enabled is defined in the properties that are set for each NCU type.

---

**Note** – An interface NCU must always be associated with an underlying link NCU. Each interface NCU becomes active when its associated link NCU is enabled. You can override the default behavior of an NCU by using the `netadm` command. However, the dependency on the underlying link NCU can never be removed. For example, if you enable an interface NCU without enabling its associated link NCU, the interface do not actually come online until the underlying NCU for that interface is enabled.

---

## NCU Activation Properties

How network connections are enabled is set in the link NCU properties. The following properties are used to define the NCP activation policy:

- `activation-mode` property

This property can be set to either `manual` or `prioritized`.

- `manual` – The NCU activation is managed by the administrator. You can use the `netadm` command or the network administration GUI to enable or disable the NCU. If an NCU's `activation-mode` property is set to `manual`, values that are set for both the `priority-group` and `priority-mode` NCU properties are ignored.
- `prioritized` – The NCU is enabled according to the values that are set in the `priority-group` and `priority-mode` properties for the specified NCU. The enabled property is always true for prioritized NCUs.

Prioritized activation enables groups of links to be enabled at the same time. This activation mode also enables one or more links to be preferred over other links. The `priority-group` property assigns a numeric priority level to a given link. All links at the same priority level are examined as a group. The `priority-mode` property defines how many of the group members might or must be available for the group to be enabled.

- `enabled` property (`activation-mode` is set to `manual`)

The value of this property can be `true` or `false`. You cannot set the value of this property. Rather, the value reflects the current state of a manually enabled NCU, which can be changed by using the `netadm` command or by using the network administration GUI.

- `priority-group` property (`activation-mode` is set to `prioritized`)

The value is numeric. Zero (0) indicates the highest priority. Negative values are invalid.

Among all of the available priority groups, only the NCUs in the highest available priority group are enabled. When more than one NCU with the same priority is available, activation behavior is defined by the `priority-mode` property. The priority number is not an absolute value. It can change, as the NCP repository is updated.

---

**Note** – The priority order is strictly enforced.

---

- `priority-mode` property (`activation-mode` is set to `prioritized`)

The property is set when a value for the `priority-group` property has been specified.

The values for this property are as follows:

- `exclusive` – Specifies that only one NCU in the priority group can be active at any given time. The first available NCU within the priority group is enabled, and the other NCUs in the group are ignored.
- `shared` – Specifies that multiple NCUs in the priority group can be active at the same time. Any available NCUs in the priority group are enabled.
- `all` – Specifies that all of the NCUs in the priority group must be made available for the priority group to be considered available and thus made active.

## Examples of an NCP Policy

In the following example, NCU properties are set according to an NCP policy which specifies that multiple wired links are enabled at the same time.

For all physical links:

- `NCU type: link`
- `NCU class: phys`
- `activation-mode: prioritized`
- `priority-group: 0` for wired
- `priority-mode: shared` for wired

In the following example, NCU properties are set according to an NCP policy which specifies that there can be only one active link on the system at any given time.

For all physical links:

- `NCU type: link`
- `NCU class: phys`
- `activation-mode: prioritized`
- `priority-group: 0` for wired
- `priority-mode: exclusive`

## Location Activation Selection Criteria

The properties that define the activation criteria specify information about the conditions under which a Location profile is enabled. A Location profile can be manually enabled by using the `netadm` command or by using the network administration GUI. If you do not explicitly enable a location, the network management daemon, `nwamd`, checks the activation rules for all of the conditionally enabled and system-enabled Location profiles, and then chooses the location that best matches the current network environment.

The `nwamd` daemon uses an algorithm to continuously reevaluate the selection criteria for all the configured locations, each time determining which location has the criteria that is the best match for the current network environment. If there is no suitable match for a location, the `Automatic` location is then enabled.

Changes in the network environment cause the `nwamd` daemon to continually reassess the location selection to determine the best match for the new environment. However, if you explicitly enable a Location profile by using the `netadm` command (either a location that is manually enabled or a location that is conditionally enabled), that location remains active until you explicitly disable it or enable a different location. In this situation, changes in the network environment do not result in a change in Location profiles, regardless of whether there might be a better match available. The fact that you explicitly specified the current location makes it, in effect, the best possible match. For instructions about enabling and disabling profiles, see [“Enabling and Disabling Profiles” on page 69](#).

The selection criteria for when and how a user-defined location is enabled are specified by the following properties:

- `activation-mode`
- `conditions`

The `activation-mode` property is set to one of the following possible values:

- `manual`
- `conditional-any`
- `conditional-all`
- `system`

---

**Note** – The `system` value of the `activation-mode` property can only be assigned to system-provided locations: the `Automatic`, `NoNet`, and `DefaultFixed` locations. The `system` value indicates that the system determines when to activate these locations.

---

If the `activation-mode` property is set to `conditional-any` or `conditional-all`, the `conditions` property contains a conditional expression or expressions that are user-defined. Each expression contains a condition that can be assigned a boolean value, for example, `ncu ip:net0 is-not active`. The condition in this example can be used for activating a location or an ENM. The condition is true when the IP NCU for `net0` is not online. This expression determines when the location or ENM is enabled and if the condition is not met, the location or ENM is disabled.

If the `activation-mode` property is set to `conditional-any`, the condition is satisfied if any one of the conditions is true.

If the `activation-mode` property is set to `conditional-all`, the condition is satisfied only if *all* of the conditions are true.

Locations and ENMs can be activated based on a set of user-specified conditions. The conditions can be set for the object types which include profile types and profile properties. The criteria and operations that can be used to construct the condition strings are defined in the following table.

**TABLE 1-1** Criteria and Operations for Constructing Condition Strings

Object Type	Condition	Object	Example
ncp, ncu, enm, loc	is/is-not active	Name of the object	ncp Automatic is active
ssid	is/is-not contains/does-not-contain	ssid of the WiFi network	ssid contains guest
bssid	is/is-not	bssid/MAC address of the WiFi network's access point	bssid is clear-guest
ip-address	is/is-not	IPv4 or IPv6 address	ip-address is 10.0.8.0/24
ip-address	is-in-range/is-not-in-range	IPv4 or IPv6 address plus netmask/prefixlen	ip-address is-in-range 10.34.24.0/24
advertised-domain	is/is-not contains/does-not-contain	Name of the domain	advertised-domain is example.com
system-domain	is/is-not contains/does-not-contain	Name of the domain	system-domain contains mycompany

---

**Note** – The `ssid` property represents an Extended Server Set Identifier (ESSID), which is the network name of a wireless LAN (WLAN). The `bssid` property represents a Basic Service Set Identifier (BSSID), which is the MAC address of a specific wireless access point (WAP) or any access point (AP).

---

Note the distinction between the `advertised-domain` and the `system-domain` profile properties. The advertised domain is discovered through external communications, for example, the `DNSdomain` or `NISdomain` domain names, which are advertised by a DHCP server. This profile property is useful for the conditional activation of locations, for example, if the advertised domain is `mycompany.com`, then enable the work location. The `system-domain` profile property is the domain that is currently assigned to the system. It is the value that is returned by the `domainname` command. This profile property is useful for the conditional activation of ENMs, as it becomes true only after a location has been enabled, and the system has been configured for that particular domain. For more information, see the [domainname\(1M\)](#) man page.

For more information about location properties, see [“Description of a Location Profile”](#) on page 14.

## Profile Configuration Tasks

In reactive network configuration, you can create and configure profiles and obtain information about them by using the `net cfg` and `net adm` commands. To configure your network connections through profiles, you can use the `net cfg` command. To administer and obtain the status of profiles (NCPs, locations, ENMs, and WLANs) and NCUs, the individual configuration objects that make up an NCP, you can use the `net adm` command. In addition, you can use the `net adm` command to interact with the network management daemon, `nwamd`, in the absence of a GUI.

The following are the tasks that you perform in a reactive networking environment:

- Create a user-defined profile by using the `net cfg create` command. For information, see [“Creating User-Defined Profiles”](#) on page 39.
- Set or modify one or all of the properties of a specified user-defined profile by using the `net cfg set` or `net cfg walkprop` command. For information, see [“Setting and Changing Property Values for a Profile”](#) on page 60 and [“Viewing and Changing Property Values by Using the walkprop Subcommand”](#) on page 68.
- Delete any changes that were made to a profile and revert to the previous configuration for that profile by using the `net cfg revert` command.
- List all of the profiles that exist on a system and their property values by using the `net cfg list` command. For information, see [“Listing All of the Profile Configuration Information on a System”](#) on page 63.
- List all of the property values for a specified profile by using the `net cfg list` command. For information, see [“Displaying the Current State of a Profile”](#) on page 76.
- List each property that is associated with a profile by using the `net cfg get` command. For information, see [“Obtaining the Value of a Specific Property”](#) on page 65.
- Verify that a profile has a valid configuration by using the `net cfg verify` command.
- Commit the current profile specification to persistent storage and also verify that a profile has a valid configuration by using the `net cfg commit` command.
- Remove a user-defined profile by using the `net cfg destroy` command. For information, see [“Removing Profiles”](#) on page 81.

---

**Note** – You cannot create or destroy a system-defined profile.

---

- Export the current configuration for a user-defined profile to standard output or a file by using the `net cfg export` command. For information, see [“Exporting and Restoring a Profile Configuration”](#) on page 77.

---

**Note** – You cannot export any system-defined profiles. System-defined profiles include the Automatic and DefaultFixed NCPs and the Automatic, NoNet, and DefaultFixed locations.

---

- Enable and disable a specified profile by using the `netadm enable` and `netadm disable` commands. For information, see [“Enabling and Disabling Profiles” on page 69](#).
- List all of the available profiles and their current states by using the `netadm list` command. For information, see [“Displaying Information About Profile States” on page 75](#).
- Listen to and display a stream of events from reactive networking by using the `netadm show-events` command. For information, see [“Monitoring the Current State of All Network Connections” on page 84](#).
- Initiate a wireless scan for a specified link and select a wireless network to connect to from the scan results on that specified link by using the `netadm scan-wifi` and `netadm select-wifi` commands. For information, see [“Performing a Wireless Scan and Connecting to Available Wireless Networks” on page 83](#).

For all task-related information, see [Chapter 2, “Creating and Configuring Reactive Network Profiles \(Tasks\)”](#), and [Chapter 3, “Administering Your Reactive Network Configuration \(Tasks\)”](#).

---

**Note** – For NCUs, the set of properties that you can view or modify by using the `netcfg` command is limited. You can use the `ipadm` and `dladm` commands to create, view, or modify all possible link and interface properties of the currently active NCP. However, for reactive NCPs, the `netcfg` command must be used to modify an NCU's activation conditions.

For more information about the `ipadm` and `dladm` commands, see [Chapter 4, “Working With IP Interfaces,” in \*Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1\*](#) and [Chapter 3, “Working With Datalinks,” in \*Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1\*](#).

---

You can use the `netcfg` command in interactive mode, command-line mode, or command-file mode. Because the `netcfg` command is hierarchical, it is more easily understood when used in interactive mode. For more information about the different modes, see [“Configuring Profiles by Using the `netcfg` Command” on page 32](#).

For information about the `netcfg` command, see the `netcfg(1M)` man page. For information about the `netadm` command, see the `netadm(1M)` man page.

## How Reactive Network Profiles Work

The system provides the `Automatic NCP` and the `Automatic Location` profile, as the default reactive profiles. These profiles perform the basic configuration of your wired or wireless networking automatically, without any user interaction. The only time you are required to interact with reactive networking is if you are prompted by the system for more information, for example, to provide a security key or password for a wireless network.

The automatic or reactive network configuration is triggered by the following events and activities:

- Connecting or disconnecting an Ethernet cable
- Connecting or disconnecting a WLAN card
- Booting a system when a wired interface, a wireless interface, or both, is available
- Resuming from suspend when a wired interface, a wireless interface, or both, is available (if supported)
- Acquiring or losing a DHCP lease

To perform the basic configuration of your network automatically, the `Automatic NCP` implements the following basic policy:

- Configure all available (connected) Ethernet interfaces by using DHCP.
- If no Ethernet interfaces are connected, or if none can obtain an IP address, enable one wireless interface, automatically connecting to the best available WLAN from the `Known WLAN` list. Alternatively, wait for the user to select a wireless network to connect to.
- Until at least one IPv4 address has been obtained, keep the `NoNet` location active. This Location profile provides a strict set of IP Filter rules that only pass data that is relevant to IP address acquisition (DHCP and IPv6 `autoconf` messages). All of the properties of the `NoNet` location, with the exception of the activation conditions, can be modified.
- When at least one IPv4 address has been assigned to one of the system's interfaces, activate the `Automatic` location. This Location profile has no IP Filter or IPsec rules. The Location profile applies the domain name system (DNS) configuration data that is obtained from the DHCP server. As with the `NoNet` location, all of the properties of the `Automatic` location, with the exception of its activation conditions, can be modified.
- Always apply the `NoNet` location when the system has no IPv4 addresses assigned to it. When at least one IPv4 address is assigned, select the Location profile with the activation rules that best match the current network conditions. In the absence of a better match, fall back to the `Automatic` location.

For more information, see [“Profile Activation Policy” on page 17](#).

For more information about how to administer the DHCP service to automatically configure the network, see [Working With DHCP in Oracle Solaris 11.1](#).

# How Reactive Networking Works With Other Oracle Solaris Networking Technologies

Reactive network configuration works with the following Oracle Solaris networking technologies:

- **Network virtualization**

Reactive network configuration works with the various Oracle Solaris network virtualization technologies as follows:

- **Virtual machines: Oracle VM Server for SPARC (formerly Logical Domains) and Oracle VM VirtualBox**

Reactive network profiles are supported in both Oracle Solaris hosts and guests. Reactive network configuration manages only the interfaces that belong to the specified virtual machines and does not interfere with other virtual machines.

- **Oracle Solaris Zones and stack instances**

Reactive network profiles work in the global zone or in an exclusive stack, non-global zone.

---

**Note** – Reactive network profiles cannot be used in a shared stack zone, as the network configuration for shared stack zones is always managed in the global zone.

---

- **Dynamic reconfiguration and NCPs**

The system's network configuration supports dynamic reconfiguration (DR) and hot-plug features only on systems that support these capabilities. You can use these features to add or remove a device if the active NCP on the system is either reactive (`Automatic` or any user-defined reactive profile) or fixed (`DefaultFixed`). However, the behavior of the system varies depending on the active profile.

When the `Automatic` profile is active and a device is plugged in, the `Automatic` NCP automatically creates the IP configuration for the newly added device. If a device is removed while any reactive (`Automatic` or user-defined) profile is active, IP is unconfigured for the device, though only the `Automatic` NCP removes the persistent configuration. When a fixed profile is the active NCP, IP configuration must be explicitly added after adding a device, or removed before removing a device.

For more information about dynamically configuring devices, see [Oracle Solaris 11.1 Administration: Devices and File Systems](#). For more information about performing dynamic reconfiguration when you are using a fixed profile, see “[How to Replace a Network Interface Card With Dynamic Reconfiguration](#)” in [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

- **Fixed networking commands**

You can use the `ipadm` and `dladm` commands to view the current network configuration and to modify the currently active NCP, when the active NCP is `DefaultFixed` or a user-defined NCP that is managed by reactive networking. Note that when a reactive (NWAM-managed) NCP is active, links and interfaces created with these commands are assigned implicit activation conditions, such that they depend on their underlying link or interface. For example, if `dladm` is used to create a VNIC, that VNIC NCU has an implicit dependency on its underlying link.

For more information about the `ipadm` and `dladm` commands, see [Chapter 4, “Working With IP Interfaces,”](#) in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1* and [Chapter 3, “Working With Datalinks,”](#) in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1*.

## SMF Network Services

In Oracle Solaris, network configuration is implemented by multiple SMF services as follows:

- `svc:/network/loopback:default` – Creates the IPv4 and IPv6 loopback interfaces.
- `svc:/network/netcfg:default` – Manages the network configuration repository, with its primary function being to start the `netcfgd` daemon. This service is a prerequisite for the `svc:/network/physical:default` service.
- `svc:/network/physical:default` – Brings up links and plumbs IP interfaces. This service starts the network management daemon, `nwamd`.
- `svc:/network/location:default` – Enables the Location profile that is selected by the `nwamd` daemon. This service is dependent on the `svc:/network/physical:default` service.

---

**Note** – The `svc:/network/location:default` service has a property that stores the current Location profile. Do not directly manipulate this property. Rather, use the CLI or the network administration GUI to make these types of changes.

---

## Network Configuration Security and Authorizations

Security for reactive network configuration encompasses the following components:

- CLI (`netcfg` and `netadm` commands)
- Network administration GUI
- Network profile repository daemon (`netcfgd`)
- Network management daemon (`nwamd`)
- Network configuration management library (`libnwam`)

The `netcfgd` daemon controls the repository where all of the network configuration information is stored. The `netcfg` command, the network administration GUI, and the `nwamd`

daemon send requests to the `netcfgd` daemon to access the repository. These functional components make requests through the network configuration management library, `libnwam`.

## Authorizations and Profiles Related to Network Configuration

The current network configuration implementation uses the following authorizations to perform specific tasks:

- `solaris.network.autoconf.read` – Enables the reading of network profile data, which is verified by the `netcfgd` daemon
- `solaris.network.autoconf.write` – Enables the writing of network profile data, which is verified by the `netcfgd` daemon
- `solaris.network.autoconf.select` – Enables new configuration data to be applied, which is verified by the `nwamd` daemon
- `solaris.network.autconf.wlan` – Enables the writing of known WLAN configuration data

These authorizations are registered in the `auth_attr` database. For more information, see the [auth\\_attr\(4\)](#) man page.

The `solaris.network.autoconf.read` authorization is included in the Basic Solaris User rights profile, which is assigned to all users by default. Any user with this authorization is therefore able to view the current network state and the contents of all network profiles.

Two additional rights profiles are provided: Network Autoconf User and Network Autoconf Admin. The Network Autoconf User profile has `read`, `select`, and `wlan` authorizations. The Network Autoconf Admin profile adds the `write` authorization. The Network Autoconf User profile is assigned to the Console User profile. Therefore, by default, anyone who is logged in to the console can view, enable, and disable profiles. Because the Console User profile is not assigned the `solaris.network.autoconf.write` authorization, any user with this authorization cannot create or modify NCPs, NCUs, locations, or ENMs. However, the Console User profile can view, create, and modify WLANs.

## Authorizations Required to Use the User Interfaces

The `netcfg` and `netadm` commands can be used to view network profiles by any user who has the Basic Solaris User rights profile. This profile is assigned to all users by default.

The `netadm` command can also be used to enable network profiles by any user who has the Network Autoconf User or Console User profile. The Console User profile is automatically assigned to the user who is logged in to the system from `/dev/console`.

To modify network profiles by using the `netcfg` command, you need the `solaris.network.autoconf.write` authorization or the Network Autoconf Admin profile.

You can determine the privileges that are associated with a rights profile by using the `profiles` command with the profile name. For more information, see the [profiles\(1\)](#) man page.

For example, to determine privileges that are associated with the Console User rights profile, use the following command:

```
$ profiles -p "Console User" info
Found profile in files repository.
  name=Console User
  desc=Manage System as the Console User
  auths=solaris.system.shutdown,solaris.device.cdrw,solaris.smf.manage.vbiosd,
  solaris.smf.value.vbiosd
  profiles=Suspend To RAM,Suspend To Disk,Brightness,CPU Power Management,
  Network Autoconf User,Desktop Removable Media User
  help=RtConsUser.html
```

The network administration GUI includes the following components, which are not privileged. These components are granted authorizations, depending on how they are started and the tasks they need to perform.

- **Network configuration and status panel presence**

This component is the panel applet in the desktop that enables a user to interact with the network configuration. The panel can be run by any user and is used to monitor the autoconfiguration of the system and handle event notifications. The panel can also be used to perform some basic network configuration tasks, for example, selecting a WiFi network or manually switching locations. To perform these types of tasks, the Network Autoconf User rights profile is required. This rights profile is available in the default configuration, because the panel is running with the authorizations of the user who is logged in from `/dev/console`, and hence has the Console User profile.

- **Network administration GUI**

The network administration GUI (previously known as NWAM GUI) is the primary means for interacting with the network configuration from the desktop. The GUI is used to view the network status, to create and modify NCPs and Location profiles, and to start and stop configured ENMs. Interaction with the GUI requires four of the `solaris.network.autoconf` authorizations or the Network Autoconf Admin profile. By default, the Console User profile has sufficient authorizations to view the network status and profiles by using the GUI. In addition, you require the `solaris.network.autoconf.write` authorization or the Network Autoconf Admin profile to modify profiles by using the GUI.

You can obtain additional authorizations in one of the following ways:

- Assign the Network Autoconf Admin profile to a specific user.

You can assign appropriate authorizations, or rights profiles, directly to a given user by editing the `/etc/user_attr` file for that user.

- Assign the Network Autoconf Admin profile to the Console User profile.  
 You can assign this profile to the Console User profile instead of the Network Autoconf User profile that is assigned by default. To assign this profile, edit the entry in the `/etc/security/prof_attr` file.

## Where to Find Network Configuration Tasks

The following table lists network configuration topics and where to go for more information.

Networking Task	For More Information
Create, modify, and list profiles and configuration objects by using the <code>netcfg</code> command.	Chapter 2, “Creating and Configuring Reactive Network Profiles (Tasks)”
View information about and administer profiles and configuration objects by using the <code>netadm</code> command.	Chapter 3, “Administering Your Reactive Network Configuration (Tasks)”
View information about your network status, switch network connections, and create and modify profiles and configuration objects by using the network administration GUI from the desktop.	Chapter 4, “Using the Network Administration Graphical User Interface,” and the online help
Switch between reactive network configuration and fixed network configuration.	“Switching Between Fixed and Reactive Network Configurations” on page 74
Create a network configuration in the currently active NCP.	Chapter 3, “Working With Datalinks,” in <i>Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1</i> and Chapter 4, “Working With IP Interfaces,” in <i>Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1</i>
Configure and manage virtual networks.	Chapter 1, “Network Virtualization and Resource Management in Oracle Solaris,” in <i>Using Virtual Networks in Oracle Solaris 11.1</i>



## Creating and Configuring Reactive Network Profiles (Tasks)

---

This chapter describes profile-based network configuration tasks that you can perform to configure reactive network on your system by using the `net cfg` command in either interactive mode or command-line mode. These configuration tasks include creating user-defined profiles, modifying user-defined profiles, as well as managing the various SMF services that control the system network configuration.

Although the primary focus of this chapter is on reactive profiles, the `net cfg` command also includes limited features related to fixed profiles, primarily for viewing fixed profiles and their properties. For more information, see [“Listing All of the Profile Configuration Information on a System” on page 63](#).

The following topics are covered in this chapter:

- “Configuring Profiles by Using the `net cfg` Command” on page 32
- “`net cfg` and `net adm` Subcommands” on page 35
- “Creating User-Defined Profiles” on page 39
- “Setting and Changing Property Values for a Profile” on page 60
- “Listing Profile Configuration Information on a System” on page 63
- “Enabling and Disabling Profiles” on page 69

For information about switching network configuration, displaying profile states, exporting and restoring profiles, removing profiles, and managing known wireless networks, see [Chapter 3, “Administering Your Reactive Network Configuration \(Tasks\)”](#).

For information about how to interact with the system network and to manage your network configuration from the desktop, see [Chapter 4, “Using the Network Administration Graphical User Interface”](#).

For overview information about reactive network configuration, see [Chapter 1, “Reactive Network Configuration \(Overview\)”](#).

## Configuring Profiles by Using the `net cfg` Command

You can use the `net cfg` command to select, create, modify, and remove user-defined profiles. For information about the `net cfg` subcommands, see [“`net cfg` Subcommands” on page 35](#). The `net cfg` command can be used in either interactive mode or command-line mode. This command also supports the export of profile configuration information to an output file.

You can use the `net cfg` command to display profile configuration data, and to display, create, and modify Known WLAN objects, if you have the `Console User` privileges. These privileges are automatically assigned to any user who is logged in to the system from `/dev/console`. Users who have the `Network Autoconf Admin` rights profile can also create and modify all types of reactive network (NWAM-managed) profiles and configuration objects. For more information, see [“Network Configuration Security and Authorizations” on page 26](#).

You can create and configure your profiles in any of the following modes:

- Command-line mode
- Interactive mode
- Command-file mode

When you are in `net cfg` interactive mode, it is fairly easy to understand the syntax to use for this command. However, in command-line mode, the syntax might be less obvious.

### `net cfg` Interactive Mode

The concept of a *scope* is used for the `net cfg` command. When you use the command interactively, the scope you are in at any given time depends on the profile type and the task that you are performing. When you type the `net cfg` command in a terminal window, a prompt is displayed at the *global scope*.

From the global scope prompt, you can use the `select` or `create` subcommands to view, modify, or create the following profile types, which are the top-level profiles:

- NCPs
- Locations
- ENMs
- Known WLANs

Before you can create or select a profile, the `net cfg` interactive prompt is displayed in the following form:

```
net cfg>
```

After you have created or selected a profile, the `net cfg` interactive prompt is displayed as follows:

```
net cfg:profile-type:profile-name>
```

You can use the netcfg command in interactive mode to perform the following tasks:

- Create a profile.
- Select and modify a profile.
- Verify that all of the required information about a profile is set and valid.
- Commit the changes for a new profile.
- Cancel the current profile configuration without committing any changes to persistent storage.
- Revert the changes that you made for a profile.

Selecting or creating a top-level profile while working in netcfg interactive mode results in a command prompt that is displayed in the *profile scope* for Location profiles and ENMs. For example:

```
netcfg> select loc test-loc
netcfg:loc:test-loc>
```

If an NCP is selected, the command prompt is displayed is the *NCP scope*. From the NCP scope, an NCU can be selected or created. Selecting or creating an NCU results in a profile scope prompt for the selected NCU. In this scope, all of the properties that are associated with the currently selected profile can be viewed and set.

In the following example, the User NCP is first selected, then an NCU is created in the NCP scope. This action results in the profile scope for the newly created NCU. In this scope, the properties of the NCU can be viewed or set.

```
netcfg> select ncp User
netcfg:ncp:User> create ncu phys net2
Created ncu 'net2'. Walking properties ...
activation-mode (manual) [manual|prioritized]>
```

At any given scope, the command prompt indicates the currently selected profile. Any changes that you make to the profile in this scope can be *committed*, meaning that the changes are saved to the persistent storage. Changes are implicitly committed upon exiting the scope. If you do not want to commit the changes that you made to the selected profile, you can revert to the last committed state for that profile. Doing this action reverts any changes that you made to the profile at that level. The revert and cancel subcommands work similarly.

---

**Note** – The walkprop subcommand, which “walks” you through each property that is associated with a profile is meaningful when used in interactive mode. For information about the netcfg subcommands, see [“netcfg Subcommands” on page 35](#).

---

## netcfg Command-Line Mode

In command-line mode, any subcommand that affects a selected profile or property must be performed in the particular scope in which the selected profile or property exists. Thus, to obtain the value of a property of an NCU, you would use the `get` subcommand in the scope of that particular NCU.

For example, to obtain the value of a property `ip-version` which is an attribute of an NCU called `myncu` in the User NCP, you would use the following syntax:

```
$ netcfg "select ncp User; select ncu ip myncu; get ip-version"
```

In this syntax, note the following:

- Each scope is separated by a semicolon.
- The `select` subcommand is issued at each scope, once at the global scope and once at the profile scope.
- The `get` subcommand is used within the scope in which the property `ip-version` exists.
- Straight quotation marks are required to prevent the shell from interpreting the semicolons.

---

**Note** – In command-line mode, you must type the complete command on a single line. Changes that you make to a selected profile by using the `netcfg` command in command-line mode are committed to the persistent storage as soon as you finish typing the command.

You can use any of the subcommands listed in “[netcfg Subcommands](#)” on page 35 in command-line mode except the `walkprop` subcommand.

---

## netcfg Command-File Mode

In command-file mode, profile configuration information and commands are taken from a file. The commands in the file are same as that in the interactive mode or those that are given by the `export` subcommand. The `export` subcommand is used to produce this file. The configuration can then be printed to standard output, or the `-f` option can also be used to specify an output file. For example, the following command exports the current configuration to a file:

```
$ netcfg export -f /tmp/nwam.config
```

To import configuration from a file, type the following command:

```
$ netcfg -f /tmp/nwam.config
```

The `export` subcommand can also be used interactively. For information about how to export profile configuration by using `netcfg` command-file mode see, [Example 3-4](#).

## netcfg and netadm Subcommands

The `netcfg` command manipulates system network configuration profiles. The `netcfg` command can be invoked interactively, with an individual subcommand, or by specifying a command file that contains a series of subcommands. The `netadm` command administers the profiles and also interacts with `nwamd` by using the subcommands.

### netcfg Subcommands

The following `netcfg` subcommands are supported in interactive mode and command-line mode. Note that certain subcommands have different semantics within each scope. If a subcommand cannot be used in a certain mode, the subcommand's description notes that. The subcommands are ordered alphabetically.

- `cancel`  
Ends the current profile specification without committing the current changes to persistent storage, then proceeds to the previous scope, which is one level higher.
- `clear prop-name`  
Clears the value for the specified property.
- `commit`  
Commits the current profile specification to persistent storage. A configuration must be correct to be committed. Therefore, this operation automatically performs a `verify` operation on the profile or object as well. The `commit` operation is attempted automatically upon exiting the current scope by using either the `end` or `exit` subcommand.
- `create [ -t template ] object-type [ class ] object-name`  
Creates an in-memory profile with the specified type and name. The `-t template` option specifies that the new profile be identical to *template*, where *template* is the name of an existing profile of the same type. If the `-t` option is not used, the new profile is created with the default values.
- `destroy -a`  
Removes all user-defined profiles from memory and persistent storage.
- `destroy object-type [ class ] object-name`  
Removes the specified user-defined profile from memory and persistent storage.




---

**Caution** – This operation is immediate and does not need to be committed. A removed profile cannot be reverted.

---

- `end`

Ends the current profile specification and proceeds to the previous scope, which is one level higher. The current profile is verified and committed before the edit operation ends. If either the `verify` or `commit` operation fails, an error message is displayed. You are then given the opportunity to end the operation without committing the current changes. Alternatively, you can remain in the current scope and continue editing the profile.

- `exit`

Exits the `netcfg` interactive session. The current profile is verified and committed before the current session ends. If either the `verify` or `commit` operation fails, an error message is displayed. You are then given the opportunity to end the session without committing the current changes. Alternatively, you can remain in the current scope and continue editing the profile.

- `export [ -d ] [ -f output-file ] [ object-type [ class ] object-name ]`

Prints the current configuration at the current or specified scope to standard output or to a file that is specified with the `-f` option. The `-d` option generates the `destroy -a` subcommand as the first line of output. This subcommand produces output in a form that is suitable for use in a command file. For information about how to export and restore profile configuration, see “Exporting and Restoring a Profile Configuration” on page 77.

---

**Note** – You cannot export system-defined profiles. System-defined profiles include the `Automatic` and `DefaultFixed` NCPs and the `Automatic`, `NoNet`, and `DefaultFixed` locations.

---

- `get [ -V ] prop-name`

Gets the current, in-memory value of the specified property. By default, both the property name and value are printed. If the `-V` option is specified, only the property value is printed.

- `help [ subcommand ]`

Displays general help or help about a specific subject.

- `list [-a] [object-type [ class ] object-name ]`

Lists all profiles property-value pairs that are used at the current or specified scope. When listing properties of an object, the default behavior is to only list properties that apply to the specified configuration. That is, if listing an IP NCU for which `ipv4-addrsrc` is `dhcp`, the `ipv4-addr` property is not listed. Including the `-a` option results in all properties being listed, whether or not they apply to the current settings.

- `revert`

Deletes any current changes that were made to a profile, then reverts to the values from persistent storage.

- `select object-type [ class ] object-name`

Selects the object that is specified.

- `set prop-name=value`

Sets the current, in-memory value of the specified property.

If performed in command-line mode, the change is also committed immediately to persistent storage.

The delimiter for properties with multiple values is a comma (,). If an individual value for a given property contains a comma, it must be preceded it with a backslash (\). Commas within properties that only have a single value are not interpreted as delimiters and do not need to be preceded by a backslash.

- `verify`

Verifies that the current, in-memory profile or object has a valid configuration.

- `walkprop [-a]`

“Walks” each property that is associated with the current profile. For each property, the name and current value are displayed. A prompt is provided to enable you to change the current value.

The delimiter for properties with multiple values is a comma (,). If an individual value for a given property contains a comma, it must be preceded by a backslash (\). Commas within properties that only have a single value are not interpreted as delimiters and do not need to be preceded by a backslash.

By default, only properties that are required based on properties that are already set are walked. If `ipv4-addrsrc` is set to `dhcp`, then `ipv4-addr` is not walked. Including the `-a` option iterates all available properties for the specified profile or object.

---

**Note** – The `walkprop` subcommand is meaningful when used in interactive mode only.

---

## netadm Subcommands

The following `netadm` subcommands are supported:

- `enable [-p profile-type] [-c ncu-class] profile-name`

Enables the specified profile. If the profile name is not unique, the profile type must be specified. If the profile type is `ncu`, and the name is not unique, for example, if both a link and an interface NCU have the same name, both NCUs are enabled, unless the `-c` option is used to specify the NCU class.

The profile type must be one of the following:

- `ncp`
- `ncu`
- `loc`
- `enm`
- `wlan`

The NCU class must be specified as either `phys` for link NCU or `ip` for interface NCU.

- `disable [ -p profile-type ] [ -c ncu-class ] profile-name`

Disables the specified profile. If the profile name is not unique, the profile type must be specified to identify the profile that is to be disabled. If the profile type is `ncu` and the name is not unique, for example, if both a link and an interface `ncu` have the same name, both NCUs are disabled, unless the `-c` option is used to specify the NCU class.

The profile type must be one of the following:

- `ncp`
- `ncu`
- `loc`
- `enm`
- `wlan`

The NCU class must be specified as either `phys` or `ip`.

- `list [ -x ] [ -p profile-type ] [ -c ncu-class ] [ profile-name ]`

Lists all of the available profiles and their current state. If a profile is specified by name, then only the current state of that profile is listed. If the profile name is not unique, all of the profiles with that specified name are listed. Alternatively, the profile type, the NCU class, or both can be included to identify a specific profile. If just the profile type is specified, all of the profiles of that type are listed.

Listing the enabled NCP includes all of the NCUs that make up that NCP.

If the `-x` option is specified, an expanded description of the auxiliary state of each listed profile is included in the output.

Possible profile auxiliary state values include the following:

- `disabled`

Indicates a manually enabled profile that has not been enabled.

- `offline`

Indicates a conditionally enabled or system-enabled profile that has not been enabled. The profile might not be active because its conditions have not been satisfied. Alternatively, the profile might not be active because another profile with more specific conditions that are met has been enabled. This condition applies to profile types that must be enabled one at a time, for example, the Location profile.

- `online`

Indicates a conditionally enabled or system-enabled profile whose conditions have been met and that has been successfully enabled. Alternatively, it might indicate a manually enabled profile that has been successfully enabled at the request of the user.

- `maintenance`

Indicates that activation of the profile was attempted, but failed.

- `initialized`

Indicates that the profile represents a valid configuration object for which no action has yet been taken.

- uninitialized

Indicates that the profile represents a configuration object that is not present on the system. For example, this state could indicate an NCU that corresponds to a physical link that was removed from the system.

- show-events

Listens for and displays a stream of events from the network management daemon, `nwamd`.

- scan-wifi *link-name*

Initiates a wireless scan on the link that is specified as *link-name*.

- select-wifi *link-name*

Selects a wireless network to connect to from scan results on the link that is specified as *link-name*.

- help

Displays a usage message with a short description of each subcommand.

## Creating User-Defined Profiles

You can use the `netcfg` command to create user-defined profiles. The command can be used in either interactive mode or command-line mode. The `netcfg` command also supports the export of profile configuration information to an output file. For more information about command-line mode and interactive mode, see [“netcfg Command-Line Mode” on page 34](#) and [“netcfg Interactive Mode” on page 32](#).

You can use the `netcfg` command to create user-defined profiles, if you have the Console User privileges. These privileges are automatically assigned to any user who is logged in to the system from `/dev/console`. Users who have the Network Autoconf Admin rights profile can also create and modify all types of reactive network (NWAM-managed) profiles and configuration objects. For more information, see [“Network Configuration Security and Authorizations” on page 26](#).

You can create the following profiles and configuration objects:

- Network configuration profiles (NCPs)
- Location profiles
- External network modifiers (ENMs)
- Known wireless local area networks (Known WLANs)
- Network configuration units (NCUs)

For information about profiles and configuration objects, see [“Network Profiles and Types” on page 11](#).

---

**Note** – The `Automatic` and `DefaultFixed` NCPs and Location profiles are system-defined. Do not attempt to create these profiles by using the `netcfg` command.

---

The basic command syntax to create a profile from the command-line is as follows:

**netcfg create** [ **-t** *template* ] *object-type* [ *class* ] *object-name*

**create** Creates an in-memory profile (or configuration object) of the specified type and name.

**-t *template*** Specifies that the new profile be identical to *template*, where *template* is the name of an existing profile of the same type. If the **-t** option is not used, the new profile is created with default values.

***object-type*** Specifies the type of profile to be created.

You can specify one of the following values for the *object-type* option:

- `ncp`
- `ncu`
- `loc`
- `enm`
- `wlan`

All profiles that are specified by the *object-type* option, with the exception of an `ncu`, must be created at the global scope before you can use the `netcfg select` command to select the particular object.

***class*** Specifies the class of profile that is specified by *object-type*. This parameter is only used for the `ncu` object type, and has two possible values, `phys` (for link NCUs) or `ip` (for interface NCUs).

***object-name*** Specifies the name of the user-defined profile. For an NCU, *object-name* is the name of the corresponding link or interface. For all the other profile types, *object-name* is any user-defined name.

---

**Note** – For the creation of NCPs, the `class` option is not required.

---

Optionally, you can use a copy of the `Automatic` NCP as your template, then make changes to that profile, as shown here:

```
$ netcfg> create -t Automatic ncp test
```

To create a Location profile with the name of `office`, you would type the following command:

```
$ netcfg> create loc office
```

For information about the `netcfg` subcommands, see “[netcfg Subcommands](#)” on page 35.

## Creating an NCP

Creating a profile in interactive mode results in a command prompt in one of the following scopes:

- In the NCP scope, if an NCP is created
- In the profile scope, if a Location profile, an ENM profile, or a Known WLAN profile is created

Creating an NCP or an NCU moves the focus into that object's scope, walking you through the default properties for the specified profile.

To interactively create an NCP, you begin by initiating a `netcfg` interactive session. Then, you use the `create` subcommand to create the new NCP. For example:

```
$ netcfg
netcfg> create ncp User
netcfg:ncp:User>
```

## Creating NCUs for an NCP

The NCP is essentially a container that consists of a set of NCUs. All NCPs contain both link and interface NCUs. Link NCUs specify both the link configuration and link selection policy. Interface NCUs specify the interface configuration policy. If IP connectivity is required, both a link and an interface NCU are required. NCUs must be added or removed explicitly by using the `netcfg` command or by using the network administration GUI. For more information about adding and removing NCUs using the network administration GUI, see “[Editing Network Profiles](#)” on page 102.

The `DefaultFixed` NCP cannot be modified by using the `netcfg` command. You can use the `ipadm` and `dladm` commands to create, modify, or delete NCUs in the `DefaultFixed` NCP while the NCP is active. You can also use the `ipadm` and `dladm` commands to add NCU classes other than physical links and IP interfaces to reactive NCPs. The `ipadm` and `dladm` commands provide the capabilities to create and modify more complex link and interface classes.

For more information about the `ipadm` and `dladm` commands, see [Chapter 3, “Working With Datalinks,”](#) in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1* and [Chapter 4, “Working With IP Interfaces,”](#) in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1*.

---

**Note** – You can add NCUs that do not correlate to any link that is currently installed on the system. Additionally, you can remove NCUs that map to a link that is currently installed on the system.

---

You can create NCUs by using the `netcfg` command in either interactive mode or command-line mode. Because creating an NCU involves several operations, it is easier and more efficient to create NCUs in interactive mode, rather than trying to construct a single-line command that creates the NCU and all of its properties. NCUs can be created when you initially create an NCP or afterward. The process of creating or modifying an NCU involves setting general NCU properties, as well as setting properties that specifically apply to each NCU type.

The properties that you are presented with during the process of creating NCUs for an NCP make the most sense based on the choices that you made during the creation of that particular NCP.

When you create an NCU interactively, `netcfg` walks you through each relevant property, displaying both the default value, where a default exists, and the possible values. Pressing Return without specifying a value applies the default value (or leaves the property empty if there is no default), or you can specify an alternate value. The properties that are displayed during the process of creating NCUs for an NCP are relevant based on the choices that you have already made. For example, if you choose `dhcp` for the `ipv4-addrsrc` property for an interface NCU, you are not prompted to specify a value for the `ipv4-addr` property.

The following table describes all of the NCU properties that you might specify when creating or modifying an NCU. Some properties apply to both NCU types. Other properties apply to either a link NCU or an interface NCU. For a complete description of all of the NCU properties, including rules and conditions that might apply when you specify these properties, see the [netcfg\(1M\)](#) man page.

TABLE 2-1 NCU Properties to Create or Modify an NCU

Property	Description	Possible Values	NCU Type
<code>type</code>	Specifies the NCU type, either link or interface.	link or interface	Link and interface
<code>class</code>	Specifies the NCU class.	<code>phys</code> (for link NCUs) or <code>ip</code> (for interface NCUs)	Link and interface
<code>parent</code>	Specifies the NCP to which this NCU belongs.	<i>parent-NCP</i>	Link and interface

TABLE 2-1 NCU Properties to Create or Modify an NCU (Continued)

Property	Description	Possible Values	NCU Type
enabled	Specifies whether the NCU is enabled or disabled. This property is read-only. It is changed indirectly when you use the <code>netadm</code> command or the network administration GUI to enable or disable the NCU.	true or false	Link and interface
activation-mode	Specifies the type of trigger for the automatic activation of the NCU.	manual or prioritized The default value is manual.	Link
priority-group	Specifies the group priority number.	0 (for wired links) or 1 (for wireless links)  For user-defined NCPs, different policies can be specified, for example, wireless link 1 is priority 1, wired link 1 is priority 2, and wired link 2 is priority 3.  <b>Note</b> – A lower number indicates a higher priority.	Link
priority-mode	Specifies the mode that is used to determine the activation behavior for a priority group, if the <code>activation-mode</code> property is set to <code>prioritized</code> .	exclusive, shared, or all  For the rules that apply when you specify these values, see the <a href="#">netcfg(1M)</a> man page.	Link
mac-address	Specifies the MAC address that is assigned to this link. By default, the factory-assigned or the default MAC address is used for the link. A different value can be set here to override that selection.	A string containing a 48-bit MAC address	
autopush	Identifies modules that are automatically pushed over the link when it is opened.	A list of strings (modules that are to be pushed over the link)  For information, see the <a href="#">autopush(1M)</a> man page.	Link
mtu	Is automatically set to the default MTU for the physical link. The value can be overridden by setting the property to a different value.	MTU size for the link	Link
ip-version	Specifies the version of IP to use. Multiple values can be assigned.	ipv4 and ipv6  The default value is ipv4, ipv6.	Interface

TABLE 2-1 NCU Properties to Create or Modify an NCU (Continued)

Property	Description	Possible Values	NCU Type
ipv4-addrsrc	Identifies the source of IPv4 addresses that are assigned to this NCU. Multiple values can be assigned.	dhcp and static The default value is dhcp.	Interface
ipv6-addrsrc	Identifies the source of IPv6 addresses assigned to this NCU. Multiple values can be assigned.	dhcp, autoconf, or static The default value is dhcp, autoconf.	Interface
ipv4-addr	Specifies one or more IPv4 addresses to be assigned to this NCU.	One or more IPv4 addresses to be assigned	Interface
ipv6-addr	Specifies one or more IPv6 addresses to be assigned to this NCU.	One or more IPv6 addresses to be assigned	Interface
ipv4-default-route	Specifies the default route for an IPv4 address.	An IPv4 address	Interface
ipv6-default-route	Specifies the default route for an IPv6 address.	An IPv6 address	Interface

## ▼ How to Interactively Create an NCP With NCUs

The following procedure describes how to create an NCP and NCUs for the NCP in interactive mode.

---

**Note** – The “walk” process that the system network performs during the initial profile creation ensures that you are prompted for only those properties that are applicable, given the choices that you made previously.

---

### 1 Initiate an netcfg interactive session.

```
$ netcfg
netcfg>
```

### 2 Create the NCP.

```
netcfg> create ncp User
netcfg:ncp:User>
```

where ncp is the profile type and User is the profile name.

Creating the NCP automatically takes you into the NCP scope. If you were creating a location, an ENM, or a WLAN object, the command prompt would take you to that profile scope.

---

**Note** – Repeat Steps 3 and 4 until all of the required NCUs for the NCP are created.

---

### 3 Create the link and interface NCUs for the NCP.

#### a. To create the link NCU, type the following command:

```
netcfg:ncp:User> create ncu phys net0
Created ncu 'net0', Walking properties ...
```

where `ncu` is the object type, `phys` is the class, and `net0` (for example purposes *only*) is the object name.

Creating an NCU moves you into that object's scope and walks you through the default properties for the object.

For information about NCU properties, see [Table 2-1](#).

#### b. To create an interface NCU, type the following command:

```
netcfg:ncp:User> create ncu ip net0
Created ncu 'net0'. walking properties ...
```

where `ncu` is the object type, `ip` is the class, and `net0` (for example purposes *only*) is the object name.

Creating an NCU moves you into that object's scope and walks you through the default properties for the object.

During the creation of an NCU, the `class` option is used to differentiate between the two types of NCUs. This option is especially valuable in situations where different NCU types share the same name. If the `class` option is omitted, it is much more difficult to distinguish NCUs that share the same name.

### 4 Add the appropriate properties for the NCU that you created.

### 5 During the creation of the NCU, or when setting property values for a specified NCU, use the `verify` subcommand to ensure that the changes that you made are correct.

```
netcfg:ncp:User:ncu:net0> verify
All properties verified
```

The `verify` subcommand verifies your configuration and notifies if any required values are missing. You can verify your changes by using the `verify` subcommand explicitly when creating or modifying a profile.

### 6 Commit the properties that you set for the NCU.

```
netcfg:ncp:User:ncu:net0> commit
committed changes.
```

The `commit` subcommand implicitly verifies your changes.

Alternatively, you can use the `end` subcommand to perform an implicit commit, which moves the interactive session up one level to the next higher scope. In this instance, if you have completed creating the NCP and adding NCUs to it, you can exit the interactive session directly from the NCP scope.

In interactive mode, changes are not saved to persistent storage until you commit them. When you use the `commit` subcommand, the entire profile is committed. To maintain the consistency of persistent storage, the `commit` operation also includes a verification step. If the verification fails, the `commit` operation also fails. If an implicit commit fails, you are given the option of ending or exiting the interactive session without committing the current changes. Alternatively, you can remain in the current scope and continue making changes to the profile.

---

**Note** – To cancel the changes that you made, use the `cancel` or the `revert` subcommand.

The `cancel` subcommand ends the current profile configuration without committing the current changes to persistent storage, then moves the interactive session up one level to the next higher scope. The `revert` subcommand undoes the changes that you made and rereads the previous configuration. When you use the `revert` subcommand, the interactive session remains in the same scope.

---

**7 Use the `list` subcommand to display the NCP configuration.**

**8 When you are finished configuring the NCP, exit the interactive session.**

```
netcfg:ncp>User> exit
```

Any time that you use the `exit` subcommand to end a `netcfg` interactive session, the current profile is verified and committed. If either the verification or the `commit` operation fails, an appropriate error message is issued, and you are given the opportunity to exit without committing the current changes. Alternatively, you can remain in the current scope and continue making changes to the profile.

---

**Note** – To exit the scope without exiting the `netcfg` interactive session, type the `end` subcommand:

```
netcfg:ncp>User> end
netcfg>
```

---

### Example 2-1 Interactively Creating an NCP With NCUs

In the following example, an NCP and two NCUs (one link and one interface) are created.

```
$ netcfg
netcfg> create ncp User
netcfg:ncp>User> create ncu phys net0
Created ncu 'net0', Walking properties ...
```

```

activation-mode (manual) [manual|prioritized]>
mac-address>
autopush>
mtu>
netcfg:ncp:User:ncu:net0> end
Committed changes
netcfg:ncp:User> create ncu ip net0
Created ncu 'net0'. Walking properties ...
ip-version (ipv4,ipv6) [ipv4|ipv6]> ipv4
ipv4-addrsrc (dhcp) [dhcp|static]> dhcp
ipv4-default-route>
netcfg:ncp:User:ncu:net0> verify
All properties verified
netcfg:ncp:User:ncu:net0> end
Committed changes
netcfg:ncp:User> list
ncp:User
    management-type      reactive
NCUs:
    phys      net0
    ip        net0
netcfg:ncp:User> list ncu phys net0
ncu:net0
    type          link
    class         phys
    parent        "User"
    activation-mode manual
    enabled       true
netcfg:ncp:User> list ncu ip net0
ncu:net0
    type          interface
    class         ip
    parent        "User"
    enabled       true
    ip-version    ipv4
    ipv4-addrsrc  dhcp
netcfg:ncp:User> exit
$

```

In this example, because the value `ipv4` is chosen, no prompt is displayed for the `ipv6-addrsrc` property, as this property is unused. Likewise, for the `phys` NCU, the default value (`manual` activation) for the `priority-group` property is accepted, so no other conditionally related properties are applied.

### Example 2–2 Interactively Creating an NCU for an Existing NCP

To create an NCU for an existing NCP or to modify the properties of any existing profile, use the `netcfg` command with the `select` subcommand.

In the following example, an IP NCU is created for an existing NCP. The process of modifying an existing profile in interactive mode is similar to creating a profile. The difference between the following example and [Example 2–1](#) is that in this example, the `select` subcommand is used instead of the `create` subcommand because the NCP already exists.

```

$ netcfg
netcfg> select ncp User
netcfg:ncp:User> list
ncp:User
    management-type    reactive
NCUs:
    phys    net0
netcfg:ncp:User> create ncu ip net0
Created ncu 'net0'. Walking properties ...
ip-version (ipv4,ipv6) [ipv4|ipv6]> ipv4
ipv4-addrsrc (dhcp) [dhcp|static]> dhcp
ipv4-default-route>
netcfg:ncp:User:ncu:net0> end
Committed changes
netcfg:ncp:User> list
ncp:User
    management-type    reactive
NCUs:
    phys    net0
    ip      net0
netcfg:ncp:User> list ncu phys net0
ncu:net0
    type                link
    class                phys
    parent              "User"
    activation-mode     manual
    enabled              true
netcfg:ncp:User> list ncu ip net0
NCU:net0
    type                interface
    class                ip
    parent              "User"
    enabled              true
    ip-version           ipv4
    ipv4-addrsrc         dhcp
netcfg:ncp:User> exit
$

```

## Creating a Location Profile

A Location profile contains properties that define network configuration values that are not directly related to basic link and IP connectivity. Some examples include naming service and IP Filter settings that are applied together, when required. At any given time, one Location profile and one NCP must be active on the system.

There are system-defined locations and user-defined locations. System-defined locations are the default locations chosen by the network management daemon, `nwamd`, under certain conditions, for example, if you did not specify a location, or if no manually enabled locations are enabled, and none of the conditions of the conditionally enabled locations has been met. System-defined locations have a `system` activation mode. User-defined locations are configured to be manually or conditionally enabled, according to network conditions, for example, an IP address that is obtained by a network connection.

For information about manually activating (enabling) a Location profile, see “[Enabling and Disabling Profiles](#)” on page 69.

You can create locations by using the `netcfg` command in either interactive mode or command-line mode. When you create a Location profile, you must set the properties for the location by specifying values that define the particular configuration properties for that location. Location properties are categorized by group, where the group signifies a particular class of configuration preferences.

Location properties are also stored in a repository. When a particular Location profile is enabled, its properties are automatically applied to the running system. Creating or modifying Location profiles involves setting various properties that define how the profile is configured and setting properties that define when the profile should be enabled. The properties that you are presented with during the configuration process are based on the property values that you have already set.

The following table describes all of the location properties that can be specified. Note that location properties are categorized by group. For a complete description of all of the location properties, including any rules, conditions, and dependencies that might apply when you specify any of these properties, see the `netcfg(1M)` man page.

TABLE 2-2 Location Properties and Their Descriptions

Property Group and Description	Property Value and Description
<p><b>Selection criteria</b></p> <p>Specifies the criteria for how and when a location is enabled or disabled.</p>	<ul style="list-style-type: none"> <li>■ <code>activation-mode</code> The possible values for the <code>activation-mode</code> property are <code>manual</code>, <code>conditional-any</code>, and <code>conditional-all</code>.</li> <li>■ <code>conditions</code></li> </ul> <p>For information about the criteria and operations that can be used to construct the condition strings, see <a href="#">Table 1-1</a>.</p>
<p><b>System domain</b></p> <p>Determines a host's domain name for direct use by the NIS naming service.</p>	<p>The <code>system-domain</code> property consists of the <code>default-domain</code> property. This property specifies the system-wide domain that is used for Remote Procedure Call (RPC) exchanges.</p>

TABLE 2-2 Location Properties and Their Descriptions (Continued)

Property Group and Description	Property Value and Description
<p><b>Name services information</b></p> <p>Specifies the naming service to use and the naming service switch configuration.</p>	<p>The following is a list of properties for the specified naming service:</p> <ul style="list-style-type: none"> <li>■ domain-name</li> <li>■ nameservices</li> <li>■ nameservices-config-file</li> <li>■ dns-nameservice-configsrc</li> <li>■ dns-nameservice-domain</li> <li>■ dns-nameservice-servers</li> <li>■ dns-nameservice-search</li> <li>■ dns-nameservice-sortlist</li> <li>■ dns-nameservice-options</li> <li>■ nis-nameservice-configsrc</li> <li>■ nis-nameservice-servers</li> <li>■ ldap-nameservice-configsrc</li> <li>■ ldap-nameservice-servers</li> </ul> <p>For more information about these properties, see the “Location Properties” section in the <a href="#">netcfg(1M)</a> man page.</p>
<p><b>NFSv4 domain</b></p> <p>Specifies the NFSv4 domain.</p>	<p>The value that is used for the system's <code>nfsmapid_domain</code> property. This value is used to set the <code>nfsmapid_domain</code> SMF property, as described in the <code>nfsmapid</code> man page, while the location is active. If this property is not set, the system's <code>nfsmapid_property</code> is cleared when the location is active. For more information, see the <a href="#">nfsmapid(1M)</a> man page.</p>
<p><b>IP Filter configuration</b></p> <p>Specifies the parameters that are used for IP Filter configuration. For these properties, the paths to the appropriate <code>ipf</code> and <code>ipnat</code> files containing IP filter and NAT rules are specified.</p>	<ul style="list-style-type: none"> <li>■ ipfilter-config-file</li> <li>■ ipfilter-v6-config-file</li> <li>■ ipnat-config-file</li> <li>■ ippool-config-file</li> </ul> <p>If a configuration file is specified, the rules that are contained in the identified file are applied to the appropriate <code>ipfilter</code> subsystem.</p>
<p><b>Configuration files for IPsec</b></p> <p>Specifies which files to use for IPsec configuration.</p>	<ul style="list-style-type: none"> <li>■ ike-config-file</li> <li>■ ipsecpolicy-config-file</li> </ul>

## ▼ How to Interactively Create a Location Profile

The following procedure describes how to create a Location profile.

---

**Note** – The “walk” process that the reactive network performs during an initial profile creation only prompts you for those properties that are applicable, given the values that you entered previously.

---

For information about the `netcfg` subcommands, see “[netcfg Subcommands](#)” on page 35.

### 1 Initiate an `netcfg` interactive session.

```
$ netcfg
netcfg>
```

### 2 Create or select the location.

```
netcfg> create loc office
netcfg:loc:office>
```

In this example, the location `office` is created.

Creating the location automatically moves you into the profile scope for this location.

### 3 Set the appropriate properties for the location.

For information about the location properties, see [Table 2-2](#).

### 4 Display the profile configuration.

For example, the following output displays the properties for the location `office`:

```
netcfg:loc:office> list
LOC:office
  activation-mode          conditional-any
  conditions               "ncu ip:wpi0 is active"
  enabled                  false
  nameservices             dns
  nameservices-config-file "/etc/nsswitch.dns"
  dns-nameservice-configsrc dhcp
  ipfilter-config-file    "/export/home/test/wifi.ipf.conf"
```

### 5 Verify that the profile configuration is correct.

In the following example, the configuration for the location `office` is verified:

```
netcfg:loc:office> verify
All properties verified
```

The `verify` subcommand verifies your configuration and notifies if any required values are missing. You can verify your changes by using the `verify` subcommand explicitly when creating or modifying a profile.

### 6 When you complete the verification, commit the Location profile to persistent storage.

```
netcfg:loc:office> commit
Committed changes
```

The `commit` subcommand implicitly verifies your changes.

Alternatively, you can use the `end` subcommand to end the session, which also saves the profile configuration.

```
netcfg:loc:office> end
Committed changes
```

In interactive mode, changes are not saved to persistent storage until you commit them. When you use the `commit` subcommand, the entire profile is committed. To maintain the consistency of persistent storage, the `commit` operation also includes a verification step. If the verification fails, the `commit` operation also fails. If an implicit commit fails, you are given the option of ending or exiting the interactive session without committing the current changes. Alternatively, you can remain in the current scope and continue making changes to the profile.

---

**Note** – To cancel the changes that you made, use the `cancel` subcommand.

The `cancel` subcommand ends the current profile configuration without committing the current changes to persistent storage, then moves the interactive session up one level to the next higher scope.

---

## 7 Exit the interactive session.

```
netcfg> exit
$
```

### Example 2-3 Interactively Creating a Location Profile

In the following example, a location named `office` is created.

```
$ netcfg
netcfg> create loc office
Created loc 'office'. Walking properties ...
activation-mode (manual) [manual|conditional-any|conditional-all]> conditional-any
conditions> ncu ip:wpi0 is active
nameservices (dns) [dns|files|nis|ldap]>
nameservices-config-file ("/etc/nsswitch.dns")>
dns-nameservice-configsrc (dhcp) [manual|dhcp]>
nfsv4-domain>
ipfilter-config-file> /export/home/test/wifi.ipf.conf
ipfilter-v6-config-file>
ipnat-config-file>
ippool-config-file>
ike-config-file>
ipsecpolicy-config-file>
netcfg:loc:office> list
LOC:office
    activation-mode          conditional-any
    conditions                "ncu ip:wpi0 is active"
    enabled                   false
    nameservices              dns
    nameservices-config-file  "/etc/nsswitch.dns"
    dns-nameservice-configsrc dhcp
```

```

    ipfilter-config-file          "/export/home/test/wifi.ipf.conf"
netcfg:loc:office> verify
All properties verified
netcfg:loc:office> commit
Committed changes
netcfg:loc:office> end
netcfg> list
NCPs:
  DefaultFixed
  User
  Automatic
Locations:
  Automatic
  NoNet
  office
  DefaultFixed
WLANS:
  sunwifi
  ibahn
  gogoinflight
  admiralsclub
  hhonors
  sjcfreewifi
netcfg> exit
$

```

In this example, the following properties were specified for the office location:

- The activation-mode property was set to conditional-any, which resulted in a command prompt that enabled the conditions for activation to be specified. For information about the criteria and operations that can be used to construct the condition strings, see [Table 1-1](#).
- The condition for activation was specified as: ncu ip:wpi0 is active.

---

**Note** – The conditions property was required because the conditional-any property was specified in the previous step. If, for example, the manual property had been specified, the conditions property would not be required.

---

- The following default values were accepted by pressing Return:
  - nameservices
  - nameservices-config-file
  - dns-nameservice-configsrc
  - nfsv4-domain
- For the ipfilter-config-file property, the /export/home/test/wifi.ipf.conf file was specified.
- The following default values were accepted by pressing Return:
  - ipfilter-v6-config-file
  - ipnat-config-file
  - ippool-config-file

- `ike-config-file`
- `ipsecpolicy-config-file`
- The `list` subcommand was used to view the properties of the Location profile.
- The `verify` subcommand was used to perform a verification of the configuration.
- The `commit` subcommand was used to commit the changes to persistent storage.
- The `list` subcommand was used again to ensure that the new location was created correctly and that it contains the correct information.
- The `exit` subcommand was used to exit the `netcfg` interactive session.

## Creating an ENM Profile

ENMs enable you to specify when applications or scripts, for example, a VPN application, should perform their own network configuration external to the configuration specified in the NCP and Location profiles. For more information about ENMs, see [“Description of an ENM” on page 15](#).

---

**Note** – The system does not automatically recognize an application for which you might create an ENM. These applications must first be installed and then configured on your system before you can use the `netcfg` command to create an ENM for them.

---

To create an ENM, type the following command:

```
$ netcfg
netcfg> create enm my_enm
Created enm 'my_enm'. Walking properties ...
```

where `enm` is the ENM profile and `my_enm` is the object name.

The process of creating the ENM takes you to the profile scope for the newly created ENM, and automatically begins a walk of the properties in the newly created ENM. From the profile scope, you can set properties for the ENM that dictate when and how the ENM is enabled, as well as other conditions, including the ENM's start and stop method.

For further instructions about specifying ENM properties, see the [netcfg\(1M\)](#) man page.

The following table describes the properties that you might specify when creating or modifying an ENM.

TABLE 2-3 ENM Properties and Descriptions

Property Name	Description	Possible Values
<code>activation-mode</code>	Mode that is used to determine activation of an ENM.	<code>conditional-any</code> , <code>conditional-all</code> , <code>manual</code>

TABLE 2-3 ENM Properties and Descriptions (Continued)

Property Name	Description	Possible Values
conditions	If activation-mode is conditional - any or conditional - all, specifies the test to determine whether the ENM must be enabled.	A string or strings formatted as specified in the Table 1-1, if the property is used
start	(Optional) Absolute path to the script to be executed upon activation.	Path to script, if this property is used
stop	(Optional) Absolute path to the script to be executed upon deactivation.	Path to script, if this property is used
fmri	(Optional) FMRI (fault managed resource identifier) to be enabled upon ENM activation.  <b>Note</b> - Either an FMRI or a start script must be specified. If an FMRI is specified, both the start and stop properties are ignored.	Path to script

## ▼ How to Interactively Create an ENM Profile

The following procedure describes how to create an ENM profile by using `test-enm` as an example.

### 1 Initiate an `netcfg` interactive session.

```
$ netcfg
netcfg>
```

### 2 Create the ENM.

```
netcfg> create enm test-enm
Created enm 'test-enm'. Walking properties ...
activation-mode (manual) [manual|conditional-any|conditional-all]>
fmri> svc:/application/test-enm:default
start>
stop>
netcfg:enm:test-enm>
```

Creating the ENM automatically moves you into the profile scope for this ENM and walks the properties. Then, set the `fmri` property.

For information about ENM properties, see [Table 2-3](#).

### 3 Display the profile configuration.

```
netcfg:enm:test-enm> list
ENM:test-enm
  activation-mode    manual
  enabled            false
```

```

    fmri                "svc:/application/test-enm:default"
netcfg:enm:test-enm>

```

#### 4 Verify that the profile configuration is correct.

```

netcfg:enm:test-enm> verify
All properties verified

```

The `verify` subcommand verifies your configuration and notifies if any required values are missing. You can verify your changes by using the `verify` subcommand explicitly when creating or modifying a profile.

#### 5 When you complete the verification, commit the ENM profile to persistent storage.

```

netcfg:enm:test-enm> commit
Committed changes

```

The `commit` subcommand verifies the changes implicitly and then commits the changes.

Alternatively, you can use the `end` subcommand to end the session, which also saves the profile configuration.

```

netcfg:enm:test-enm> end
Committed changes

```

### Example 2-4 Interactively Creating an ENM Profile

In the following example, an ENM named `test-enm` is created in interactive mode.

```

$ netcfg
netcfg> create enm test-enm
Created enm 'testenm'. Walking properties ...
activation-mode (manual) [manual|conditional-any|conditional-all]>
fmri> svc:/application/test-app:default
start>
stop>
netcfg:enm:test-enm> list
ENM:test-enm
  activation-mode      manual
  enabled              false
  fmri                 "svc:/application/test-enm:default"
netcfg:enm:test-enm> verify
All properties verified
netcfg:enm:test-enm> end
Committed changes
netcfg> list
NCPs:
  DefaultFixed
  User
  Automatic
Locations:
  Automatic
  NoNet
  test-loc
  DefaultFixed
ENMs:

```

```

    test-enm
WLANs:
    sunwifi
    ibahn
    gogoinflight
    admiralsclub
    hhonors
    sjcfreewifi
netcfg> exit
$

```

In this example, an ENM named `test -enm` was created with the following property values:

- The default value (`manual`) for the `activation-mode` property was accepted by pressing the Return key.
- The SMF FMRI property `svc:/application/test-enm:default` was specified as the method to use for enabling and disabling the application.

Note that because an FMRI was specified, the `start` and `stop` method properties were bypassed.

- The `list` subcommand was used to view the properties of the ENM.
- The `verify` subcommand was used to ensure that the profile configuration is correct.
- The `end` subcommand was used to implicitly save the configuration.
- The `end` subcommand was used again to end the interactive session.

## Creating a Known WLAN Profile

Known WLAN profiles store information about wireless networks, enabling NCPs to automatically configure wireless interfaces based on the configuration information of wireless networks that you connect to from your system. For more information about known WLANs, see [“Description of a Known WLAN” on page 16](#).

To create a WLAN object, type the following command:

```

$ netcfg
netcfg> create wlan mywifi
Created wlan 'mywifi'. Walking properties ...

```

where `wlan` is the WLAN object and `mywifi` is the object name.

The process of creating a WLAN object takes you to the profile scope for the newly created WLAN, and automatically begins a walk of the properties in the newly created WLAN. From here, you can set properties for the WLAN that define its configuration.

The following table describes the properties that you might specify when creating or modifying WLANs.

TABLE 2-4 Known WLAN Properties and Data Types

Known WLAN Property	Data Type for Property
name	ESSID (wireless network name).
bssids	Base Station IDs of WLANs that your system has connected to while connected to the specified WLAN.
priority	WLAN connection preference (lower values are preferred).
keyslot	Slot number (1–4) in which the WEP key is contained.
keyname	Name of the WLAN key that is created by using the <code>dladm create-secobj</code> command.  For more information about the <code>dladm</code> command, see <a href="#">Chapter 3, “Working With Datalinks,” in <i>Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1</i></a> .
security-mode	The type of encryption key in use. The type must be <code>none</code> , <code>wep</code> , or <code>wpa</code> .

## ▼ How to Interactively Create a Known WLAN Profile

The following procedure describes how to create a known WLAN profile by using `mywifi` as an example.

### 1 Initiate an `netcfg` interactive session.

```
$ netcfg
netcfg>
```

### 2 Create the WLAN.

```
netcfg> create wlan mywifi
Created wlan 'mywifi'. Walking properties ...
priority (0)> 100
bssids>
keyname> mywifi-key
keyslot>
security-mode [none|wep|wpa]> wpa
netcfg:wlan:mywifi>
```

Creating the WLAN automatically moves you into the profile scope for this WLAN and walks the properties.

For information about the known WLAN properties, see [Table 2-4](#).

### 3 Display the profile configuration.

```
netcfg:wlan:mywifi> list known wlan:mywifi
  priority          100
  keyname           "mywifi-key"
  security-mode     wpa
netcfg:wlan:mywifi>
```

**4 Verify that the profile configuration is correct.**

```
netcfg:wlan:mywifi> verify
All properties verified
```

The `verify` subcommand verifies your configuration and notifies if any required values are missing. You can verify your changes by using the `verify` subcommand explicitly when creating or modifying a profile.

**5 When you complete the verification, end the session.**

```
netcfg:wlan:mywifi> end
Committed changes
```

The `end` subcommand ends the session and also saves the profile configuration.

**6 Exit the interactive session.**

```
netcfg> exit
```

**Example 2-5 Interactively Creating a WLAN Profile**

In the following example, a WLAN object named `mywifi` is created.

This example assumes that a secure object named `mywifi-key`, which contains the key that is specified by the `keyname` property for the WLAN `mywifi`, is created *before* adding the WLAN.

The priority number can change as other WLANs are added or removed. Note that no two WLANs can be assigned the same priority number. Lower numbers indicate a higher priority, in terms of which WLANs are preferred. In this example, the WLAN is assigned the priority number 100 to ensure that it has a lower priority than any other known WLANs.

When the `list` subcommand is used at the end of the procedure, the new WLAN is added to the bottom of the list, indicating that it has the lowest priority of all the existing known WLANs. If the WLAN was assigned a priority number of zero (0), which is the default, it would have been displayed at the top of the list, indicating the highest priority. Subsequently, the priority of all other existing WLANs would have shifted down in priority and would have been displayed in the list after the newly added WLAN.

```
$ netcfg
netcfg> create wlan mywifi
Created wlan 'mywifi'. Walking properties ...
priority (0)> 100
bssids>
keyname> mywifi-key
keyslot>
security-mode [none|wep|wpa]> wpa
netcfg:wlan:mywifi> list
known wlan:mywifi
    priority          100
    keyname            "mywifi-key"
    security-mode      wpa
netcfg:wlan:mywifi> verify
```

```
All properties verified
netcfg:wlan:mywifi> end
Committed changes
netcfg> list
NCPs:
    DefaultFixed
    User
    Automatic
Locations:
    Automatic
    NoNet
    test-loc
    DefaultFixed
ENMs:
    test-enm
WLANS:
    sunwifi
    ibahn
    gogoinflight
    admiralsclub
    hhonors
    sjcfreewifi
    mywifi
netcfg> exit
$
```

## Setting and Changing Property Values for a Profile

Property values for new and existing user-defined profiles are set or modified by using the `netcfg` command with the `set` subcommand. This subcommand can be used in interactive mode or in command-line mode. If a property value is set or changed in command-line mode, the change is immediately committed to persistent storage.

---

**Note** – You can modify the `DefaultFixed` location by directly changing the relevant SMF properties or by using the tools provided by a given subsystem, such as `nscfg`. The property changes are directly saved in the SMF repository and are propagated to the network repository only when the `DefaultFixed` location is disabled. You can view the modified `DefaultFixed` location properties by using the `netcfg` command that accesses the network repository, only when the `DefaultFixed` location is disabled. The property values stored in the SMF repository are the authoritative values when the `DefaultFixed` location is active.

---

The syntax for the `set` subcommand is as follows:

```
$ netcfg set prop-name=value1[,value2...]
```

For information about the `netcfg` subcommands, see [“netcfg Subcommands” on page 35](#).

If you need to retrieve a specific property value, use the `netcfg get` command. For more information, see [“Obtaining the Value of a Specific Property” on page 65](#).

**EXAMPLE 2-6** Setting Property Values in `net cfg` Command-Line Mode

If you are using the `net cfg` command to set a property value in command-line mode, multiple subcommands can be typed on the command-line.

For example, to set the `mtu` property for a link NCU named `net1`, you would type the following command:

```
$ netcfg "select ncp User; select ncu phys net1; set mtu=1492"
```

In this example, the `select` subcommand is used to select the top-level profile, then again to select the NCU that contains the `mtu` property value that is modified.

From the command-line, multiple values can be set for a given property at the same time. When setting multiple values, each value must be separated by a comma (,). If individual values for a specified property also contain a comma, the comma that is part of the property value must be preceded by a backslash (\). Commas within properties that only have a single value are not interpreted as delimiters and therefore do not need to be preceded by a backslash.

In the following example, the `ip-version` property value for the NCU, `myncu`, in the NCP `User` is set:

```
$ netcfg "select ncp User; select ncu ip myncu; set ip-version=ipv4,ipv6"
```

## ▼ How to Interactively Set Property Values

When interactively setting property values, you must first select a profile at the current scope, which moves the interactive session into that profile's scope. From this scope, you can select the object whose property you want to modify. The selected profile is then loaded into memory from persistent storage. At this scope, you can modify the profile or its properties.

The following procedure describes how to set property values by taking an example to set the `ipfilter-config-file` property of the location `test-loc`.

### 1 Initiate an `net cfg` interactive session.

```
$ netcfg
netcfg>
```

### 2 (Optional) List the profiles.

```
netcfg> list
NCPs:
  DefaultFixed
  Automatic
  User
Locations:
  Automatic
  NoNet
  test-loc
  DefaultFixed
```

**3 Select the profile or configuration object that needs to be set.**

```
netcfg> select loc test-loc
```

**4 (Optional) List the configuration information of the selected profile.**

```
netcfg:loc:test-loc> list
LOC:test-loc
  activation-mode      manual
  enabled              false
  nameservices         dns
  dns-nameservice-configsrc  dhcp
  nameservices-config-file  "/etc/nsswitch.dns"
```

**5 Set the property value.**

```
netcfg:loc:test-loc> set ipfilter-config-file = /path/to/ipf-file
```

**6 (Optional) List the configuration information to verify the setting.**

```
netcfg:loc:test-loc> list
LOC:test-loc
  activation-mode      manual
  enabled              false
  nameservices         dns
  dns-nameservice-configsrc  dhcp
  nameservices-config-file  "/etc/nsswitch.dns"
  ipfilter-config-file    "/path/to/ipf-file"
```

**7 End the session.**

```
netcfg:loc:test-loc> end
Committed changes
```

The end subcommand saves the change and ends the session.

**8 Exit the interactive session.**

```
netcfg> exit
```

**Example 2-7 Interactively Setting Property Values for a Profile**

```
$ netcfg
netcfg> select ncp User
netcfg:ncp:User> select ncu ip iw0
netcfg:ncp:User:ncu:iw0> set ipv4-default-route = 172.24.1.1
```

In the above example, the `ipv4-default-route` property of the NCP User is set. For more information about configuring an IPv4 router, see “Configuring an IPv4 Router” in *Configuring and Administering Oracle Solaris 11.1 Networks*.

In the following example, the `mtu` property of the NCU `net0` in the NCP User is modified interactively:

```
$ netcfg
netcfg> select ncp User
netcfg:ncp:User> select ncu phys net0
```

```

netcfg:ncp:User:ncu:net0> list
NCU:net0
  type          link
  class         phys
  parent       "User"
  enabled       true
  activation-mode prioritized
  priority-mode exclusive
  priority-group 1
netcfg:ncp:User:ncu:net0> set mtu = 5000
netcfg:ncp:User:ncu:net0> list
NCU:net0
  type          link
  class         phys
  parent       "User"
  enabled       true
  activation-mode prioritized
  priority-mode exclusive
  priority-group 1
  mtu          5000
netcfg:ncp:User:ncu:net0> commit
Committed changes
netcfg:ncp:User:ncu:net0> exit
$

```

## Listing Profile Configuration Information on a System

The `netcfg` command can be used with the `list` subcommand to list all of the profiles, property-value pairs, and resources that exist at the current or specified scope. Use the `list` subcommand to query the system for general information about all profiles or to retrieve specific information about a particular profile. The `list` subcommand can be used in either interactive mode or command-line mode.

For information about the `netcfg` subcommands, see [“netcfg Subcommands” on page 35](#).

If you need to obtain information about profiles and their current state, use the `netadm` command with the `list` subcommand. For more information, see [“Displaying the Current State of a Profile” on page 76](#).

## Listing All of the Profile Configuration Information on a System

The `netcfg list` command lists all of the system-defined and user-defined profiles on a system. Note that using the `list` subcommand without any options displays all of the top-level profiles that are on a system. The command does not list the state of each profile. To display a list of the profiles and their state (online or offline), use the `netadm list` command.

You can list all of the top-level profiles on a system by using the `list` subcommand.

```
$ netcfg list
NCPs:
    DefaultFixed
    Automatic
    User
Locations:
    Automatic
    NoNet
    home
    office
    DefaultFixed
ENMs:
    myvpn
    testenm
WLANs:
    workwifi
    coffeeshop
    homewifi
```

In this example, the following profiles are listed:

- NCPs

The following NCPs are listed:

- DefaultFixed NCP – System-defined fixed profile
- Automatic NCP – System-defined reactive profile
- User NCP – User-defined reactive NCP

- Locations

The following Location profiles are listed:

- System-defined locations:
  - Automatic
  - NoNet
  - DefaultFixed
- User-defined reactive locations:
  - home
  - office

- ENMs

The following ENMs are listed:

- myvpn – An ENM for an installed and configured VPN application
- testenm – A test ENM for testing the working of ENMs

- WLANs

The following WLANs are listed:

- workwifi – WLAN for work
- coffeeshop – WLAN for the local coffee shop
- homewifi – WLAN for the user's home wireless network

---

**Note** – Only user-defined profiles can be created, modified, or removed.

---

## Listing All Property Values for a Specific Profile

Use the `netcfg` command with the `list` subcommand to list all of the property values for a specified profile.

The syntax for the `list` subcommand is as follows:

```
$ netcfg list [ object-type [ class ] object-name ]
```

**EXAMPLE 2-8** Listing All of the Property Values of an NCU

For example, to list all of the property values for an IP NCU in the User NCP, you would type the following command:

```
$ netcfg "select ncp User; list ncu ip net0"
NCU:net0
    type                interface
    class               ip
    parent              "User"
    enabled             true
    ip-version          ipv4
    ipv4-addrsrc       dhcp
    ipv6-addrsrc       dhcp,autoconf
```

**EXAMPLE 2-9** Listing All of the Property Values of an ENM

In the following example, all of the properties for an ENM named `myenm` are listed.

```
$ list enm myenm
ENM:myenm
activation-mode manual
enabled true
start "/usr/local/bin/myenm start"
stop "/bin/alt_stop"
```

In this example, the output of the `list` subcommand displays the following information:

- The `activation-mode` property for this ENM is set to `manual`.
- The ENM is enabled.
- The `start` and `stop` method properties have been specified, rather than using an FMRI.

## Obtaining the Value of a Specific Property

You can use the `netcfg` command with the `get` subcommand to obtain and list the specific value for a specified property. This subcommand can be used in either interactive mode or command-line mode.

The syntax for the `get` subcommand is as follows:

```
netcfg get [ -V ] prop-name
```

To obtain the value of the `ip-version` property of an NCU named `myncu`, which is a part of the User NCP, you would type the following command. For example:

```
$ netcfg "select ncp User; select ncu ip myncu; get -V ip-version"  
ipv4
```

If the `-V` option is used with the `get` subcommand, only the property value is displayed, as shown here:

```
netcfg:ncp:User:ncu:net0> get -V activation-mode  
manual
```

Otherwise, both the property and its value are displayed. For example:

```
netcfg:ncp:User:ncu:net0> get activation-mode  
activation-mode      manual
```

## ▼ How to Interactively Obtain a Single Property Value

This procedure describes how to obtain and list a single property value by using the `netcfg get` command while in the `netcfg` interactive mode. In this particular procedure, some of the examples show how to obtain a single property value for an NCU in the User NCP. These examples are used for demonstration purposes *only*. The information that you provide when using this command would vary, depending on the profile and the property value that you attempt to retrieve.

If you want to view all of the property values for a profile, you can alternatively use the `walkprop` subcommand. This subcommand walks you through all of the properties of a given profile, one at a time, enabling you to modify one or all of the profile's properties. For more information, see [“Viewing and Changing Property Values by Using the `walkprop` Subcommand”](#) on page 68.

### 1 Initiate an `netcfg` interactive session.

```
$ netcfg  
netcfg>
```

### 2 Select the profile or configuration object that contains the property value that you want to obtain.

```
netcfg> select object-type [ class ] object-name
```

---

**Note** – The `class` parameter is applicable *only* if you are selecting an NCU. Also, the `class` parameter must be specified if both the `phys` and `ip` class NCU share the same name. However, if the NCU name is unique, the `class` parameter is not required.

---

For example, to select the User NCP, you would type:

```
netcfg> select NCP User
```

In this example, selecting the User NCP moves the interactive session into the selected object's scope.

### 3 (Optional) Display the components of the profile.

```
netcfg:ncp:User> list
ncp:User
  management-type    reactive
NCUs:
  phys    net0
  ip      net0
```

### 4 Select the object that contains the property value that you want to obtain.

In the following example, the link (`phys`) NCU `net0` in the User NCP is selected:

```
netcfg:ncp:User> select ncu phys net0
```

Selecting the NCU `net0` moves the interactive session to that object's scope and loads the current properties for the NCU from memory.

### 5 Obtain the specified property value.

```
netcfg:ncp:User:ncu:net0> get property-value
```

For example, to obtain the value of the `activation-mode` property, you would type:

```
netcfg:ncp:User:ncu:net0> get activation-mode
activation-mode    manual
```

**Next Steps** At this point, you can set a new value for the property by using the `set` subcommand, or you can exit the interactive session without making any changes. Note that if you modify a property value while in interactive mode, you must use the `commit` or `exit` subcommand to save your changes. For information about setting a property value in `netcfg` interactive mode, see [“Setting and Changing Property Values for a Profile” on page 60](#).

## Viewing and Changing Property Values by Using the walkprop Subcommand

The `walkprop` subcommand can be used interactively to view the properties of a profile. This subcommand “walks” you through a profile, one property at a time, displaying the name and current value for each property. An interactive command prompt is also displayed, that you can use to change the current value of the specified property. The delimiter for multi-valued properties is a comma (,). If an individual value for a given property contains a comma, it must be preceded with a backslash (\). Commas within properties that only have a single value are not interpreted as delimiters and do not need to be preceded by a backslash. For information about the `netcfg` subcommands, see “[netcfg Subcommands](#)” on page 35.

---

**Note** – The `walkprop` subcommand is meaningful when used in interactive mode only.

---

### EXAMPLE 2-10 Viewing and Changing Property Values for a Specific Profile

In the following example, the `activation-mode` property for the location `test-loc` is viewed and then changed by using the `walkprop` subcommand. Note that when using the `walkprop` subcommand, you do not need to use the `set` subcommand to set the property value.

```
$ netcfg
netcfg> select loc test-loc
netcfg:loc:test-loc> list
loc:test-loc
    activation-mode          manual
    enabled                  false
    nameservices             dns
    nameservices-config-file "/etc/nsswitch.dns"
    dns-nameservice-configsrc dhcp
    nfsv4-domain             "Central.example.com"
netcfg:loc:test-loc> walkprop
activation-mode (manual) [manual|conditional-any|conditional-all]> conditional-all
conditions> advertised-domain is example.com
nameservices (dns) [dns|files|nis|ldap]>
nameservices-config-file ("/etc/nsswitch.dns")>
dns-nameservice-configsrc (dhcp) [manual|dhcp]>
nfsv4-domain ("Central.example.com")>
ipfilter-config-file>
ipfilter-v6-config-file>
ipnat-config-file>
ippool-config-file>
ike-config-file>
ipsecpolicy-config-file>
netcfg:loc:test-loc> list
loc:test-loc
    activation-mode          conditional-all
    conditions               "advertised-domain is example.com"
    enabled                  false
    nameservices             dns
    nameservices-config-file "/etc/nsswitch.dns"
    dns-nameservice-configsrc dhcp
```

EXAMPLE 2-10 Viewing and Changing Property Values for a Specific Profile (Continued)

```

nfsv4-domain                "Central.example.com"
netcfg:loc:test-loc> commit
Committed changes
netcfg:loc:test-loc> end
netcfg> exit
$

```

---

**Note** – Only relevant properties are walked. For example, if the `ipv4-addrsrc` property is set to `static`, the `ipv4-addr` property is included in the walk. However, if `ipv4-addrsrc` is set to `dhcp`, the `ipv4-addr` property is not walked.

---

## Enabling and Disabling Profiles

User-defined NCUs, Location profiles, and ENMs all have `activation-mode` properties. The `activation-mode` property is set when you create or modify a profile by using the `netcfg` command. For more information, see “[Profile Activation Policy](#)” on page 17. NCPs do not have an `activation-mode` property. All NCPs are manually enabled. The possible values for the `activation-mode` property of different profile types is shown in the following table:

TABLE 2-5 `activation-mode` Property Values

Profile Type	<code>activation-mode</code> Value
NCU	manual or prioritized
Location	manual, conditional-any, conditional-all, or system
ENM	manual, conditional-any, or conditional-all

To manually enable or disable (activate and deactivate) a profile or configuration object, use the `netadm enable` command or the `netadm disable` command.

At any given time, there must be one active NCP and one active Location profile on the system. The active NCP remains active until you enable a different NCP. Enabling a different NCP implicitly disables the currently active NCP. You cannot explicitly disable the NCP that is currently active on a system. If you explicitly disable the currently active NCP, the basic network connectivity of the system shuts down.

You can also manually enable and disable individual NCUs that are a part of the currently active NCP and whose `activation-mode` property is set to `manual`. If the NCU class is not specified, all of the NCUs with that name (one link and one interface NCU) are enabled or disabled.

By default, the system chooses the best Location profile to enable. The system selects a location from the set of locations with the `system` or `conditional` `activation-mode`. However, the user can at any time override the system's selection by manually enabling any location, regardless of the location's activation mode. When you enable a Location profile manually, the system does not change the active location automatically. The automatic selection of a location by the system is disabled. You must explicitly disable the manually enabled location to restore the conditional location selection by the system.

ENMs can have a `manual` or `conditional` `activation-mode` property. If you set the `activation-mode` property to `conditional`, the system enables or disables the ENM based on the specified conditions. For information about the criteria and operations that can be used to construct the condition strings, see [Table 1-1](#). If you set `activation-mode` to `manual`, you can enable or disable the ENM by using the `netadm` command. There are no constraints on ENM activation. Zero or more ENMs can be active on a system at any given time. Enabling or disabling an ENM has no effect on other currently active ENMs.

Enabling and disabling of objects is performed asynchronously. Therefore, the request to enable or disable might succeed, while the action itself fails. Such failure is reflected in the profile's state, which changes to `maintenance`, indicating that the last action taken on the profile failed. For information about displaying the state of profiles, see [“Displaying Information About Profile States” on page 75](#).

#### EXAMPLE 2-11 Enabling a Profile

In the following example, a location named `office` is enabled:

```
$ netadm enable -p loc office
```

Similarly, an NCP named `User` is enabled:

```
$ netadm enable -p ncp User
Enabling ncp 'User'
.
.
.
```

Note that when you specify profile names, the `netadm` command is case-insensitive.

#### EXAMPLE 2-12 Disabling a Link NCU

In the following example, a link NCU named `net1` is disabled:

```
$ netadm disable -p ncu -c phys net1
```

#### EXAMPLE 2-13 Switching Profiles

In the following example, the fixed profile (`DefaultFixed`) is enabled:

```
$ netadm enable -p ncp DefaultFixed
```

**EXAMPLE 2-13** Switching Profiles *(Continued)*

Similarly, the Automatic NCP is enabled:

```
$ netadm enable -p ncp Automatic
```

For more information about the `netadm` command, see the [netadm\(1M\)](#) man page.



# Administering Your Reactive Network Configuration (Tasks)

---

This chapter describes how to administer these profiles by using the `netadm` command: NCPs, locations, ENMs, and known WLANs. You can manage NCUs, which are the individual configuration objects that make up an NCP by using the `netadm` command. You can also interact with the daemon, `nwamd`, in the absence of the network administration GUI, by using the `netadm` command. This chapter also describes how to export and remove user-defined profiles by using the `netcfg` command.

For more information about using the `netadm` command see the [netadm\(1M\)](#) man page. For more information about using the `netcfg` command, see the [netcfg\(1M\)](#) man page.

The following topics are covered in this chapter:

- “Switching Between Fixed and Reactive Network Configurations” on page 74
- “Displaying Information About Profile States” on page 75
- “Exporting and Restoring a Profile Configuration” on page 77
- “Removing Profiles” on page 81
- “Performing a Wireless Scan and Connecting to Available Wireless Networks” on page 83
- “Troubleshooting Reactive Network Configuration Issues” on page 84

For information about creating and configuring profiles, modifying profiles, listing profiles, and enabling and disabling profiles, see [Chapter 2, “Creating and Configuring Reactive Network Profiles \(Tasks\)”](#).

For information about how to interact with the reactive network configuration and how to manage your network configuration from the desktop by using the network administration GUI, see [Chapter 4, “Using the Network Administration Graphical User Interface.”](#)

For overview information about reactive network configuration, see [Chapter 1, “Reactive Network Configuration \(Overview\).”](#)

# Switching Between Fixed and Reactive Network Configurations

Network configuration management is profile-based and involves switching between the two types of network configuration: fixed and reactive. To switch between the fixed and reactive networks configurations, enable the appropriate NCP. For fixed network configuration, enable the `DefaultFixed` NCP. For reactive network configuration, enable the `Automatic` NCP or a user-defined NCP. For more information about fixed network configuration, see [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

## ▼ How to Switch From Reactive Network Configuration to Fixed Network Configuration

If you prefer fixed network configuration management, you can enable the `DefaultFixed` NCP, as explained in the following procedure.

- 1 **Become the root user.**

- 2 **Enable the `DefaultFixed` NCP.**

```
$ netadm enable -p ncp DefaultFixed
```

- 3 **Verify that the `network/physical:default` service has restarted and is online.**

```
$ svcs -xv network/physical:default
svc:/network/physical:default (physical network interface configuration)
  State: online since Thu Jun 21 17:30:25 2012
    See: man -M /usr/share/man -s 1M ipadm
    See: man -M /usr/share/man -s 5 nwam
    See: man -M /usr/share/man -s 1M dladm
    See: /var/svc/log/network-physical:default.log
  Impact: None.
$
```

- 4 **Verify that the `DefaultFixed` NCP is active.**

```
$ netadm list
TYPE          PROFILE          STATE
ncp           DefaultFixed    online
ncp           ncp1             disabled
ncp           Automatic        disabled
loc           Automatic        offline
loc           NoNet            offline
loc           User             disabled
loc           DefaultFixed    online
$
```

## ▼ How to Switch From Fixed Network Configuration to Reactive Network Configuration

To switch back to the reactive network configuration from the fixed network configuration, enable the network configuration profile that you want to use.

- 1 Become the root user.
- 2 Enable an NCP, for example, Automatic.
 

```
$ netadm enable -p ncp Automatic
```
- 3 Verify that the network/physical:default service has restarted and is online.

```
$ svcs -xv network/physical:default
svc:/network/physical:default (physical network interface configuration)
State: online since Thu Jun 21 15:30:25 2012
See: man -M /usr/share/man -s 1M ipadm
See: man -M /usr/share/man -s 5 nwam
See: man -M /usr/share/man -s 1M dladm
See: /var/svc/log/network-physical:default.log
Impact: None.
$
```

- 4 Check the state of the NCP and the other reactive (NWAM-managed) profiles.

```
$ netadm list -x
TYPE          PROFILE          STATE          AUXILIARY STATE
ncp           DefaultFixed    disabled      disabled by administrator
ncp           Automatic        online        active
ncu:phys     net0             online        interface/link is up
ncu:ip       net0             online        interface/link is up
ncu:phys     net1             offline       interface/link is down
ncu:ip       net1             offline       conditions for activation are unmet
ncp          User             disabled      disabled by administrator
loc          Automatic        online        active
loc          NoNet            offline       conditions for activation are unmet
loc          DefaultFixed    offline       conditions for activation are unmet
$
```

## Displaying Information About Profile States

You can use the `netadm` command with the `list` subcommand to display all of the available profiles on a system and their current state, or to display a specific profile and its state. For information about the `netadm` subcommands, see [“netadm Subcommands” on page 37](#).

The syntax for the `list` subcommand is as follows:

```
netadm list [ -p profile-type ] [ -c ncu-class ] [ profile-name ]
```

For example, to display all of the profiles on a system and their state, you would type the following command:

```

$ netadm list
TYPE      PROFILE      STATE
ncp       DefaultFixed disabled
ncp       ncp1         disabled
ncp       Automatic    online
ncu:phys  net0         online
ncu:phys  net1         offline
ncu:ip    net0         online
ncu:ip    net1         offline
loc       Automatic    online
loc       NoNet        offline
loc       User         disabled
loc       DefaultFixed offline
$
    
```

In this example, the current state is displayed for every system-defined and user-defined profile that is on the system. Note that the `list` subcommand displays the enabled NCP and all of the NCUs that make up that particular NCP.

## Displaying the Current State of a Profile

The profile type and NCU class can be included in the command syntax to identify a specific profile. If only a profile type is provided, all of the profiles that are of that type are displayed. If a profile is specified by name, the current state of that profile is displayed. If the profile name is not unique, all of the profiles with that name are listed.

### EXAMPLE 3-1 Displaying the Current State of a Specified Profile

The following example lists the current state of profiles named `Automatic`, which has been specified by name.

```

$ netadm list Automatic
TYPE      PROFILE      STATE
ncp       Automatic    online
ncu:ip    net1         offline
ncu:phys  net1         offline
ncu:ip    net0         online
ncu:phys  net0         online
loc       Automatic    online
$
    
```

In the following example, the `list` subcommand is used with the `-p` option to display all of the locations that are currently on the system.

```

$ netadm list -p loc
TYPE      PROFILE      STATE
loc       office       disabled
loc       NoNet        offline
loc       Automatic    online
$
    
```

In the following example, the `list` subcommand is used with the `-c` option to display all of the interface NCUs in the active NCP.

**EXAMPLE 3-1** Displaying the Current State of a Specified Profile *(Continued)*

```
$ netadm list -c ip
TYPE      PROFILE      STATE
ncu:ip    net0         online
ncu:ip    net1         disabled
$
```

## Displaying Auxiliary State Values

The auxiliary state of a profile provides an explanation about why a given profile is online or offline (enabled or disabled). To list auxiliary state values, use the `-x` option with the `list` subcommand, as shown in the following example:

```
$ netadm list -x
TYPE      PROFILE      STATE      AUXILIARY STATE
ncp       DefaultFixed disabled    disabled by administrator
ncp       ncp1         disabled    disabled by administrator
ncp       Automatic    online      active
ncu:phys  net0         online      interface/link is up
ncu:phys  net1         offline     interface/link is down
ncu:ip    net0         online      interface/link is up
ncu:ip    net1         offline     conditions for activation are unmet
loc       Automatic    offline     conditions for activation are unmet
loc       NoNet        offline     conditions for activation are unmet
loc       office       online      active
loc       DefaultFixed offline     conditions for activation are unmet
$
```

Auxiliary state values vary, depending on the profile type. For detailed information about auxiliary states, see the [nwamd\(1M\)](#) man page.

## Exporting and Restoring a Profile Configuration

You can use the `export` subcommand of the `netcfg` command to save and restore profile configurations. Exporting a profile can be useful for system administrators who are responsible for maintaining multiple servers that require identical network configurations. The `export` subcommand can be used in either interactive mode or command-line mode. Alternatively, you can use the command in command-file mode to specify a file as the output of the command.

---

**Note** – The `export` feature is of limited use for some configurations. You can only export or restore configuration objects that are initially created by the `netcfg` command. You cannot export the configuration objects of an NCP that were created by using the `dladm` or `ipadm` command, such as aggregations or IPMP groups. Also, you cannot export or restore the `DefaultFixed` NCP and Location profiles.

---

The command syntax for the `export` subcommand is as follows:

```
$ netcfg export [ -d ] [ -f output-file ] [ object-type [ class ] object-name ]
```

where *output-file* is the output file name, *object-type* is the profile type, *class* is the NCU class, and *object-name* is the profile name.

For information about the `netcfg` subcommands, see [“netcfg Subcommands” on page 35](#).

---

**Note** – The `-d` and `-f` options of the `export` subcommand can be used independently of each other. The `-f` option prints the current configuration at the current or specified scope to standard output, or to a file specified. The `-d` option generates a `destroy -a` as the first line of output.

---

#### EXAMPLE 3-2 Exporting a Profile Configuration in `netcfg` Interactive Mode

In the following example, the `export` subcommand of the `netcfg` command is used to display a system's profile configuration onscreen.

```
$ netcfg
netcfg> export
create ncp "User"
create ncu ip "net2"
set ip-version=ipv4
set ipv4-addrsrc=dhcp
set ipv6-addrsrc=dhcp,autoconf
end
create ncu phys "net2"
set activation-mode>manual
set mtu=5000
end
create ncu phys "wpi2"
set activation-mode=prioritized
set priority-group=1
set priority-mode=exclusive
set mac-address="13:10:73:4e:2"
set mtu=1500
end
end
create loc "test"
set activation-mode>manual
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfsv4-domain="domainl.example.com"
end
create loc "test-loc"
set activation-mode=conditional-all
set conditions="system-domain is example.com"
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfsv4-domain="domain.example.com"
end
create enm "myenm"
set activation-mode=conditional-all
```

**EXAMPLE 3-2** Exporting a Profile Configuration in `netcfg` Interactive Mode (Continued)

```

set conditions="ip-address is-not-in-range 10.2.3.4"
set start="/my/start/script"
set stop="/my/stop/script"
end
create wlan "mywlan"
set priority=0
set bssids="0:13:10:73:4e:2"
end
netcfg> end
$

```

**EXAMPLE 3-3** Exporting a Profile Configuration in `netcfg` Interactive Mode With the `-d` Option

In the following example, the `-d` option is used with the `export` subcommand. The `-d` option adds the `destroy -a` command as the first line of the `netcfg export` output.

```

$ netcfg
netcfg> export -d
destroy -a
create ncp "User"
create ncu ip "net2"
set ip-version=ipv4
set ipv4-addrsrc=dhcp
set ipv6-addrsrc=dhcp,autoconf
end
create ncu phys "net2"
set activation-mode=manual
set mtu=5000
end
create ncu phys "wpi2"
set activation-mode=prioritized
set priority-group=1
set priority-mode=exclusive
set mac-address="13:10:73:4e:2"
set mtu=1500
end
end
create loc "test"
set activation-mode=manual
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfsv4-domain="domain.example.com"
end
create loc "test-loc"
set activation-mode=conditional-all
set conditions="system-domain is example.com"
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfsv4-domain="domain.example.com"
end
create enm "myenm"
set activation-mode=conditional-all
set conditions="ip-address is-not-in-range 10.2.3.4"

```

**EXAMPLE 3-3** Exporting a Profile Configuration in net cfg Interactive Mode With the -d Option  
(Continued)

```

set start="/my/start/script"
set stop="/my/stop/script"
end
create wlan "mywlan"
set priority=0
set bssids="0:13:10:73:4e:2"
end
netcfg> end
$

```

**EXAMPLE 3-4** Exporting a Profile Configuration in net cfg Command-File Mode

In the following example, the configuration information for the User NCP is written to a file by using the net cfg export command with the -f option. The -f option writes the output to a new file named user2. The -d option adds the dest roy -a command as the first line of the netcfg export output.

```

$ netcfg export -d -f user2 ncp User

$ ls -al
drwx----- 3 root    root      4 Oct 14 10:53 .
drwxr-xr-x 37 root    root     40 Oct 14 10:06 ..
-rw-r--r-- 1 root    root    352 Oct 14 10:53 user2
$

$ cat user2
destroy -a
create ncp "User"
create ncu ip "net2"
set ip-version=ipv4
set ipv4-addrsrc=dhcp
set ipv6-addrsrc=dhcp,autoconf
end
create ncu phys "net2"
set activation-mode=manual
set mtu=5000
end
create ncu phys "wpi2"
set activation-mode=prioritized
set priority-group=1
set priority-mode=exclusive
set mac-address="13:10:73:4e:2"
set mtu=1500
end
end
create loc "test"
set activation-mode=manual
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfvsv4-domain="domain.example.com"

```

EXAMPLE 3-4 Exporting a Profile Configuration in net cfg Command-File Mode (Continued)

```

end
create loc "test-loc"
set activation-mode=conditional-all
set conditions="system-domain is example.com"
set nameservices=dns
set nameservices-config-file="/etc/nsswitch.dns"
set dns-nameservice-configsrc=dhcp
set nfsv4-domain="domain.example.com"
end
create enm "myenm"
set activation-mode=conditional-all
set conditions="ip-address is-not-in-range 10.2.3.4"
set start="/my/start/script"
set stop="/my/stop/script"
end
create wlan "mywlan"
set priority=0
set bssids="0:13:10:73:4e:2"
end
$

```

## Restoring a User-Defined Profile

You can restore an exported configuration by using the net cfg command with the -f option, as follows:

```
$ netcfg [ -f ] profile-name
```

For example:

```
$ netcfg -f user2
```

This command executes the command file that contains the exported configuration.

## Removing Profiles

You can remove all user-defined profiles or a specified user-defined profile from memory and persistent storage by using the netcfg destroy -a command.

---

**Note** – You cannot remove system-defined profiles. System-defined profiles include the Automatic and DefaultFixed NCPs and the NoNet, Automatic, and DefaultFixed Location profiles.

---

The syntax for the destroy subcommand is as follows:

```
netcfg destroy [ -a | object-type [ class ] object-name]
```

For information about the `netcfg` subcommands, see “[netcfg Subcommands](#)” on page 35.

---

**Note** – At least one profile must be active on the system at all times. Make sure that you enable the Automatic NCP before using the `destroy -a` command to avoid in-use errors when removing user-defined profiles.

---

**EXAMPLE 3-5** Removing a Specific User-Defined Profile by Using `netcfg` Command-Line Mode

To remove a specific user-defined profile on the system, for example, the NCP named `User`, type the following command:

```
$ netcfg destroy ncp User
```

The `destroy` subcommand can also be used to remove NCUs from an existing NCP. In the following example, an interface NCU with the name `net1` is removed from the user-defined NCP.

```
$ netcfg "select ncp User; destroy ncu ip net1"
```

To confirm that a profile has been removed, use the `list` subcommand, as shown here:

```
$ netcfg
netcfg> select ncp User
netcfg:ncp:User> list
ncp:User
      management-type    reactive
NCUs:
      phys    net1
netcfg:ncp:User> exit
$
```

**EXAMPLE 3-6** Removing a Specific User-Defined Profile by Using `netcfg` Interactive Mode

In the following example, an IP NCU named `net2` is removed.

```
$ netcfg list
NCPs:
      DefaultFixed
      Automatic
      User
Locations:
      Automatic
      NoNet
      test
      test-loc
      DefaultFixed
$ netcfg
netcfg> select ncp User
netcfg:ncp:User> list
ncp:User
      management-type    reactive
NCUs:
```

**EXAMPLE 3-6** Removing a Specific User-Defined Profile by Using `netcfg` Interactive Mode  
(Continued)

```

        phys    net2
        ip      net2
netcfg:ncp:User> destroy ncu ip net2
Destroyed ncu 'net2'
netcfg:ncp:User> list
ncp:User
        management-type    reactive
NCUs:
        phys    net2
netcfg:ncp:User> end
netcfg> exit
$

```

## Performing a Wireless Scan and Connecting to Available Wireless Networks

You can scan for and connect to available wireless networks by using the `netadm` command.

Use the `netadm scan-wifi link-name` command to scan a wireless link to obtain a list of available wireless networks.

Use the `netadm select-wifi link-name` command to select and connect to a wireless network from the scan results on the link that is specified as *link-name*. The `select-wifi link-name` subcommand prompts you for a WiFi selection, a key, and a key slot, if required.

For information about the `netadm` subcommands, see “[netadm Subcommands](#)” on page 37.

---

**Note** – You must have already created a key prior to using the `netadm select-wifi` command.

---

You can also trigger a subsequent scan of the network to search for available wireless networks by using the `netadm scan-wifi link-name` command. Note that a subsequent scan might not trigger a scan event, if the new scan results are identical to the existing scan results. The `nmcli` daemon performs the scan, regardless of whether the data has changed since the last scan.

In the following example, the `netadm scan-wifi` command is used to perform a scan of the wireless link, `net1`. The `netadm select-wifi` command is then used to display a list of wireless networks from which to select. The list that is displayed is based on the results of the scan that was previously performed on `net1`.

**EXAMPLE 3-7** Connecting to Wireless Networks

```

$ netadm select-wifi net1
1: ESSID home BSSID 0:b:e:85:26:c0
2: ESSID neighbor1 BSSID 0:b:e:49:2f:80

```

**EXAMPLE 3-7** Connecting to Wireless Networks (Continued)

```
3: ESSID testing BSSID 0:40:96:29:e9:d8
4: Other
Choose WLAN to connect to [1-4]: 1
$
```

In this example, the wireless network that is represented by the number 1, selects the home network.

**EXAMPLE 3-8** Connecting to a Wireless Network That Is Not Listed

```
$ netadm select-wifi net1
1: ESSID home BSSID 0:b:e:85:26:c0
2: ESSID neighbor1 BSSID 0:b:e:49:2f:80
3: ESSID testing BSSID 0:40:96:29:e9:d8
4: Other
Choose WLAN to connect to [1-4]: 4
Enter WLAN name: clear
1: None
2: WEP
3: WPA
Enter security mode:1
$
```

In this example, the Other option to select a wireless network that is not listed, which is represented by the number 4, prompts you to enter the name of the wireless network and the security mode.

If the WLAN requires a key, you are prompted to enter the key and key slot, if WEP is specified for the security mode. For example:

```
Enter WLAN key for ESSID home: mywlankey
Enter key slot [1-4]: 1
```

## Troubleshooting Reactive Network Configuration Issues

This section describes how to troubleshoot reactive network configuration issues.

### Monitoring the Current State of All Network Connections

The `netadm` command can be used with the `show-events` subcommand to listen for and display events that are being monitored by the network management daemon, `nwamd`. This subcommand provides useful information about events that are related to the configuration process for network profiles and configuration objects.

The syntax for the `netadm show-events` command is as follows:

### netadm show-events [-v]

For information about the netadm subcommands, see “[netadm Subcommands](#)” on page 37.

In the following example, the netadm show-events command is used with the -v option when an Automatic NCP is enabled. The -v option display events in verbose mode to show the change in different states.

```
$ netadm show-events -v
EVENT                DESCRIPTION
OBJECT_ACTION        ncp Automatic -> action enable
OBJECT_STATE          ncp Automatic -> state online, active
OBJECT_STATE          ncu link:net0 -> state offline*, (re)initialized but not config
OBJECT_STATE          ncu link:net0 -> state online, interface/link is up
OBJECT_STATE          ncu interface:net0 -> state offline*, (re)initialized but not c
OBJECT_STATE          ncu interface:net0 -> state offline*, waiting for IP address to
PRIORITY_GROUP       priority-group: 0
LINK_STATE            net0 -> state up
OBJECT_STATE          loc NoNet -> state offline*, method/service executing
OBJECT_STATE          loc Automatic -> state offline, conditions for activation are u
OBJECT_STATE          loc NoNet -> state online, active
IF_STATE              net0 -> state flags 1004843 addr 10.153.125.198/24
OBJECT_STATE          ncu interface:net0 -> state offline*, interface/link is up
OBJECT_STATE          ncu interface:net0 -> state online, interface/link is up
IF_STATE              net0 -> state flags 2080841 addr 2002:a99:7df0:1:221:28ff:fe3c:
IF_STATE              net0 -> state flags 2004841 addr 2001:db8:1:2::4ee7/128
OBJECT_STATE          loc Automatic -> state offline*, method/service executing
OBJECT_STATE          loc NoNet -> state offline, conditions for activation are unmet
OBJECT_STATE          loc Automatic -> state online, active
```

## Troubleshooting Network Interface Configuration Issues

The netadm list -x command is useful for determining why a network interface might not be configured correctly. This command displays the various profiles and configuration objects, their current state, and the reason why they are in that state.

For example, if a cable is unplugged, you can use the netadm list -x command to determine if the link state is offline and why, for example, “link is down.” Similarly, for duplicate address detection, the output of the netadm list -x command reveals that the physical link is online (up), but the IP interface is in a maintenance state. In this instance, the reason that is given is “Duplicate address detected.”

The following is an example of the netadm list -x command output:

```
$ netadm list -x
TYPE      PROFILE      STATE      AUXILIARY STATE
ncp       DefaultFixed offline     disabled by administrator
ncp       Automatic    online     active
```

```

ncu:phys net0 offline interface/link is down
ncu:ip net0 offline conditions for activation are unmet
ncu:phys net1 offline* need WiFi network selection
ncu:ip net1 offline conditions for activation are unmet
ncp User disabled disabled by administrator
loc Automatic offline conditions for activation are unmet
loc NoNet online active
loc office offline conditions for activation are unmet
loc DefaultFixed offline conditions for activation are unmet
$

```

After determining the reason that a link or interface is offline, you can proceed to correct the problem. In the case of a duplicate IP address, you must modify the static IP address that is assigned to the specified interface by using the `netcfg` command. For instructions, see [“Setting and Changing Property Values for a Profile” on page 60](#). After you commit the changes, run the `netadm list -x` command again to check that the interface is now configured correctly, and that its state is displayed as `online`.

Another example of why an interface might not be configured correctly is if no known WLANs are available. In this case, the WiFi link's state would be displayed as `offline`, and the reason would be `need WiFi network selection`. Alternatively, if a WiFi selection was made, but a key is required, the reason would be `need WiFi key`.

# Using the Network Administration Graphical User Interface

---

This chapter provides an introduction to the network administration graphical user interface (formerly known as NWAM GUI) on the Oracle Solaris desktop, which includes a description of the components that make up its network administration GUI. Basic instructions for interacting with reactive network profiles from the desktop, controlling network connections, adding wireless networks, and creating and managing network profiles are also included in this chapter.

This chapter does not provide step-by-step instructions on managing your network exclusively by using the network administration GUI. For detailed instructions, refer to the online help, which can be accessed by right-clicking the Network Status icon that is displayed in the panel notification area of the desktop at all times. Links within the network administration GUI take you to pages in the online help that provide more detailed information about each topic. You can also navigate through the online help by clicking links that are displayed in the text or by clicking the various topics in the side pane.

The following topics are covered in this chapter:

- “Introduction to the Network Administration Graphical User Interface” on page 88
- “Functional Components of the GUI” on page 90
- “Interacting With Reactive Network Profiles From the Desktop” on page 92
- “Joining and Managing Favorite Wireless Networks” on page 96
- “Managing Network Profiles” on page 99
- “Creating and Managing Locations” on page 105
- “About External Network Modifiers” on page 109

# Introduction to the Network Administration Graphical User Interface

The network administration GUI is the graphical equivalent to the network command-line interface (CLI). The network administration GUI enables you to view and monitor the status of your network from the desktop, as well as interact with reactive network profiles to manage your Ethernet and wireless configuration. In addition, you can perform various networking tasks from the desktop, such as connecting to a wired or wireless network at startup and configuring new wired or wireless networks. The network administration GUI can also be used to create and manage locations, which are profiles that simplify the complex task of system-wide network configurations, such as those configurations that require a different name server or security type, or a network interface configuration that must be enabled at different times. The GUI includes a feature that displays notifications about the current status of your network connection, as well as information about the overall condition of your network environment.

Basic capabilities of the network administration GUI include the following:

- Network status notification
- Detection of hot-plugged events
- Creation and management of network profiles
- Management of wireless networks

The network administration GUI manages network configuration the same way that the network CLI does, by storing desired property values in the form of profiles on the system. The system's network service determines which profile should be active at a given time, based on current network conditions, and then enables the most appropriate profile.

## Accessing the Network Administration GUI From the Desktop

Two components make up the network administration GUI: the Network Status notification icon that is displayed continuously on the desktop panel and the network configuration dialogs. These dialogs can be accessed from the System → Administration menu or by right-clicking the notification icon. The network administration GUI behaves much the same as any other application that has a continuous status notification icon, for example, the power management icon. These applications enable you perform certain tasks by accessing their right-click (context) menu or by using configuration dialogs that are accessed from either the icon or from various preferences menus.

The panel icon is your most frequent point of contact with network configuration. The icon shows whether you are currently connected to a wired or wireless network. By hovering your mouse over the icon, a tool tip displays additional information, such as the currently active NCP

and Location profile. By right-clicking the icon, you can change basic network configuration of your system, such as connecting to a different wireless network.

Clicking (left-clicking) the panel icon opens the Network Preferences dialog. This dialog can also be opened from the System →Administration menu. Here, you can perform more detailed network configuration such as defining static IPv4 and IPv6 addresses, setting connection priorities, managing external network modifiers (ENMs), and creating groups of network settings for use in different locations.

## Differences Between the Network Administration GUI and the Network CLI

You can use either the network administration GUI or the network CLI to manage the network configuration and interact with the reactive network configuration. Whether you choose to use the GUI or the CLI to perform a particular task depends on the task and the given situation. For some tasks, the most logical choice is to use the network administration GUI. An example would be checking the status of your currently active network connection or choosing a wireless network to connect to at startup. These tasks can be more easily and quickly performed by directly interacting with reactive network configuration from the desktop through the GUI. For more complicated tasks, such as specifying a script as the start and stop method for a new ENM, you might choose to work in the command-line mode.

Although the CLI and GUI are essentially the same, the following differences should be noted:

- **Functionality differences**

The network administration GUI includes functionality that enables you to interact with reactive network configuration and check network connections from the desktop. How you obtain information regarding the status of your network varies slightly between the GUI and the CLI commands. If you are using the GUI, notifications are displayed on the desktop as they occur. If you are using the CLI, you can monitor the reactive networking events as they occur by using the `netadm show -events` command. For more information, see [“Monitoring the Current State of All Network Connections” on page 84](#).

Also, to obtain information about the status of your network by using the network administration GUI, you would visually check, hover your mouse over, or click the Network Status notification icon that is displayed on the desktop. To obtain information about the status of your network from the command line, use the `netadm` command with the `list` subcommand. The output of this command provides information about the basic state of each network object that is configured on your system. However, the network administration GUI provides more complete information and details about your network status, such as which wireless network you are connected to and the IP address of your network connection.

Some commands that you can perform by using the CLI cannot be performed by using the GUI. For example, you cannot export a profile configuration by using the GUI. To export a profile configuration, use the `netcfg export` command. For more information, see “Exporting and Restoring a Profile Configuration” on page 77.

In addition, you cannot create or modify fixed network profiles by using the GUI. You can use the `ipadm` and `dladm` commands to modify the fixed profile.

For more information about the `ipadm` command, see the `ipadm(1M)` man page and Chapter 4, “Working With IP Interfaces,” in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1*.

For more information about the `dladm` command, see the `dladm(1M)` man page and Chapter 3, “Working With Datalinks,” in *Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1*.

- **Component name and term usage differences**

In the GUI, a network configuration profile (NCP) is the same as a *network profile*. What are called network configuration units (NCUs) in the CLI are referred to as *network connections* in the GUI.

Enabling and disabling NCPs by using the CLI is the same as the task for switching network profiles or connections if you are using the GUI.

## Functional Components of the GUI

The network administration GUI includes several functional components that are used to accomplish virtually the same tasks that you can perform by using the CLI. Table 4–1 describes each of these components. Note that some dialogs can be accessed or opened in several ways. Also, some dialogs display different information, depending on how the dialog was accessed. Specific information about these differences are noted in the related sections throughout this chapter and explained in detail in the online help.

TABLE 4–1 Network Administration GUI Primary Components

Component	Function	How to Access
Network Status notification icon	Method for viewing the status of your network and interacting with the network from the desktop. The icon also contains a contextual menu that can be accessed to create and manage network configuration by using the GUI.	<ul style="list-style-type: none"> <li>▪ By viewing the icon, which is displayed on the desktop panel's notification area at all times.</li> <li>▪ By hovering your mouse over the icon to display a tool tip that provides information about your current network status.</li> <li>▪ By clicking the icon, which displays the Network Preferences dialog.</li> <li>▪ By right-clicking the icon, which opens its contextual menu.</li> </ul>

TABLE 4-1 Network Administration GUI Primary Components (Continued)

Component	Function	How to Access
Network Preferences dialog	<p>Method for switching between reactive and fixed network profiles. This method is also used for enabling and managing the two primary network profile types, the system-defined Automatic profile and multiple user-defined network profiles. The Automatic and user-defined network profiles manage network configuration for individual network interfaces.</p> <p>This dialog is also used to configure IPv4 and IPv6 addresses for individual network interfaces and to manage favorite wireless networks.</p>	<ul style="list-style-type: none"> <li>■ By clicking the Network Status notification icon on the desktop.</li> <li>■ By choosing System → Administration → Network from the Main Menu bar on the desktop panel.</li> <li>■ By choosing Network Preferences from the Network Status notification icon's contextual menu.</li> </ul>
Network Locations dialog	<p>Method for creating, enabling, and managing the properties of system-defined and user-defined Location profiles. Locations specify certain elements of a network configuration, for example a naming service and firewall settings, that are applied together when required.</p>	<ul style="list-style-type: none"> <li>■ By choosing Network Locations from the Network Status notification icon's contextual menu.</li> <li>■ From the Connection Status view of the Network Preferences dialog, click the Locations button.</li> </ul>
Join Wireless Network dialog	<p>Method for joining wireless networks and managing a list of favorite networks.</p> <p><b>Note</b> – This dialog opens automatically if you attempt to add a wireless network and more information about that network is required.</p>	<ul style="list-style-type: none"> <li>■ By selecting the Join Unlisted Wireless Network option in the notification icon's contextual menu.</li> <li>■ By clicking the Join Unlisted button in the Wireless Chooser dialog.</li> <li>■ By clicking a notification message that says, “No wireless networks found. Click this message to join an unlisted wireless network.”</li> </ul>
Wireless Chooser dialog	<p>Method for choosing and connecting to a wireless network.</p>	<p>By clicking a notification message that says, “<i>interface</i> disconnected from <i>ESSID</i>. Click this message to view other available networks.”</p> <p><b>Note</b> – This dialog opens automatically whenever you have a choice of available wireless networks to join.</p>

TABLE 4-1 Network Administration GUI Primary Components (Continued)

Component	Function	How to Access
Network Modifiers dialog	<p>Method for adding external network modifier applications that are capable of creating or modifying the network configuration.</p> <p>This dialog is also used to stop or start the network modifier. For information about network modifiers, see <a href="#">“About External Network Modifiers” on page 109</a></p>	<ul style="list-style-type: none"> <li>■ By clicking the Modifiers button in the Connection Status view of the Network Preferences dialog.</li> <li>■ By right-clicking the Network Status notification icon, then selecting the Network Modifier Preferences menu item.</li> </ul>

## Interacting With Reactive Network Profiles From the Desktop

The Network Status notification icon, which is displayed on the desktop panel's notification area at all times is the primary method for viewing the status of your network and for interacting with automatic network configuration processes. The Network Status notification icon is also where informational messages about your network are displayed. The icon's contextual (right-click) menu enables quick access to essential network functionality. The icon's appearance indicates the overall condition of your network.

### Checking the Status of Your Network Connection

The quickest way to obtain essential information about your network is to look at the Network Status notification icon that is displayed in the panel notification area of the desktop. The Network Status notification icon is the primary method for viewing the status of your currently enabled network connection and for interacting with reactive network configuration. The icon's appearance changes, depending on the status of the currently enabled network connection. Another way you can display information about your currently enabled network connection is to hover your mouse over the Network Status notification icon. To access the notification icon's context menu, right-click the icon. From here, you can change the currently enabled network interface and view more detailed information about the wireless network, if any, you are connected to.

---

**Note** – The Network Status notification icon is displayed on the desktop when any network profile is active. If a fixed profile is active, you cannot modify the network configuration but you can still view properties. For example, you can view IP address, status, and connection speed in the panel icon tool tip and in the Connection Status view of the Network Preferences dialog.

---

The following table illustrates the Network Status icon's appearance, which changes to reflect the status of the network connections that are enabled on your system when a reactive profile is active.

TABLE 4-2 Network Status Icon's Appearance When a Reactive Profile Is Active

Icon	Status	Description
	Full connectivity	Indicates that all manually enabled connections that are in the active network profile are online and that the required number of connections in the active profile group (if such a group exists) are online. The required number is as follows: <ul style="list-style-type: none"> <li>One connection if the group is of the Exclusive priority type</li> <li>One or more connections if the group is of the Shared priority type</li> <li>All connections in the group if the group is of the All priority type</li> </ul> For more information, see <a href="#">“Working With Priority Groups” on page 104</a> .
	Partial connectivity	Indicates that one or more manually enabled or priority group connections are offline. It also indicates that a connection is waiting for user input, such as the choice of an available wireless network to connect to or the input of a WEP/WPA key.
	No connectivity	Indicates that the network has a configuration issue.

The following table illustrates the Network Status icon's appearance when a fixed network profile is active.

TABLE 4-3 Network Status Icon's Appearance When a Fixed Profile Is Active

Icon	Status	Description
	Full connectivity	Indicates that all configured connections are online.
	Partial connectivity	Indicates that one or more configured connections are offline.
	No connectivity	Indicates that the network has a configuration issue.

For more information about reactive and fixed network profiles, see [“Managing Network Profiles” on page 99](#).

## ▼ How to Show Details About an Enabled Network Connection

- 1 **Open the Network Preferences dialog and select Connection Status from the drop-down list, if required.**

You can open the Network Preferences dialog in one of the following ways:

- Click the **Network Status** notification icon on the desktop panel.
- Choose **System** → **Administration** → **Network** from the Main Menu bar on the desktop panel.
- **Right-click the Network Status notification icon to open its menu, then select Network Preferences.**

For wireless network connections, the IP address, signal strength, connection speed, connection status, and security type are displayed.

If a fixed network profile is active, the list shows the status of all wired and wireless connections in the profile.

If a reactive network profile is active, the list shows the status of all of the connections that are manually enabled.

- 2 **To view or edit more properties of a specific network connection, double-click the connection in the list or select the connection from the Show drop-down menu that is located at the top of the dialog.**

---

**Note** – The properties of specific network connections cannot be displayed when a fixed network profile is active using this method.

---

## Controlling Network Connections From the Desktop

By default, network configuration attempts to maintain a network connection at all times. If a wired network connection fails, an attempt is made to connect to one of your favorite wireless networks. If the attempt fails, other available wireless networks are tried, with your permission.

You can also manually switch between wired and wireless networks, as required.

---

**Note** – For all connection types, the connection behavior is set for the current session *only*. When you reboot your system or disconnect, an attempt is made to establish network connections, according to the priorities that are defined by the enabled network profile.

---

You can control network connections from the desktop by using the network configuration in the following ways:

- **Modify the default connection priority.**

By default, all wired network connections take priority over all wireless network connections. That is, a wireless network connection is only attempted if a wired connection cannot be established. If more than one wireless network is available at the current location, you are prompted to select which network to join. This behavior is defined by the `Automatic` network profile (a network profile in GUI is same as NCP), which is enabled by default. To enforce a different behavior, you must create and enable a different network profile.

You can add a connection to a user-defined profile. This connection is enabled when the profile becomes active. To disable the connection, you can remove the connection from the profile. For more information about adding and removing connections, see [“Editing Network Profiles” on page 102](#).

- **Switch from a wired network to a wireless network.**

If the `Automatic` network profile is enabled, disconnect any network cables from all enabled wired interfaces.

By default, if any of your favorite wireless networks are available, an attempt is made to join them in the order in which they appear in the favorites list. Otherwise, the `Wireless Chooser` dialog is displayed. In this dialog you can select which network to join.

---

**Note** – You can change the way wireless networks are joined on the `Wireless` tab of the `Connection Properties` view.

---

If a network profile other than the `Automatic` network profile is enabled, the method that you use to switch to a wireless network depends on the definition of that network profile.

Choose one of the following methods:

- Use the `Connections` submenu of the `Network Status` notification icon's contextual menu to disable the wired connection and then enable a wireless connection.

Note that this method is only possible if both connections have the `Manual` activation type, and the active network profile is of the reactive type.

- Edit the enabled network profile to enable the wireless connection and disable other connections, as required.

Note that this method is only possible if the active network profile is of the reactive type.

When the wireless connection is established, a notification message is displayed.

- **Switch from a wireless network to a wired network.**

If the `Automatic` network profile is enabled, plug a network cable into an available wired interface.

If a network profile other than the Automatic network profile is enabled, the method that you use to switch to a wired network depends on the definition of that network profile.

Choose one of the following methods:

- Use the Connections submenu of the Networks Status notification icon's contextual menu to disable the wireless connection and then enable a wired connection.  
Note that this method is only possible if both connections have the Manual activation type, and the active network profile is of the reactive type.
- Edit the enabled network profile to enable the wired connection and disable the wireless connection.

Note that this method is only possible if the active network profile is of the reactive type. When the wired connection is established, a notification message is displayed.

---

**Note** – You cannot manually switch between connections when a fixed network profile is active.

---

For other tasks that you can perform by using the network administration GUI, see the online help.

## Joining and Managing Favorite Wireless Networks

By default, when wireless network connection is enabled, reactive network configuration attempts to connect to any available network in the favorites list, without asking, in the priority order in which the connections are listed. If no favorite networks are available, the Wireless Chooser dialog opens. In this dialog you can choose which wireless network to join.

You can also modify the way in which connections to wireless networks are attempted in the Wireless tab of the Network Preferences dialog's Connection Properties view. When a reactive profile is active, you can manually connect to a different wireless network by accessing the Network Status notification icon's contextual menu.

---

**Tip** – You can access the Connection Properties view for a selected network through the Network Preferences dialog. This dialog contains a drop-down list that is labeled, Show. This list enables you to switch between views for a given network. In each view, there are different tasks you can perform and information about the selected network that is specific to that view.

The following views exist for every network connection in each network profile that is on the system:

- Connection status
- Network profile
- Connection properties

For more information about working with network profiles, including a description of the Network Preferences dialog, see “[Managing Network Profiles](#)” on page 99.

## ▼ How to Join a Wireless Network


Wireless networks are joined by choosing the Join Wireless Network option that is available by right-clicking the Network Status notification icon. The Wireless Chooser dialog is where you select a wireless network to connect to, from the list of available networks that is displayed.

- 1 **To manually connect to a different wireless network when a reactive network profile is active, you can do one of the following:**
  - **Choose an available wireless network from the Network Status notification icon's contextual menu.**
  - **Choose the Join unlisted wireless network option from the Network Status notification icon's contextual menu.**

An unlisted wireless network has been configured so that it does not broadcast its network name, yet is still available to join.
  - **Select an available wireless network from the Wireless Chooser dialog.**

This dialog is displayed automatically when there is a choice of available wireless networks to join.

FIGURE 4-1 Wireless Chooser Dialog



**Note** – You cannot manually select a different wireless network when a fixed network profile is active.

- 2 If the Join Wireless Network dialog opens, provide all of the necessary information for the wireless network you have chosen.

For more details about the information that you might need to provide, refer to the network administration GUI online help.

## Managing Favorite Networks

By default, when you join a wireless network for the first time, a check box that is labeled, Add to list of favorite networks on successful connection, is displayed in the Join Wireless Network dialog.

- To add the wireless network to your list of favorites, if the connection is successful, select this box. If you do not want the network to be added to your list of favorites, deselect the box. The box is selected by default.
- To add a wireless network that is not currently available, or not currently broadcasting its network name to your favorites list, go to the Wireless tab of the Connection Properties view, then click the Add button. To add the network, you need to know its network name, security type, and security key.

FIGURE 4-2 Wireless Tab of the Connection Properties View



# Managing Network Profiles

In the network administration GUI, network profiles are equivalent to the NCPs that are described in [“Description of an NCP” on page 12](#).

A network profile specifies which network interfaces can be enabled or disabled at any given time. Using network profiles can be helpful in situations where you have more than one network interface available. For example, most modern laptop brands have both a wired and a wireless interface. Depending on your physical location and your work environment, you might want to use only one of those interfaces and disable the other interface for security or other reasons.

The network profiles that are available in the network administration GUI are either reactive or fixed. By default, there is one reactive network profile, `Automatic`, and one fixed network profile, `DefaultFixed`. You can switch between the profiles by using the GUI, as required. You can create, edit, and delete user-defined reactive profiles by using the GUI, but you cannot edit or delete the default system-defined profiles.

By default, the `Automatic` network profile first attempts to enable one wired connection. If that attempt fails, it then attempts to enable one wireless connection.

## About the Network Preferences Dialog

The Network Preferences dialog is where individual network connections are configured and how the current state of each network connection is viewed. The dialog provides access to various views that you can switch to by using the drop-down list located at the top of the dialog.

You can open the dialog in the following ways:

- By clicking the Network Status notification icon on the desktop
- By choosing `System` → `Administration` → `Network` from the Main Menu bar on the desktop panel
- By choosing `Network Preferences` from the Network Status notification icon's contextual menu

At the top of the Network Preferences dialog is a drop-down list that is labeled `Show`. This list enables you to switch between the `Connection Status` view, the `Network Profile` view, and the `Connection Properties` view for every network connection in each network profile.

- **Connection Status view**


The `Connection Status` view displays information about network connections in the active network profile. If the profile is of the fixed type, this view shows all configured wired and wireless connections in the profile. If the profile is of the reactive type, this view shows each enabled network connection with the `Manual` activation type. For more information, see [“How to Show Details About an Enabled Network Connection” on page 94](#).

- **Network Profile view**

Network profile information can be viewed in the Network profile view of the Network Preferences dialog.

To display this view, select Network Profile in the drop-down list that is located at the top of the Network Preferences dialog.

FIGURE 4-3 Network Preferences Dialog



- **Connection Properties view**

The Connection Properties view enables you to view and change properties of a specified network connection. To switch to this view, select the connection name from the Show drop-down list or double-click the connection name while in either the Connection Status or the Network Profile view. A tabbed view is displayed, whereby you can view or edit the connection's properties.


---

**Note** – You cannot access the Connection Properties view for any connection when a fixed network profile is active.

---

The Connection Properties view has two tabs: an IP address tab and a wireless tab. The wireless tab is only displayed if the connection type is wireless. In this IP address tab, you can configure both IPv4 and IPv6 addresses. In the wireless tab, you can configure the list of favorite networks and choose how the wireless interface connects to available networks.

FIGURE 4-4 Connection Properties View



## Viewing Information About Network Profiles

Network profile information can be viewed in the Network Profile view of the Network Preferences dialog.

To display this view, select Network Profile in the drop-down list that is located at the top of the Network Preferences dialog.

The Network Profiles list displays the name of each available network profile. The currently enabled profile is shown with a radio button indicator. By default, there is one reactive network profile, Automatic, and one fixed network profile, DefaultFixed. You can enable these default system-defined profiles, but you cannot edit or delete them. However, you can create multiple user-defined reactive network profiles. The reactive network profiles that are manually created can be enabled, edited, or deleted, as needed.

Below the Network Profiles list is a summary of the profile that is selected. To view the selected profile in full or to edit the profile, click the Edit button.

---

**Note** – The *selected* profile might be different than the *enabled* profile.

---

### ▼ How to Switch From One Network Profile to Another Network Profile

- 1 Open the Network Profile view of the Network Preferences dialog.
- 2 Select the radio button next to the network profile that you want to enable.
- 3 To switch network profiles, click OK or Cancel to close the dialog without switching profiles.

## Adding or Removing a Network Profile

To create or edit a network profile, select Network Profile from the drop-down list that is located at the top of the Network Preferences dialog.

- To create a new network profile, click the Add button, then type the name of the new profile. Note that only reactive network profiles can be created.
- To duplicate an existing network profile, select the profile in the list, click the Duplicate button, then type the name of the new profile. Note that only reactive network profiles can be duplicated.
- To remove a network profile, select the profile in the list, then click the Remove button.

---

**Note** – You cannot remove the Automatic network profile or the DefaultFixed network profile.

---

For more information about editing a profile that you have added or duplicated, see [“Editing Network Profiles” on page 102](#).

## Editing Network Profiles

To edit a reactive network profile, select the profile in the Network Profile view of the Network Preferences dialog, and then click the Edit button. The Edit Network Profile dialog opens. In this dialog, you can add or remove connections (NCUs) from the profiles. If you add a connection to a profile, the added connection is enabled when the profile is active. If you remove a connection from the profile, the connection is disabled. See [“Working With Priority Groups” on page 104](#).

---

**Note** – You can edit and remove a manually created network profile. However, you cannot edit or remove the Automatic network profile.

---

### ▼ How to Edit a Fixed Network Profile

You cannot edit fixed network profiles by using the Edit Network Profile dialog.

- 1 **Select the profile in the Network Profile view of the Network Preferences dialog.**
- 2 **Select the radio button of the fixed network connection profile that you want to edit, and then click OK to enable the profile.**
- 3 **Use the `ipadm` and `dladm` commands to make the required changes to the active profile.**


For more information about the `ipadm` and `dladm` commands, see the `ipadm(1M)` man page, the `dladm(1M)` man page, and [Connecting Systems Using Fixed Network Configuration in Oracle Solaris 11.1](#).

## ▼ How to Add or Remove Connections

You can add or remove connections (NCUs) from the profiles. If you add a connection to a profile, the added connection is enabled when the profile is active. If you remove a connection from the profile, the connection is disabled.

- 1 **Select the profile in the Network Profile view of the Network Preferences dialog, and then click the Edit button.**

FIGURE 4-5 Edit Network Profiles Dialog



The network connections that are enabled for the selected profiles are listed. You can add or remove connections for the selected profile.

---

**Note** – The Automatic network profile cannot be edited or deleted. Any time the Automatic network profile is selected in the Edit Network Profile dialog, all of the profile editing buttons and drop-down lists are disabled.

---

For more information, see the online help.

- 2 **In the Edit Network Profile dialog, click the Connections button.**

Alternatively, you can choose a connection from the list of available connections to be enabled or disabled and click the Enable or Disable button.

The Edit Connections dialog is displayed.

- 3 **To add or remove connections, choose one of the following:**

- **Select the connections to add to the profile, and click OK.**

The connections are added to the profile and are enabled when the profile becomes active.

- **Deselect the selected connections to remove from the profile, and click OK.**

The connections are removed from the profile and are disabled.

---

**Note** – By default, all wired network connections take priority over all wireless network connections. That is, a wireless network connection is only attempted if a wired connection cannot be established. If more than one wireless network is available at the current location, you are prompted to select which network to join.

---

## Working With Priority Groups

You can create a network profile that treats one or more network interfaces as a group. If one or more of the interfaces in the highest priority group cannot be enabled, according to the group's priority type, then the group with the next highest priority is considered.

The following table describes the three different priority group types that are available.

PriorityType	Description
Exclusive	One connection in the group is enabled, and all the other connections are disabled. As long as at least one connection in the group is enabled (not necessarily the same one all the time), no attempt is made to enable connections in any of the lower priority groups.
Shared	All of the connections in the group that can be enabled are enabled. As long as at least one connection in the group remains enabled, no attempt is made to enable connections in any of the lower priority groups.
All	All of the connections in the group are enabled. If any of the connections are lost, all of the connections in the group are disabled. As long as all of the connections remain enabled, no attempt is made to enable connections in any of the lower priority groups.

For example, the default `Automatic` network profile contains two exclusive priority groups. The higher priority group contains all of the *wired* network connections. The lower priority group contains all of the *wireless* network connections.

For detailed instructions about performing these and other tasks, see the online help.

### ▼ **How to Move a Network Connection to the Always Enabled Group**

A network connection in the “always enabled” group is always enabled when the selected network profile is active.

- 1 **Enable the network profile that you want to edit.**

- 2 In the **Edit Network Profile** dialog, select the connection to be always enabled.
- 3 Click the **Up** button until the connection moves to the “always enabled” group.

### ▼ **How to Remove a Network Connection**

A network connection is disabled if it is removed from the profile when the profile is active.


- 1 In the **Edit Network Profile** dialog, click the **Connections** button.  
The **Edit Connections** dialog is displayed.
- 2 **Deselect the connection to be disabled and click OK.**

## **Creating and Managing Locations**

A location contains certain elements of a network configuration, for example, a naming service and firewall settings, that are applied together, when required. You can create multiple locations for various uses. For example, one location can be used when you are connected at the office by using the company intranet. Another location can be used at home when you are connected to the public Internet by using a wireless access point. Locations can be enabled manually or automatically, according to environmental conditions, such as the IP address that is obtained by a network connection.

The **Network Locations** dialog is where you can to switch locations, edit location properties, create new locations, and remove locations. Note that only user-defined locations can be created and removed. The **Locations** dialog can be opened from the **Connection Status** view of the **Network Preferences** dialog.

FIGURE 4-6 Locations Dialog



The Locations list is similar to the list in the Network Status notification icon's contextual menu. Each available location, with an icon that represents its activation type, is listed.

Location types are dependent on their activation mode. They are as follows:

- **System** – Locations of this type are system-defined locations (`Automatic`, `NoNet`, and `DefaultFixed`), which means the system determines when to enable the location, based on current network conditions. The `DefaultFixed` location is only enabled when the corresponding `DefaultFixed` network profile is enabled. A `DefaultFixed` location cannot be manually enabled or disabled.
- **Manual** – Locations of this type can be manually enabled or disabled by using the Network Locations dialog or by interacting with the Network Status notification icon.
- **Conditional** – Locations of this type are enabled or disabled automatically, according to the rules that you specify during the creation of the location.

---

**Note** – When a system location or a fixed location is selected, the drop-down list shows `Activated by System` or `Activated by Fixed Profile`, respectively. Both the drop-down list and the `Edit Rules` button are disabled.

---

## ▼ How to Change a Location's Activation Mode

The following procedure describes how to change the activation mode for a location by using the GUI. If you are using the `netcfg` command, you would change the activation mode by modifying the properties of the specified location. For more information, see [“Setting and Changing Property Values for a Profile” on page 60](#).

- 1 **From the Network Status notification icon's Location submenu, choose Network Locations. Or, from the Connection Status view of the Network Preferences dialog, click the Locations button.**

- 2 To change the activation mode of a location, select the location in the list, then select the new activation mode from the Selected location drop-down list.**

When a system location or a fixed location is selected, the drop-down list shows Activated by System or Activated by Fixed Profile, respectively. Both the drop-down list and the Edit Rules button are disabled.

When a manual or a conditional location is selected, the drop-down list options are as follows:

- **Manual activation only:** This location is only enabled when it is manually selected. When this option is selected, the Edit Rules button is *disabled*.
- **Activated by rules:** This location is automatically selected under certain network conditions. When this option is selected, the Edit Rules button is *enabled*.

- 3 (Optional) To set rules for how and when a location is enabled, click the Edit Rules button.**

For further instructions, see “Working With the Rules Dialog” in the online help.

## ▼ **How to Switch From One Location to Another Location**

The following procedure describes how to switch from one location to another location by using the GUI. To switch locations by using the CLI, use the `netadm` command to enable a new location. Because exactly one location must be enabled on the system at all times, enabling a new location implicitly disables the currently enabled location. The same rule applies when enabling a network profile. For more information about enabling and disabling locations, see “[Enabling and Disabling Profiles](#)” on page 69.

- **From the Network Status notification icon's Location submenu, choose the location that you want to enable.**

If the switch locations automatically option is selected on the Locations submenu, you cannot manually choose a location to enable. The most appropriate System or Conditional location is enabled automatically at any given time, according to changes in the network environment.

If the switch locations manually option is selected on the Location submenu, you can enable any available location, regardless of its activation type. The selected location remains enabled indefinitely.

- **Alternatively, you can switch locations in the Network Locations dialog. To do so, follow these steps:**
  - a. From the Network Status notification icon's Location submenu, select Network Locations. Or, from the Connection Status view of the Network Preferences dialog, click the Locations button.**

- b. Select the radio button of the location to which you want to switch, then click OK.
  - If the switch locations automatically radio button is selected in the Network Locations dialog, you cannot manually choose a location to enable. The most appropriate System or Conditional location is enabled automatically at any given time, according to changes in the network environment.
  - If the switch locations manually radio button is selected in the Network Locations dialog, you can enable any available location, other than a fixed location. The new location remains enabled indefinitely.

## Editing Locations

Editing a location by using the GUI is the equivalent to modifying a location's properties if you are using the CLI.

### ▼ How to Edit a Location

- 1 **Choose Network Locations from the Network Status notification icon's submenu.**

Alternatively, from the Connection Status view of the Network Preferences dialog, click the Locations button.
- 2 **Select the location in the list, then click Edit.**

Alternatively, you can double-click the location in the list.

---

**Note** – You cannot edit the properties of fixed locations.

---

The Edit Location dialog opens, with the following two tabs available:

Name Services	Enables you to configure naming services in the specified location.
Security	Enables you to select configuration files to be used by IP Filter and IPsec features, when the specified location is enabled.

- 3 **Select the appropriate tab to display the information to be edited.**

## About External Network Modifiers

External Network Modifiers (ENMs) provide the ability to specify when applications or scripts, for example, a VPN application, should perform their own network configuration external to that specified in the NCP and Location profiles. ENMs can also be defined as services or applications that directly modify the network configuration when they are enabled or disabled. ENMs are configured and monitored in the GUI by using the Network Modifiers dialog.

---

**Note** – Before you can manage a network modifier application or service by using the GUI, you must manually install it, then complete any initial setup, such as the installation of a certificate or shared secret.

---


An ENM can be started and stopped manually, as required. An ENM can also be started automatically, according to user-defined rules. To be managed by using this dialog, a network modifier application must either be implemented as a command-line tool, or as an SMF service.

To learn more about how to create and manage ENMs by using the CLI, see [“Creating an ENM Profile” on page 54](#).

## About the Network Modifiers Dialog

This dialog is used to add or remove, start and stop, and edit ENMs, applications that are capable of creating and modifying network configuration.

FIGURE 4-7 Network Modifiers Dialog



Open the dialog by using one of the following methods:

- Click the Modifiers button in the Connection Status view of the Network Preferences dialog.
- Right-click the Network Status notification icon, then choose the Network Modifier Preferences menu item.

The main section of the dialog Available network modifiers that displays the following information for each ENM:

- Activation state icon (Manual or Conditional)
- User-defined name (Modifier Name), for example, “OpenVPN”
- Current status, “Running” or “Stopped”

The Start/Stop according to rules check box is checked if the selected network modifier application has a Conditional activation type, and unchecked if the activation type is Manual. To change the activation type, toggle the check box.

## ▼ How to Add a Command-Line ENM

The following procedure describes how to add a command-line ENM. For information about adding a network modifier application service, see the online help.

- 1 Open the Network Modifiers dialog by using one of the following methods:**
  - From the Connection Status view of the Network Preferences dialog, click the Modifiers button.
  - Right-click the Network Status notification icon, then choose the Network Modifier Preferences menu item.
- 2 Click the Add button.**
- 3 Type the name of the new network modifier application.**
- 4 To add a new entry or cancel your changes, choose one of the following:**
  - **To add a new entry that has the Manual activation type, press Enter or Tab.**

The two Manage modifiers radio buttons are enabled. The first of these, Command Line Applications, is selected by default. The Start and Stop command fields, and the two Browse buttons, are also enabled.
  - **To cancel your changes, press Escape.**
- 5 Type the command that starts the network modifier application into the Start Command field.**

Alternatively, you can use the Browse button to open a file chooser dialog, where you can select the command to use.

The Start button remains disabled for the network modifier application until a valid command has been typed into this field.
- 6 Type the command that stops the network modifier application into the Stop Command field.**

Alternatively, you can use the Browse button to open a file chooser dialog, where you can select the command to use.

The Stop button remains disabled for the network modifier application until a valid command has been typed into this field.
- 7 To add this application, click OK.**

The external network modifier is added.



# Index

---

## A

- accessing the network GUI from the desktop, 88–89
- activation-mode property, 17, 18
  - possible values for Location profile, 20
  - property values for different profile types, 69
- adding a command-line ENM, 110–111
- adding or removing a network profile, 102
- administering reactive network configuration, 73–86
- authorizations, 27
  - network administration GUI, 28
  - network configuration and status panel
    - presence, 28
  - required to use the user interfaces, 27–29
- Automatic Location profile, 15
- Automatic NCP, 13
  - policy for performing basic configuration, 24
- auxiliary state values, displaying, 77

## C

- cancel subcommand of netcfg command, 35
- changing
  - property values by using the walkprop subcommand, 68–69
  - property values for a profile, 60–63
  - the activation mode of a location, 106–107
- checking the status
  - of a network connection, 92–94
  - when a fixed profile is active, 93
  - when a reactive profile is active, 93
- clear subcommand of netcfg command, 35

- command-file mode for netcfg, 34
- command-line mode for netcfg, 34
- commands, for fixed networking, 26
- commit subcommand of netcfg command, 35
- connecting to available wireless networks, 83–84
  - performing a wireless scan, 83–84
- controlling network connections, 94–96
- create subcommand of netcfg command, 35
- creating and configuring reactive network profiles, 31–71
- creating and managing locations, 105–108
  - changing the activation mode of a location, 106–107
  - editing locations, 108
  - switching from one location to another, 107–108
- creating profiles, 39–60
  - creating
    - a known WLAN profile, 57–60
    - a Location profile, 48–54
    - an ENM profile, 54–57
    - an NCP, 41–48
    - an NCU for an NCP, 41–44
  - interactively creating
    - a known WLAN profile, 58–60
    - a Location profile, 50–54
    - an ENM profile, 55–57
    - an NCP with NCUs, 44–48

## D

- datalinks, 14

DefaultFixed location, 60  
 DefaultFixed Location profile, 15  
 DefaultFixed NCP, 13, 41  
 desktop
 

- checking the status of your network connection, 92–94
- interacting with reactive network profiles, 92–96

 destroy subcommand of netcfg command, 35  
 differences between the network administration GUI and CLI, 89–90
 

- component name and term usage differences, 90
- functionality differences, 89

 disable subcommand of netadm command, 38  
 disabling a profile, 70  
 displaying
 

- auxiliary state values, 77
- information about profile states, 75–77

 dynamic reconfiguration and NCPs, 25

## E

editing
 

- fixed network profile, 102
- locations, 108
- network profiles, 102–104
  - adding or removing connections, 103–104

 enable subcommand of netadm command, 37  
 enabling a profile, 70  
 enabling and disabling profiles, 69–71  
 end subcommand of netcfg command, 35  
 ENMs, 15–16, 109–111
 

- adding a command-line ENM, 110–111
- creating an ENM profile, 54–57
- interactively creating an ENM profile, 55–57
- Network Modifiers dialog, 109–110
- properties of an ENM profile, 54–55

 examples
 

- changing property values for a specific profile by using the walkprop subcommand, 68–69
- connecting to wireless networks, 83
- disabling a profile, 70
- displaying monitored events, 84
- enabling a profile, 70
- exporting a profile configuration, 78–79

examples, exporting a profile configuration (*Continued*)
 

- in command-file mode, 80–81
- in interactive mode, 79–80

 interactively creating
 

- a Location profile, 52–54
- a WLAN, 59–60
- an ENM profile, 56–57
- an NCP, 46–47
- an NCU for an existing NCP, 47–48

 interactively setting property values, 62–63  
 NCP activation policy, 19  
 removing
 

- a profile interactively, 82–83
- a specific user-defined profile, 82

 setting property values in netcfg command-line mode, 61  
 switching profiles, 70–71  
 exit subcommand of netcfg command, 36  
 export subcommand of netcfg command, 36  
 exporting and restoring a profile configuration, 77–81  
 external network modifiers (ENMs), 109–111
 

- Network Modifiers dialog, 109–110

## F

fixed networking commands, 26  
 functional components of the GUI, 90–92

## G

get subcommand of netcfg command, 36

## H

help subcommand of netadm command, 39  
 help subcommand of netcfg command, 36  
 highlights of profile-managed network configuration, 10

**I**

interacting with reactive network profiles from the desktop, 92–96  
 checking the status of a network connection, 92–94  
 interactive mode of `netcfg` command, 32–34  
 interactively creating  
 a known WLAN profile, 58–60  
 an ENM profile, 55–57  
 an NCP with NCUs, 44–48  
 Location profile, 50–54  
 interactively obtaining a single property value, 66–67  
 interactively setting property values, 61–63  
 interface NCUs, 14

**J**

joining  
 a wireless network, 97–98  
 and managing favorite wireless networks, 96–98

**K**

known WLAN profile, interactively creating, 58–60  
 known WLANs, 16–17  
 creating a known WLAN profile, 57–60  
 properties, 58

**L**

link NCUs, 14  
`list` subcommand of `netadm` command, 38  
`list` subcommand of `netcfg` command, 36  
 listing  
 all of the profiles, 63–65  
 all property values for a specific profile, 65  
 profile information on a system, 63–69  
 values of a specific property, 65–67  
 location activation selection criteria, 19–22  
 criteria and operations, 21  
 Location profile, 14–15  
 activation-mode property, 20  
 Automatic location, 15

Location profile (*Continued*)

creating a Location profile, 48–54  
 DefaultFixed location, 15  
 interactively creating  
 a Location profile, 50–54  
 NoNet location, 15  
 properties, 49–50  
 system-defined locations, 48  
 user-defined locations, 48  
 locations  
 changing the activation mode of a  
 location, 106–107  
 creating and managing, 105–108  
 editing, 108  
 switching from one location to another, 107–108

**M**

managing  
 favorite networks, 98  
 network profiles, 99–108  
 monitoring the current state of all network  
 connections, 84–85

**N**

NCP activation policy, 17–19  
 NCPs, 12–14  
 activation-mode property, 18  
 Automatic NCP, 13  
 creating an NCP, 41–48  
 interactively creating an NCP with NCUs, 44–48  
 NCP activation policy, 17–19  
 NCUs, 14  
 user-defined NCP, 13  
 NCUs, 14  
 creating, 41–44  
 properties of, 42–44  
`netadm` command  
`disable` subcommand, 38  
`enable` subcommand, 37  
`help` subcommand, 39  
`list` subcommand, 38

- netadm command (*Continued*)
  - scan-wifi subcommand, 39
  - select-wifi subcommand, 39
  - show-events subcommand, 39
- netcfg command
  - cancel subcommand, 35
  - clear subcommand, 35
  - command-file mode, 34
  - command-line mode, 34
  - commit subcommand, 35
  - create subcommand, 35
  - destroy subcommand, 35
  - end subcommand, 35
  - exit subcommand, 36
  - export subcommand, 36
  - get subcommand, 36
  - help subcommand, 36
  - interactive mode, 32–34
  - list subcommand, 36
  - revert subcommand, 36
  - select subcommand, 36
  - set subcommand, 36
  - verify subcommand, 37
  - walkprop subcommand, 37, 68–69
- network administration GUI
  - accessing from the desktop, 88–89
  - differences between the CLI and the GUI, 89–90
  - functional components of, 90–92
  - introduction, 88–90
  - primary components of, 90–92
  - using, 87–111
- network configuration authorizations
  - and related profiles, 27
  - and security, 26–29
  - required to use the user interfaces, 27–29
- network configuration profiles, 12–14
- network connections
  - checking the status
    - of a network connection, 92–94
    - when a fixed profile is active, 93
    - when a reactive profile is active, 93
  - controlling network connections, 94–96
  - modifying the default connection priority, 95
- network connections (*Continued*)
  - showing the details of enabled network connections, 94
  - switching
    - from wired network to wireless network, 95
    - from wireless network to wired network, 95
- Network Modifiers dialog, 109–110
- Network Preferences dialog, 99–101
  - Connection Properties view, 100
  - Connection Status view, 99
  - Network Profile view, 100
- network profile configuration
  - creating
    - a known WLAN profile, 57–60
    - a Location profile, 48–54
    - an ENM profile, 54–57
    - an NCP, 41–48
  - enabling and disabling profiles, 69–71
  - exporting and restoring a profile configuration, 77–81
  - listing profile information on a system, 63–69
  - setting and changing property values for a profile, 60–63
- network profiles, 11–17
  - adding or removing network profile, 102
  - creating
    - a known WLAN profile, 57–60
    - a Location profile, 48–54
    - an ENM profile, 54–57
    - an NCP, 41–48
    - and configuring a reactive network profile, 31–71
  - creating profiles, 39–60
  - dynamic reconfiguration, 25
  - editing, 102–104
  - editing fixed network profile, 102
  - enabling and disabling profiles, 69–71
  - ENMs, 12, 15–16
  - exporting and restoring a profile configuration, 77–81
  - interacting with reactive network profiles from the desktop, 92–96
  - known WLANs, 12, 16–17
  - listing profile information on a system, 63–69

network profiles (*Continued*)

- Location profiles, 12, 14–15
  - NCPs, 12
  - NCUs, 12
  - removing profiles, 81–83
  - restoring an exported profile, 81
  - setting and changing property values for a profile, 60–63
  - switching from one network profile to another, 101
  - viewing information about network profiles, 101
- NoNet Location profile, 15

**O**

- obtaining values of a specific property, 65–67

**P**

- priority-group property, 18, 43
- priority groups, 18, 104
  - working with priority groups, 104–105
- priority-mode property, 18, 43
- profile activation policy, 17–22
  - location activation selection criteria, 19–22
    - criteria and operations, 21
  - NCP activation policy, 17–19
- profile configuration tasks, 22–23
- profiles, network profile types, 11–17
- properties
  - activation-mode property, 17, 18
  - changing property values by using the `walkprop` subcommand, 68–69
  - ENM profile properties, 54–55
  - interactively obtaining and listing a single property value, 66–67
  - interactively setting property values, 61–63
  - known WLANs properties, 58
  - listing all property values for a specific profile, 65
  - Location profile properties, 49–50
  - NCU activation properties, 18–19
  - NCU properties, 42–44
  - obtaining values of a specific property, 65–67
  - priority-group property, 18

properties (*Continued*)

- priority-mode property, 18
- setting and changing property values for a profile, 60–63

**R**

- reactive network configuration
  - connecting to available wireless networks, 83–84
  - creating and configuring a reactive network profile, 31–71
  - creating profiles, 39–60
  - dynamic reconfiguration, 25
  - exporting a profile configuration, 80–81
  - highlights of profile-managed network configuration, 10
  - how reactive networking works with other networking technologies, 25–26
  - network profiles and types, 11–17
  - overview, 9–29
  - removing profiles, 81–83
  - SMF network services, 26
  - switching
    - from a fixed to a reactive network configuration, 75
    - from a reactive to a fixed network configuration, 74
  - what is a reactive network configuration, 11
  - when to use a reactive network, 11
- reactive network profiles
  - Automatic NCP, 13
  - ENMs, 15–16
  - how a reactive network profile works, 24
  - known WLANs, 16–17
  - Location profile, 14–15
  - NCUs, 14
  - profile activation policy, 17–22
  - user-defined NCPs, 13
- removing profiles, 81–83
- restoring a profile, 81
- revert subcommand of `netcfg` command, 36

**S**

- scan-wifi subcommand of netadm command, 39
- security and authorizations, 26–29
- select subcommand of netcfg command, 36
- select-wifi subcommand, 39
- set subcommand of netcfg command, 36
- setting and changing property values for a
  - profile, 60–63
  - interactively setting property values, 62–63
- show-events subcommand of netadm command, 39
- showing the details of an enabled network
  - connection, 94
- SMF network services, 26
- status of network connections
  - fixed profile, 93
  - reactive profile, 93
- subcommands
  - netadm command, 37–39
  - netcfg command, 35–37
- switching
  - from a fixed to a reactive network configuration, 75
  - from a reactive to a fixed network configuration, 74
  - from one location to another, 107–108
  - from one network profile to another, 101
  - profiles, 70–71

**T**

- top-level profiles, 32
- troubleshooting network interface configuration
  - issues, 85–86

**U**

- user-defined NCPs, 13
- using the network administration GUI, 87–111
  - introduction, 88–90

**V**

- verify subcommand of netcfg command, 37
- viewing information about network profiles, 101

**W**

- walkprop subcommand, viewing and changing
  - property values, 68–69
- walkprop subcommand of netcfg command, 37
- WLANs, 16–17
- working with priority groups, 104–105