

Generic Interface
Oracle FLEXCUBE Universal Banking
Release 11.3.0
[May] [2011]
Oracle Part Number E51535-01



Table of Contents

1. ABOUT THIS MANUAL.....	1-1
1.1 INTRODUCTION.....	1-1
1.1.1 Audience	1-1
1.1.2 Abbreviations Used.....	1-1
1.1.3 Glossary of Icons	1-2
1.1.4 Conventions used.....	1-2
1.1.5 Related documents	1-3
2. GENERIC INTERFACE.....	2-1
2.1 INTRODUCTION.....	2-1
2.2 MAINTAINING GI PARAMETER	2-1
2.3 DEFINING GI OBJECT.....	2-3
2.3.1 Viewing Summary Details of Object.....	2-5
2.3.2 Maintaining AUDF (ASCII User Defined Function) Details.....	2-7
2.3.3 Viewing AUDF Summary Details	2-8
2.4 SPECIFYING INTERFACE DEFINITION DETAILS.....	2-9
2.4.1 Specifying Component Details.....	2-16
2.4.2 Specifying Incoming File Names	2-20
2.4.3 Viewing Interface Definition Summary.....	2-21
2.5 GENERATING DYNAMIC INTERFACE COMPONENT.....	2-22
2.5.1 Processing Outgoing Interface	2-22
2.5.2 Processing Incoming Interface	2-23
2.5.3 Processing File Transfer to Upload Tables.....	2-23
2.5.4 Processing Data Process from Upload Table to Base Table.....	2-23
2.5.5 Parallel Processing of Generic Interface	2-25
2.5.6 Maintaining CRC Algorithm Details	2-25
2.5.7 Viewing CRC Summary Details.....	2-26
2.5.8 Maintaining File Transferring Details	2-27
2.5.9 Viewing File Transfer Summary.....	2-28
2.5.10 Triggering File Transfer.....	2-30
2.5.11 Maintaining Translation Details.....	2-31
2.5.12 Viewing Translation Summary Details	2-32
2.5.13 Viewing FTP Log Files.....	2-33
2.5.14 Viewing Interface Run chart.....	2-34
2.6 INVOKING GI PROCESS.....	2-36
2.6.1 Archiving Process.....	2-37
2.6.2 Folder Structure.....	2-37
2.7 TRACKING THE STATUS OF INTERFACE PROCESSING.....	2-38
2.7.1 Viewing Error Details of Individual Record.....	2-39
2.7.2 Viewing Upload Exception Details	2-40
2.8 INTEGRATING GI WITH EOD	2-42
2.8.1 Processing Unprocessed Interface	2-42
2.8.2 Processing GI Batch.....	2-42
2.9 GLOBAL VARIABLES AND MASK ATTRIBUTES	2-42
2.9.1 Global variables	2-42
2.9.2 Mask Attributes.....	2-42
3. SCREEN GLOSSARY	3-1
3.1 FUNCTION ID LIST.....	3-1

1. About this Manual

1.1 Introduction

This User Manual is prepared to familiarize you with the interface between Oracle FLEXCUBE and external systems. The manual gives you an overview of the usage of the system, and the maintenances and process of Generic Interfaces required for its smooth functioning.

1.1.1 Audience

This manual is intended for the following User/User Roles:













Role	Function
Back office clerk	Input functions for contracts
Back office managers/officers	Authorization functions
End of day operators	Processing during end of day/ beginning of day
Financial Controller / Product Managers	Generation of reports

1.1.2 Abbreviations Used

UI	User Interface
GW	Gateway
DB	Database
SMS	Security Services
ID	Identification Number
SDE	System Defined Element
IB	Inter Branch
GI	Generic Interfaces
AUDF	ASCII User Defined Function
EOD	End Of Day
Mark EOTI	Mark End of transaction Input
Mark TI	Mark transaction Input
CRC	Cyclic Redundancy Check
OS	Operating System


1.1.3 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	New
	Copy
	Save
	Delete
	Unlock
	Print
	Close
	Re-open
	Reverse
	Template
	Roll-over
	Hold
	Authorize
	Liquidate
	Exit
	Sign-off
	Help
	Add
	Delete
	View

1.1.4 Conventions used

The following conventions are used in this User Manual:

- Important information is preceded with the  symbol
- System/error/override messages are shown in the following manner:

This is a system message

1.1.5 Related documents

You may have to refer the other Oracle FLEXCUBE User Manuals as and when required.

2. Generic Interface

2.1 Introduction

Oracle FLEXCUBE interfaces with other systems installed at your bank to handle Incoming/Outgoing data using batch mechanism (Flat files). This chapter discusses the features that are supported by Oracle FLEXCUBE to streamline the exchange of data between the system and external systems.

2.2 Maintaining GI Parameter

You can set the parameters for the framework of Generic Interface processing in the following screen 'Parameters' screen invoked from the Application Browser. You can invoke this screen by typing 'GIDPARAM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a 'Parameters' window with the following fields and controls:

- Holiday Treatment:**
 - Holiday Treatment
 - Next Run Date: Previous Working Day, Next Working Day
 - Purging Days:
- Incoming:**
 - Uploaded Record Status:
 - Bad File Path:
 - Log File path:
- Outgoing:**
 - Archival Required
 - File Writing Process:
- Footer:**
 - Input By:
 - Date Time:
 - Authorized By:
 - Date Time:
 - Modification Number:
 - Authorized
 - Open
 -

You can maintain the following parameters for generic interface here.

Holiday Treatment

You can specify the parameters for interface processing if the schedule date falls on a holiday.

Holiday Treatment

Check this box to indicate your preference for interface processing on a holiday.

Next Run Date

Specify how the system should process if the schedule date falls on a holiday. You can select the options as either move the interface processing to previous working date or next working date if the interface processing day falls on a holiday.



The default holiday treatment is movement to 'next working date'.

Purging Days

Specify the purging days if you want to maintain any days to be purged while processing interface.

Incoming

You can specify the parameters for interface processing for the incoming files.

Uploaded Record Status

Select the input status of the transaction record after upload as:

- Authorized
- Unauthorized



By default 'Authorized' option is selected.

Bad File Path

Specify the path where the external tables should write the bad records, while reading from the Incoming file.

Log file Path

Specify the path where the external tables should write the Log file, while reading from the Incoming file.

Outgoing

You can specify the parameters for interface processing for the outgoing files.

Archival Required

Check this box to specify if the upload table data and file log data should be archived at the time of EOD or before deleting the same.

File writing process

Select the tool to write the data into output file from the following options:

- Oracle - This component uses ORACLE UTIL packages to write the data into output file.
- Java - This component uses java libraries ages to write the data into output file



By default 'Oracle' option is selected.

You need to note the following details while selecting the tool for file writing:

- This feature is applicable only for the outgoing process
- Low volume sites are recommended to use Oracle tool only in case of high volume Java tool is recommended.
- If Java tool is selected then the necessary Java software/component should be installed in the database server and jvm is enabled in database.

2.3 Defining GI Object

You can prepare complex queries to use them in the outgoing interface definition for data extraction. 'Object Definition' screen can be used to create queries which can be invoked from the Application Browser. You can invoke this screen by typing 'GIDOBDEF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Object Definition' window. At the top, there are input fields for 'Name *' and 'Description', and radio buttons for 'Type' (Static and Dynamic). Below that is a 'Static Query' field with a help icon. The 'Object Mapping' section contains a table with columns 'Object Name *' and 'Alias Name'. The 'Object Field Mapping' section contains a table with columns 'Field Name *', 'Alias Name', 'Data Type', and 'Data Length'. Below these tables are input fields for 'Where', 'Order By', 'Group By', 'Having', and 'Query', each with a help icon. At the bottom, there is a 'View SQL' button and a footer with fields for 'DOC002', 'Authorized By', 'Modification Number', 'Authorized', 'Open', and a 'Cancel' button.

You can maintain the objective definition for generic interface here.

Name

Specify the unique interface object name which is created here.


Description

Specify a description for the object name.

Type

Select the required object definition type from the following options:


- Static definition – Select this option if you have a predefined query or you would write query of the object.

 Static field gets enabled for you to specify the query when you select the type of definition as 'static'.

- Dynamic definition – Select this option if you want to prepare or create the desired query using the dynamic maintenance.

Static

Specify the predefined query for the static definition here.


 This field gets enabled only if you select the type of definition as 'static'.

Object Mapping

You can map the database object details here.

Object Name

Select the database object name that is used for the dynamic query.

 Database object would be either table or Synonym or view.

Alias Name

The alias name for the database object gets displayed which is same as the object name by default. However, you can edit it.

Field Mapping

You can map the fields of the database object selected here.

Field Name

Select the column which can be used from the database object.

Alias

The alias of the column name in the select query that is generated which by default the column name itself. However, you can edit it.

Data Type

The data type of the field gets displayed here.

Data Length

The data length of the field gets displayed here.

Where Clause

Specify the where clause for the resultant dynamic query here. You can define the join conditions of multiple tables along with the filter condition of the query.

Group By

Specify the group by clause for the resultant dynamic query here.

Order By

Specify the order by clause for the resultant dynamic query here.

Having Clause

Specify the having clause for the resultant dynamic query here.

Query

Specify the indexes which can be used for the query. This index gets used for the query.

2.3.1 Viewing Summary Details of Object

You can view the details of objectives maintained in the system through 'Object Summary' screen. You can invoke this screen by typing 'GISOBDEF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Authorization Status	Record Status	Name	Description
----------------------	---------------	------	-------------

You can click 'Search' button to view all the object definition records of your bank. However, you can to filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the object defined from the dropdown list. The options are:

- Authorized

- Unauthorized

Name

Select the name of the object maintained from the option list.

Order by Clause

Select the order by clause maintained for the object from the option list

Having Clause

Select the having clause maintained for the object from the option list

Record Status

Select the record status of the object from the drop-down list. The options are:

- C – Closed record
- O – Open record

Description

Select the description maintained for the object from the option list

Group by Clause

Select the group by clause maintained for the object from the option list

Where Clause

Select the where clause maintained for the object from the option list

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Name
- Description

2.3.1.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.3.2 Maintaining AUDF (ASCII User Defined Function) Details

You can maintain the AUDF (ASCII User Define Function) details in the 'AUDF Maintenance' screen. You can invoke this screen by typing 'GIDAUDFM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "AUDF Maintenance" with the following fields and controls:

- AUDF Name * (text input)
- Description (text input)
- Unit Name * (text input with a help icon)
- AUDF Type * (dropdown menu showing "Message")
- DOC002 (text field)
- Authorized By (text field)
- Modification Number (text field)
- Date Time (text field)
- Authorized (checkbox)
- Open (checkbox)
- Cancel (button)

Specify the following AUDF details in this screen.

AUDF Name

Specify the name of the AUDF here.

Description

Specify a description for the AUDF here.

Unit Name

Specify the invoked function name here.

AUDF Type

Select the AUDF types from the drop-down list. The following options are available:

- Message
- Component
- Record
- Field

2.3.3 Viewing AUDF Summary Details

You can view AUDF details maintained in the system using 'AUDF Summary' screen. You can invoke this screen by typing 'GISAUDFM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'AUDF Summary' application window. At the top, there are two dropdown menus for 'Authorization Status' and 'Record Status'. Below them are input fields for 'AUDF Name' and 'Description'. There are three buttons: 'Search', 'Advanced Search', and 'Reset'. Below the search area, there is a table with the following columns: 'Authorization Status', 'Record Status', 'AUDF Name', and 'Description'. The table is currently empty. At the bottom of the window, there are two legend boxes: one for 'Authorization Status' with options 'A - Authorized' and 'U - Unauthorized', and another for 'Record Status' with options 'C - Closed' and 'O - Open'. An 'Exit' button is located in the bottom right corner.

You can click 'Search' button to view all the AUDF records of your bank. However, you can to filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the AUDF you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

Record Status

Select the record status of the AUDF from the drop-down list. The options are:

- C – Closed
- O - Open

AUDF Name

Select the name of the AUDF from the option list.

Description

Select the description of the AUDF from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- AUDF Name
- Description

2.4 Specifying Interface Definition Details

You can define the format details and properties associated with interface file in the 'Interface Definition' screen. You can invoke this screen by typing 'GIDIFTDF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Interface Definition' window with the following fields and options:

- Branch Code ***: Text input field.
- Interface Type**: Dropdown menu (set to 'Incoming').
- File Mask**: Text input field.
- CRC Required**:
- CRC Algorithm**: Text input field.
- CRC File Mask**: Text input field.
- CRC File Path**: Text input field.
- External System ***: Text input field.
- Format Type**: Dropdown menu (set to 'Fixed').
- File Path ***: Text input field.
- Data Log Required**:
- Commit/Fetch Frequency**: Text input field.
- Date Format ***: Dropdown menu (set to 'YYYYMMDD').
- No Of Executions/Day**: Text input field.
- Duplication File Check Req'd For Current Date**:
- Interface Code ***: Text input field.
- Delimiting Character**: Text input field.
- Confirmation File Required**:
- When To Run**: Dropdown menu.
- Mandatory**:
- Trigger Type**: Dropdown menu (set to 'Manual').
- Confirmation File Mask**: Text input field.
- Confirmation File Path**: Text input field.
- Justification**: Date, Number, Text dropdown menus.
- Frequency Type**: Dropdown menu (set to 'Daily').
- Week Day**: Dropdown menu.
- Month**: Dropdown menu.
- Date**: Text input field.
- Last Run Date**: Text input field.
- Next Run Date**: Text input field.
- Padding Character**: Date, Number, Text dropdown menus.
- Pre Message**: Text input field.
- Post Message**: Text input field.
- Pre Message AUDF**: Text input field.
- Post Message AUDF**: Text input field.
- Incoming**: Function Id, Processed File Mask, Default Action, On Override, Outgoing Interface, Suppress Start Reference, Incoming File Mask, Log Output dropdown menus.
- Parallel process**: Parallel Process Required, Parallel process, No Of Records, No Of Parallel Process dropdown menus.
- Component Details**: Input By, Authorized By, Modification Number, Authorized, Open checkboxes.
- Incoming File Names**: Section header.
- Exit**: Button.

You can define the following interface file properties, formats and components here.

Branch Code

Specify the code of the branch to which the interface belongs.

Interface Type

Select the interface type from the following options:

- Incoming - Select this option if the file data needs to be uploaded into Oracle FLEXCUBE
- Outgoing - Select this option if data from Oracle FLEXCUBE needs to be written into file

File Mask

Specify the file mask for the outgoing interface file.

CRC Required

Check this box if you want to check the CRC while transferring the data.

In case of incoming interface, system checks for the CRC value in the file name maintained in 'CRC file mask'. For outgoing interface, system generates the CRC value in a CRC file.

CRC File Algorithm

Specify the CRC algorithm which has to be used to calculate the CRC Value.

CRC File Mask

The path of CRC File mask gets displayed here.

CRC File Path

The path of CRC File gets displayed here.

External System

Specify the external system with which Oracle FLEXCUBE is interfacing.

Format Type

Select the type of data length in the interface from the following options:

- Fixed – Select this option if the file data has to be in fixed width.
- Delimited - Select this option if the file data has to be in delimited format.

Delimiting Character field gets enabled for you to specify the delimiting character if you select the format type of definition as 'Delimited'.

File Path

Specify the path of the file.

Data Log Required

Check this box to indicate if the confirmation details are required in logged file

Commit/Fetch Frequency

Specify the number of transaction committed or fetched at a given point of time.

Date Format

Specify the date format for the interface file.

No of Executions Day

If you select frequency type as 'Daily', specify the total number of interface file processing executions in a day.

This field is applicable only for incoming interface file process.

Duplication File Check Reqd for Current Date

Check this box to indicate that the duplicate files should not be added for the current date.

Interface Code

Specify a unique interface code to identify the interface as incoming or outgoing.

Delimiting Character

Specify the delimiting character if you select the format type of definition as 'Delimited'.

When to Run

Select the stage of application the interface has to be triggered.

Mandatory

Check this box to indicate that the interface has to be mandatorily processed before moving on to the next stage of EOD. If this box is checked system checks if the interface has been processed or not and if it is not processed system will not allow movement to the next EOD stage.

Triggering

Select an appropriate option to indicate how the interface should be triggered. The options available are:

- Manual – Select this option if the interface has to be triggered manually.
- System – Select this option if the interface has to be triggered automatically.

During EOD if there are any mandatory unprocessed interfaces and if the triggering type is selected as 'System' then the interface is triggered automatically. In case of Incoming interface if triggering type is selected as 'System' then system checks if the file is available in the 'ready' folder for that interface. If the file is present the system will process it. In case of outgoing interface if triggering type is selected as 'System' then, system will automatically trigger the Outgoing interface.



If the interface is mandatory the triggering type must be system. However, even if the triggering type is mentioned as System, you can manually trigger the interface whenever required through Interface triggering screen.

Conformation File Required

Check this box to indicate if confirmation is required for an incoming file. If this box is checked then when incoming file is processed, system checks whether confirmation file is available in the folder specified. If the file is not available then incoming file processes will raise an error indicating the confirmation file is not available.

Conformation File Path

The path of confirmation file gets displayed here.

Conformation File Mask

The path of confirmation file mask gets displayed here.

Justification

You can specify the justification details of fixed format type interface file here.

Date

Select the justification type for date field from the drop-down list. The options are:

- Right
- Left

Number

Select the justification type for number field from the drop-down list. The options are:

- Right
- Left

Text

Select the justification type for text field from the drop-down list. The options are:

- Right
- Left



Default justification type for text and date field type is Left and number field type is right.

Frequency Type

Select the frequency type for interface file processing from the following drop-down options:

- Daily
- Weekly
- Fort Nightly
- Monthly
- Quarterly
- Yearly
- Adhoc



If Adhoc is specified it will override any existing restrictions.

Week Day

If you select frequency type as 'Weekly', select the day from the drop-down list for processing the interface file. The options available are:

- Sunday
- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday

Month

If you select frequency type as 'Quarterly, Half Yearly and Yearly', select the month for the interface file execution from the drop-down list. The options available are:

- January
- February
- March
- April
- May
- June
- July
- August
- September
- October
- November
- December

Date

If you select frequency type as 'Monthly, Quarterly, Half Yearly and Yearly', select the date of the month for the interface file execution from the drop-down list.

Last Run Date

The last run date gets displayed here

Next Run Date

The day on which the interface can be triggered gets displayed here.

Padding Character

You can specify the padding character of fixed length format type interface file here. All the data types can have the same padding character

Date

Specify the padding character for date field.

Number

Specify the padding character for number field..

Text

Specify the padding character for text field.



All the data types can have the same padding character.

Pre Message

Specify the value that should be calculated before triggering the interface in the predefined format.

Post Message

Specify the value that should be calculated after Interface processing is done in the predefined format.

Pre Message AUDF

Specify the AUDF that needs to be invoked before triggering the interface. You can use this to add additional functionality required at the message level.

Post Message AUDF

Specify the AUDF that needs to be invoked after triggering the interface. You can use this to add additional functionality required at the message level.

Incoming File

You can specify the interface details applicable for incoming file details here.

Function ID

Specify the function id for which the incoming data need to be sent.

Incoming File Mask

Specify the file mask for selecting the incoming files from the file directory. System supports four types of file masking:

- Date and Time mask (YYYYMMDDHHMISS) – (year, month, date, hours, minutes and second)
- Sequence number based mask(nnn) – 3 digit numeric numbers
- File names starting with a specific signature. (Upload all files which are starting with incoming File name)
- Exact File Name (File Names which are exact match with the file name in interface definition)

System searches all the files which are matching the mask criteria and process the files one by one “_” as the split separator for the file name and the mask criteria.



System will continue or break the uploading of records based on the error handling defined in the 'On Override' field. If it is Continue, then the system will ignore the current record and continue with the next record. If it is Reject, then the system will stop the execution of the file and start executing the next available incoming file.



By default system append the Incoming File Mask type to the file name while searching the physical file name. If an interface supports for multiple type incoming files, then same file mask is applicable for all type of incoming files.

Processed File Mask

Specify the file mask for renaming the incoming file after uploading the data.

Default Action

Select the default action which needs to be invoked to process the uploaded data in the upload table from the drop-down list below:

- New
- Modify
- Close

On Override

Select the action to be taken if an override occurs from the drop-down list below:

- Reject
- Continue
- Skip

Outgoing Interface

Specify the corresponding outgoing interface file for the above incoming file.

Suppress Start Reference

Check this box to indicate that the start reference number should be suppressed.

If the checkbox is selected and start reference element is defined in the component definition, system raises an error message while saving the interface. System validates the start reference check for Header, Body and Footer.

For a given interface, mask and suppress start reference are applicable to all the file names configured for that interface

Log Output

Select the type of details to be updated in the log file from the adjoining drop-down list. This list displays the following values:

- Error
- Success
- Both

While processing the interface file, system verifies the log output value and the below details:

- If the value of “Log Output” is “Error”, then, system creates an error file (<INTERFACE_NAME>_FILENAME>_ERR_<ProcessRefNo>.dat) in Log_Failure folder and update the primary key elements and the corresponding error details (error code and message).
- If the value of “Log Output” is “Success”, then, system creates a data file (<INTERFACE_NAME>_FILENAME>_SUC_<ProcessRefNo>.dat) in Log_Success folder and update the primary key elements. “
- If the value of “Log Output” is “Both”, then, system creates both error file and data file in log folder.

During the interface configuration, log_failure and log_success folders are created in the interface configured folder.

Parallel Processes

You can specify the parallel process details here.

Parallel Process Required

Check this box to indicate if parallel processing is required if multiple interface files has to be processed at a given time.

When you select parallel process required parallel process type field gets enabled.

Parallel Process

Select the type of parallel process you want to keep for the interface processing:

- Record Based – Select this option if you want parallel processing to be based on the number of records you maintained.
- Process Based – Select this option if you want parallel processing to be based on the number of parallel processes that you maintained.

No of Records

Specify the number of records of parallel process can be performed at a given time. This field gets enabled only if you select the parallel process type as 'Record based'.

No of Parallel Process

Specify the number of parallel process can be performed at a given time. This field gets enabled only if you select the parallel process type as 'Process based'.

2.4.1 Specifying Component Details

You can specify the component details here. Click 'Component Details' button in the 'Interface Definition' screen.

Serial Number	Component Name	Component Type	Parent	Relation	Batch By Field	Where Clause
<input type="checkbox"/>	<input type="text"/>	Header	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>

Serial Number	Field Name	Field Type	Default	Data Type	Length	Column Name	Object Name
<input type="checkbox"/>	<input type="text"/>	Message	<input type="text"/>	Character	<input type="text"/>	<input type="text"/>	<input type="text"/>

The following details are captured here:

Component Linkage

You can specify the component linkage details here.

Serial Number

Specify the component position here.

Component Name

Specify a name for the component.

Component Type

Select the type of component from the options available in the drop-down list. The options available are:

- Header
- Body
- Footer
- Batch Header
- Batch Footer
- Batch Body

If header and footer are defined in component details section and opted for suppressing start reference, then system consider the first line as header and bottom most line as the footer and continues the execution.

Parent

Specify the parent component to which component is linked

Relation

If parent component is specified, then specify the relation here.

Batch by Field

Specify the field in the component based on which you want to create a batch.

This is applicable only for Outgoing Interfaces.

Where Clause

Specify the where Clause for the component

Group By

Specify the group by clause for the component.

Order By

Specify the order by clause for the component.

Pre Component

Specify the value to be calculated before the component is processed, if any.

Pre Component AUDF

Specify the AUDF that has to be executed before the component is processed, if any.

You can use this to add any additional functionality required at the component level.

Post Component

Specify the value to be calculated after the Component is processed, if any.

Post Component AUDF

Specify the AUDF that has to be executed after the component is processed, if any.

You can use this to add any additional functionality required at the component level.

Pre Record

Specify the value that needs to be calculated before the record is processed, if any.

Pre Record AUDF

Specify the AUDF that has to be executed before the record is processed, if any.

You can use this to add any additional functionality required at the record level.

Post Record

Specify the value that needs to be calculated after the record is processed, if any.

Post Record AUDF

Specify the AUDF that has to be executed after the record is processed, if any.

You can use this to add any additional functionality required at the record level.

Component Field Linkage

You can specify the component field linkage details here.

Serial Number

Specify the order of fields here.

Field Name

Specify the field name here

Field Type

Select the type of field from the options available in the drop-down list. The options available are

- Message
- Intermediate
- Start Identifier

- End Identifier
- Action

Default

Specify the default value for the field here.

Data type

Specify the data type of the field here.

Length

Specify the length of the field here.

Column Name

Specify the column name in the database of the field here.

Object Name

Specify the object name from which the field should be derived.

Start Position

Specify the start index of the field in the fixed length format.

Precision

If the field is of numeric type, then specify precision here.

Translation

If the field value needs to be translated then select the translation code that has to be used for the translation.

Un-translated

Specify the action to be taken if the translation value is not present

Derivation

Specify the derivation logic for the field.

Pre Field

Specify the value that needs to be calculated before the field value is processed.

Pre Field AUDF

Specify the AUDF that should be executed before the processing of the field here.

Post Field


Specify the value that needs to be calculated after the field value is processed.

Post Field AUDF

Specify the AUDF that should be executed after the processing of the field.


Primary Key

Check this box to indicate the primary key to identify the individual record in the incoming file.

 System allows a maximum of 5 elements as Primary Key element for a component and it is applicable to component body alone. If the interface has multiple components, then system allows defining primary key in any one of the component.

2.4.2 Specifying Incoming File Names

Click on 'Incoming File Names' button in the 'Interface Definition' screen to specify the incoming interface file names.



File Names	
<input type="checkbox"/>	File Name*
<input type="checkbox"/>	

You can specify the Incoming file names here.

File Names

The incoming file names are maintained here.

File Name

Specify the incoming interface file name here.

2.4.3 Viewing Interface Definition Summary

You can view the interface details maintained in the system using 'Interface Definition Summary' screen. You can invoke this screen by typing 'GISIFTDF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled 'Summary' with the following elements:

- Authorization Status:
- Record Status:
- Branch Code:
- External System:
- Interface Code:
- Interface Type:
- Buttons: Search, Advanced Search, Reset
- Records per page: 15, 1 of 1, Go
- Table headers: Authorization Status, Record Status, Branch Code, External System, Interface Code, Interface Type
- Legend:
 - Interface Type: I - Incoming, O - Outgoing
 - Authorization Status: A - Authorized, U - Unauthorized
 - Record Status: C - Closed, O - Open
- Exit button

You can click 'Search' button to view all the interface records of your bank. However, you can to filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the Interface definition you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

Branch code

Select the branch code belonged to the interface details from the option list.

Interface code

Select the interface code belonged to the interface details from the option list

Record Status

Select the record status of the interface details from the drop-down list. The options are:

- C – Closed
- O - Open

External System

Select the name of the external system belonged to the interface details from the option list.

Interface Type

Select the type of interface from the option list as incoming or outgoing.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Branch Code
- External System
- Interface Code
- Interface Type

2.4.3.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.5 Generating Dynamic Interface Component

While saving the Interface Definition details, a dynamic package is created in the database along with external tables for each component in case of incoming file.

2.5.1 Processing Outgoing Interface

The steps involved in Outgoing interface file processing is explained below:

- When a Outgoing Interface Definition is saved, a dynamic package is created in the Database. The outgoing package consists of fn_handoff, fn_process_components functions and function per component as defined in the Outgoing Interface definition.
- Function fn_handoff is the triggering point for the Outgoing process, which internally call the function fn_process_components after the completion of initiation and message level processing.
- Except the child component functions, independent component functions are invoked by the fn_process_components function in the order on the Component Definition.
- Child component functions are internally invoked by the corresponding parent component function with required parameters based on the relationship between them.
- Each function call gets appended with its result in the Clob which is at package level. This Clob is the result of the Outgoing process, which is written into a flat file for Outgoing in the relevant folder.
- Update the last and next run date of the interface. If data logging is required then the system would insert the file data into log table.

2.5.2 Processing Incoming Interface

There are two upload tables for handling the process of incoming interface. The master Upload table is for handling the master data and detail Upload table for the child data which can have 200 VARCHAR2 (4000) fields to store data for each field in the file. Intermediate fields cannot be considered for transaction processing but could be used only for derivation/transaction of transaction data.

- When an Incoming Interface Definition is saved, a dynamic package and external tables for each component is created in the Database. The generated dynamic package consists of fn_process_file and fn_upload for maintenance functions.
- External tables per component will be created on the file name mentioned in the Interface Maintenance, which is used for reading the corresponding component's data from the file.
- The processing of the Incoming interface would takes place in two steps
 - **File process (FP):** This process transfers data from file to upload tables.
 - **Data process (DP):** This process transfers data from upload table to the base tables using the function ID specific FCJ package invocation.

2.5.3 Processing File Transfer to Upload Tables

You can trigger file transfer process by invoking the fn_process_file function in the dynamic package. This function consists of cursors based on the external tables created. When a parent record is read from the external table a Record Identifier is generated for that record and it is assigned to the children when inserted into the upload table which helps in identifying the corresponding children for that parent record in 'D' Process.

If a relation is mentioned in the component definition and the relation fields are provide in the file then the corresponding fields are used for identifying the child records. Which one to use will be determined by the dynamic package generator based on the Interface Maintenance parameters.

The files taken for processing at the time of processing is decided by the incoming file mask selected for the particular interface.

Example

In Interface Definition (BIS):

if the incoming file name is defined as "CCYUPLOAD.TXT" and incoming file mask is defined as "YYYYMMDDHHMISS", then system will search and process the file names like CCYUPLOAD_20100110201000.TXT, CCYUPLOAD_20100110202001.TXT.

If the incoming file mask is defined as "nnn" then system will search and process the file names like CCYUPLOAD_001, CCYUPLOAD_002.

If the incoming file mask is defined as "Starting with File Name", system will search and process all the files which are starting with Incoming File name like (CCYUPLOAD_20100110200010.TXT, CCYUPLOAD_201001102020.TXT, CCYUPLOAD_001, CCYUPLOAD_002).

2.5.4 Processing Data Process from Upload Table to Base Table

You can trigger data process by invoking the fn_upload function in the dynamic package. This function can be divided into two parts:

- Populating the appropriate FCJ type with values from the upload tables.
- Invoking the FCJ function ID package for processing the data.

Populating the appropriate FCJ type with values from the upload tables is taken care by invoking the fn_upload_table_to_type function which populates the data from upload table to type using the cursors on upload table based on the base table columns.

Invoking the FCJ function ID package for processing the data is taken care by the function itself by invoking the appropriate function ID package's fn_main function with the populated type and action. The validation and business process which are already incorporated as part of the function ID development.

After data processing, the log is written for the records if the primary key has been selected at the interface definition level. Else, the log is not written for that record.

Example

Here, (component definition) contract_ref_no, version, customer id, amount, ccy are defined as fields in the component and contract_ref_no and version number are checked as primary key for the interface code BIS and File Name CCYUPLOAD:

Serial No	File Name	Data Type	Length	Primary Key
1	CONTRACT_REF_NO	VARCHAR2		Y
2	VERSION	NUMBER		Y
3	CUSTOMER_NO	VARCHAR2		N
4	AMOUNT	NUMBER		N
5	CCY	VARCHAR2		N

Suppose the incoming file CCYUPLOAD_20100110200010.TXT has 4 records as shown below

001ESUC07332000711900105\$\$\$\$\$1000USD

001ESUC07332001611900404\$\$\$\$\$100AZD

001ESUC07332002011900306\$\$\$\$\$2500AZD

001ESUC07332002811930108\$\$\$\$\$5000USD

CONTRACT_REF_NO	VERSION	CUSTOMER_NO	AMOUNT	CCY
001ESUC073320007	1	1900105	\$\$\$\$\$1000	USD
001ESUC073320016	1	1900404	\$\$\$\$\$100	AZD
001ESUC073320020	1	1900306	\$\$\$\$\$2500	AZD
001ESUC073320028	1	1930108	\$\$\$\$\$5000	USD

During the execution of interface, system encounters an error at 2 and 3rd record, then system will create a error file (BIS_CCYUPLOAD_20100110200010_ERR_124.dat) in error folder with below details:

001ESUC0733200161 GI-10001 CCY not maintained

2.5.5 Parallel Processing of Generic Interface

Parallel processing feature is available only for Incoming file process and under incoming process it would be supported for data process i.e D-process. You need to select parallel option and the number of parallel processes or each process for processing specified number of records in the 'Interface Definition' screen.

During file processing stage, system would check whether parallel process is required or not. If required, based on the parallel process parameter system would internally updates the process number field of master upload table.

During data processing stage, system could check maximum number of process and submit job for each process number. System would wait till all the processes are completed. If any process is resulted in error then the interface would be considered as error.

2.5.6 Maintaining CRC Algorithm Details

Generic Interface supports CRC-32 and Adler-32 Checksum algorithms for generating CRC value of the file. Other CRC components which are developed in Java and PL/SQL are also supported by GI using the 'CRC Maintenance' screen.

You can invoke this screen by typing 'GIDCRCFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "CRC Maintenance" with the following fields and controls:

- CRC Name ***: A text input field with an asterisk indicating it is required.
- Description**: A text input field.
- Invocation Stub**: A dropdown menu with "Declare" and "l_abs_file_path" as visible options.
- Status Bar**: Contains the following information:
 - DOC002
 - Authorized By
 - Modification Number
 - Date Time
 - Authorized (checkbox)
 - Open (checkbox)
 - Cancel button

You can write the invocation stub along with the CRC component details here:

CRC Name

Specify the CRC Algorithm used to calculate the CRC value for the file.

Description

Specify the description of the CRC Algorithm here.

Invocation Stub

Specify the stub to invoke the CRC generation component.

2.5.7 Viewing CRC Summary Details

You can view the CRC details maintained in the system using 'CRC Summary' screen. You can invoke this screen by typing 'GISCRCFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'CRC Summary' application window. At the top, there are two dropdown menus for 'Authorization Status' and 'Record Status'. Below them are text input fields for 'CRC Name' and 'Description'. A search bar contains the text '15' and '1 of 1'. To the right of the search bar are buttons for 'Search', 'Advanced Search', and 'Reset'. Below the search bar is a table header with columns: 'Authorization Status', 'Record Status', 'CRC Name', and 'Description'. At the bottom of the window, there are two legend boxes: 'Authorization Status' with options 'A - Authorized' and 'U - Unauthorized', and 'Record Status' with options 'C - Closed' and 'O - Open'. An 'Exit' button is located in the bottom right corner.

You can click 'Search' button to view all the CRC records of your bank. However, you can filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the CRC algorithm from the drop-down list. The options are:

- Authorized
- Unauthorized

CRC Name

Select the name of the CRC algorithm from the option list.

Record Status

Select the record status of the CRC algorithm from the drop-down list. The options are:

- C – Closed

- O - Open

Description

Select the description of the CRC algorithm from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- CRC Name
- Description

2.5.7.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.5.8 Maintaining File Transferring Details

Though Generic Interface doesn't support file transfer, file transfer components available as independent component can be used for transferring files.

You can maintain the file transfer details in 'External System Maintenance' screen and other details in 'File Transfer Definition'. You can invoke this screen by typing 'GIDFTPDEF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a 'File Transfer Definition' dialog box with the following fields and controls:

- FTP Name ***: Text input field.
- Description**: Text input field.
- Mode Type**: Dropdown menu set to 'Push'.
- External System**: Text input field with a browse button.
- File Name**: Text input field.
- Local Path**: Text input field.
- Remote Path**: Text input field.
- Protocol**: Dropdown menu set to 'HTTP'.
- Status Bar**: Contains 'DOC002', 'Authorized By', 'Modification Number', 'Date Time', and 'Date Time'.
- Checkboxes**: 'Authorized' (unchecked) and 'Open' (checked).
- Buttons**: 'Cancel' button.

You can maintain file following transfer details here:

File Transfer Name

Specify a name for the File Transfer here.

Description

Specify a description for the FTP name given here.

Mode

Select the mode of transaction of the file from the drop-down list. The options are:

- Push – Select this option if you are transferring the file from your system to another one.
- Pull – Select this option if you are transferring the file from another system to yours.

External System

Select the external system name, whose credentials are used to do the FTP transfer

File Name

Specify the file which has to be transferred.

Local Path

Specify the path from where the file has to be taken for transferring.

Remote Path

Specify the path in the external system to where the file has to be transferred.

Protocol

Select the protocol to be used for file transfer from the drop-down list. They are:

- FTP (File Transfer Protocol)
- HTTP (Hypertext Transfer Protocol) – MIME(From Client to Application Server)
- Connect Direct (Only in case of Mainframes)

2.5.9 Viewing File Transfer Summary

You can view the details of file transferred in the system using 'File Transfer Summary' screen. You can invoke this screen by typing 'GISFTPDP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can click 'Search' button to view all the file transaction records of your bank. However, you can to filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the file transaction you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

File Transfer Name

Select the name of file transfer used for file transaction from the option list.

File Name

Select the name of the file used for file transaction from the option list

Record Status

Select the record status of the file transaction from the drop-down list. The options are:

- C – Closed
- O - Open

External System

Select the name of the external system belonged to the file transaction from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- File Transfer Name
- External System
- File Name

2.5.9.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.


Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.5.10 Triggering File Transfer

You can use 'File Transfer' to trigger the file transfer. You can invoke this screen by typing 'GIDFTPTF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a window titled "File Transfer" with a blue header bar. Inside the window, there are three text input fields labeled "Transfer Name", "Transfer Type", and "Location". Below the "Transfer Name" field is a small icon button. Below the "Transfer Type" and "Location" fields is a "Transfer" button. In the bottom right corner of the window, there is an "Exit" button.

You can specify the file details to transfer the same.

Transfer Name

Select the name of the file which has to be transferred.

By default 'Transfer Type' and 'Location' gets displayed. Click to transfer the selected file.

2.5.11 Maintaining Translation Details

You can maintain translation details required between the external system values to Oracle FLEXCUBE Values and vice Versa in the 'Translation Definition' screen. You can invoke this screen by typing 'GIDTRANS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Translation Definition' window. It features a 'Table Name *' input field at the top. Below it is a 'Translate Parameter' section with a table. The table has two columns: 'In Parameter' and 'Out Parameter'. The 'In Parameter' column has a checkbox. To the right of the table are three icons: a plus sign, a minus sign, and a list icon. At the bottom of the window, there are several fields: 'DOC504' with a 'Date Time' label below it; 'Authorized By' with a 'Date Time' label below it; 'Modification Number'; a checkbox for 'Authorized'; a checked checkbox for 'Open'; and a 'Cancel' button.

You can capture the following details here:

Translation Name

Specify the translation name you want to keep for the set. The translation name gets linked to the interface field whose value needs to be translated during Interface Processing.

Translation Parameters

The following details are specified here:

In Param

Specify the system value for the corresponding external systems value.

Out Param

Specify the external system's value for the corresponding Oracle FLEXCUBE value.

2.5.12 Viewing Translation Summary Details

You can view the translation details maintained in the system using 'Translation Summary' screen. You can invoke this screen by typing 'GISTRANS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Translation Summary' application window. At the top, there are two dropdown menus for 'Authorization Status' and 'Record Status', and a text input field for 'Table Name'. Below these are three buttons: 'Search', 'Advanced Search', and 'Reset'. A navigation bar shows 'Records per page' set to 15, and '1 of 1' records. Below this is a table with three columns: 'Authorization Status', 'Record Status', and 'Table Name'. At the bottom, there are two legend boxes: one for 'Authorization Status' with options 'A - Authorized' and 'U - Unauthorized', and another for 'Record Status' with options 'C - Closed' and 'O - Open'. An 'Exit' button is located in the bottom right corner.

You can click 'Search' button to view all the translation records of your bank. However, you can filter your search based on any of the following criteria:

Authorization Status

Select the authorization status of the translation you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

Record Status

Select the record status of the translation from the drop-down list. The options are:

- C – Closed
- O - Open

Translation Name

Select the name of the translation from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Translation Name

2.5.12.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.5.13 Viewing FTP Log Files

You can view the log files of the files that are transferred using the 'FTP File Log' screen. You can invoke this screen by typing 'GISFTPLG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'FTP File Log' application window. At the top, there are search criteria fields: 'Transfer Name', 'File Name', 'User Id', and 'Status'. Below these fields are three buttons: 'Search', 'Advanced Search', and 'Reset'. A table with the following columns is displayed: 'Transfer Name', 'File Name', 'User Id', 'Transferred On', and 'Status'. The table shows '1 of 1' records. At the bottom right, there is an 'Exit' button.

You can click 'Search' button to view all the FTP file log records of your bank. However, you can filter your search based on any of the following criteria:

Transfer Name

Select the transfer maintenance name used to transfer the file from the option list.

User Id

Select the user id used for transferring the file from the option list.

Status

Select the status of file transfer process from the option list.

File Name

Select the name of the file which is transferred from the option list.

Transferred On

Select the timestamp at which the file is transferred from the adjoining calendar.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Transfer Name
- File Name
- User Id
- Transferred on
- Status

2.5.13.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.5.14 Viewing Interface Run chart

You can use 'Run Chart Summary' to list the interfaces that should be processed in the branch on current branch date. You can invoke this screen by typing 'GISRNCHT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can click 'Search' button to view the list the interfaces that should be processed on the current date. However, you can to filter your search based on any of the following criteria:

Branch Code

Select the branch code of the branch for which you want to view the run chart from the option list.

External System

Select the name of the external system to which the interface code is linked from the option list.

Interface Code

Select the name of interface code which has to be processed from the option list.

Interface Type

Select the type of interface from the option list as incoming or outgoing.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Branch Code
- External System
- Interface Code
- Interface Type
- Stage
- Mandatory
- Processed

2.5.14.1 Search Functionalities

The search functions available are:

Advanced - Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

Reset - Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.

Query - After specifying your search criteria click **Query** to view the list of results which match your search criteria.

Refresh - Click **Refresh** to refresh the list of results.

2.6 Invoking GI Process

You can trigger the process of Generic Interface using Gateway Messages, EOD run or through 'Interface Trigger' screen. You can invoke this screen by typing 'GIDIFPRS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Interface Trigger' application window. It features a title bar with a diamond icon and the text 'Interface Trigger'. The main area contains the following fields and controls:

- Branch Code * 000
- Interface Code * (with a search icon)
- External System *
- Interface File Name (with a search icon)
- Status U
- Process Code (dropdown menu showing 'File Processing')
- Process button

The footer area includes:

- Date Time
- Authorized By
- Modification Number
- Authorized (checkbox)
- Open (checkbox)
- Exit button

You can provide the following details here to invoke the GI routing package.

Branch Code

Specify the branch code from where the GI file process has to be initiated.

Interface Code

Select the Interface Code that has to be processed.

Based on the selected interface code, system defaults external system and interface type.

File Name

Specify the file name if the selected Interface Code is Incoming.

Process Code

Select the process code from the drop-down list, if the selected Interface Code is Incoming. The options available are:

- FP - Populating the Upload tables using the file data.

- DP- Populating the Base tables from the Upload tables.
- AL-This is will trigger 'FP' and 'DP' processes one after another.
- RT-This is Retry operation the previous process that failed is triggered.
- RE-This will rerun the 'DP' process for error records.

For an outgoing file it is a single process of reading for database and writing in to file. But for incoming file there are two steps,

1. Reading the data from file and inserting into upload table - File Process (FP)
2. Reading the data from upload table and uploading as part of base table - Data Process (DP)

2.6.1 Archiving Process


When you select the interface data for archiving while maintaining the parameters, the data gets archived. The upload table data and file log data is moved to archive tables. If parameter is set to delete then data is deleted from the upload/log tables without archiving.

2.6.2 Folder Structure

During generic interface for an incoming file, the file is placed in the ready folder when it's ready for upload. When Interface is triggered and after the successful file validation, it is moved to file processed folder and the interface processing unit gets triggered.


If the file validation fails the file is moved to the Error folder. After the successful processing of the file, it is renamed with actual file name and current date time stamp (YYYYMMDDHHMISS format) which is separated by underscore (_) and moved to the processed folder.

During generic interface for an outgoing file, the file writing process takes place in the WIP folder and after the successful completion of the writing process, the file is moved to the Ready folder. The file is renamed based on the file mask maintained.



2.7 Tracking the Status of Interface Processing

You can track the status of interface processing using the 'File Log' screen. You can invoke this screen by typing 'GISFILOG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can click 'Search' button to view all the interface transaction records of your bank. However, you can to filter your search based on any of the following criteria:

Branch code

Select the branch code of the interface file you want to track from the option list.

Interface Code

Select the interface code of the interface file you want to track from the option list.

Date of Processing

Select the date of the interface file transaction you want to track from the option list.

External System

Select the external system name with which the interface files transaction you want to track from the option list.

Status

Select the status of the interface file transaction you want to track from the option list.

Process code

Select the process code of the interface file you want to track from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Branch Code
- External System
- Interface code
- Status
- Date of Processing
- File Name
- User ID
- Process Code
- Last Maker Date Stamp
- Records Processed
- Records Errored
- Error Code
- Error Param
- Upload file name

2.7.1 Viewing Error Details of Individual Record

You can view the individual record error details of the uploaded file in the 'View Error Details' (GIDFILOG) screen. From the summary screen (GISFILOG), double click the selected record to view the error details screen.

You can invoke View Error Details screen by typing 'GIDFILOG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Based on the upload file name and process reference number, system displays the error details here:

- Upload File Name
- Branch code
- Interface Code
- Process Reference Number
- File Name
- Started Time
- Ended Time
- Status

Following field mapping details are also displayed

- Key 1
- Key 2
- Key 3
- Key 4
- Key 5
- Error Code
- Error Description

2.7.2 Viewing Upload Exception Details

You can view a standard online report for the upload exception details of the interface in the 'File Process Report' screen.

You can invoke this screen by typing 'GIRFILOG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "File Process Report" with the following fields and controls:

- Interface Code ***: A text input field with a dropdown arrow icon.
- Branch Code**: A text input field.
- File Name**: A text input field.
- Upload File Name**: A text input field with a dropdown arrow icon and a help icon.
- Process Ref No**: A text input field with a dropdown arrow icon.
- Status**: A text input field with a dropdown arrow icon.
- Start Date**: A date selection field with a calendar icon.
- End Date**: A date selection field with a calendar icon.

At the bottom right of the window, there are two buttons: "Ok" and "Exit".

You can filter the report based on below details:

Upload File Name

Select the name of the file for upload from the options maintained.

Branch Code

Select the branch code for file upload from the options maintained.

Interface code

Select the interface code of the upload file from the options maintained

Process Reference Number

Select the process reference number of the upload file from the options maintained

File Name

Select the file name from the options maintained

Start Date

Specify the start date

End Date

Specify the end date

Status

Select the status of the file from the option list maintained.

2.8 Integrating GI with EOD

During the EOD batch run, GI EOD process also gets invoked at every stage. GI EOD process would in turn check whether all the required interfaces are processed at that stage or not.

System executes the following GI processes as part of EOD operation:

- Processing unprocessed interface
- GI Batch

2.8.1 Processing Unprocessed Interface

GI EOD process checks if all the required interfaces are process at that stage. If any interface is not processed, system process these interface and if it's a mandatory interface system would wait till it processed.



If any mandatory interface is not processed before the respective stage then system would raise an error.

2.8.2 Processing GI Batch

Based on the interface frequency information and GI Batch would publish the Run-Chart for the present day run. Also it archives the interface data. GI Batch runs after Mark TI.

2.9 Global Variables and mask Attributes

The global variables and mask attributes used in the generic interface are explained here.

2.9.1 Global variables

The global variables used in the generic interface are explained below:

- @BRANCH – defaults the value to Current Branch of the User
- @BRANCHDATE – defaults the value to branch date.
- @LCY – defaults the value local currency of the branch
- @APPDATE – defaults the value application date
- @LENGTH – defaults the value length of the value of this field.
- @LENGTH ([COMPONENT_NAME]. [FIELD_NAME]) – defaults the length of the mentioned field and assigns to this field.
- @SUM ([COMPONENT_NAME]. [FIELD_NAME]) –defaults the sum of the field mentioned.
- @RECNUM () - defaults the number of rows of the mentioned component.

2.9.2 Mask Attributes

The mask attributes used in the generic interface are explained below:

- \$D - Date
- \$M - Month
- \$Y - Year
- \$H - Hour

- \$I - Minute
- \$S - Second
- / - will indicate the following character is a Constant

3. Screen Glossary

3.1 Function ID List

The following table lists the function id and the function description of the screens covered as part of this User Manual.

Function ID	Function Description
GIDAUDFM	AUDF Maintenance
GIDCRCFN	CRC Maintenance
GIDFILOG	File log Detailed
GIDFTPDP	File Transfer Definition
GIDIFPRS	Interface Trigger
GIDIFTDF	Interface Definition
GIDOBDEF	Object Definition
GIDPARAM	Parameters
GIRFILOG	File Process Report
GISAUDFM	AUDF Summary
GISCRCFN	CRC Summary
GISFILOG	File Log
GISFTPDP	File Transfer Summary
GISFTPLG	FTP File Log
GISIFTDF	Interface Definition Summary
GISOBDEF	Object Summary
GIDIFPRS	Interface Trigger
GISTRANS	Translation Summary



Generic Interface
[May [2011]
Version 11.3

Oracle Corporation
World Headquarters
500 Oracle Parkway
Redwood Shores, CA 94065
U.S.A.

Worldwide Inquiries:
Phone: +1.650.506.7000
Fax: +1.650.506.7200
[www.oracle.com/ financial_services/](http://www.oracle.com/financial_services/)

Copyright © [2011] Oracle Financial Services Software Limited. All rights reserved.

No part of this work may be reproduced, stored in a retrieval system, adopted or transmitted in any form or by any means, electronic, mechanical, photographic, graphic, optic recording or otherwise, translated in any language or computer language, without the prior written permission of Oracle Financial Services Software Limited.

Due care has been taken to make this document and accompanying software package as accurate as possible. However, Oracle Financial Services Software Limited makes no representation or warranties with respect to the contents hereof and shall not be responsible for any loss or damage caused to the user by the direct or indirect use of this document and the accompanying Software System. Furthermore, Oracle Financial Services Software Limited reserves the right to alter, modify or otherwise change in any manner the content hereof, without obligation of Oracle Financial Services Software Limited to notify any person of such revision or changes.

All company and product names are trademarks of the respective companies with which they are associated.