

Core Services
Oracle FLEXCUBE Universal Banking
Release 11.83.03.0.0
[November] [2016]
Oracle Part Number E80246-01



Table of Contents

1.	ABOUT THIS MANUAL.....	1-1
1.1	INTRODUCTION.....	1-1
1.2	AUDIENCE.....	1-1
1.3	ORGANIZATION.....	1-1
1.4	CONVENTIONS USED IN THIS MANUAL.....	1-3
1.5	RELATED DOCUMENTS.....	1-4
1.6	GLOSSARY OF ICONS.....	1-4
2.	BANK PARAMETERS.....	2-1
2.1	DEFINING BANK LEVEL PARAMETERS.....	2-1
2.1.1	<i>Specifying Details of Head Office Branch.....</i>	2-2
2.1.2	<i>Maintaining Financial Preferences.....</i>	2-2
2.1.3	<i>Generating Automatic Balancing Entries.....</i>	2-3
2.1.4	<i>Maintaining General Preferences.....</i>	2-5
2.1.5	<i>Placing User Restrictions on Data Entry Batches.....</i>	2-12
2.1.6	<i>Specifying UDF Details.....</i>	2-17
2.1.7	<i>Specifying Account Generation Parameters at Bank Level.....</i>	2-18
2.1.8	<i>Defining Bank-wide Preferences.....</i>	2-25
2.1.9	<i>Specifying Additional Preferences.....</i>	2-37
2.2	MAINTAINING DEPARTMENT DETAILS.....	2-38
3.	RAMADAN MAINTENANCE.....	3-1
3.1	INTRODUCTION.....	3-1
3.2	MAINTAINING RAMADAN DAY.....	3-1
4.	DEALER MAINTENANCE.....	4-1
4.1	DEFINING DEALER.....	4-1
5.	BRANCH PARAMETERS.....	5-1
5.1	CREATING BRANCHES.....	5-1
5.1.1	<i>System Features.....</i>	5-1
5.1.2	<i>Creating Reporting Structure.....</i>	5-2
5.1.3	<i>Basic Parameters for Branch.....</i>	5-4
5.1.4	<i>Maintaining General Details for Branch.....</i>	5-5
5.1.5	<i>Maintaining Financial Details for Branch.....</i>	5-10
5.1.6	<i>Maintaining Duplication Check Details.....</i>	5-16
5.1.7	<i>Maintaining SWIFT Address for Branch.....</i>	5-18
5.1.8	<i>Defining Account Mask.....</i>	5-19
5.1.9	<i>Maintaining Customer Number Range.....</i>	5-20
5.1.10	<i>Maintaining Global Interdict Functions.....</i>	5-22
5.1.11	<i>Maintaining Preferences.....</i>	5-23
5.1.12	<i>Maintaining LCY Message Preference for Branch.....</i>	5-31
5.1.13	<i>Specifying UDF Details.....</i>	5-33
5.1.14	<i>Specifying Cheque Book Preferences.....</i>	5-34
5.1.15	<i>Maintaining Department Restrictions.....</i>	5-35
5.2	DEFINING TRANSACTION CUT-OFF TIME.....	5-36
5.2.1	<i>Maintaining Cut-off Sources.....</i>	5-37
5.2.2	<i>Viewing Cut-off Source Details.....</i>	5-38
5.3	MAINTAINING VALUE DATE SPREAD FOR BRANCH.....	5-41
5.4	MAINTAINING INDEX CODES.....	5-42

5.5	MAINTAINING CPI RATES FOR A CURRENCY.....	5-43
5.6	MAINTAINING TILL PREFERENCES.....	5-44
5.7	MAINTAINING ADVICE SEQUENCE.....	5-45
5.8	MAINTAINING TAX CYCLE	5-47
5.8.1	<i>Updating Tax Cycle</i>	5-47
5.8.2	<i>Maintaining Tax</i>	5-48
5.8.3	<i>Maintaining Clearing Currencies</i>	5-49
5.8.4	<i>Account Statement Handoff</i>	5-50
5.8.5	<i>Account Statement Generation</i>	5-50
5.9	NOTARY CHARGES	5-51
5.9.1	<i>Setting Up Recovery of Notary Charges</i>	5-52
5.9.2	<i>Notary Charge Maintenance</i>	5-53
5.10	MAINTAINING ROLE TO HEAD MAPPING AT BRANCH LEVEL	5-54
5.10.1	<i>Viewing Accounting Role to Head Mapping Details</i>	5-56
5.10.2	<i>Enquiring Holiday Details</i>	5-57
6.	SYSTEM DATES MAINTENANCE	6-1
6.1	INTRODUCTION	6-1
6.1.1	<i>Maintaining Dates Change</i>	6-2
7.	ACCOUNTS FOR INTER-BRANCH TRANSACTIONS.....	7-1
7.1	DEFINING ACCOUNTS FOR INTER-BRANCH TRANSACTIONS	7-1
7.1.1	<i>System Features</i>	7-2
7.1.2	<i>Specifying Customer Accounts</i>	7-4
7.2	DEFINING ACCOUNTS FOR INTER-BRANCH FUND TRANSACTIONS	7-7
7.2.1	<i>Accounting entries in inter-branch accounting - An example</i>	7-8
7.2.2	<i>Maintaining Netting Group</i>	7-8
7.2.3	<i>Querying on Netting Batch</i>	7-11
8.	CURRENCY MAINTENANCE.....	8-1
8.1	INTRODUCTION	8-1
8.2	MAINTAINING CURRENCY DETAILS.....	8-1
8.2.2	<i>Specifying Exchange Rate Limits</i>	8-9
8.2.3	<i>Mapping Currency to Country</i>	8-9
8.2.4	<i>Specifying User Defined Fields</i>	8-10
8.2.5	<i>Annexure</i>	8-11
8.2.6	<i>Specifying Currency Cut-Off Parameters</i>	8-14
8.3	HANDLING EURO	8-15
8.4	MAINTAINING EURO RELATED INFORMATION.....	8-16
8.4.1	<i>Maintaining Currency Details</i>	8-16
8.4.2	<i>Maintaining Conversion GLs</i>	8-19
8.4.3	<i>Implications of Currency Redenomination</i>	8-20
8.4.4	<i>Specifying Preferred ERI Currency for Counterparty</i>	8-22
8.4.5	<i>Specifying Settlement Message Details</i>	8-23
8.4.6	<i>Settlements of Foreign Exchange Deals</i>	8-24
8.4.7	<i>Reports and Advices</i>	8-25
8.4.8	<i>Maintaining Limits Type</i>	8-25
8.4.9	<i>Maintaining Transaction Limits</i>	8-27
8.5	MAINTAINING SEQUENCE GENERATION FORMAT.....	8-29
8.6	MESSAGE DELIVERY IN ORACLE FLEXCUBE	8-33
9.	MAINTAINING CURRENCY DENOMINATION	9-1
9.1	INTRODUCTION	9-1
9.2	MAINTAINING CURRENCY DENOMINATION DETAILS	9-1
10.	EXPRESSING AMOUNTS IN WORDS	10-1

10.1	INTRODUCTION	10-1
11.	DEFINING CURRENCY PAIRS.....	11-1
11.1	INTRODUCTION	11-1
11.2	SYSTEM FEATURES	11-2
11.3	MAINTAINING PARAMETERS FOR CURRENCY PAIR	11-2
11.3.1	<i>Specifying Points Multiplier</i>	11-5
12.	MAINTAINING EXCHANGE RATES	12-1
12.1	INTRODUCTION	12-1
12.1.1	<i>Authorizing Exchange Rates</i>	12-4
12.1.2	<i>Revising Exchange Rates</i>	12-4
12.1.3	<i>Viewing Exchange Rates</i>	12-5
12.1.4	<i>Specifying Limits for Cross Currency Transactions</i>	12-6
12.2	MAINTAINING INDEX CURRENCY RATES	12-9
13.	MAINTAINING CURRENCY SPREAD FOR CUSTOMER.....	13-1
13.1	MAINTAINING CUSTOMER SPREAD DETAILS	13-1
13.1.2	<i>Computing Buy and Sell Spreads</i>	13-2
13.1.3	<i>Maintaining Currency Margins for Customer</i>	13-3
14.	DEFINING CURRENCY RATE TYPES.....	14-1
14.1	INTRODUCTION	14-1
15.	MAINTAINING RATE TEMPLATE	15-1
15.1	RATE TEMPLATE	15-1
16.	MAINTAINING FLOATING RATES	16-1
16.1	FLOATING RATES	16-1
17.	MAINTAINING PACKET TEMPLATES.....	17-1
17.1	INTRODUCTION	17-1
17.2	MAINTAINING PACKET TEMPLATES	17-1
17.2.1	<i>Specifying Account Details</i>	17-2
17.2.2	<i>Specifying Limit Details</i>	17-3
17.2.3	<i>Specifying Debit Card Details</i>	17-4
17.2.4	<i>Viewing Packet Template Details</i>	17-6
17.3	CREATING PACKETS	17-7
17.3.1	<i>Specifying Account Details</i>	17-9
17.3.2	<i>Specifying Limit Details</i>	17-11
17.3.3	<i>Specifying Debit Card Details</i>	17-12
17.3.4	<i>Viewing the Benefit Plan Details</i>	17-13
17.3.5	<i>Viewing Packet Creation Details</i>	17-14
18.	PERIOD CODE MAINTENANCE.....	18-1
18.1	INTRODUCTION	18-1
18.2	INVOKING PERIOD CODE MAINTENANCE SCREEN	18-1
18.3	SYSTEM FUNCTIONS	18-3
19.	STATUS CODE MAINTENANCE.....	19-1
19.1	INTRODUCTION	19-1
19.2	INVOKING STATUS MAINTENANCE SCREEN.....	19-1
19.2.1	<i>Maintaining Status Codes for Contracts</i>	19-3
19.2.2	<i>Viewing Restrictions</i>	19-4
19.2.3	<i>Maintaining Status Codes for OD Account</i>	19-4
19.3	MAINTAINING DORMANCY PARAMETER DETAILS	19-5

19.4	MAINTAINING CR\DR STATISTICS DETAILS.....	19-7
20.	TRANSACTION CODE MAINTENANCE.....	20-1
20.1	INTRODUCTION.....	20-1
20.2	MAINTAINING TRANSACTION CODE.....	20-1
20.2.1	<i>Maintaining Transaction Details.....</i>	<i>20-2</i>
20.2.2	<i>Maintaining Transaction Tax Details.....</i>	<i>20-11</i>
20.3	MAINTAINING GMF TAX PREFERENCES.....	20-12
20.3.1	<i>Specifying Tax Details.....</i>	<i>20-12</i>
20.3.2	<i>Maintaining Country Name Details.....</i>	<i>20-13</i>
21.	REASON CODE MAINTENANCE.....	21-1
21.1	INTRODUCTION.....	21-1
21.2	MAINTAINING REASON CODE.....	21-1
21.3	MAINTAINING REVERSAL/REASON CODE.....	21-2
22.	ACCOUNT REVALUATION MAINTENANCE.....	22-1
22.1	INTRODUCTION.....	22-1
23.	MAINTAINING BRANCH HOLIDAYS.....	23-1
23.1	INTRODUCTION.....	23-1
23.2	INVOKING LOCAL HOLIDAY SCREEN.....	23-1
23.2.1	<i>Steps to Define Yearly Holidays.....</i>	<i>23-2</i>
23.2.2	<i>Defining Holidays.....</i>	<i>23-3</i>
23.2.3	<i>Annual Holidays.....</i>	<i>23-3</i>
23.2.4	<i>Designating Unexpected Holidays for Branch.....</i>	<i>23-3</i>
24.	MAINTAINING CURRENCY HOLIDAYS.....	24-1
24.1	INTRODUCTION.....	24-1
24.2	INVOKING CURRENCY HOLIDAY SCREEN.....	24-1
24.2.1	<i>Steps to Define Currency Holidays.....</i>	<i>24-2</i>
24.2.2	<i>Defining Currency Holidays.....</i>	<i>24-2</i>
24.3	UPLOADING HOLIDAY FILE.....	24-3
25.	MAINTAINING CLEARING HOLIDAYS.....	25-1
25.1	INTRODUCTION.....	25-1
25.1.1	<i>Steps to Define Clearing House Holidays.....</i>	<i>25-2</i>
25.1.2	<i>Defining Clearing House Holidays.....</i>	<i>25-2</i>
25.1.3	<i>Designating Unexpected Holidays for Clearing House.....</i>	<i>25-2</i>
26.	DOCUMENT MAINTENANCE.....	26-1
26.1	INTRODUCTION.....	26-1
26.2	MAINTAINING DOCUMENT CATEGORY DETAILS.....	26-1
26.3	VIEWING DOCUMENT CATEGORY DETAILS.....	26-2
26.4	MAINTAINING DOCUMENT TYPE.....	26-3
26.5	VIEWING DOCUMENT TYPE DETAILS.....	26-3
26.6	MAINTAINING DOCUMENT CHECKLIST DETAILS.....	26-5
26.7	VIEWING DOCUMENT TYPE DETAILS.....	26-6
27.	CONFIGURING OVERRIDES.....	27-1
27.1	INTRODUCTION.....	27-1
27.1.1	<i>Types of Overrides.....</i>	<i>27-1</i>
27.2	SPECIFYING OVERRIDE TYPE.....	27-2
27.2.1	<i>Maintaining Override Conversion.....</i>	<i>27-3</i>
28.	MAINTAINING FEATURES.....	28-1

28.1	INTRODUCTION	28-1
28.2	MAINTAINING FEATURE ID	28-1
28.2.1	<i>Specifying UDF Values</i>	28-3
28.3	VIEWING FEATURE ID SUMMARY	28-4
29.	PURGING DATA	29-1
29.1	INTRODUCTION	29-1
29.2	MAINTAINING PURGE DETAILS	29-2
30.	TANKING OF MAINTENANCE RECORDS.....	30-1
30.1	INTRODUCTION	30-1
30.2	TANKING NEW AND MODIFIED MAINTENANCE RECORDS	30-1
30.2.1	<i>Tanking New Records</i>	30-2
30.2.2	<i>Tanking Modified Records</i>	30-2
30.2.3	<i>Closing a Record</i>	30-2
30.2.4	<i>Re-opening a Record</i>	30-2
30.2.5	<i>Authorizing a Record</i>	30-2
30.2.6	<i>Deleting a Record</i>	30-2
30.2.7	<i>Viewing Summary of Records</i>	30-2
30.2.8	<i>Modifying Tanking Preferences</i>	30-3
31.	EXTERNAL DEAL MAINTENANCE.....	31-1
31.1	INTRODUCTION	31-1
32.	ANNEXURE B - FILE FORMATS.....	32-1
32.1	INTRODUCTION	32-1
32.2	UPLOAD FILE FORMATS	32-1
33.	ANTI-MONEY LAUNDERING REPORTING	33-1
33.1	GUARDING AGAINST MONEY LAUNDERING	33-1
33.1.1	<i>Creating Product Categories in Oracle FLEXCUBE</i>	33-1
33.2	MAINTAINING LIMIT CODES	33-4
33.3	MAINTAINING ANTI MONEY LAUNDERING CUSTOMER GROUPS	33-5
33.4	MONITORING AML ACCOUNTING	33-8
34.	DEVELOPER AND DEVELOPER PROJECT MAINTENANCE	34-1
34.1	INTRODUCTION	34-1
34.2	MAINTAINING DEVELOPER DETAILS	34-1
34.2.1	<i>Viewing Project Details</i>	34-3
34.2.2	<i>Viewing UDF Details</i>	34-3
34.3	VIEWING DEVELOPER MAINTENANCE SUMMARY	34-4
34.4	MAINTAINING DEVELOPER PROJECT DETAILS.....	34-5
34.4.1	<i>Viewing UDF Details</i>	34-6
34.5	VIEWING DEVELOPER PROJECT MAINTENANCE SUMMARY.....	34-7
35.	PROJECT FINANCING.....	35-1
35.1	INTRODUCTION	35-1
35.2	PROCESSING FINANCE FOR PROJECT.....	35-1
35.3	MAINTAINING PROJECT FINANCING TRANSACTION.....	35-5
35.3.1	<i>Specifying the Project Details</i>	35-5
35.3.2	<i>Specifying the Main Details</i>	35-7
35.3.3	<i>Specifying Milestones Details</i>	35-9
35.3.4	<i>Specifying the Venture Details</i>	35-10
35.3.5	<i>Specifying PPC Limits Details</i>	35-11
35.3.6	<i>Specifying Non PPC Limits Details</i>	35-13
35.4	MAINTAINING PPC.....	35-15

35.4.1	<i>Specifying PPC Maintenance Details</i>	35-15
35.4.2	<i>Specifying Joint Venture Details</i>	35-17
35.4.3	<i>Maintaining PPC Liquidation</i>	35-18
35.5	VIEWING DASHBOARD DETAILS.....	35-19
35.5.1	<i>Viewing PPC Details</i>	35-20
35.5.2	<i>Viewing Limit Details</i>	35-21
35.5.3	<i>Viewing Commitment Details</i>	35-22
35.5.4	<i>Viewing Loan Details</i>	35-23
35.6	QUERYING DASHBOARD DETAILS.....	35-24
35.7	QUERYING ACCOUNTING ENTRIES.....	35-25
36.	ERROR AND ERROR CODES FOR PROJECT FINANCING	36-1
36.1	ERROR AND ERROR CODES.....	36-1
37.	REPORTS	37-1
37.1	INTRODUCTION.....	37-1
37.2	LIST OF DELETED TRANSACTIONS.....	37-1
37.2.1	<i>Contents of Report</i>	37-3
37.3	ACCOUNTING JOURNAL.....	37-4
37.3.1	<i>Contents of Report</i>	37-5
37.4	CASH FLOW REPORT.....	37-7
37.4.1	<i>Contents of Report</i>	37-8
37.4.2	<i>Cash Flow (Summary) Report</i>	37-9
37.5	FUTURE DATED ACCOUNT BALANCE REPORT.....	37-9
37.6	CURRENT RATES REPORT.....	37-10
37.6.1	<i>Contents of Report</i>	37-11
37.7	RATE HISTORY REPORT.....	37-12
37.8	ACCOUNT OPENING CONFIRMATION.....	37-13
37.8.1	<i>Contents of the Report</i>	37-13
37.9	ACCOUNT CLOSING CONFIRMATION.....	37-14
37.9.1	<i>Contents of Report</i>	37-14
37.10	ACTIVITY JOURNAL REPORT.....	37-15
37.10.1	<i>Contents of Report</i>	37-15
37.11	CORE EXCEPTION REPORT.....	37-16
37.11.1	<i>Contents of Report</i>	37-16
37.12	UNCOLLECTED FUNDS REPORT.....	37-17
37.12.1	<i>Contents of Report</i>	37-18
37.13	REVALUATION REPORT.....	37-18
37.13.1	<i>Contents of Report</i>	37-19
37.14	ACCOUNTS MOVEMENT REPORT.....	37-20
37.14.1	<i>Contents of Report</i>	37-21
37.15	CUSTOMER DETAILS REPORT.....	37-21
37.15.1	<i>Contents of Report</i>	37-22
37.16	CUSTOMER ACCOUNTS REPORT.....	37-23
37.16.1	<i>Contents of Report</i>	37-23
38.	SCREEN GLOSSARY	38-1
38.1	FUNCTION ID LIST.....	38-1

1. About this Manual

1.1 Introduction

This manual is designed to help you quickly get acquainted with the Core Services module of Oracle FLEXCUBE.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of day operators	Processing during end of day/ beginning of day
Financial Controller/Product Managers	Generation of reports

1.3 Organization

The manual is organized in the following manner:

Chapter 1	<i>About this Manual</i> gives a brief introduction of the module, the audience it addresses and the organization of the various chapters. It also includes the list of related documents to be referred, if any, and the conventions used in the document
Chapter 2	<i>Bank Parameters</i> explains the maintenance of various basic details about your bank
Chapter 3	<i>Ramadan Maintenance</i> explains maintenance of <i>Ramadan</i> year.
Chapter 4	<i>Dealer Maintenance</i> explains how you can capture profiles of dealers involved in buying and selling of foreign exchange

Chapter 5	<i>Branch Parameters</i> explains the process of creating and maintaining branches of your bank, with all necessary details
Chapter 6	<i>System Dates Maintenance</i> explains how you can maintain system dates for the branches of your bank
Chapter 7	<i>Accounts for Inter-Branch Transactions</i> explains how you can maintain internal accounts for branches involved in inter-branch transactions
Chapter 8	<i>Currency Maintenance</i> explains the process of maintaining currencies in the system, with all necessary static attributes
Chapter 9	<i>Maintaining Currency Denomination</i> explains the maintenance of standard currency denominations for each currency
Chapter 10	<i>Expressing Amounts in Words</i> describes the details of maintaining amounts in words
Chapter 11	<i>Defining Currency Pairs</i> explains the maintenance of static attributes for currency pairs for which exchange rate quotes are available
Chapter 12	<i>Maintaining Exchange Rates</i> explains the maintenance of exchange rates used to buy and sell currencies one for another
Chapter 13	<i>Maintaining Currency Spread for a Customer</i> explains the maintenance of currency spread and margin details for a customer
Chapter 14	<i>Defining Currency Rate Types</i> explains the maintenance of different types of currency rates applicable to the different transaction categories in your bank
Chapter 15	<i>Maintaining Rate Template</i> explains the maintenance of rate template
Chapter 16	<i>Maintaining Floating Rates</i> explains the maintenance of floating rates for a currency
Chapter 17	<i>Maintaining Packet templates</i> explains the maintenance for creation/association of products as part of a package
Chapter 18	<i>Period Code Maintenance</i> explains the maintenance of financial periods into which each financial cycle is to be divided
Chapter 19	<i>Status Code Maintenance</i> explains the maintenance of codes that you can assign to the different statuses that a contract or a customer account can attain
Chapter 20	<i>Transaction Code Maintenance</i> explains the maintenance of codes that you can use to represent different types of transactions
Chapter 21	<i>Reason Code Maintenance</i> explains the maintenances for reason codes
Chapter 22	<i>Account Revaluation Maintenance</i> explains the maintenance of parameters for account revaluation

Chapter 23	<i>Maintaining Branch Holidays</i> explains the maintenance of the holiday calendar for the different branches of your bank
Chapter 24	<i>Maintaining Currency Holidays</i> explains the maintenance of the holiday calendar for the different currencies in which your bank transacts
Chapter 25	<i>Maintaining Clearing Holidays</i> explains the maintenance of the holiday calendar for the different clearinghouses with which your bank transacts
Chapter 26	<i>Document Maintenance</i> explains the various document categories, type of document to be submitted, and the document checklist to be maintained.
Chapter 27	<i>Configuring Overrides</i> details on configuring overrides of the system
Chapter 28	<i>Maintaining Features</i> explains the method of installing features in a branch to improve the performance of the system during online or batch processes.
Chapter 29	<i>Purging Data</i> explains the details of purging data
Chapter 30	<i>Tanking of Maintenance Records</i> explains the process of tanking maintenance records.
Chapter 31	<i>External Deal Maintenance</i> explains the process of capturing deals booked in an external system.
Chapter 32	<i>Annexure B – File Formats</i> contains a list of file formats
Chapter 33	<i>Anti-Money Laundering Reporting</i> explains the process of guarding against money laundering, a facility provided by Oracle FLEXCUBE
Chapter 34	<i>Developer and Developer Project Maintenance</i> explains how you can maintain details of the real-estate developer and developer projects
Chapter 35	<i>Project Financing</i> explains the process of project financing and the maintenances
Chapter 36	<i>Error and Error Codes for Project Financing</i> details the error and error codes related to project financing
Chapter 37	<i>Reports</i> explains the procedure of generating Reports.
Chapter 38	<i>Screen Glossary</i> lists the function id and the function description of the screens covered as part of this User Manual

1.4 Conventions Used in this Manual

Important information is preceded with the  symbol.





1.5 Related Documents

- The Procedures User Manual
- The Settlements User Manual

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	New
	Copy
	Save
	Delete
	Unlock
	Print
	Close
	Re-open
	Reverse
	Template
	Roll-over
	Hold
	Authorize
	Liquidate
	Exit
	Sign-off
	Help
	Add row

Icons	Function
	Delete row
	Option List
	Confirm
	Enter Query
	Execute Query

Refer the Procedures User Manual for further details about the icons.

2. Bank Parameters

2.1 Defining Bank Level Parameters

In the 'Bank Wide Parameters' screen, you maintain basic information about your bank such as its name, head office, account number structure, local currency and so on.

The details that you maintain in this screen will be made applicable to all branches of your bank. For instance, the account number structure that you define in this screen will be a common format for customer accounts in all branches of your bank.

Invoke the 'Bank Parameters' screen by typing 'STDBANKP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Bank Parameters Maintenance' window. It has a title bar with a diamond icon and standard window controls. The main area contains several sections of input fields. The top section has 'Bank Code *' and 'Name'. Below that is 'Head Office Branch' and 'Code *', with 'Description' to the right. A tabbed interface is present with 'Financial Preferences' and 'General Preferences'. Under 'Financial Preferences', there are 'Bank Default Currency Codes' with sub-fields 'Local *', 'Discount *', 'Head Off *', and 'Reporting *', each with a 'Description' field. Below this are 'Control Accounts For Real Entries' and 'Control Accounts for Contingent Entries', each with 'Currency Mismatch Control Account' and 'Value Date Mismatch Control Account' fields. At the bottom left are 'Clearing Bank Code' and 'Routing Mask'. At the bottom right is a checkbox for 'Auto Generate Currency Mismatch Entries'. The bottom of the window has a dark bar with tabs: 'Account Mask', 'Preferences', 'Fields', and 'Additional Preferences'. The 'Preferences' tab is selected and shows 'Input By', 'Date Time', 'Authorized By', 'Date Time', 'Modification Number', 'Authorized', 'Open', 'Ok', and 'Exit' buttons.

You can maintain the following details in this screen:

Bank Code

In Oracle FLEXCUBE a bank is identified by a unique four-character code. You can follow your own convention in devising this code. In all inter-bank transactions this code identifies your bank.

Name

You can also specify the detailed name of the bank. This name will always be displayed whenever the bank code is used.

2.1.1 Specifying Details of Head Office Branch

After specifying a code to identify your bank, you should specify details of the head office of your bank.

Code

From the list of the branches you have already maintained of your bank, designate one as your Head Office

Description

The description of the branch designated as Head Office is displayed.

2.1.2 Maintaining Financial Preferences

In this screen, you can maintain information regarding default currency for the branch, specify if balancing entries must be automatically generated in case of mismatches, define routing mask, clearing bank code etc.

2.1.2.1 Specifying Default Currency Codes

You can indicate currency preferences for your bank. You can specify preferences to indicate the default currencies for the following purposes:

- **Local** – The currency that you indicate as the local currency will be taken as the local currency for all branches of your bank and the default currency for all transactions input into Oracle FLEXCUBE. The income and expense balances of your bank will also be maintained in this currency
- **Discount** – If the discount rate for a particular currency is not maintained the discount rate of the specified discount currency will be picked up for discounting profits on forward foreign exchange contracts
- **Head Office** – The default currency for the Head Office
- **Reporting** – The default currency in which all financial reporting should be done

You will not have an option to modify the default currencies that you specify after the Bank Parameters record has been stored and authorized.

Auto Generate Currency and Value Date Mismatch Entries

You can specify that balancing entries must be generated automatically by Oracle FLEXCUBE, in the case of currency or value date mismatches in accounting entries due to transactions that are not balanced with respect to currency or value dates, for each branch (single entity) of your bank.

To specify the automatic generation of such balancing entries for currency mismatches, select the options 'Auto Generate Currency Mismatch Entries' and for generation of balancing entries to correct value date mismatches, select 'Auto Generate Value Date Mismatch Entries' in the Bank Wide Parameters screen.

If indicated in the Bank Wide Parameters, balancing entries will be automatically generated for any event if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, with the exception of manually entered journal entries.


2.1.2.2 Specifying Control Accounts for Auto Balancing Entries (Real and Contingent)

If you specify that such automatic balancing entries must be generated, you can also specify the control accounts into which the entries must be booked.

There are two sets of accounts that you can maintain in the Bank-Wide Parameters screen, one for mismatches arising out of entries to real accounts and another for mismatches arising out of entries to contingent accounts. The relevant Control accounts must therefore be of Real or Contingent nature (as defined in the GL – Chart of Accounts). Such balancing entries will be automatically generated if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, except Journal Entry.

In your Chart of Accounts, you must ensure that the following conditions are not indicated for the control accounts that you have specified for the currency mismatch and value date mismatch entries:

- Position accounting: Even if position accounting is set to 'Yes' for the control account, the system will not pass any position accounting entries, since position accounting is done only for the main set of entries and not for the auto-balancing entries.
- Account revaluation: Account revaluation must be set for the control accounts since the effect of revaluing these balances would be offset the effect of revaluing the original GLs. (the GLs into which the main entries were posted).
- Direct posting: If you post a manual entry to one of the Control Accounts and the Position Entry Flag for the Control Account is set to 'Yes', then the system will do position accounting for that entry. Hence, for the GLs set-up as Control Accounts, the 'Direct Posting' flag in the Chart of Accounts maintenance must be turned OFF.

 Additionally, it is also recommended that these Control Account GL's that you have specified in the Bank Wide Parameters screen for the mismatch entries are not used as part of Role to Head Mapping in any of the products. If maintained, the system would pass mismatch adjustment entries into the same GLs in which the main entries have been passed. There is no system-enforced validation of this and this aspect needs to be taken care of during Product set-up.

2.1.3 Generating Automatic Balancing Entries

In the case of transactions entered in any of the front-end modules of Oracle FLEXCUBE, the accounting process checks the entries at each business event, and automatically generates the balancing entries in case of a mismatch in currency or value date entries (or both).

Manually Entered Journal Entries

In the case of manually entered journal entries, a journal batch that has been opened must be closed before it is authorized. During closure, the accounting process checks to see that the batch is balanced with respect to currency and value date entries. If a mismatch is detected, the accounting process raises an override to this effect. Depending upon how the override is configured, for your bank, the user who has opened the batch could adopt either of the following courses of action:

- If the override is configured to be an error, the system will not allow the user to close the batch without balancing the mismatches.
- If the override is configured to be a warning (either 'Override' or 'Ignore'), the user can save the batch with the mismatches. No balancing entries are automatically generated by the system for the mismatch.

Uploaded Journal Entries

In the case of uploaded journal entries, a journal batch that has mismatched entries is not rejected, but an override is raised by the accounting process. Depending upon how the override is configured, for your bank, the accounting process takes either of the following paths:

- If the override is configured to be an error, then the batch is rejected, and must be uploaded again with the corrected entries.
- If the override is configured to be a warning, the accounting process automatically generates the balancing entries for the currency or value date mismatches, for the batch, and posts them to the requisite control accounts specified in the Bank Parameters.

In each case, the transaction reference for the balancing entries is the same as that of the original accounting entry, in which the mismatch occurred, and the other details of the balancing entries are, by default, the corresponding values in the original entries.

The mismatch balancing entries are generated in the following order or preference:

- Currency mismatch balancing entries
- Value Date mismatch balancing entries

In the case of mismatches in accounting entries due to inter-branch transactions, the inter-branch balancing entries are generated before any balancing entries for currency mismatches, and then, finally, the value date mismatches.

Routing Mask

A mask defines the manner in which a Routing Number is generated for your bank. It is on the basis of the routing number that Oracle FLEXCUBE processes clearing transactions.

The following is a typical mask format: 'BBBbbbSSS', wherein, 'BBB' indicates the bank code, 'bbb' indicates the branch, and 'SSS' indicates the sector to which the branch belongs. On the basis of the routing number, clearing transactions are routed to the appropriate branch of your bank.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

2.1.4 Maintaining General Preferences

In this screen, you can define format masks (for general ledger, CIF), choose if batch numbers should be auto-generated by the system, specify the details for cheque numbering etc.

The screenshot shows the 'Bank Parameters Maintenance' window with the 'General Preferences' tab selected. The window contains several sections for configuration:

- Bank Code *** and **Name** text boxes.
- Head Office Branch** section with **Code *** and **Description** text boxes.
- Financial Preferences** and **General Preferences** tabs.
- Format Masks** section with **CIF Mask**, **General Ledger Mask ***, and **Account Sequence** (dropdown menu set to 'Bank Level').
- Year End Profit and Loss** section with **General Ledger *** and **Transaction Code *** text boxes.
- Spread** section with **Spread Application** (dropdown menu), **Spool File Purge Days**, and **Inter Pay Lead days** text boxes.
- Cheque Numbering Details** section with **Scheme** (dropdown menu).
- General Ledger Purge Days** section with **General Ledger Purge Days** text box and checkboxes for **Auto Batch**, **User Restriction For Batch Number**, **SSO Enabled**, and **Lodgment Numbers**.
- Checksum Algorithm** (dropdown menu).
- Account Mask**, **Preferences**, **Fields**, and **Additional Preferences** tabs at the bottom.
- Input By** and **Authorized By** text boxes with **Date Time** labels.
- Modification Number** text box.
- Authorized** and **Open** checkboxes.
- Ok** and **Exit** buttons.

2.1.4.1 Defining Format Masks

A format mask is a structure that you can define for various elements that need to be entered in Oracle FLEXCUBE. You can define format masks for the following elements:

- General Ledgers
- Customer Identification File codes
- Customer account numbers

Once defined, you can modify the structure of a format mask only if no Customer or General Ledger Account has been opened using the mask. Customer Account mask is defined from the 'Account Mask' Button.

For more details on defining customer account mask, refer the section titled 'Specifying Account Generation Parameters at Bank Level'.

CIF Mask

You can maintain a mask for generation of identification numbers (CIF Number) for customers of your bank. During customer information maintenance, the system will automatically generate the CIF numbers based on the mask you define here and the customer number range maintained at the branch level.

A CIF mask consists of a maximum of 9 digits. The CIF mask could have only numbers or could be alpha numeric or could also have the branch code as a part of it.

For instance, you can maintain the CIF Mask as 'bbbnnnnn' where 'bbb' represents a three-digit branch code and 'nnnnn' represents a 6-digit number.

GL Mask

You can indicate a mask for the general ledgers that are maintained for your bank. The mask that you define here will be enforced whenever a General Ledger is created in the Chart of Accounts screen.

A GL mask can consist of a maximum of nine alphanumeric characters. It can be built using a combination of numbers and letters to indicate for instance, the category of the GL - asset, liability etc., the GLs hierarchical position and so on.

Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate 'a'. To represent a number, indicate 'n'. The last character would be a D or d, which indicates a check digit generated by the system. For a numeric check digit define it as 'd'; for an alphanumeric check digit define it as 'D'.

You may use any of the following punctuation in the GL mask:

- dash (-)
- comma (,)
- asterisk (*)
- Full Stop (.)
- Forward slash (/)

Example

You wish to create a two level GL structure for your bank. You could define the first two characters of the GL to represent the category asset, liability etc., aa; the next two characters, nn, to represent the first level GL; and the next three characters, nnn, to represent the second level GL. A GL based on the given structure would read as AS01001 where AS represents the GL category - asset; 01 represents the first level GL; 001 represents the second level GL.

For creating this structure you would define your GL mask as - aannnn'd/D'.

If you want to define your second level GL with a 4 digit numeric code instead of 3; other parameters remaining the same your mask would read as aannnnn'd/'D'.

Customer Account Mask

Specify the Customer Account Mask. You can maintain the following masks:

- KNNNNNNYYYYY
- LLLLLLnnnnnd
- nnnnnnnnnnd
- dnnnnnnnn

KNNNNNNYYYYY

This mask will be used by the system to generate an account number based on Julian date account mask. The system will generate the running sequence no from 000000 and will reset the sequence on the next day.

Where:

- K - is always zero
- NNNNNN - Running sequence number, which starts with 000000 and gets reset on the next day
- YYYYYY - System Date, where the first two digits belong to the year (from 06 to 99), and the last three belong to the days of the year (from 1 to 366)

Example

On 31st July, 2009 the Account number will be as below, assuming the running sequence number is 000100.

000010009212 (ANNNNNYYYYY)

LLLLLRRRRRd

This is an alphanumeric mask which will be used by the system to auto generate account numbers.

In this mask,

- LLLLLL - Account Class
- RRRRRR - Sequence Number
- d - Check digit

The running sequence number is unique across the bank or each branch depending on the parameter maintained in 'Account Sequence' field in this screen.

If the account generation is at bank account class level then for the first account in an account class, the start value of the sequence will be considered. For subsequent accounts in the same account class, the maximum value of the sequence for that account class across branches will be incremented by 1 to get the sequence value for the account.

If the account generation is at branch account class level then for the first account in an account class in a branch, the start value of the sequence maintained at branch level will be taken. For subsequent accounts in the same account class and branch, the maximum value of the sequence for the combination of branch and account class will be incremented by 1 to get the sequence value for the account.

Example: Suppose there are 3 branches - BR1, BR2 and BR3 and there are 2 Account Classes for Current Accounts - CTCTE1, CTCTE2. Assume that the Start Sequence Number has been maintained as 0000001 at bank level and for each of the branches too.

Based on the above conditions, following combinations are possible for bank level account generation:

Bank	Branch	Account Class	Auto Generated Customer Account
BXX	BR1	CTCTE1	CTCTE1 0000001 (DV)
BXX	BR2	CTCTE1	CTCTE1 0000002 (DV)
BXX	BR3	CTCTE1	CTCTE1 0000003 (DV)
BXX	BR1	CTCTE2	CTCTE2 0000001 (DV)
BXX	BR1	CTCTE2	CTCTE2 0000002 (DV)
BXX	BR2	CTCTE2	CTCTE2 0000003 (DV)
BXX	BR3	CTCTE2	CTCTE2 0000004 (DV)
BXX	BR2	CTCTE2	CTCTE2 0000005 (DV)

If the account generation is at the branch level the combinations will be as below:

Bank	Branch	Account Class	Auto Generated Customer Account
BXX	BR1	CTCTE1	CTCTE1 0000001 (DV)
BXX	BR2	CTCTE1	CTCTE1 0000001 (DV)
BXX	BR3	CTCTE1	CTCTE1 0000001 (DV)
BXX	BR1	CTCTE2	CTCTE2 0000001 (DV)
BXX	BR1	CTCTE2	CTCTE2 0000002 (DV)
BXX	BR2	CTCTE2	CTCTE2 0000001 (DV)
BXX	BR3	CTCTE2	CTCTE2 0000001 (DV)
BXX	BR2	CTCTE2	CTCTE2 0000002 (DV)

RRRRRRRRRRRRd

This is a numeric mask which will be used by the system to auto generate account numbers.

In this mask,

- RRRRRRRRRRRR - Sequence Number
- d - Check digit

The running sequence number is unique across the bank or each branch depending on the parameter maintained in 'Account Sequence' field in this screen.

If the account generation is at the bank level then for the first account of that bank, the start value of the sequence number maintained at bank level will be considered. Subsequently, the maximum value of the sequence across branches will be incremented by 1 to get the sequence value.

If the account generation is at branch level then for the first account of that branch, the start value of the sequence number maintained at branch level will be considered. Subsequently, the maximum value of the sequence for the branch, irrespective of the account class, will be incremented by 1 to get the sequence value.

Example: Suppose there are 3 branches - BR1, BR2 and BR3 and there are 2 Account Classes for Current Accounts - CTCTE1, CTCTE2. Assume that the Start Account Number has been maintained as 100000000000 at bank level and for each of the branches too.

Based on the above conditions, following combinations are possible for bank level account generation:

Bank	Branch	Account Class	Auto Generated Customer Account
BXX	BR1	CTCTE1	100000000000 (DV)
BXX	BR2	CTCTE1	100000000001 (DV)
BXX	BR3	CTCTE1	100000000002 (DV)
BXX	BR1	CTCTE2	100000000003 (DV)
BXX	BR1	CTCTE2	100000000004 (DV)
BXX	BR2	CTCTE2	100000000005 (DV)
BXX	BR3	CTCTE2	100000000006 (DV)
BXX	BR2	CTCTE2	100000000007 (DV)

If the account generation is at the branch level the combinations will be as below:

Bank	Branch	Account Class	Auto Generated Customer Account
BXX	BR1	CTCTE1	1000000000000 (DV)
BXX	BR2	CTCTE1	1000000000000 (DV)
BXX	BR3	CTCTE1	1000000000000 (DV)
BXX	BR1	CTCTE2	1000000000001 (DV)
BXX	BR1	CTCTE2	1000000000002 (DV)
BXX	BR2	CTCTE2	1000000000001 (DV)
BXX	BR3	CTCTE2	1000000000001 (DV)
BXX	BR2	CTCTE2	1000000000002 (DV)

dnnnnnnnnnn

The system will use this account mask to auto generate account number based on 20 digit account mask.

In this mask,

- d - Check digit (generated by the system)
- nnnnnnnnnn - Running serial number

The running serial number will be used for generating the 20 digit account mask as follows:

A	B	C	D	E
---	---	---	---	---

Where:

- A - 4 digit bank code
- b - 4 digit branch code
- d - Check digit based on A and B (generated by the system)
- D - Check digit based on B and E (generated by the system)
- N - 10 digit Running Serial Number

Here, ABC will be the Checksum left mask that you have specified at branch parameters level. The running serial number will be taken from the customer account mask (dnnnnnnnnnn) maintained in 'Branch Parameters Maintenance' screen. Thus, the account number will be generated by concatenating account number prefix, check digit and the running serial number.

Account Sequence

Select the account sequence from the drop-down list. You have the following options:

- Bank level
- Branch level
- Bank Account Class level
- Branch Account Class level

Based on your selection, the system will generate the account numbers at bank level, branch level, and so on.



The options 'Bank Account Class Level' and 'Branch Account Class Level' will be applicable only if you have specified the Customer Account Mask as 'AAAAbbbbdDNNNNNNNNNN'.

2.1.4.2 Indicating Year-end Profit & Loss

General Ledger

At the end of any financial year the balances in the income and expense accounts are posted by Oracle FLEXCUBE into a separate year-end account for the purpose of consolidation of balances and turnovers. This account is called the Year End profit and loss General Ledger Account.

You also specify year-end profit and loss GL for each GL account you maintain in the 'Chart of Accounts' screen. The year-end account specified at the bank level is the default year end profit and loss GL for all GL accounts maintained in the 'Chart of Accounts - GL' screen. If you do not specify the account to which year end balances of a particular GL should be posted, it will be posted to the bank's year-end profit and loss account.

You can select a GL code from the option list of all assets, liabilities, income and expense GLs maintained in the chart of accounts screen.

Transaction Code

Indicate the transaction code that should be used to post the balances in the income and expense accounts to the year-end GL account.

You can select a transaction code from the list of transaction codes maintained in the 'Transaction Code Maintenance' screen.

Spread

Capture the following details.

Spread Application

Indicate the transaction legs for which the spread should be applicable. Choose the appropriate option from the following available in the adjoining drop-down list:

- Single Leg
- Both Legs

Spool File Purge Days

Specify the duration for which spool files should be stored in the spool file directory.

Interpay Lead Days

Specify the inter-pay lead days required for fetching billing records for inter-pay files for automatic billing of clients..

Auto Batch

Each time you post journal and multi offset entries, you need to open a batch. You can specify that the batch numbers of the journal entry batches opened in your bank should be generated automatically by enabling the Auto Batch option.

Consequently, the system automatically generates batch numbers while posting journal and multi offset entries.

2.1.5 Placing User Restrictions on Data Entry Batches

You can restrict the usage of batches to specific user by placing bank-wide User level batch restrictions. If you enable this option as a Bank Parameter, you need to allocate the batch number range for each user through the 'Batch Restriction Maintenance' screen.

The restriction on the usage of batch numbers is made applicable on data entry and PC transactions. The user will be allowed to enter only those batches reserved for the user profile. As a result, each time a user specifies a batch number; it will be validated against the 'Allocated Batch Number Range'.

This feature is applicable only when batch generation is manual. Therefore, if you enable this option, you must ensure that the Auto Generate option has not been enabled. In a scenario where the User Restriction for Batch Number field is enabled and Auto Batch option has also been enabled, the following error message will be displayed:

Not a Valid Batch Number For the User


In case you choose to auto generate batch numbers, the System will not perform the batch restriction validation.

You can invoke the 'Batch Restrictions Maintenance' screen by typing 'STDBREST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Allocated Batch Number Range		
<input type="checkbox"/>	Start Number *	End Number
<input type="checkbox"/>		
<input type="checkbox"/>		

Specify the following details in this screen:

- The User Profile for which the restrictions are being maintained. A list of all the User Profiles with access rights to the DE and PC modules is displayed in the option list. You can select the appropriate.
- The branch of your bank for which the restrictions will be made applicable. You can either choose a specific branch or make the restriction applicable to 'All' the branches of your bank.
- The module for which you are maintaining the Allocated Batch Number Range. This can either be PC or DE.
- The batch number range, which is indicated in terms of Start and End numbers. The range that you specify is allocated to the user. For distinct numbers, the start number and end number of the range will be the same.

 While processing DE and PC transactions, the batch number specified by the user is validated against the allotted range. If the validation fails, an error message is displayed.

These validations are made applicable even during the Batch Upload operations for the following functions:

1. Journal Online – Single Entry
2. Multi-offset Entry

3. Teller Transaction Input

SSO Enabled

To enable Single Sign On (SSO) for your installation check the SSO Enabled check box. This enables restricted login from external systems into Oracle FLEXCUBE.

General Ledger Purge Days

You can specify here the maximum number of working days, the average GL balance computation for which is to be retained in the System.

2.1.5.1 Specifying Cheque Numbering Details


Scheme

In Oracle FLEXCUBE, cheque numbers can be generated automatically or can be manually entered. If you indicate manually, you can draw up numbering conventions and assign numbers to the cheques that are issued.

Checksum Algorithm

If you choose the automatic generation option you can indicate the algorithm based on which the cheque digit should be generated. A cheque number consists of three components:

- A check digit
- A cheque type
- A running serial number



You have the option to choose the algorithm to be used to arrive at the check digit. Currently Oracle FLEXCUBE supports only the Modulo-7 algorithm. Based on this algorithm the check type and serial number is divided by seven, and the remainder is taken to be the check digit. If the remainder is zero, then the check digit is set to seven.

The cheque type indicates whether the cheque is a Euro or Commercial cheque. The numeral 1 before a cheque serial indicates a Euro cheque and 2 indicates a Commercial cheque.

The cheque serial number is generated sequentially starting from 0001. This running serial number is assigned taking into account the last check number issued for the account.

Cheque Numbers Unique For Branch

For cheque numbers that are automatically generated, you can choose to make cheque numbers unique across the branches of your bank.

If you indicate that serial numbers need not be unique, you can have the same cheque number assigned to cheque leaves of different accounts within a branch. In effect cheque numbers remain unique to an account.

Lodgment Numbers Unique for Branch

You can indicate whether lodgment leaves must have unique numbers in a branch, or must be unique for individual accounts.

Example

In the Bank Wide Parameters, you have specified that lodgment book numbers must be unique for the branch. This means that lodgment numbers need to be unique across all accounts of that branch. For instance, if a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of any other account, with these numbers.

If you have specified that lodgment book numbers must be unique to accounts in the branch, and a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of the same account, with these numbers. However, you can start a book with the same numbers in respect of another account in the branch.

2.1.5.2 Specifying TRS Details

You can maintain the following details that will be used by the system to raise direct debit for Tax Relief at Source (TRS) rebate availed by customers on mortgage loans. The direct debit is raised during the End of Day (EOD) process after the LD batch processes.

Sort Code

Specify the destination bank code for which the bank raises direct debits for TRS claims.

Account Number

The destination account for which the bank raises direct debits for TRS claims.

Payment & Collection Product Category

Specify the Payments and Collections (PC) product category that would be used by the bank to raise direct debits for TRS claims.

Suspense Account

Specify the account that would be debited with the TRS amount, to credit customer account.

For more details about processing for TRS, refer the Loans module user manual and the Payments and Collections user manual.

2.1.5.3 Viewing Trade License Details

Expiry Advice Generation Days

If the trade license is set to expire on a particular date, the number displayed here denotes the number of days before that date when an advice is generated and sent to the customer informing about the impending expiration.

2.1.5.4 Specifying Mandatory Limit Tracking For Customer Type

You can maintain limit tracking as a mandatory option based on the customer type.

Corporate

Check this box if it is mandatory to link customer of Corporate type to credit line.

Bank

Check this box if it is mandatory to link customer of Bank type to credit line.

Individual

Check this box if it is mandatory to link customer of Individual type to credit line.



If a contract is saved without selecting the limit line for customers checked for mandatory limit tracking, then the system displays the following error message:

Limit tracking is mandatory for this customer <Customer CIF>


2.1.5.5 Specifying Cheque Discounting Details

Cheque Return Count for Drawer Blacklisting

The system displays the number of cheque returns for a drawer. During the cheque return processing, the system check the number of cheque returns against this maintenance and marks the drawer as 'Blacklisted' drawer.

2.1.6 Specifying UDF Details

You can associate values to all the User Defined fields created and attached to the Bank Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button. The screen appears as shown below:




You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

2.1.7 Specifying Account Generation Parameters at Bank Level

Account numbers in your bank are generated in the format of the account mask that you specify through the 'Account Parameters' sub-screen of the Bank-wide Parameters screen. Click 'Account Mask' button in the Bank-wide Parameters screen. Account Parameters screen is displayed. The screen appears as shown below:



STOP Since account level parameters are defined at the bank-level, by default these parameters will be defaulted to all the branches of your bank. However, individual branches of your bank will be allowed to change these specifications.

2.1.7.1 Specifying Customer Account Mask

Account numbers can either be generated automatically or you can choose to allocate them manually. In Oracle FLEXCUBE you have the option of maintaining three types of account masks.

They are as follows:

- Alphanumeric – this type of an account mask is a combination of alphabets and numbers where you can build the mask with components such as the Branch Code, the Account Class, the Currency Code, a check digit, etc
- Numeric - is a numeric type of account mask where the checksum algorithm associated with the account mask is either Modulo 11, Modulo 11 with weights or Modulo 97.
- Pure Numeric – is a numeric type of account mask, which does not have a checksum algorithm, associated with it. If you are maintaining a pure numeric mask you have to identify the start and end account number which is to be associated with it.

Alphanumeric Customer Account Masks

The alphanumeric customer account mask can have a maximum of twenty alphanumeric characters. It can comprise of one or more of the following elements in combination:

- **Account Class** — Use 'AClass' to indicate that the account class to which the account belongs should be part of the mask.
- **CIF Number** — You can incorporate the nine-character CIF code assigned to the customer into the mask. To do so indicate 'CIF Number' in the mask.
- **Currency** — To add the currency of the customer account, use 'CCY'
- **To indicate an alphabet or number** — Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate 'a'. To represent a number, indicate 'n'.
- **Punctuation Marks** — When defining the customer account mask you have the option of separating the elements. To do this, you may use the following punctuation marks:
 - Dash (-)
 - Comma (,)
 - Asterisk (*)
 - Full stop (.)
 - Forward slash (/)
- **For Check Digit** - The last character in the customer account mask should always be a 'D' or 'd'. This indicates the check digit, which is generated by the system. When specified in the mask, the check digit component is generated using either of the following methods:
 - Modulo 11
 - Modulo 97
 - Modulo 11 with Weights
 - User Defined Algorithm

If you choose Modulo 97, all components of the account mask (for example, the Branch Code, the Account Class, the CIF ID, etc.) should be numeric. For example, if you enter 'bbb' in the account mask field (indicating that the branch code should be part of the account number), and choose the Modulo 97 option, ensure that the branch code is a numeric value, such as '000', '123', etc.



The maximum length of twenty characters for the customer account mask is inclusive of the check digit

All customer accounts that are entered in any branch of your bank will compulsorily have to conform to the mask.

Example

You want the following elements to be part of the customer account mask:

- The currency of the account
- The nature of the account (savings, current etc.) and
- The Customer Id

Given the above criteria the customer account mask would be:

AClassCCYcIFNUMBERn'D'

This corresponds to:

LLLLL\$\$\$CCCCCND

All customer accounts entered in any branch of your bank would now comprise of these elements, in the order defined in the mask.

A customer with CIF number 10005 has opened his first USD savings account with your bank, and the Account class for savings accounts is INDSB. His account number would read:

INDSB-USD-10005-01'D'

Similarly, the second GBP current account of a corporate customer with CIF Number 20005, would read

CUCOR-GBP-20005-02'D'

'CUCOR' being the account class representing current accounts of corporate customers.

Customer Account Number Containing a UDF Value

While defining a customer account if you include 'U' in the account mask, it indicates that the customer account numbers will have the value of a user-defined field.

The number of U's will depend on the length of the UDF value that has to be included in the customer account number. For example, if you want to include 3 characters from a UDF, the account mask should consist of UUU (in addition to other parameters which you want to include in the customer account numbers).



Note the following:

- A user-defined field can be part of the customer account mask only if the customer account number generation is not automatic.
- Since a customer account number in Oracle FLEXCUBE can accommodate only up to 20 characters you have to ensure that the account mask you have defined does not exceed this number.

Numeric Account Masks with Modulo 11 and Modulo 97 as Checksum Algorithms

A numeric type of mask can have a maximum of twenty numeric characters, inclusive of the checksum algorithm.

If you associate Modulo 11, as the checksum algorithm, a single character D will be appended to the numeric mask. Let us assume that you have an account mask with five numeric values – 'nnnnn' and associated Modulo 11 as the checksum algorithm. The system automatically appends 'D' to the numeric mask. The generated account numbers will have the following format – nnnnD.

Similarly, if you associate Modulo 97, with an account mask of five numeric values, the system appends a double-digit value of DD to the mask. The generated accounts will have the following format – nnnnDD.

Numeric Account Masks with 'Modulo 11 with Weights' as Checksum Algorithm

The account mask with 'Modulo 11 with Weights' algorithm can have a maximum of 13 digits. It comprises of the following elements:

- Branch Code (3 digits) – Indicates the branch at which the customer account is maintained.
- Account Code (1 digit) – This will indicate the account code of the account class to which the customer account belongs. During account number generation (in the Customer Account Maintenance screen), you need to select the account class from the option-list provided. The system will then convert it to the account code maintained for that account class. The account code thus becomes a part of the customer account number.
- Currency Type (1 digit) – This will represent the currency type of the account currency. As explained for account code, you will select a 3-digit currency code during account generation. The system will convert it to the currency type maintained for that currency. The currency type will then form a part of the account mask.
- CIF Number – You can also include the CIF number of the customer as part of the account mask. The CIF number is automatically generated by the system when you capture customer details in the Customer Information Maintenance screen. During customer account maintenance, you can select the CIF number from the option list provided.
- Sequence Number (1 digit) – The sequence number is automatically generated by the system for a combination of account code + currency type + customer. This means that, for this combination, you can maintain nine accounts. To maintain the 10th account for the same combination, the system will use the 'Dummy Customer No. Range' maintained at the branch level'.

Refer the section titled 'Creating Branches' of this document for more details on dummy number range.

- Control Number (1 digit) - This is the 13th digit of the account number. This number is also automatically generated by the system based on the 'Modulo 11 with Weights' algorithm.

For the above combination, the customer account mask would be:

'bbbTZCCCCCSd'

Where,

- bbb – is the branch code

- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm

The following example illustrates the manner in which the system calculates the 13th digit for a customer account number using the 'Modulo 11 with Weights' algorithm.

Assume that the account number of a customer is '000-4-1-123456-1'. As per this algorithm, the value of each position (1 to 12) is multiplied with the weight for each position (the weights are provided by your bank). Further, the sum of the product obtained is divided by 11. The remainder of the division will determine the value of the 13th digit.

The position-wise weight and account number and the product (of weight and number) is as follows:

Position	1	2	3	4	5	6	7	8	9	10	11	12
Weight (W)	2	4	8	5	10	9	7	3	6	2	3	5
Acct. No (N)	0	0	0	1	2	3	4	5	6	4	1	1
Product (W * N)	0	0	0	5	20	27	28	15	36	8	3	5

Sum of the product = 147.

Divide the value 147 by 11 to obtain the remainder

Remainder = (147/11) = 4

As per this algorithm, if the remainder is 10, then the control number will be zero. If it is any value other than 10, the remainder itself will be taken as the control number.

Therefore, the 13th digit = 4.

The customer account number will now read as '**000-4-1-123456-1-4**'

Numeric Account Masks with User Defined Algorithms as Checksum Algorithm

If the check digit component within a Customer Account Number is to be generated using a method of your choice you must identify the following:

- The User Defined Algorithm for the Customer Account Number – this identifies the name of the user-defined algorithm for check digit generation of account numbers.
- The User Defined Algorithm for Consumer Number – this stores the name of the user-defined algorithm for validating consumer numbers.

While capturing Customer Account numbers, the System checks for your specification for the checksum algorithm. If you have selected User Defined, the check digit is generated using the specified user-defined algorithm.



Since these parameters are maintained for your bank, they are defaulted to the branches of your bank. You will not be allowed to change these for a specific branch of your bank.

Pure Numeric Masks

A numeric account mask, which does not have a checksum algorithm associated with it, is called a pure numeric mask. Since it does not have a checksum algorithm associated with it you will have to specify the start and end account numbers and enable the auto-generated option.

The start account number forms the basis on which customer accounts numbers are to be generated. Similarly, you will not be allowed to maintain account numbers beyond the end account number.

Let us assume, that you are have maintained the following details in the Account Parameters screen at your bank:

Customer Account Mask	nnnnn
Start Account Number	1
End Account Number	50000
Cust Acc Auto Generate	Yes

While generating a new account number the system will automatically generate 00001 corresponding to nnnnn. The next account will be – 00002.

Including Value of a UDF as Part of Customer Account Number

If your bank has not opted for automatic generation of account numbers, you can specify a structure for customer account numbers. The structure can be a combination of CIF number, account class, value of a user defined field, currency, branch code, alphabets/numeric and a check digit which is automatically generated by the system.

Example for an account mask is CCCCCCLLbbbUUU\$\$\$ad.

This implies that a customer account number will contain:

- CIF Id – represented by C
- Account Class represented by L
- Branch Code represented by b
- Values of a user defined field represented by U
- Any user-input alphabet represented by a (enter 'n' if you want to include a numeric)
- Currency Code represented by \$\$\$
- A check digit (which is automatically generated by the system) represented by 'd'



The number of C's in the account mask should match with the CIF mask that you have specified. For instance, if the CIF mask is aaaannn (7characters), the account mask should consist 7 C's to include the CIF Id in the customer account number.

The value of a user-defined field can be used to include an additional parameter (for example: the code of the country to which the customer belongs) in the customer account number.

The steps involved for including the value of a user-defined field in a customer account number are as follows:

1. Include 'U' in the customer account mask to indicate that the customer account number should contain the value of a UDF
2. Create a new user defined field
3. Link it to the Function Id STDCIF
4. Specify the value of the user defined field at the time of creating a customer
5. Specify the UDF whose value has to be included in the customer account number to the Oracle FLEXCUBE implementer. The implementer will indicate this at the back end.

Maintaining Ten Digit Masks with Running Sequence Numbers

You can maintain a 10-digit mask of any combination, wherein the last two digits will necessarily be a running sequence number. This number will be automatically generated by the system. For instance, if you want to maintain a mask for the customer number and currency combination followed by the two digit running number, you will have to maintain the mask as CCCCC\$\$\$SS. Here, CCCCC stands for the customer number, \$\$\$ stands for the currency of the account and SS stands for the running number. The system will generate the last two-digit number in a continuous sequence irrespective of the combination that you specify in the mask.

Example

Let us assume that you want the customer account number to be a combination of the customer number and the account currency followed by the serial number. To achieve this, you have to specify the mask as CCCCC\$\$\$SS. Based on this mask, for a customer with CIF ID 40207 with account in USD, the account number will be 40207USD01. If the same customer has another account in GBP, the next account number would be 40207GBP02. That is, there will not be any holes in the system generated running number.

2.1.7.2 Specifying Auto Account Creation Parameters

You may wish the system to automatically create current accounts for customers at the time of loan initiation. These system-created current accounts are for use as settlement accounts.

Here, you need to specify the range of numbers available for such auto created accounts by mentioning a start and an end number.

If you wish to retain the facility of auto creation of current accounts at loan initiation, you will have to ensure that the account number mask does not have any user input character.

2.1.8 Defining Bank-wide Preferences

In the Bank-Wide Preferences screen, you can specify the following:

- The route of inter-branch accounting — through HO, through RO or directly between branches
- Exchange rate preferences — to be maintained for the bank as a whole or at each branch
- Preference relating to update of GL balances — on-line or at the End of day
- Preference relating to Position Accounting
- Interface details

Click the 'Preferences' button to invoke the 'Preferences' screen.

The screenshot shows the 'Preferences' dialog box with the following sections and options:

- Interface Details**
 - Journal Account: _____
 - Width: _____
- Inter Branch Scheme**
 - Inter Branch Entity: [Dropdown]
 - Inter Branch Account: [Dropdown]
 - Schedule: [Dropdown]
- Fund Inter Branch Scheme**
 - Inter Branch Account: [Normal] [Dropdown]
 - Schedule: [Dropdown]
 - Inter Branch Entity: [Dropdown]
- Preferences**
 - Online General Ledger Update
 - Auto Generate CIF Numbers
 - Copy Exchange Rates to Branches
 - Position Accounting Required
 - Propagate Customer Address to Nodes
 - Propagate CIF to other Nodes
 - Propagate Bank Instruction Codes Details to Nodes
 - Pair wise Positioning Required
 - Branch wise Limits
 - Limits History Required
 - Daily MIS Refinancing
 - Propagate Floating Rates to Branches
 - Allow Inventory Tracking
- Node wise CIF mask Maintenance**
- Buttons: Ok, Exit

Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Through HO' to indicate that inter-branch transactions should be settled through the Head Office
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch

The receivable and payable accounts between the branches, referred to as 'due from' and 'due to' accounts, are maintained in the 'Inter-branch parameters' screen.

Example

Suppose the University Savings Bank has the following set up for its head office and branches in Headington, Oxford:

- Roosevelt Avenue Branch, is the HO with Branch Code 000
- Foxlake Drive Branch (Branch Code 001)
- Mountainwood Road branch (Branch Code 002)

You have indicated that inter-branch transactions should be routed through the Head Office. Ms. Tanya Agnihotri has an account in Branch 002. She makes a cash withdrawal from Branch 001. This being an inter-branch transaction, Branch 001 will have to recover the money from Branch 002.

In this example the following movement of funds is involved:

- At Branch 001, the cash account is credited for the transaction amount and due from Head Office account debited.
- At Branch 000, the due from Branch 002 is debited and the due to Branch 001 is credited.
- At Branch 002, the Customer Account is debited and the due to Head Office account credited

Inter Branch Entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch transactions to either of the following:

- Customer Accounts
- General Ledgers
- Both

If you select Customer Accounts as an inter-branch entity, you can specify the currency and the actual customer accounts involved in an inter-branch transaction between two branches of your bank. If the inter-branch entity is specified as 'General Ledgers', you need to specify the internal accounts that would be involved in a transaction between two different branches of your bank. If you select 'Both' option, it indicates that inter branch accounting entries could be posted for both GL and Customer accounts.

Fund Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch fund transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Normal' to indicate the inter-branch routing defined for corporate transactions will be applicable to the inter-branch fund transactions as well.
- Choose 'Through HO' to indicate inter-branch transactions should be settled through the Head Office.
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO.
- If you specify 'Through RO and HO', the accounting entries would be routed through the Regional Office of the first branch, then the Head Office. From the Head Office, the entries would be routed through the Regional Office of the second branch.
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch.

The receivable and payable accounts between the branches, referred to as due from and due to accounts, are maintained in the 'Inter-branch parameters' screen.

Inter Branch entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch fund transactions to a General Ledger that you have specified.

If you choose '**Normal**' as the inter-branch routing, and you have not selected the option 'Allow Corporate Access' in the Branch Parameters screen, the Inter Branch transfer options you have chosen will be used.

If you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the entity will be defaulted as General Ledger. The GL will be based on the maintenance you have carried out in the Fund Inter Branch Accounts Maintenance screen, for the fund id. The same is explained in the chapter **Accounts for Interbranch transactions**.

Online GL Updates

The update of GL balances can take place either on-line or during End of Day. For an on-line update select this checkbox.

Auto-generate CIF Numbers

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

Copy Exchange Rates to Branches

Exchange rates are maintained for a currency pair and are used to calculate the equivalent of one currency against the other. These exchange rates can be maintained in each branch or at the Head office. You can indicate your preference.

If you check against the option 'Copy to Branches' the exchange rates maintained at the Head Office will be made applicable to all branches of the bank. Leave it unchecked to indicate that exchange rates should be maintained at each branch.

Position Accounting Required

You can retrieve the position of a foreign currency, any time, by opting for position accounting in your bank. When you opt for position accounting, you maintain a Position GL and a Position Equivalent GL for every foreign currency maintained in your bank. The Position GL reflects the current position of the currency.

If you opt for position accounting while defining Bank-Wide Parameters, you have to maintain Position GLs and Position Equivalent GLs for every foreign currency that your bank deals in. When maintaining GLs for your bank, you can opt to link the different currencies, associated with the GL to either of the following:

- The Position GLs that you have specified for the currency (Your specifications in the Currency Definition screen will default here)
- Position GLs of your choice

Daily MIS Refinancing

As part of setting up the bank level preferences you can indicate whether MIS refinancing processing is required on a daily basis for the particular branch of your bank.

If you indicate that MIS refinancing should be done on a daily basis, refinance processing will be done on a daily basis for the following modules:

- Loans and Deposits
- Money Market



You can indicate the rate type that is to be used for individual LD, and MM transactions while processing the contract.

Propagate Floating Rates to Branches

You have to indicate whether the floating rates maintained at the head-office of your bank should be propagated across all the branches of your bank.

Check the box positioned next to this field to indicate that floating rates need to be propagated across branches. Consequently, each time you maintain a floating rate for a particular rate code and currency combination at your bank, a corresponding floating rate record will be created and sent to all the branches of your bank.

Allow Inventory Tracking

You can use this check box to allow/disallow inventory management and tracking. To use inventory management module, check this box.



If inventory tracking is allowed then 'Cheque Numbering Scheme' should be left blank/null.

Check this box for inventory passbook maintenance. If this is not checked, in that case, the user has to manually enter the passbook number at the customer Account maintenance screen

For more details on Inventory Tracking, refer the Instruments Inventory Tracking User Manual.

Limits History Required

You can indicate whether date-wise limits history needs to be maintained for the Bank. If you choose to enable this option, the limits history is maintained at the following levels:

- Liability level history for storing liability records
- Limit level history for storing Lines records
- Line level history for storing Line Utilization records

Conditions for collating Limits History data:

- There is no retrospective effect on limits history.
 - Back-valued contracts and account transactions do not result in any adjustment to the previous records in the history. Such transactions are inserted with the current EOD date. Similarly any future-dated contracts and account transactions are also inserted with the current EOD dates.
 - In cases where the main line is changed to a sub line, the utilization is transferred from the old main line to the new main line and the effect cascades to the ultimate parent line. But existing records are not changed or updated.
 - Existing data will not reflect the change in the liability number for a customer.
- Revaluation has no effect on the limits history data
- Limits history is not maintained country-wise

The data is archived during the EOD processing. The history data is not updated for holidays.



If there is no change for a liability/limit/line, data is not archived for that day

The example below illustrates the functionality:

* All the Currencies are in USD

Customer	Liability	Liability Amount
Cust1	Cust1	100000
Account	Credit Line	Limit Amount
Acct1	Line 1	60000
Acct2	Line 2	40000

Case I

On Day 1, which is 1st Jan 2001, No Transactions have been processed. Therefore no data is stored in any of the history tables.

Case II

On Day 2, which is the 3rd of Jan 2001 (2nd Jan 2001 was a holiday) no transactions have been processed in the System. Therefore data is not stored in any of the limits history tables.

Case III

On Day 3, which is The 4th of Jan 2001, transactions have been processed in the System. The data in the History tables after the EOD will be as follows:

Account	Type of transaction	Debit Amount	Contract Ref No
Acct1	Journal Entry	10000	ACCT1
Acct1	Loan	20000	Laon1

Liability History

History Date	Overall Limit	Utilized Amount
4-Jan-2001	100000	30000

Lines History

History Date	Line	Limit Amount	Available Amount	Utilization
4-January-2001	Line1	60000	30000	30000
4-January-2001	Line2	40000	40000	0

Line Utilizations History

History Date	Reference No	Line	Amount	Liability Utilization
4-January-2001	Acct1	Line1	10000	10000
4-January-2001	Loan1	Line1	20000	20000

Further drill down to the contract screens/ account balances screen will be possible from the line utilization history level

Case IV

On Day 4, which is the 5th of Jan 2001, the following loan transactions have been processed in the System. The data in the History tables after the EOD processes will be as follows:

The value date of the contract is 2nd January 2001.

Account	Type of transaction	Debit Amount	Contract Ref No
Acct1	Loan	15000	LOAN2

The value date of the contract is 3th January 2001

Account	Type of transaction	Debit Amount	Contract Ref No
Acct2	Loan	6000	LOAN3

Liability History

History Date	Overall Limit	Utilized Amount
4-January-2001	100000	30000
5-January-2001	100000	51000

Lines History

History Date	Line	Limit Amount	Available Amount	Utilization
4-Jan-2001	Line1	60000	30000	30000
4-Jan-2001	Line2	40000	40000	0
5-Jan-2001	Line1	60000	15000	45000
5-Jan-2001	Line2	40000	34000	6000

Line Utilizations History

History Date	Reference No	Line	Amount	Liability Utilization
4-January-2001	Acct1	Line1	10000	10000
4-January-2001	Loan1	Line1	20000	20000
5-January-2001	Loan2	Line1	15000	15000
5-January-2001	Loan3	Line2	6000	6000



This option can be enabled or disabled at any point of time. Limits history will be recorded with effect from the day the option is enabled. Disabling the option will however not automatically purge history data.

You have the option of querying Liability history and drilling down to Limits Line history and further drilling down to Contract-wise Utilization history. Clean risk data is displayed only as of the date of query and history for the same is not maintained.

Branch wise Limits

This option indicates whether or not the limits tracking must be done at the branch level. If this box is checked, you will be allowed to view/change only the lines created from that branch for a given liability.

To illustrate, if you open any credit line facility in branch BR1, then in the Limit Restriction screen, the only branch available will be BR1.

Checking this option will also allow you to View details of line utilization at the branch level in the Limits Query screen.

Example

Consider that the Liabilities Liab 1, 2 and 3 are present and different branches want to open different lines under these liability numbers

Liab1	Line1	BR1
Liab2	Line2	BR2
Liab3	Line3	BR3

In the above case, line 1, line 2 and line 3 are opened in Branches 1, 2 and 3 respectively for liability numbers Liab 1, 2 and 3.

If the Branchwise Limits parameter specified at the bank level is checked, then the branch allowed for each of the above lines would default as the branch in which these lines are opened and you will not be able to change the branch restriction setting in the Limits Restrictions screen under Limits.

This in turn would restrict the above-mentioned lines for liability, to only the corresponding branch.

Example

For Liab1 Line1 BR1

The branch allowed would be BR1. Hence, during contract input, in BR1, you would be provided with only one option i.e. line1.

Now, if you wanted to use another line facility in Branch 1, you would have to open one more line called line4

You would not be allowed to use Line 2 or 3 because the branches allowed for these lines are BR2 and BR3 respectively.

Therefore, if the Branch-wise Limits option is checked at the Branch level, then the following becomes true:

Current Branch	Liability	Line	Branch Allowed
BR1	Liab1	Line1	BR1
BR1	Liab2	Line4	BR1

Current Branch	Liability	Line	Branch Allowed
BR2	Liab3	Line2	BR2
BR3	Liab4	Line3	BR3

The Branch Allowed would default as the current branch. If you are viewing the records, then the system would provide the records for the current branch only. As per this example, Line1 and Line4 would be available for View/change in branch BR1.

Similarly, if the Branch-wise Limit option is checked, the records related to the current branch would be shown in the Limits Summary View.

If Branch-wise Limits option is left unchecked, then the existing setup would hold good; that is, you would be able to see all the line facility records for any branch. You would also be able to utilize any line during contract input irrespective of the branch it was opened in.

With the above setup, Line Utilization would be tracked at the branch level but liability utilization would be tracked at instance level

To go back to the first example, if there are 3 instances, then for the 3rd instance, line 2 and line 3 would be tracked at branch BR2 and BR3 respectively. However, liability tracking would be a consolidation of line 2 and line 3.

Hence, Liability tracking would be at the instance level whereas line tracking would be at the branch level.

For a total utilization of a global customer maintained in HO, you would have to generate a report of the limit utilization for each instance.

Pairwise Positioning Required

You have to select this option to indicate whether pair wise positioning entries need to be stored/handed off or not. If selected, the system will store position creating pair entries separately for handoff to other external systems.

When processing accounting entries, the system will check whether you have opted for pair wise positioning. If you opt for this option, the system will check for the following conditions in all the accounting entries that are posted:

- The set of entries posted are balanced i.e. total LCY debit is equal to total LCY credit
- At least one pair of accounting entry is in FCY
- Both the currencies are not the same

If the above conditions hold true, the system will store the entries along with the following information:

- Dr. Account: indicates the debit leg's account GL
- Cr. Account: indicates credit leg's account GL
- Event Code: is the event of the transaction
- Dr CCY/Bought Currency
- Dr. Amount/Bought Amount

- Cr. CCY/Sold Currency
- Cr. Amount/Sold Amount
- Dr Booking Date/Cr Booking Date
- Dr Value Date/Cr Value Date
- Dr Transaction Code/Cr Transaction Code
- Exchange Rate
- Hand Off Flag



While passing pair wise position entries, the main component will be passed with TRF_AMT tag and the equivalent entry will be passed with the AMT_EQUIV tag.

Example

Let the local currency of your branch be JPY.

Dr/Cr	Acc/GL	Amount	Rate	LCY Eqv.
Dr	Loan GL	1000 USD	100	100,000 JPY
Cr	Customer Acc.	1600 EUR	62.5	100,000 JPY
Position Entries created				
Dr	Position Eqv.			100,000 JPY
Cr	Position	1000 USD	100	100,000 JPY
Dr	Position	1600 EUR	62.5	100,000 JPY
Cr	Position Eqv.			100,000 JPY

As seen in the table above, the actual loan disbursement entries have created an FCY position in both USD and EUR. Therefore, these two entries will be captured and stored separately as a single entry with the Dr currency (bought currency) as USD and Credit currency (sold currency) as EUR. The same would be applicable if FCY-LCY or LCY-FCY transaction is considered.

In case of accruals/revaluation also, if position entries are created, the corresponding entries will be stored separately for hand off.



Pair-wise Positioning Required will decide whether position creating pair entries need to be stored by the accounting processor separately for handing off to other system.

Propagate CIF to other Nodes

You need to indicate whether or not the CIF number maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the CIF number has to be propagated to other Nodes/instances.

Propagate Customer Addresses to Nodes

You need to indicate whether or not the customer addresses maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the Customer addresses has to be propagated to other Nodes/instances.

Propagate Bank Instruction Codes Details to Nodes

This indicates whether or not the BIC data maintained in HO has to be propagated to other branches present in different instances. Check this box to propagate BIC details.

Maintenance of Customer Identification Mask at Branch/Node level

This option gives you the flexibility to define different CIF masks at the Nodes/Bank level. If you select 'Bank' from the option list, then the CIF mask given at Bank level will be applied to all the branches under it.

Mudarabah Fund Shareholder Balance Type

Specify whether the system should consider the month-end balance or the monthly average balance of the GL to compute the shareholders' investment in the linked *Mudarabah* fund. Choose from the following options available in the drop-down list:

- Monthly Average Balance
- Month End Balance

The option specified here will be common to all the shareholder GLs identified under the *Mudarabah* fund and once *Mudarabah* fund shareholder balance type is input and authorized, it will not be allowed to modify later.

Staff Account Restriction Required


Check this option to apply staff account restriction at the bank level.

Auto Account Closure

Check this box to enable Account Auto Closure functionality.

If you select 'Node' from the option list, you will need to maintain CIF masks at the Node level in the 'Node-wise CIF Mask Maintenance' screen. This would ensure that the branches maintained in different nodes/instances have different CIF masks.

Click 'Nodewise CIF mask Maintenance' button to access this screen. The screen appears as shown below:



You can specify the following details here:

Nodes

This indicates the node/instance for which the CIF mask is required. Select a node from the option list provided.

Customer Identification File Mask


This indicates the CIF mask for the corresponding instance/node. Select a CIF mask from the option list provided.

Autogenerate Customer Identification File Number

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

2.1.9 Specifying Additional Preferences

You can maintain debit card preferences using 'Additional Preferences' screen. Click the 'Additional Preferences' button to invoke this screen.



You can specify the following details here:

Debit Card Details

Auto Generate Debit Card No

Check this box to indicate that the card number is to be generated automatically.

Debit Card Mask

The system generates the debit card mask number only if the check box 'Auto Generate Debit Card No' is checked. This field will contain 18 alphanumeric characters (BBBBBTDDNNNNNNNN). This field will only accept the characters 'B' (BIN Number), 'T' (Type), 'N' (Oracle Sequence number) and 'D' (Check Digit Number).

Auto Renewal of Cards

This box is checked by default; however you can uncheck this if required.

Collection Services Details

Collection Agreement Auto Gen

Check this box to indicate that the collection agreement ID has to be generated automatically. If this box is not checked, then it has to be entered manually.


Collection Agreement Mask

System displays the agreement mask as: 'JJJJJJSSSSS'. This is a read-only field.

2.2 Maintaining Department Details

Certain banking transactions are carried out through sub-divisions known as departments of the bank. You can maintain the details of such individual departments using 'Department Maintenance' screen.

To invoke the 'Department Maintenance' screen, type 'SMDDPTMT' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



The screenshot shows a window titled "Department Maintenance" with a blue header bar. Below the header, the text "Department Details" is followed by a horizontal line. Underneath, there are three input fields, each with a red asterisk indicating a required field: "Department Code *", "Department Short Name *", and "Department Description *". At the bottom of the window, there are two columns of fields. The first column has "Maker" and "Checker" labels. The second column has "Date Time:" labels. A "Cancel" button is located in the bottom right corner.

Specify the following details:

Department

Specify a unique department code. This code will be a unique identifier of the department you maintain.

Description

Specify a brief description of the department.

Country Code

Specify the Country code. Choose the appropriate one from the option list.

Once you have specified the details, save the maintenance.

3. Ramadan Maintenance

3.1 Introduction

Zakat is a charge which is applied on the balance in an account if the balance is above a certain threshold amount. This charge is applicable only to savings accounts and Term Deposits (TD). It cannot be levied on current accounts.

The minimum threshold amount above which *Zakat* will be payable is decided every year before *Ramadan*. In addition, the percentage to be applied on the capital amount for calculation of *Zakat* is also decided.

This charge is levied on the savings accounts and TD accounts at *Ramadan*. For savings accounts, *Zakat* is computed on the balance as on the first day of *Ramadan* for all active accounts. The applicable amount is then deducted from the accounts.

In the case of TD accounts, *Zakat* is computed whenever there is a redemption of the principal. It is computed on the redeemed principal amount, provided the first day of *Ramadan* (for any one year of the TD tenor) falls between the profit start date of the deposit and the maturity date.

For computation and collection of *Zakat* you need to capture the first day of Ramadan every year.

3.2 Maintaining Ramadan Day

You can capture the first day of *Ramadan* for a given year in the 'Ramadan Day Maintenance' screen. This is a bank-level maintenance that needs to be done at your Head Office. To invoke the 'Ramadan Day Maintenance' screen, type 'CSDRAMDN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Ramadan Day Maintenance". Inside the window, there are two input fields: "Year*" and "First Day of Ramadan". At the bottom of the window, there is a status bar with the following fields: "Date Time", "Authorized By", "Modification Number", and two checkboxes labeled "Authorized" and "Open". There are also "Ok" and "Exit" buttons.

Here you can specify the following details:

Year

Specify the year for which you are capturing the first day of *Ramadan*. Note that you cannot maintain multiple records for the same year.

First Day of Ramadan

Specify the date on which *Ramadan* starts in the specified year. Note that the date should be valid as per the *Ramadan* calendar.


Refer the chapters titled 'Defining the attributes specific to an Interest or Charge product' and 'Daily Processing of Interest and Charges' in the Interest and Charges User Manual for details on Zakat computation and application.

4. Dealer Maintenance

4.1 Defining Dealer

At the time of entering the details of a foreign exchange, money market, or securities deal, you will be required to enter details of the dealer who has struck the deal.

The dealers at your bank, who are associated with the buying and selling of foreign exchange, money or securities in the treasury, should each be assigned an identification number (ID number). The dealer list is maintained for the bank through the 'Dealer Maintenance' screen. Invoke this screen by typing 'STDDEALR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a window titled "Dealer Maintenance" with a close button (X) in the top right corner. Inside the window, there are two input fields: "Dealer Id *" with a red asterisk and a small red box, and "Dealer Name" with a yellow speech bubble icon to its right. Below these fields is a "Fields" section with a blue header. Under "Fields", there are several parameters: "Input By DOC7", "Date Time", "Modification Number", "Authorized" (with an unchecked checkbox), "Authorized By", "Date Time", "Open" (with a checked checkbox), and a "Cancel" button.

The following parameters need to be maintained to define a dealer ID:

Dealer Id

Enter a unique code to identify the dealer. The identification code can have a maximum of six alphanumeric characters.

The dealer will be identified by this code for all transactions entered in Oracle FLEXCUBE. You can also retrieve dealer-wise information on the treasury deals entered into by your bank.

Dealer Name

You can also enter a detailed name of the dealer. The name of the dealer will be displayed whenever the dealer Id is used.

5. Branch Parameters

5.1 Creating branches

In the 'Branch Parameters' screen you create the various branches of your bank, define their reporting hierarchy, and maintain parameters such as their names, their address of location, SWIFT, TELEX, and HOST addresses.


In this screen you can do the following:

- Create the Regional Offices and branches of your bank by assigning each a unique branch code
- Maintain the address of location of each of the branches and also their SWIFT, TELEX and HOST addresses
- Specify the Suspense GL for posting all those accounting entries for which no GL has been specified or the specified GL has been closed
- Define preferences, such as - the retention duration, a CIF number for walk-in customers and the GL for netting FX contracts
- Maintain customer number range for generation of CIF numbers for customers of your bank.

The HO creates the branches at the bank level. All subsequent modifications on the table are done from the respective branches.

5.1.1 System Features

Oracle FLEXCUBE supports a three level reporting structure.



At the top stands the Head Office followed by the Regional Offices. At the lowest level are the branches. There can be any number of branches, but the number of regional offices is restricted to six. The system validates to check that the number of parent branches is not more than six. If the number of parent branches is more than six, system will give an error and restrict the number to six.

The branches report to the RO; and the ROs in turn report to the HO. Within this three level structure you can also have a branch reporting independently to the Head office (as branch, BR7 in the diagram).

It is also possible to have a two level reporting structure with only the HO and the branches, where each individual branch reports directly to the HO.

5.1.2 Creating Reporting Structure

The order in which you create the HO, the ROs and the branches should follow the hierarchy. Hence, the first branch to be created should be the HO, followed by the ROs, and then the branches.


The Head Office of your bank is created during installation. You only have to create the Regional Offices and the various branches. During installation, the system automatically populates this screen with the branch code and name of your Head Office that you have specified to the CITIL implementer. The 'Parent branch' and the Regional Office fields' also default to this branch code.

To create an RO, invoke a new screen. Then, enter the code and name of the RO against 'Branch Code' and 'Name' respectively. You do not need to specify the 'Regional office' because the HO Code is the default for the field. (All ROs report to the HO).

Then create all the branches. If a branch reports to an RO, to specify that RO is the branch's 'Regional Office', select the code you want from the option list provided for this field.

But before designating, you should authorize all the RO records you have created; the system will not allow you to use any unauthorized record.

(Diagrammatic Representation)



5.1.3 Basic Parameters for Branch

In Oracle FLEXCUBE, the Head Office and the Regional Offices are defined as branches. You can maintain the details of the Head Office, regional offices and branches in the 'Branch Parameters Maintenance' screen. Invoke this screen by typing 'STDBRANC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details here:

Branch Code

This is the code you assign to the office or branch. The code acts as an identifier in the system for the office / branch. Input a code using a maximum of 3 characters, alphanumeric.

Branch Name

This is the name of the office or branch, the code of which is input. Enter the name using a max. Of 35 characters, alphanumeric

Branch Available

The system displays the Branch Available status. If the status is 'Yes', it indicates that the branch can accept transactions for the day and if the status is 'No' , then it indicates that the transactions will be accepted but it will be in effect only from the next business day.

Accordingly accounting entries will be passed checking the following, for tanking branch transactions:

- The Branch Available Status

- The Branch date and host date i.e. entries will be tanked if branch date is ahead of host date

When the Branch Available status is 'NO' or if branch date is ahead of host date, then the transactions will be tanked. These transactions will be untanked by the BOD program which runs post date change i.e. POSTDTCH.



If you want to check whether the transaction is tanked or not, you should login to host and refer to the corresponding query function.

For more information on 'Querying the Transactions' refer Retail Teller, Clearing and Utility Payment Chapters under Oracle FLEXCUBE host module.

5.1.4 Maintaining General Details for Branch

You can maintain the branch details regarding the local currency, the parent branch, regional office of the branch, address details including telex, BIC etc.

Local Currency

Specify the currency of operation for your branch and the default currency for all transactions of your branch. The income and expense balances of your branch will also be maintained in this currency.

Parent Branch

Parent Branch is to define an alternate reporting line, other than the three level HO-RO-Branch structure. The 'Parent' for all the branches you create is the HO code (default). To specify the Parent, other than the HO, select from the options displayed. The name of the parent branch is displayed alongside.

Regional Office

This is the branch code of the Head Office or Regional Office to which the branch (whose code is input eg. Branch Code) reports.

For a Head Office or a Regional office, this code should be the Head Office branch code, which is also the default for this field. For the branches, specify that branch as the RO, to which the branch reports. Select from the list of options displayed.

Country Code

Specify the code of the country in which the branch operates. Select from the options provided in the pick list

Customer Identity

Specify the customer's identity.

GL Class

Specify the GL Class. The adjoining option list displays a list of all the valid GL class codes and their description. You can choose the appropriate one.



You can also select 'ALL' as an option. This indicates that all the GL codes are allowed for this branch.

City Code

Specify the city code from the adjoining option list.

5.1.4.1 Specifying ATM Details

Specify the following details

ATM Branch

Specify the ATM branch.

Institution Identification

Your bank may have a branch or multiple branches for different countries. You have to capture the identification code that uniquely identifies your bank branch in the ATM transactions interchange environment. Specify a code to identify the institution. This institution ID will help identify whether a particular transaction has been sent from an external network or whether it has originated from your bank branch.

Inter Branch Transaction Code

You can specify the Transaction Code through which accounting entries for inter-branch transactions should be settled.

Customer Transfer

Check this option to indicate that transfer transaction should be permitted through the ATM

5.1.4.2 Specifying Address Details

For each branch of your bank you maintain the following parameters:

Branch Address

Input the address of location of the branch. Each line can have a maximum of 35 characters.

BIC

Input the SWIFT address for a branch using 8 or 11 characters, alphanumeric

Telex

Specify the branch's TELEX address, using a maximum of 14 characters, alphanumeric

Host Name

Against 'HOST' enter the name of the Host server for this branch, in not more than 35 characters, alphanumeric

Time Level

In this field is displayed the system time level status, represented by a number between 0 and 9

In Oracle FLEXCUBE, user access to the system can be controlled by assigning each user and the system, a time level. Both the system and the users are set to different time levels. Only those users who have a time level equal to or greater than the system time level can log into the system.

A control clerk, during the EOC process, does the change in time level status

Fund Branch

Even though the fund and the bank are in the same database, the fund is treated as a different legal entity and as such the books of the fund are maintained separately from those of the bank. Funds are created in a separate branch and any transaction initiated in the fund branch belongs to a fund. Check this box to indicate that the branch you are maintaining if is a fund branch. Since the fund is a different legal entity, it should not be possible to initiate inter-branch accounting entries from the fund branch.

Any settlement with an external entity is routed through the normal settlements interface. In order to facilitate this, all the account fields in the system accept only the accounts in the transaction branch, if the branch happens to be a fund branch.

Allow Corporate Access

Select this option to specify that the fund subscription/redemption operations in the fund branch can access the accounts of corporate branch.



Note the following:

- You will not be allowed to change this field once the branch record has been authorized.
- This field will be enabled only if the branch is a fund branch.

External Value

Specify the name of the branch as maintained in an external system. This value can be used to interface with the external system.

EOC Status

Under EOC status one of the following alphabets will be displayed which stand for the following:

- **B** - Beginning of financial input; indicates system transactions in progress
- **I** -- Indicates that user transactions are in progress
- **T**-- End of user transaction input; indicates system transactions in progress
- **F** -- End of financial input; system transactions also completed
- **E** -- End of Day, Branch awaiting date change

The values are updated by EOC process.

5.1.4.3 Specifying Time Zone Offset

For branches with different time zones, you can define the offset time that is to be displayed in maker/checker stamp and all the reports generated for the branch.

The offset time is specified in terms of hours and minutes, and the time will be added/subtracted from the Server Time maintained for the bank.

Hours

Specify the number of hours to be offset from Server Time to arrive at the local branch time

This is the number of hours by which the branch leads or lags behind the Server Time

Minutes

Indicate the additional minutes by which the branch leads or lags behind the Server Time



The reference of time is always the System Time (Server Time)

Ahead

The system calculates the local time of the Branch by adding/subtracting the Server Time and the Time Zone Offset time. When you maintain the offset time for the time zone, you need to specify whether the system should add or subtract the offset time from the Time Zone Offset.

Checking the Ahead box indicates that the offset time is added to the Server Time. Consequently, if the box is unchecked, the offset time is subtracted from the Server Time.

Additionally, the system validates the cutoff time depending on the time you specify here. The validation is based on following 3 parameters:

- Cutoff Time maintained for the currency in Currency Definition Screen
- Cutoff Offset Time maintained for the Branch in Branch Parameters Screen
- Time Zone Offset maintained for Branch in Branch Parameters Screen

5.1.4.4 Indicating Cutoff Offset Time

When defining a currency, you can indicate a cut-off time for the currency. If your bank operates in branches located in different time zones, the cut-off time maintained for the bank will not be applicable across branches.

Therefore, you can set up an offset time for your branch based on the cut-off time set for the bank. You can specify an offset time for your branch in the Branch Parameters screen.

Hours & Minutes

The offset time is expressed in hours and minutes. The time you specify here is added or subtracted from the cut-off time maintained for the bank. This depends on the time difference between your branch and the Head Office.

The following example demonstrates time zone offset time and cutoff offset time:

Assume:

Head Office: '000'

Branch: 'XYZ'

'000' and 'XYZ' are located in places falling under different Time Zones.

For '000', 'Cut Off Time' for Currency 'INR' (specified in Currency Definition Detailed Screen) is 18.00 Hrs.

In the 'Branch Parameters - Detail View' for 'XYZ' suppose the 'CutOff Offset Time' is maintained as 2 Hrs, then 'Cut Off Time' for Currency 'INR' for Branch 'XYZ' will be $18.00 + 2.00 = 20.00$ Hrs.

In the 'Branch Parameters - Detail View' for 'XYZ' suppose the 'Time Zone Offset' is maintained as 1 Hr and 30 Minutes (and 'Ahead' box is checked). Then if the 'Server Time' is 15.00 Hrs, then 'Local Time of 'XYZ' will be $15.00 + 1.30 = 16.30$ Hrs.

If an FT Contract is booked in 'INR' from the Branch 'XYZ' @ < 20.00 Hrs, then the system does not display the Override Message – 'The cut off time has been exceeded'.

If the FT Contract is booked in 'INR' from the Branch 'XYZ' @ > 20.00 Hrs, then the system displays the Override Message - 'The cut off time has been exceeded.'

5.1.5 Maintaining Financial Details for Branch

You can specify the details regarding suspense GLs, Financial cycle, preference for floating rate, message generation (103,103+) for the branch in this screen. The screen appears as shown below:

The screenshot displays the 'Branch Parameters Maintenance' window. At the top, there are fields for 'Branch Code *' and 'Branch Name *', along with a checkbox for 'Branch Available Status'. Below this, there are three tabs: 'General Details', 'Financial Details', and 'Duplication Check Details'. The 'Financial Details' tab is active, showing several sections:

- Suspense General Ledger:** Includes fields for 'Real Local Currency *', 'Cont Local Currency *', 'Real Foreign Currency', 'Cont Foreign Currency', and 'ATM', each with a description field and a selection icon.
- Financial Cycle:** Includes 'Current Cycle' and 'Current Period' fields.
- Referral Cut Off Time:** Includes 'Hours' and 'Minutes' fields.
- Revaluation / Position Transfer Details:** Includes 'Transfer Type' (dropdown), 'Transfer Branch', 'Position Asset GL', 'Position Liability GL', and 'Transaction Code' (all with selection icons).
- Job Status and Auto Authorization:** Two checkboxes.
- Amount Block Processing:** Includes 'Transaction Code for Amount Block Release' and 'Transaction Code for Credit Balance Transfer' (both with selection icons).
- Euro Redenomination General Ledger:** Includes 'Conversion General Ledger' and 'Conversion Transaction Code' (both with selection icons).
- Payment Messages:** Includes a 'Floating Rate' field and checkboxes for 'Generate 103+', 'Proceed without', and 'Suspense Entry Required'.

At the bottom, there is a navigation bar with tabs: 'Preferences', 'SWIFT Address', 'Account Mask', 'CIF Range', 'GI Functions', 'Tax', 'Branch Currency', 'Fields', 'Department Restriction', and 'Cheque Book Preferences'. Below this, there are fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with a 'Cancel' button.

5.1.5.1 Specifying Suspense GL

The accounting entries generated by different modules of Oracle FLEXCUBE will be passed into the specified 'Suspense GL' account if:

- The GL into which the entries are to be passed is not defined, or
- If the GL has been closed

Suspense GLs are of two types:

Real Suspense GL (Local and Foreign Currency)

The accounting entries that belong to asset, liability, income or expense GL categories will be passed to the 'Real suspense GL'. To indicate the real suspense GL for a branch, click option list and select a GL code from the option list.

Contingent Suspense GL (Local and Foreign Currency)

The accounting entries that belong to contingent asset or contingent liability GL categories will be posted to a 'Contingent Suspense GL'.

To indicate the contingent suspense GL for a branch, click option list and select a GL code from the option list.

5.1.5.2 Specifying Euro Redenomination GL

To facilitate the currency conversion process, you have to maintain a common Conversion GL and a Transaction Code.

The conversion GL that you specify in this screen will be identified as the common suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

In addition to the conversion GL you have to indicate a Transaction Code, which identifies conversion, related entries.

5.1.5.3 Indicating Payment Messages

Generate 103

As a branch level parameter, you have to indicate whether your customers can receive MT 103 as payment messages. Check the box positioned next to the Generate MT103 field to indicate that the customers of your branch are capacitated to receive payment messages in the MT 103 format. If you leave this box unchecked, the system will automatically send all payment messages to the counterparty bank in the MT 100 format.

Generate 103+

The 'Generate MT 103 + option' allows you to generate outgoing MT 103 messages in the MT 103 + format. This check box can be enabled only if you have enabled the generation of MT 103 messages as Payment Messages.



Note the following:

- The system will generate MT 103 messages as payment messages for transactions in the branch, and generate them in the MT 103 + format only if you have enabled this option in the following cases:
 - For the counterparty of the transaction, in the BIC Code Maintenance
 - By choosing the Generate 103+ option for currency in the Currency Definition
 - For the product used by the transaction, in the Product Preferences
- The system is also capable of processing incoming MT 103 messages in the MT 103 + format. During the upload process the system considers an MT 103 payment message to be of MT 103 + Format based on the presence of the STP code in the 119 field. Field 119 is present in the third block of the message i.e., {3: {119:STP}}.

Branch Code for Clearing

Indicate the code that identifies your branch in the Clearing Network. The code you specify for your branch should be the same as that defined in the Clearing Bank Code Maintenance screen.

Clearing Through Branch

If clearing transactions involving your branch are routed through another branch, specify the Oracle FLEXCUBE branch code of that branch in this field.

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

Loan Direct Debit Generation Days

Loan DD Generation days specifies the number of days before the schedule payment date, when a Direct Debit Contract is generated for the schedule due. This is applicable only for Loan Contracts in the local currency.

In order to facilitate the processing of loan repayments by customers who have their current or settlement accounts in some other bank of the clearing network you can initiate Direct Debits to these accounts. When a payment is due on a loan, a direct debit is generated 'Loan DD Generation Days' before the payment date.

As a result in Oracle FLEXCUBE the following entries will be passed:

Dr	Clearing suspense
Cr	Dummy Settlement Account

During liquidation which is performed on the schedule date the entries passed are as follows:

Dr	Dummy Settlement Account
Cr	Loan Asset GL/Interest Income GL

Refer the 'Maintaining the attributes specific to PC products' chapter of the PC manual along with the Branch Parameters section of the Core Services Manual for details on processing DDs originating from a Loan.

5.1.5.4 Processing Amount Block

Oracle FLEXCUBE passes the accounting entries for releasing an amount block through the 'Transaction Code for Amount Block Release' field. The system will check whether any amount block of type CASA for a branch is in open status. If an account is in open status, the system will group the amount blocks into primary account and primary account branch. Then, the system will remove the amount block from the cover account and debit the blocked amount of the cover account to the primary account.

Transaction Code for Amount Block Release

Specify the transaction code for the release of amount block. The adjoining option list displays all valid transaction codes maintained in the system. You can choose the appropriate one.

Transaction Code for Credit Balance Transfer

Specify a valid transaction code that should be used for transferring the amount from the current account to the LOC account. This adjoining option list displays all valid transaction codes maintained in the system. You can choose the appropriate one.

5.1.5.5 Indicating Financial Cycle

Current Cycle

This is the code for the current financial year as defined by you in the 'Period Code' screen.

Current Period

Each financial year is divided into accounting periods called 'Period Codes' defined in the 'Period Code Maintenance' Screen (for details refer 'period Code screen'). The current accounting period of the financial year is displayed in this field.

5.1.5.6 Specifying Referral Cut-off Time

Referral refers to the process of handling customer transactions that force the accounts involved in such transaction to exceed the overdraft limit. Examples of typical transactions, which force an account to move into overdraft, are Payment and Collections, Funds Transfers, Standing Instructions or Clearing transactions. If an account is marked for referral, the details of transactions resulting in the account moving into Overdraft will be sent to the referral queue.

Hours & Minutes

In branch parameter, you have to specify the referral cut-off time for accepting / rejecting transactions in the referral queue.

In case a transaction is rejected from the referral queue after the cut-off time then system displays the following override message:

'Rejected after cut off time'



Transactions are accepted into the Referral Queue even after cut-off time if account goes into overdraft.

Auto Authorisation

Oracle FLEXCUBE enables you to allow certain users (of your choice, depending on your requirements at your installation) to automatically authorize transactions.

To indicate applicability of automatic authorization for users of the branch, you must enable the Auto Authorization option in the Branch Parameters screen. When you do, you can then allow automatic authorization rights to the appropriate users at the branch.

For more details about automatic authorization, refer the Security Management System and Procedures user manuals.

Deferred Statement Status

This is a display field. This field indicates whether or not the Branch is ready for Deferred Statement Generation. 'Y' indicates the Branch is ready for deferred statement generation.

For further details on Referrals refer to the Processing Referrals in Oracle FLEXCUBE chapter of the Core Entities manual.

Install

Select the appropriate value from the drop-down list to indicate whether Oracle FLEXCUBE installation is complete or incomplete.

Proceed Without Maintaining Floating Rate

Check this option to indicate that floating rates should be propagated across all branches,

Sector code

Specify the Sector Code of your branch, as specified in the Clearing Bank Code Maintenance screen.

Routing No

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen for clearing and sector, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

5.1.5.7 Specifying Revaluation/Position Transfer Details

You can transfer the currency positions from the individual branches to the designated branch during EOD. The system transfers the position from the existing branch to the treasury branch. When the position is negative in the given GL, then the system will choose the Offset account as Position asset GL and when the position is positive in the given GL, then the system will choose the Offset account as Position liability GL. Sequence of the EOD between the designated branch and all other branches are operationally controlled.

You can maintain the following revaluation/position transfer details:

Transfer Type

Select the transfer type from the drop-down list. Following are the options available in the drop-down list:

- Position
- Reval



Note the following:

- If the Transfer Type field is left blank then neither the position transfer nor revaluation transfer to the designated branch will be done.
- For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen, should be checked to avoid creating position due to IB posting.

Transfer Branch

The system will identify the branch to which the revaluation/position transfer should be done.

During account/GL revaluation process, the system considers this branch and the GL to pass one leg of the revaluation profit and loss entries. The other leg of the entries will be passed based on the revaluation profit/loss GL and the account branch. The account branch in this case is the 'Revaluation Into' branch maintained as part of branch parameters maintenance.

Position Asset GL

Specify the GL to which the notional asset needs to be transferred..

Position Liability GL

Specify the GL to which the notional liability needs to be transferred.

Transaction Code

Specify the transaction code used to pass the accounting for position transfer.

While saving, the system will validate the difference between negotiated rate input by the user and the base rate maintained against the tolerance limit at the product level. If the difference is not within the tolerance limit, then the system will display an error message.

5.1.5.8 Specifying Suspense Batch Entry Details

Specify the following details:

Suspense Entry Required

Check this box to indicate that automatic suspense entries can be posted for a branch. If a mismatch occurs between real entries or contingent entries during the batch, then the system will post the balancing entries and will continue the EOD without interruption, if you check the 'Suspense Entry Required' option and specify the Suspense Batch Entry details. You can correct those entries manually at later stages.

If you leave this box unchecked and if a mismatch occurs in Real or contingent entries then the EOD is stopped and the error is thrown. You have to correct the entries.

Suspense Transaction Code

Specify the transaction code against which the suspense entries are posted or /reversed.

Suspense Batch Number

Specify the batch number against which the suspense entries are posted or reversed.

Reverse Suspense Entry Days

Specify the days till which the system can sustain the mismatch entries once the batch is run for the same. You can specify a value within a range of 1 to 9999.

If the 'Reverse Suspense Entry Days' is greater than the EOD suspense entry date and if reversal action is not performed for the suspense entry then the EOD is stopped and system displays an error message.

Maximum Real Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for real entry.

Maximum Cont Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for contingent entry.

5.1.6 Maintaining Duplication Check Details

You can maintain the number of days for which the duplication check should be done for a transaction in 'Duplication Check Details' tab. A transaction is compared with all previous transactions entered during the number of days maintained here, for any possible duplication.

The duplicate check is done starting from booking date till the booking date minus the number of days for duplicate check. This duplication check is carried out based on the combination of the preferences maintained at the FT/SI product respectively.



Duplicate transaction check is applicable only for FT and SI transactions.

You can specify the following details here:

Module

Specify the module for which you wish to maintain duplicate check days or select the module from the option list provided.

Duplication Check Required

Check this box to indicate that duplication check is required for the transactions related to the module selected.



Note the following:

- However, despite checking this box if the duplication check criteria are not specified in the following screens the system will not perform duplication checks for all the respective contracts under this branch.
- Payments and Collection Product Category Maintenance
- Funds Transfer Product Preference
- Standing Instruction Product Definition

Duplication Days

Specify the number of days for which the duplication checks for transactions need to be carried out. Calendar days are considered for duplication check.



You need to specify a value here if 'Duplicate Check Required' option is selected. You cannot specify a negative value.

5.1.7 **Maintaining SWIFT Address for Branch**

Click the 'SWIFT Address' in the Branch Parameters screen to invoke 'Additional SWIFT Address' screen.

The screen appears as shown below:

Swift Address *	Description
<input checked="" type="checkbox"/>	<input type="text"/>


You can specify the SWIFT addresses related to the branch in this screen.

5.1.8 Defining Account Mask

Customer Account Masks can be defined at the Branch Level or at the Bank Level.

Click the 'Account Mask' button in the Branch Parameters screen to invoke 'Account Parameters' screen.

The screen is as shown below:



For further details please refer the Section 'Specifying the Account generation Parameters at bank level' under Bank Parameters.



While defining branch parameters, you can maintain only the sequence number for account mask. However, you cannot define a new account mask here.

Fund Subscription

You may wish the system to automatically create deposit accounts for customers at the time of fund subscription. These system-created deposit accounts are for use as settlement accounts.

Here, you need to specify the range of numbers available for such auto created accounts by mentioning a start and an end number.

If you wish to retain the facility of auto creation of current accounts at loan initiation, you will have to ensure that the account number mask does not have any user input character.



Note the following:

- The range of numbers specified for the creation of current accounts should not overlap with the range specified for the creation of deposit (or contra deposit) account.

- Fund account number ranges are enabled only in the fund branch.

5.1.9 Maintaining Customer Number Range

You can specify a number range based on which the customers of your bank will be assigned CIF numbers for identification. Since the number range is maintained at the branch level, you can specify different number ranges for different branches of your bank.

To maintain the number range, click the 'CIF Range' in the Branch Parameters screen. The 'Customer Number Range' screen is displayed:

Specify the following in this screen:

Start Customer No.

This number is the basis on which the system generates the CIF numbers for customers of your branch.

The CIF number generation is determined by the following details:

- The CIF mask maintained in the Bank-Wide Parameters screen. Assume that the mask is 'bbbnnnnnn' (where 'bbb' represents a 3-digit branch code and 'nnnnnn' is a 6-digit number).
- The start customer no – assume that this number is 100

While generating CIF numbers, the system will automatically assign the number '000000100' to the first customer of your branch, assuming that the branch code is 000. This conforms to the CIF mask maintained for the bank. The next customer will be '000000101' and so on.

If the option 'Auto Generate CIF Numbers' is checked in the 'Bank Parameter Preferences' screen and the start CIF is zero or null, the new customer number will be generated for the branch as per the current running sequence number of the Head Office.

End Customer No

Just as you specify a Start Customer Number, you have to indicate the End Customer Number also. You will not be allowed to maintain customers beyond this range.

Let us assume that the 'End Customer No.' is 99999. As per the mask and the end number, the last customer CIF number that is generated at your branch will be '000099999'.

Start Dummy Customer Number & End Dummy Customer Number

You should also maintain a dummy customer number range in this screen. When maintaining a dummy range, you should ensure that dummy CIFs and the actual range do not overlap with one another.

The dummy CIF range will be used for account number generation. As explained earlier, the account number can be generated based on the following account mask:

'bbbTZCCCCCSd'

Where,

- bbb – is the branch code
- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm (explained earlier)

To recall, the sequence number that is automatically generated by the system is for an account code + currency type + customer combination. The sequence number is a single digit number (from 1 to 9). This means that, for the same combination, you will be allowed to maintain only nine accounts. To eliminate this limitation and to allow maintenance of more than nine accounts for the same combination, the dummy customer number range will be utilized. This is explained with the help of an example.

Example

Assume that you have maintained the following CIF range for your branch:

Start CIF No.	100000
End CIF No.	198999
Start Dummy No.	199000
End Dummy No.	199999

Ms. Jennifer approaches your bank to open a savings account in your branch (branch code is '000'). Further, the CIF and account number masks maintained for the branch are 'bbbnnnnn' and 'bbbTZCCCCCSd' respectively.

As per the CIF mask, Ms. Jennifer is assigned the CIF number: 000123456. According to the account number mask, the 6th to 12th digits will be the last six digits of the CIF number, which is '123456'.

The account number of the first savings account, in USD opened for Ms. Jennifer is: 000411234561 (we will consider only 12-digits for this example since the 13th digit is auto generated by the system based on Modulo 11 with Weights algorithm).

The components of the account number **000-4-1-123456-1** are as follows:


- 000 – is the branch code
- 4 – is the account code
- 1 – is the currency type
- 123456 – is the CIF number for Ms. Jennifer
- 1 – is the sequence number for the combination of account code, currency type and customer i.e. the number '4-1-123456' will be common for the first 9 accounts maintained for the same combination.

Now, Jennifer decides to open another account for the same combination. In this case, the sequence number gets incremented to 2 and the account will be assigned the number: **000-4-1-123456-2**.

This will go on till the 9th account for the same combination. The 9th account number would be **000-4-1-123456-9**.


If the customer decides to maintain the 10th account for the same combination, the sequence number will restart since it has reached the maximum allowed level. This would result in duplication of account numbers. To eliminate this, the system will now use the dummy CIF range to number the accounts.

Therefore, the 10th account number will be: **000-4-1-199000-1**. This sequence will continue for subsequent accounts maintained for the same combination.

 You can view all the dummy CIF numbers linked to a customer in the 'Customer Accounts – Allocated Dummy CIF' screen.

5.1.10 Maintaining Global Interdict Functions

Click 'GI Functions' button in the Branch Parameters Maintenance screen to invoke 'Branch Global Interdict Functions' screen.



5.1.11 Maintaining Preferences

To specify your preferences, click 'Preferences' button from the 'Branch-Wide Parameters' screen. The 'Preferences' screen is displayed.

Branch Parameters Preferences

Netting Suspense General Ledger

Walk In Customer

Internal Swap Customer

Clearing Account

Offset Clearing Account

Weekly Holiday 1

Weekly Holiday 2

Clearing Bank Code

MIS Group For Currency

Interdict Validation Required

Interdict Timeout Interval

Status Processing Basis

Provisioning Frequency

Uncollected Funds Basis

Deferred Statement Generation

Enterprise General Ledger

Minor Age Limit (Yrs)

Notification Days

Cheque Stale Days

- Back Value Details

Back Valued Check Required

Back Value Days

- Profit and Loss Adjustment

Track Previous Year Profit And Loss Adjustment

- Revaluation Split Details

Revaluation Split Required

- Suspense Product Maintenance

Debit Product

Description

Credit Product

Description

- International Banking Account Number MASKS

Bank Code

Account Number

- FGL Integration

FGL Handoff Required

- ELCM Integration

ELCM Replication

- LDAP DN Template

LDAP DN Template

LCY Message Preferences

Ok Cancel

In this screen you define the following preferences:

- The netting suspense GL into which settlement entries for netted FX Contracts should be posted
- The CIF Number against which all Walk in customers should be identified
- The format in which the IBAN Account Number and the Bank Code should be captured
- The duration for which spool files should be stored in the spool file directory
- The directory into which the files should be spooled
- MIS codes for posting of automatic balancing entries

These details can be maintained by the respective branches. For a branch you maintain the following, in the 'Preferences' screen:

Netting Suspense GL

All settlement accounting entries relating to a netted FX contract, is passed into the specified 'Netting suspense GL'. The net amount of the settlement is transferred through the Nostro accounts. For instance, let us take the following two outstanding contracts entered into by bank A; both settling on January 10, 1998:

- Bought from bank B 1 Million USD in exchange for 35 Million INR
- Sold to bank B 1/2 million USD in exchange for 18 million INR

The above contracts can be settled in either of the two ways given below, on the settlement date:

- Settle both contracts separately
- Net the settlements of the two contracts

If your bank has a netting agreement with the counterparty, the settlement entries are posted to this 'Netting suspense GL' and the net amounts are settled through the nostros.

Walk in Customer

For your branch you can create a walk in customer ID against which you track all those customers who do not hold a regular account with your bank but have approached the bank for a transaction, say, for encashment of traveler's checks or for manager's checks.

Internal Swap Customer

You need to specify an internal swap customer for processing internal swaps. The names of all the customers of your bank will be displayed in the option-list provided. This will be a unique customer meant for processing internal swaps.

Clearing Account

Specify the default GL account to be used for clearing transactions at the branch.

Offset Clearing Account

Specify the default offset GL account to be used for clearing transactions at the branch.

Weekly Holiday 1 & 2

Using this option you can indicate the holiday in a week for your branch. You can select the day for holiday from dropdown list. If you want to set only one holiday in a week for your branch, select the day for Weekly Holiday 1 and leave Weekly Holiday 2 Blank. If you want to opt for two holidays in a week, select the days for Weekly Holiday 1 & Weekly Holiday 2.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

MIS Group for Currency (Mismatch Entries)

If the posting of automatic balancing entries due to currency and value date mismatches has been specified for your bank, you can specify the MIS codes or groups to be used for posting the balancing entries.

Interdict Validation Required

For your branch you need to indicate whether Interdict Validation is required for all Customers, Customer Accounts, Funds Transfers, Standing Instructions, Foreign Exchange, Letter of Credit and DD transaction processed within your branch.

The options available are:

- Yes – the details of CIFs and Customer Accounts, captured in the specific branch of your bank will be sent to the GI system as and when they are captured in Oracle FLEXCUBE.
- No – the details maintained in the specific branch will not be sent to the GI system for online verification.

Interdict Timeout Interval

If you indicate that the details should be sent to the GI system, you will also have to specify the interdict timeout interval period. If the response time from the GI system takes longer than the time that you specify in this field, the transaction will be timed out since the processing time exceeds the time stipulated in this field.

If you enable this preference, you will have to identify the Code or ID of the function in Oracle FLEXCUBE for which such a validation should be performed by clicking on the 'GI' button in the Branch Parameters screen.

For more details, refer 'Global Interdict Interface' user manual.

Status Processing Basis

In the Branch Parameters, you can indicate the basis upon which status processing must be done at the branch, for customer accounts as well as loan contracts.

Status processing can be done either at an individual contract / account level, or at a Group / CIF level.

If you opt for Group / CIF -level processing, it is done in two stages:

- The worst status among all contracts and accounts under a specific customer group or CIF is arrived at
- All accounts and contracts involving the customer group or CIF are then moved to the worst status that was arrived at

If you opt for status processing at individual contract / account level, the status of each contract or account would be assigned according to the status processing parameters that are operative for the contract or account.

If 'Status Processing' is at Individual Contract Level, then you can change the status and trigger the status change event along with accounting entry posting. However if the 'Status Processing' is at CIF/Group level individual module (LC, CI, MO, CA, IA and BC) batches will be updating common storage with the derived status of each contract and CIF/Group level status will be triggered by the common status change batch. The common status change batch will call the individual module function for status change processing.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

Provisioning Frequency

Provision processing depends upon status processing for accounts and contracts. The provisioning batch process executes after the status processing batch. If status processing is indicated to be processed at group / CIF level, you can indicate the frequency at which the provisioning batch is to be executed for your branch. The frequency options available are daily and monthly.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

(Withdrawable) Uncollected Funds Basis

You can define how the System enforces the allowable amount of uncollected funds (on an account) that can be withdrawn within a business day.

For each customer account, you designate a limit on the amount of uncollected funds that can be withdrawn (the Uncollected Funds Limit). You can also indicate whether, for a given business day, the System should consider the uncollected funds that are allowed to be withdrawn as:

- The funds scheduled to be released on the current date (today), OR,
- The total uncollected funds available against the account subject to the Uncollected Funds Limit

You can specify your preference by choosing any of the following options:

- **Uncollected Funds** : If you select this option, an amount up to or less than the uncollected funds limit defined for the account, is allowed to be withdrawn, on a given business day.
- **Uncollected Funds Available Same Day**: If you select this option, the funds allowed to be withdrawn against uncollected funds on a given business day are the funds scheduled to be released on the current date (today).

Deferred Statement Generation

Check this option to stop the automatic account statement generation at end of day.

If this option is checked, then the account statement generation will be deferred to whenever you initiate action for executing Batch Operations for statement generation. You can do this through the Branch Statement Status Change screen.

Enterprise GL

Check this option if this branch needs to have an enterprise GL hand-off. Once checked the system will identify the said branch for creating an ASCII hand-off file containing the relevant accounting entries to be sent to the external enterprise GL.

Minor Age Limit (Yrs)

Specify the minor age limit. This varies from nation to nation. However If user does not maintain the age limit, the system will automatically defaults it as 18 years during save.

Notification Days

Specify the intimation days to send advice prior to the customer turns major based on DOB.

Cheque Stale Days

Specify the cheque stale days. Here you can identify the number of days for which stale validation is done.

5.1.11.1 Specifying Back-Valued Details

For your branch you can specify the maximum period up to which back valued posting can be processed. This restriction can be made applicable by specifying the following preferences:

Back Value Check Required

It is used to indicate whether all back-valued transactions should be validated against a specific period.

Back Value Days

If you enable the Back Value Check Required option, you must indicate the number of calendar days up to which back-valued transactions can be allowed. During transaction processing you will be allowed to post back-valued transactions up to the specified date in the past (no check will be done). Further, if the option is checked but you have not maintained the 'Back Value Days' (maintained as NULL), the system will interpret it to be 'Zero' days allowed (for back valued transactions).

The restriction for the maximum period up to which back-valued posting can be allowed, will be made on transactions processed in following modules:

- Payment and collections
- Data Entry
- Retail Teller
- Utility Payments
- Foreign Exchange
- Money Market
- Expense Processing

- Fund Transfer
- Loans and Deposits

While saving transactions pertaining to any of these modules the System validates the Value Date of the contract to check whether it adheres to the restriction. You will be intimated with an override if the Value Date is earlier than the specified period. This restriction is made applicable on all uploads as well.

Refer the Contract Processing chapter of the individual modules for additional information.

5.1.11.2 Indicating Profit and Loss Adjustment

Track Previous Year Profit and Loss Adjustment

You can collect data pertaining to the unrealized income booked for each contract during the year by triggering the Year-end batch process. But, you will be allowed to trigger the batch process for splitting the unrealized profit and loss for the previous year and the current year only if you have specified this (Track PY PnL Adjustment) as a preferred option for your branch.

If you set this preference, the data pertaining to the unrealized income is collected at contract level for the following modules:

- Securities - Unrealized Interest, Discount and Premium accrued for the year.
- Derivatives - unrealized income
- Bills and Collections - unrealized income
- Letters of Credit - unrealized income
- Money Markets - unrealized income

5.1.11.3 Indicating Revaluation Split Details

Revaluation Split Required

You can choose to break-up revaluation profit/loss into:

- Trading P&L – P&L due to revaluation of foreign currency transactions during the day
- Revaluation P&L – P&L due to revaluation of opening balances (balances without current day's turnover)

If you enable this preference, all GLs which are marked for revaluation split will have their revaluation profit/loss broken up into trading and revaluation P & L for entries posted from this branch.

For further details on Split Revaluation refer the GL user manual.

5.1.11.4 Specifying International Banking Account Number MASKS

The IBAN or International Bank Account Number is a unique account number that is used to identify a customer's account in a financial institution internationally.

International Bank Account Numbers in your bank are generated in the format of the account mask that you specify in the Branch Parameters screen. Therefore, you have to first define IBAN masks.

The IBAN Mask

Since IBANs should be maintained in a particular format you should first define the format in which the IBAN should be captured. You should also indicate the format in which the bank code of the bank in which the account resides should be maintained.

The maximum length of an IBAN should be 34 characters. The IBANK Mask should be a combination of the following parameters:

- An **ISO Country Code**, which has a maximum length of two characters. The identifier that you can use to indicate the country code is DD. The identifier will be replaced by the actual country code while defining the account number. For instance, you will replace DD with PL for Poland, US for the United States and so on.
- A **Check Digit Number** calculated according to an ISO Standard algorithm, using the Country Code, Bank Code and Account Number combination. Since this is a two-digit number you can use the identifier CC to specify this algorithm. The system arrives at and replaces this identifier with the actual check-digit based on the Country Code, Bank Code and Account Number combination.
- The **Bank Code** of the bank where the IBAN resides. This code is assigned to the respective Bank by its national bank. There are no individual restrictions on the length of Bank Code and Account Number. However, the combined length of the Bank Code and Account Number should not exceed 30 characters. You can use the identifiers **a** (for alphabets) and **n** (for numerals) as the identifiers to capture the length of the bank code.
- The **Account Number** of the customer account. The bank in which the customer account resides assigns this number. You can use the identifiers **a** (for alphabets) and **n** (for numerals) as the identifiers to capture the length of the account number.



Suppose that you maintain an IBAN mask in the following format:

DDCCaaaaaaaaannnnnnnaaaaaannnnnnnn

While capturing the IAB number you have to strictly adhere to the format mentioned above.

USccCHASEBANK000101CBNYLI450000026

In place of the 'cc's the system will generate the check digit algorithm based on the Country Code, Bank Code and Account Number combination.

The Bank Code Mask

After indicating the IBAN mask you have to specify the mask for the Bank Code. The Bank Code mask is a combination of alphabets and numerals. Therefore you can specify **A** and **N** as the identifiers. Subsequently, while capturing the bank code in the IBAN screen each of these characters will be replaced with the respective alphabet or numeral. For instance, let us assume that you have maintained a 15-character mask for the Bank Code:

A	A	A	A	A	A	A	A	A	N	N	N	N	N	N
---	---	---	---	---	---	---	---	---	---	---	---	---	---	---

You will have to capture the corresponding bank code in the same format:

C	H	A	S	E	B	A	N	K	0	0	0	1	0	1
---	---	---	---	---	---	---	---	---	---	---	---	---	---	---



The combined length of the Bank Code and Account Number should not exceed 30 characters.

Checksum Left Mask

After indicating the Bank Code mask you have to specify the Checksum Left Mask. The Checksum Left Mask is a combination of four digit bank code, four-digit branch code, and a check digit based on the combination of bank code and the branch code. You need to specify the check digit as 'd'. While generating the customer account number using this mask, the system will automatically generate the check digit based on the combination of bank code and the branch code.

Example: You can maintain a Checksum Left mask in the following format:

bbbbbbbd

Where:

- bbbb - Bank Code
- bbbb - Branch Code
- d - Check digit

The mask that you specify in this field will be used by the system as the account number prefix while generating an account number with 20 digit account mask.

For more details on 20 digit account mask, refer the section 'Defining Format Masks' in this document.

5.1.11.5 Indicating ELCM Integration

Check this box to indicate that the branch details will be replicated to ELCM system. System will select this option by default, but you can unselect it.



System will not allow unselecting this option once it is selected.

5.1.11.6 Indicating Multi Credit Transfer

Multi Customer Transfer

This option indicates whether or not the branch is Multiple Customer credit transfer compatible.

Multi Financial Institution Transfer

Enable this option to indicate that your branch is Multi Financial Institution Transfer compatible.

5.1.11.7 Specifying Consolidation Suspense General Ledger

Incoming GL

If your branch is Multi Customer Transfer or Multi Financial Transfer or both enabled, you have to mandatorily choose the incoming GL, which will be the bridge GL for all incoming MT102 and MT 203 type of transfers.

Outgoing GL

If your branch is Multi Customer Transfer or Multi Financial Transfer or both enabled, you have to mandatorily choose the outgoing GL, which will be the bridge GL for all outgoing MT102 and outgoing MT 203 type of transfers.


LDAP DN Template

The LDAP DN template needs to be maintained here for each branch. This is used in Oracle FLEXCUBE user maintenance form to populate corresponding LDAP user-id automatically from the template.

5.1.12 Maintaining LCY Message Preference for Branch

Click the 'LCY Msg Pref' button in the Preferences screen to invoke the 'LCY Message Preference' screen.

The screen is as shown below:



Branch

The system displays the branch details.

Description

The system displays the description.

Module

Specify the module details.

Module Description

Specify the description of the module.

Local Currency Message Type


Select the local currency message type from the drop-down list. Following are the options available in the drop-down list:

- Suppress LCY
- Generate LCY Message Thru SWIFT
- Generate PC Contract

5.1.13 Specifying UDF Details

You can associate values to all the User Defined fields created and attached to the Branch Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:




You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

5.1.14 Specifying Cheque Book Preferences

To specify cheque book preferences, click 'Cheque Book Preferences' button from the 'Branch Parameters maintenance' screen. The 'Cheque Book Preference' screen is displayed.



The screenshot shows a dialog box titled "Cheque Book Preferences" with a close button (X) in the top right corner. The main content area is titled "Cheque Detail Maintenance" and contains two checked checkboxes: "Auto Generate Cheque Number" and "Issue From Inventory Branch". A mouse cursor is pointing at the "Issue From Inventory Branch" checkbox. At the bottom right, there are "Ok" and "Cancel" buttons.

Auto Generate Cheque Number

Check this box to indicate that cheque numbers should be automatically generated for this branch, based on the sequence numbers you maintain for the different types of cheques.

Issue from Branch Inventory

Check this box if Issue from Branch Inventory is applicable.



You can maintain the details for the cheque number generation in the 'Cheque Type Parameters' screen.

Refer the chapter 'Maintaining Cheque Book Details' in the Current and Savings Account user manual for more details about the screen.

5.1.15 Maintaining Department Restrictions

As part of setting up the branch parameters, you can restrict the use of department codes for specific branches. To invoke 'Department Restrictions' screen, click 'Department Restrictions' button on 'Branch Parameters' screen.

The screenshot shows a window titled "Department Restriction". It has a blue header bar with a diamond icon on the left and a close button on the right. Below the header, there are two text input fields: "Branch Code" and "Branch Name". Underneath these is a section for "Departments Allowed" with two radio buttons: "Allowed" (which is unselected) and "Disallowed" (which is selected). Below this is a section titled "Departments Allowed/Disallowed" which contains a table with two columns: "Department Code" and "Department Description". The table is currently empty. At the bottom of the window, there are "Ok" and "Cancel" buttons.

In this screen you can restrict access of individual branches to the various departments that exist within your bank.

Branch Code

Specify the branch code for which you wish to maintain the department restriction. The option list displays all valid branch codes that are applicable. Choose the appropriate one.

Branch Name

Based on the branch code selected, the system displays the name of the branch.

Departments Allowed

For the selected branch, you can restrict the use of department codes. Choose one of the following restriction types:

- Allowed – If you choose this, the system will permit the branch to use the departments specified in this screen.
- Disallowed – If you choose this, the system will now allow the branch to use the departments specified in this screen.

Department Code

Specify the department code for which the restriction is applicable. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

You need to maintain a list of department codes for which the restriction should be applied. You can add more department codes to the list using add button.

Description

The system displays the description of the selected department code.

Once you have specified the details, click 'OK' button. You can also exit the screen without saving changes by clicking 'Cancel' button.

5.2 Defining Transaction Cut-Off Time

For certain operations initiated from specified channels, if any transaction is booked after a specified cut-off time, your bank's balance sheet should be affected only on the next day and not on the day the transaction was effected.

The following user defined channels and the cut off modes for the channels can be set-up using the upload sources definition on Oracle FLEXCUBE

- ATM
- POS
- Internet
- Servipeg - For transactions emanating from Servipeg, the system will assign a cut off time for the transactions to be posted in the balance sheet.
- Teller - Each teller has the option to set a cut off time wherein transactions booked after a specified time will be booked in the balance sheet only on the next day. This option of setting a time limit is a one- time decision and cannot be changed at will by the teller. Once the cut off time is set by the teller, any transaction coming from the specific teller's counter after the cut off time will be accounted in the balance sheet only on the next day.
- Web branch (FlexBranch)



For transactions falling under the cut off time, the entries will be reflected in the balance sheet on the subsequent day but the customer accounts will be immediately affected with either a debit or a credit as the case may be. Customer accounts will not be subject to the 'cut off time'.

5.2.1 Maintaining Cut-off Sources

You can maintain the various channels and the cut-off time to be assigned to each channel in the Cut-Off Sources screen for every branch.

To invoke the 'Cut-Off Sources' screen by typing 'CSDCOFSR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Source Code	Cut Off Type	Cut Off Time (Hr)	Cut Off Time (Min)	Description
	Time Driven			

The following details have to be maintained in this maintenance screen

Branch Code

Specify the branch code. From the option list, choose the branch code for which cut-off time has to be maintained.

Branch Name

The system will display the branch name whenever you select Branch Code.

Source Code

Specify the source code from the option list.

Cut-off Type

From the option you can indicate the type of cut-off to be followed by each channel. You can choose from the following options:

- Time Driven - If you choose Time Driven, the channel specified will conform to the cut-off time after a specific point of time

- Transaction Level - If you choose Transaction Level, the specified external system will decide if cut-off processing is required for each transaction
- Always Cut-off - If the type chosen is Always Cut-off, you are indicating that any transaction that is initiated from the specified external system has to follow cut-off processing.
- Channel Driven - If you choose channel Driven as the cut-off type, it indicates that any transaction that is initiated from this channel has to follow cut-off processing.

Cut-off Hours

If the 'Cut-off Type' chosen is 'Time Driven', you can specify in hours, the cut-off time up to which entries have to be posted in the balance sheet on the same day.

Cut-off Minutes


If the 'Cut-off Type' chosen is 'Time Driven', you can specify in minutes (or as a combination of hours and minutes), the cut-off time up to which entries have to be posted in the balance sheet on the same day.

Description

Description is a display field that will display a brief note about the chosen source code.

5.2.2 Viewing Cut-off Source Details

You can view the details of the cut-off source in the 'Cut-off Source Summary' screen. To invoke this screen, type 'CSSCOFSR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.



You can query on records based on any one or all of the following criteria:

- Authorization Status
- Branch Code
- Record Status

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code

5.2.2.1 Cut-Off Processing for Channels

External channels that are being maintained as 'Channel Driven' will summon a program to initiate the cut-off processing in Oracle FLEXCUBE. Once the function is called by the channel/external system, the system will control cut-off processing of all the transactions coming from the specific channel.

5.2.2.2 ATM Transaction Processing

If the transaction is received through an interface, during ATM Transaction Processing, the system checks if cut-off processing is required for the ATM external system. If it is required, the system will pick the transaction for cut-off processing.

5.2.2.3 Accounting

While posting entries, the system will check whether transaction details exist in the cut-off processing table. If a match is found in the table, the system will TANK the accounting entries. But, if the transaction is marked with a future date, it will automatically be picked for cut-off processing.

5.2.2.4 BOD Operations


During BOD process, system will post all the tanked entries in to the respective GL accounts, and will reset the cut-off processing for the specified channel with Cut-off type as 'Channel Driven'. This will discharge the tanked entries and accounting entries will be reflected in the balance sheet accordingly.



Though the transactions are recorded on the same day as the contract booked day, the entries will contribute to the balance sheet only the next day.

5.3 Maintaining Value Date Spread for Branch

The Branch Value Date Spread refers to the number of days that should be applied to transfers with a value date that is later than the effective cut-off date. You can maintain value date spread details in the 'Value Date Spread' screen. Invoke this screen by typing 'CYDVDSRP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The Value Date Spread is maintained for a Branch + Currency combination. You can select a branch and currency code from the option list available. The spread should be expressed in calendar days and is applicable only to outgoing funds transfers.

All outgoing funds transfers should be generated earlier than the cut-off time maintained for the currency involved in the transfer. This is applicable to transfers that originate from the FT Module of Oracle FLEXCUBE, through settlements of any other transaction or transfers uploaded from an external source.

When the value date of a transfer is beyond the effective cut-off time (Cut-off Time + Branch Offset Time) the branch value date spread specified for the currency involved in the transfer is added to the transfer value date. In effect, such transfers are generated as follows:

Generation Date = Transfer Value Date + Branch Value Date Spread



The reference of time is always the System Time (server).

Example

You have maintained the following details:

- Branch Value Date Spread = **2 Days**
- Cut-off Time = **8 PM**
- Branch Offset Time = **3 hours**
- Effective cutoff time = **11 PM** (Cutoff time + Branch offset time)

You have effected a transfer with Value Date 15 June 2000 at 11:30 PM. In this case, the value date of the transfer is later than the effective cut-off time.


The Branch Value Date spread is applied to the transfer value date. The transfer will be generated on 17 June 2000.

How Uploaded FTs are handled

In the case of outgoing transfers that are uploaded from a source external to Oracle FLEXCUBE, the value date will be amended directly based on the cut-off time maintained for the currency and value date spread maintained for the customer.

5.4 Maintaining Index Codes

You can maintain new index codes using 'Index Maintenance' screen. To invoke this screen, type 'CYDIDXCD' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



The screenshot shows a window titled "Index Maintenance" with a blue header bar. Inside the window, there are two text input fields: "Index Code *" and "Description". Below these fields, there are four labels: "Maker", "Checker", "Date Time:", and another "Date Time:". A "Cancel" button is located in the bottom right corner of the window.

Specify the following details:

Index Code

Specify a unique code that identifies the index.

Description

Enter a brief description of the index code.

Once you have captured the details, save the maintenance.

5.5 Maintaining CPI Rates for a Currency

You can maintain absolute CPI rates for a currency using 'CPI Rate Maintenance' screen. To invoke this screen, type 'CYDXCDRT' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

Effective Date	Rate
<input type="text"/>	<input type="text"/>

Specify the following details:

Index Code

Specify the index code for which the CPI rate is being maintained. The option list displays all valid index codes maintained in the system. Choose the appropriate one.

Currency

Specify the currency. The option list displays all valid currency codes maintained in the system. Choose the appropriate one. You can also specify 'ALL' to indicate that all the currencies are applicable for this maintenance.

Effective Date

Specify the date from which the rate becomes effective.

Rate

Specify the rate.

5.6 Maintaining Till Preferences

You can maintain currency-wise shortage and overage preferences for a till in the 'Till Preferences Maintenance' screen. You can invoke this screen by typing 'DEDTPREF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Code	Till Overage Amount	Till Shortage Amount
---------------	---------------------	----------------------

You can maintain the following details:

Branch Code

Specify the branch code. The adjoining option list displays all the branch codes maintained in the system. You can choose the appropriate one.

Maximum Retry Count

Specify the number of times you can try balancing a till under this branch. Every attempt at balancing a till will increase this count by one. Once the limit is reached, the system will display the till balance as stored in the system, so that you can balance it manually.

Currency Code

Specify the currency for which you wish to maintain shortage and overage limits. The adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

Till Overage Amount

Specify the amount up to which the till balance can exceed the system balance.

Till Shortage Amount

Specify the amount up to which the till balance can fall short of the system balance.

5.7 Maintaining Advice Sequence

You can assign sequence numbers for payment advices generated for the Retail Lending module, maintain limits (date-wise or number-wise) and parameters to generate alerts, when the limits are reached in the 'Advice Sequence Maintenance' screen. You can invoke this screen by typing 'MSDADVSQ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. The screen appears as shown below:

Fields	
Maker	Date Time:
Checker	Date Time:
Mod No	Record Status
	Authorization Status

You can capture the following details in this screen:

Sequence ID

Specify the DIAN number provided by your government.

Start Sequenced Number

Enter the beginning number for the sequence.

End Sequence Number

Enter the last number for the sequence. The system displays an error and will not allow you to save the transaction once this number is reached.

Effective date

Choose the date from which the sequence generation can begin.

Expiry Date

Choose the date till which the sequence generation is valid. Any transaction input after this date will not be saved and the system will display an error message.

Alert Level

Specify the number which should be subtracted from the End Sequence Number to derive the sequence number for alerts generation. For instance, if the End Sequence Number is 1000 and the Alert Level is set as 100, the system will start generating alerts from sequence number 900 till sequence number 1000 (both inclusive).

Alert Days

Specify the number of days before the Expiry Date when the system should start displaying alerts. For instance, if the Expiry Date is 10 January, 2008 and the Alert Days is 5, the system starts generating alerts from 5 January, 2008 till 10 January 2008 (both inclusive).

The system checks for availability of sequence numbers while saving a payment transaction based on the details in this screen. If the check fails, the transaction is halted and an error message displayed. If a sequence number exists, the system allots this to the transaction at authorization when the message is generated. Similarly, if there is a failure at any point in sequence number generation, the system displays an error message.



Note the following:

- The 'Serial No Req'd' option in the 'Advise Format Maintenance' screen should be checked to ensure that the check for sequence number is carried out.
- Running Sequence numbers, based on the parameters you have maintained for the branch, are generated when multiple advices have been selected for a payment event

5.8 Maintaining Tax Cycle

You can maintain tax cycle at the bank level through the 'Tax Cycle Maintenance' screen. Invoke this screen by typing 'STDTXCYL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a window titled "Tax Cycle Maintenance" with a blue header. Inside the window, there are four input fields: "Tax Cycle *" (with a red asterisk), "Description", "Start Date *" (with a red asterisk and a calendar icon), and "End Date *" (with a red asterisk and a calendar icon). Below the input fields is a "Fields" tab. At the bottom of the window, there is a status bar with the following labels: "Input By DOC7", "Date Time", "Modification Number", "Authorized", "Open", and a "Cancel" button.

Tax Cycle

You need to define the tax cycle, which will be uniquely identified in the system

Start and End dates for tax cycle

You need to indicate the start and end date of the tax cycle you are defining, using the adjoining calendar.


5.8.1 Updating Tax Cycle

The Current Tax Cycle would be updated as and when the tax cycle changes. This would be done during authorization of date change function on the first day of the new Tax Cycle.

5.8.2 Maintaining Tax

To maintain Tax parameters at the branch level, click the 'Tax' button in the Branch Parameters Details screen.

The screen appears as shown below:



Tax Cycle

This is the current tax cycle for the branch. This is a display field. Whenever the tax cycle changes, the field is updated during the date change authorization for that day.

Consolidated Tax Certificate Required

Check this option to indicate Consolidated Tax Certificate is required for all the transactions done in the Tax Cycle. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

The Consolidated Tax Certificate would be generated at the frequency specified at the branch level. Apart from this, the certificate would also be generated at the end of the Tax Cycle. The consolidated tax certificate would always display all the transactions pertaining to the current Tax Cycle.

Individual Tax Certificate Required

Check this option to indicate Individual Tax Certificate is required for individual transactions under the selected tax category. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

Tax Certificate Frequency

This field is enabled only if the Consolidated Tax Certificate option is checked.

You need to specify the frequency with which the tax certificate should be generated. This would be a combination of the Tax Certificate Frequency and the Tax Certificate Day. It could be any of the following:


- Monthly - This indicates that the tax certificate would be generated every month. The day of the month on which the Tax Certificate would be generated is defined in the Tax Certificate Day field.
- Quarterly (Q) – This indicates that the tax certificate is generated once in three months. The end-month for the first quarter is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field. Subsequent end-months would be derived by the system.
- Half Yearly (H) – This indicates that the Tax Certificate would be generated once in six months. The end-month for the first half-year period is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate day field. Subsequent end-months would be derived by the system.
- Yearly (Y) – This indicates that the tax certificate would be generated once a year. The month in which the certificate needs to be generated is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field.

Frequency Value

Select the appropriate month for tax certificate generation, from the adjoining drop-down list.

5.8.3 Maintaining Clearing Currencies

You can maintain a list of currencies in which clearing transactions can be processed under a branch. In order to achieve this, you need to invoke the 'Clearing Currency' screen by clicking the 'Branch Currency' button in the 'Branch Parameters – Detail View' screen.



The screenshot shows a software window titled "Branch Parameters: Clearing Currency". At the top, there are two text input fields labeled "Branch" and "Description". Below these is a table with the title "Clearing Currencies". The table has two columns: "Currency Code *" and "Currency Description". The table is currently empty. At the bottom right of the window, there are two buttons: "OK" and "Cancel".

Here you can capture the following details:

Branch Code

The branch code gets defaulted from the 'Branch Parameters – Detail View' screen. A brief description of the branch is displayed alongside.

Currency Code

Specify the currency in which you wish to allow clearing transactions under this branch. You can specify multiple currencies for a branch. Click on the adjoining option list and select the appropriate code from the list of currencies maintained in the system.

Currency Description

A description of the chosen currency code is displayed here

5.8.4 Account Statement Handoff

The account statement handoff will consider the movements on accounts based on the Statement Date and not the Transaction Date. The Statement Status Change will itself run the Account Statement handoff for the previous working date before marking the Branch Statement Status as ready.

5.8.5 Account Statement Generation

Accounting entries with Statement Date lying between From Date and To Date populated in the handoff records will be picked up for Account Statement Generation processing.

Example

The table shows the list of transactions for a customer for statement processing on 01/08/2003.

Booking date	Value date	Transaction Number	Clearing Transaction?	Appear on statement?
31/07/2003	30/07/2003	C1	N	Y
31/07/2003	31/07/2003	C2	N	Y
31/07/2003	01/07/2003	C3	N	Y
31/07/2003	30/07/2003	C4	Y	Y
01/08/2003	31/07/2003	C5	N	N
01/08/2003	31/07/2003	C6	Y	Y

As illustrated, Clearing Transactions have a special treatment as compared to other transactions. To achieve the above set up, the following set up is expected:

For Inward Clearing transactions, the Transaction Code will be maintained with the Statement Date Basis as previous working day. This means that the Clearing Transactions uploaded on 01/08/2003 will have the Statement Date as previous working day of 01/08/2003, i.e. 31/07/2003.

For transactions that are not Inward Clearing, the Transaction Code will be maintained with the Statement Date Basis as Current Working Day. This means, transactions that are not Inward Clearing and processed on 01/08/2003 will have the Statement Date as 01/08/2003.

So, when the Statement Generation processing is done on 01/08/2003 (for a statement till 31/07/2003), the Inward Clearing Transactions generated will be included and not the other transactions.

The following table will show the result of the processing with the Statement Date:

Booking Date	Value Date	Transaction Number	Clearing Transaction	Branch Statement Status	Statement Date	Appear on statement
31/07/03	30/07/03	C1	N	Y	31/07/03	Y
31/07/03	31/07/03	C2	N	Y	31/07/03	Y
31/07/03	01/07/03	C3	N	Y	31/07/03	Y
31/07/03	30/07/03	C4	Y	Y	31/07/03	Y
01/08/03	31/07/03	C5	N	N	01/08/03	N
01/08/03	31/07/03	C6	Y	N	31/07/03	Y
01/08/03	31/07/03	C5	N	Y	01/08/03	N
01/08/03	31/07/03	C6	Y	Y	01/08/03	N

Thus the Statement Date derived will drive the transactions picked up for the statement between a given date if the Statement is a Booking Dated Statement.

5.9 Notary Charges

You can set the Oracle FLEXCUBE system to recover Notary Charges, for a Line Of Credit (LOC), from the current account. The system will calculate Notary Charges in the following cases:

- Activation of LOC
- Change of limit amount for line associated with LOC
- Extension of maturity for line associated with LOC

- Change in Interest Spread of an LOC

5.9.1 **Setting Up Recovery of Notary Charges**

Follow these steps for setting up the system to recover notary charges:

- Maintain Notary Codes, and their Notary Settlement GLs (Accounts) using the Notary Code Maintenance screen (CBDNRMNT).
- Link a Notary Code to a Customer Account using the Customer Accounts Maintenance screen (STDCUSAC).
- Maintain the necessary charge rules using the 'ICCF Rule Maintenance' screen (CFDRUMNT)
- In case of change of limit amount or extension of maturity the charge mode will Ad Hoc. For Ad Hoc charges:
 - Maintain the GL using 'Role to Head Mapping Class Maintenance' screen (CSDRHMCL)
 - Define the accounting entries using the 'Events Class Maintenance – Accounting Entries' screen (CSDACTCL). Set the system to debit the customer and credit the GL.
 - Attach the rule and also the account details using the Charge Class Maintenance screen (CFDCHGCL) with application and liquidation event code as CLIQ.
- In case of account activation, the charge mode will be Deferred. For Deferred charges:
 - Map the system Bridge GL using the 'Role to Head Mapping Class Maintenance' screen (CSDRHMCL).
 - Define the accounting entries using the 'Events Class Maintenance – Accounting Entries' screen (CSDACTCL). Set up the system to debit the Inter System Bridge GL and credit the Notary GL (as customer), derived from the Notary Maintenance.
 - Attach the rule and also the account details using the Charge Class Maintenance screen (CFDCHGCL)
- Maintain the notary charges, at the branch level, using the Notary Charge Maintenance screen (STDNTCHG)

In the case of Account Activation (Deferred), the system will collect the charge in two steps.

- System will credit the Notary GL maintained at the Notary Code Maintenance and debit the System Bridge GL. This will happen at the time of account activation or active account creation
- Based on the deferred days maintained at the charge class, the system will collect the charge from the customer i.e. debit the customer account and credit the system bridge GL.

In the case of Change Of Limit Amount or Extension Of Maturity (Ad Hoc) of a LOC, the system will collect the charge in one step - System will debit the customer account and credit the Notary GL.

Notary Charges must also be collected for a change in Interest Spread. The promissory note for a LOC contains Limit Amount, Interest Spread and Expiry Date. If any changes are made to a LOC, then notary charges should be collected from the corresponding customer account.

In an indefinite LOC, the promissory note will contain only the interest spread. Hence notary charges should be collected only for change in interest spread. In case of Fixed Term LOCs, if the Interest Spread, Limit Amount and Expiry Date all change on the same day, then Notary Charges will be collected only once.

You can record the charge class for Interest Spread UDE in the 'Interest UDE Charge Class' field. At the account class level (**STDACCLS**), UDE(s) for which notary charges should be collected, must be captured. When Interest Spread (which is a UDE in IC Setup) changes at the account level, then based on the charge class defined here, the Notary charges will be collected. System will debit the customer account and credit the Notary GL.

For more details on 'Notary Code Maintenance', refer to the section 'Maintaining Notary Code' in the chapter 'Maintenances for Collection Bills' in the 'Collection Bills' user manual.

5.9.2 **Notary Charge Maintenance**

The 'Notary Charge Maintenance' screen can be used to record the notary codes for charge classes - both Ad Hoc and Deferred - in the branch.

You can invoke the 'Notary Charge Maintenance' screen by typing 'STDNTCHG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Notary Charge Maintenance". It contains the following fields:

- Branch Code *
- Limit Charge Class
- Initiation Charge Class
- Liquidation Charge Class
- Interest UDE Charge Class

Below these fields is a "Fields" tab. At the bottom of the window, there are two rows of labels: "Maker" and "Checker" on the left, and "Date Time:" on the right. A "Cancel" button is located in the bottom right corner.

The above screen records the following details.

Branch Code

Specifies the branch for which the Notary Charge Maintenance is being made.

The system will process the notary charges for a class at the branch based on the notary codes maintained against the charge, for that branch. You can specify the notary codes for the following charge classes for a branch:

- Limit Charge Class - for change of limit amount for line associated with LOC
- Initiation Charge Class - for activation of LOC
- Liquidation Charge Class - for extension of maturity for line associated with LOC
- Interest UDE Charge Class - for change in Interest Spread of an LOC

5.10 Maintaining Role to Head Mapping at Branch Level

You can maintain different General Ledgers for different branches for the accounting roles defined in the system. If you have maintained Role to Head mapping for a product at the branch level, the system uses these accounting heads instead of the heads maintained at the product level.

You can maintain Role to Head mapping for a combination of branch, product and status in 'Branch Level Role to Head Mapping' screen. You can invoke this screen by typing 'CSDACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details in this screen:

Branch Code

The branch code of the current branch gets defaulted here.

Branch Name

The name of the current branch corresponding to the branch code gets displayed here.

Product Code

Specify the product code for which you wish to maintain role to head mapping or select the product code from the option list provided.

Status

Specify the status code for which you wish to maintain role to head mapping or select the status code from the option list provided.

Accounting Role

Select the accounting role to be used for role to head mapping, from the option list provided.

Accounting Head

Select the GL accounting head to be used for role to head mapping, from the option list provided.

You can add more rows to accounting role and heads by clicking the 'plus' icon provided. You can also delete a row from this table by selecting the required row and clicking the 'minus' icon.



The accounting roles and heads maintained here will override the default role head mapping maintained for the product.

5.10.1 Viewing Accounting Role to Head Mapping Details

You can view the details related to accounting roles and heads for a branch in 'Branch Level Role to Head Mapping Summary' screen. You can invoke this screen by typing 'CSSACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch level Role To Head Mapping Summary

Authorization Status Record Status
Branch Code Product Code
Status

Search Advanced Search Refresh Reset

Records per page 15 1 of 1

<input type="checkbox"/>	Authorization Status	Record Status	Branch Code	Product Code
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input checked="" type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				

Exit

The following details get displayed in this screen:

- Authorization status
- Record status
- Branch code
- Product code
- Status

5.10.2 Enquiring Holiday Details

You can perform different kind of enquiries to identify that a particular date is a holiday or non-holiday in the 'Holiday Enquiry' screen. You can invoke this screen by typing 'STDHOLFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Holiday Enquiry". The window is divided into two main sections: "Holiday Enquiry" and "Results".

Holiday Enquiry Section:

- Branch Code ***: A text input field.
- Input Date ***: A date input field.
- Forward/Backward Days Required**: Three radio buttons labeled "No", "Forward", and "Backward". The "No" option is selected.
- Number Of Days**: A text input field.
- Find**: A button to execute the search.

Results Section:

- Resulting Date**: A text input field.
- Working Day/Holiday**: A dropdown menu.
- Last Working Date of the Month**: A text input field.
- Previous Working Date**: A text input field.
- Next Working Date**: A text input field.

An **Exit** button is located at the bottom right of the window.

You can enter the following details:

Branch Code

The system will default to the local branch. However you can modify the same. This is a mandatory field.

Input Date

Specify the date, to identify that the specified Date is a holiday or a working day.

Forward/Backward Days Reqd

Select one of the following options:

- No - When this option is chosen the 'Number of Days' field will be disabled. With the option as 'No' you can find whether the 'Input Date' is a working day or holiday, 'Last Working Date of the Month' for the given input date, Previous and Next working date for the input date.
- Forward - When this option is chosen it is mandatory to provide the value in 'Number of Days' field. Based on the number days provided it will be possible to get the results as 'Input Date + Number of Days' is a working day or holiday, Last working date of the month from the resulting date, Previous and Next working date of the resulting date.

- Backward - When this option is chosen it is mandatory to provide the value in 'Number of Days' field. Based on the number days provided it will be possible to get the results as 'Input Date - Number of Days' is a working day or holiday, Last working date of the month from the resulting date, Previous and Next working date of the resulting date.

Number of Days

Specify the number of days to identify specified input falls the working day or holiday

Results

Resulting Date

The system displays the following details:

- The value of 'Input Date' when 'Forward/Backward Days Req'd' field is chosen as 'No'.
- The value of 'Input Date + Number of Days' when the 'Forward/Backward Days Req'd' field is chosen as 'Forward'
- The value of 'Input Date - Number of Days' when the 'Forward/Backward Days Req'd' field is chosen as 'Backward'

Working Day/Holiday

The system displays the whether the Resulting Date is a working day or holiday.

Last Working Date of the Month

The system displays the last working date of the month based on the Resulting Date.

Previous Working Date

The system displays the previous working date based on the Resulting Date.

Next Working Date

The system displays the next working date based on the Resulting Date.

You can perform the following types of enquiries using this screen.

- To identify that the Input Date is a holiday or a working day
- To identify that the Input Date + Particular Number of Days = Working day or Holiday
- To identify that the Input Date – Particular Number of Days = Working day or Holiday
- To identify the next working date for the given Input Date
- To identify the previous working date for the given Input Date
- To identify whether the given Input Date is a working day, if yes consider the 'Input Date' else consider the 'Next Working Date'
- To identify whether the given Input Date is a working day, if yes consider the 'Input Date' else consider the 'Previous Working Date'

- To identify the last Working Date of the month based for the given input date

6. System Dates Maintenance

6.1 Introduction

In the 'System Dates Maintenance' screen you maintain the system dates for your branch, for instance, the business date for your branch, which is the booking, date for all transactions input in the branch.

The dates screen is maintained at the branch level by the respective branches. Invoke this screen by typing 'STDDATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Input By	Authorized By	Date Time	Date Time	Modification Number	Authorized	Open
					<input type="checkbox"/>	<input type="checkbox"/>

In this screen the following fields are maintained for your branch:

You define today's date, previous working date and next working date, for the first time, during installation of the system (for details refer to the installation manual).

Suppose Oracle FLEXCUBE is installed on 1 January 1998, in your bank. In the dates screen you would input the following:

- **Today's date:** 01-JAN-1998
- **Previous working date:** 31-DEC-1997
- **Next working date:** 02-JAN-1998

After EOD for a branch is run, the system will not allow you to run any other operation in the branch, till a date change has been invoked.

If you try to run any other application, you will be prompted to invoke a date change first.

- Simultaneously two different branches can be running on two different system dates. This may happen when EOD for a branch is delayed for some reason.
- Based on 'today's date' (post authorization) the system computes and updates the 'Current financial cycle' and the 'Current period' in the Branch Parameters screen.

6.1.1 Maintaining Dates Change

For maintaining date change, invoke the 'System dates maintenance' screen after EOD for the day is run. Click 'Unlock' in the Action menu or click unlock icon. The system populates the default dates in the screen.

For instance, on the first working date i.e., 2nd of January, 1998; the system dates will be updated to:


- **Today's date** = 02-Jan-1998
- **Previous working date** = 01-Jan-1998
- **Next working date** = 03-Jan-1998

'Today's date' is defaulted from 'Next working date' of the old record. 'Previous working date' is defaulted from 'today's date' of the old record. The 'Next working date' is picked up from the 'Local branch holiday calendar' as maintained by you. You can modify 'today's date' and the 'next working date' by either clicking unlock icon on the toolbar/selecting 'unlock' from the action menu.' 'Previous working date' cannot be modified.

Today's date, if modified, should always be greater than the 'previous working date' and less than the 'next working date'. Similarly, 'next working date' if modified should be greater than 'today's date'. On modifying the dates, the system will ask you for an override. On confirmation the change will be effected.

Date change should be immediately authorized because no application of Oracle FLEXCUBE can be run without date change authorization.

- If you have input any date modification, you cannot authorize it. A user with a different login ID should do it.
- For a branch you can have only one system dates record
- Any modification in date, (be it an authorized or unauthorized record), can be done any time after today's EOD and before BOD for the next day is run. You can modify the 'next working date' any time before running the EOD for the current day.

To authorize, click authorize icon on the toolbar. If any modifications were made, on the system date, the old and the new values will be displayed. After which an alert box will warn you that the dates change will be authorized. You will be prompted to confirm. Click  to confirm. The change will be authorized. If you do not want to authorize the change then click delete icon, you will be returned to the screen from where you invoked the authorization function. Click 'Exit' button to exit and return to the Application Browser.

7. Accounts for Inter-Branch Transactions

7.1 Defining Accounts for Inter-Branch Transactions

A transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch. For example, a customer has an account in the Head Office branch and approaches another branch of the bank for a cash withdrawal.

For each combination of branches that may be involved in an inter-branch transaction, you can define the currency and the respective customer accounts to which the related accounting entries will be posted.

The accounting entries for such inter-branch transactions can be routed in one of the following ways:

- **Directly** - where each branch will have a direct accounting relationship with all other branches
- **Through a Regional Office** -- where two branches involved in a transaction will interact through a common RO
- **Through the Head Office** -- where the two branches involved in the inter-branch transaction will interact only through the HO.

This route for all transactions is defined in the 'Bank parameters' screen.

In the 'Inter-branch Parameters Maintenance' screen you define the internal accounts for pairs of branches that would be involved in any inter-branch accounting.

Invoke this screen by typing 'ACDIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

The screenshot shows the 'Interbranch Parameters Maintenance' window. It contains the following fields and sections:

- Branch1 *:** A text input field with a search icon and a 'Description' field below it.
- Branch2 *:** A text input field with a search icon and a 'Description' field below it.
- General Ledger (Left):**
 - Accounts for: [Text Input]
 - Due To Branch2 * [Text Input]
 - Due From Branch2 * [Text Input]
 - Inter Branch Currency * [Dropdown Menu: Account Currency]
- General Ledger (Right):**
 - Accounts for: [Text Input]
 - Due To Branch1 * [Text Input]
 - Due From Branch1 * [Text Input]
 - Inter Branch Currency * [Dropdown Menu: Account Currency]
- MIS Group (Left):**
 - Due to Branch 2 [Text Input]
 - Due from Branch 2 [Text Input]
- MIS Group (Right):**
 - Due to Branch 1 [Text Input]
 - Due from Branch 1 [Text Input]

At the bottom, there is a 'Fields' tab and a status bar with the following items: 'Input By DOC7', 'Date Time', 'Modification Number', 'Authorized' (checkbox), 'Open' (checkbox), and a 'Cancel' button.

In this screen you maintain the following for each combination of branches that may be involved in an inter-branch transaction:

- Branch Code of both the branches that are involved in the transaction
- For each of the branches, whether inter-branch entries must be posted in transaction currency or settlement account currency
- Customer accounts of Branch 1
 - Due to Branch 2
 - Due from Branch 2
- Customer accounts of Branch 2
 - Due to Branch 1
 - Due from Branch 1

7.1.1 **System Features**


The system generates a set of pairs of branches for which internal accounts should be maintained. The pairs generated depend upon on two factors:

- The reporting structure for the branches as created in the 'Branch parameters' screen and

- The route defined for inter-branch transactions in the 'Bank-wide parameters -- Preferences' screen,

Example

Suppose the following represents the reporting structure of your bank:



If you have defined a direct inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and branch
- Branch and RO
- RO and HO
- Branch and HO

For the above mentioned reporting structure the system will offer the following pairs of branch combinations to be maintained:

1. BR1- BR2
2. BR1- RO1
3. BR2- RO2
4. RO1- HO
5. RO2- HO
6. BR1 - RO2
7. BR2 - RO1
8. BR1 – HO
9. BR2 – HO
10. RO1 - RO2

If you have defined 'through RO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and RO/HO
- RO and RO

In the branch and RO pair, the RO should be that RO to which this branch reports. For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. BR1 - RO1
2. BR2 - RO2
3. RO1 – HO
4. RO2 – HO
5. RO1 - RO2

If you have defined 'through HO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of,

- Branches and HO
- ROs and HO

For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. HO - RO1
2. HO - RO2
3. HO - BR1
4. HO - BR2

The system has an in-built auto escalation path for inter-branch accounting transaction which escalates from Direct to Through RO to Through HO.

Example

Suppose in the 'Bank preferences' screen you have defined a 'direct' inter-branch accounting relationship. But in the 'Inter-branch Accounts' maintenance screen (where all inter-branch accounts are maintained), you have not maintained an accounting relationship between two branches -- 000 and 002. Then, in case of an inter-branch accounting transaction between 000 and 002, the system will first look for a 'direct relationship' since that has not been maintained it will look for a relationship through RO i.e., if the two branches have a common RO; if that too does not exist then 'through HO' the transaction would take place.

7.1.2 Specifying Customer Accounts

System determines the settlement route for inter-branch transactions by considering the customer accounts that you specify for a particular currency in this screen.

Example

Let us assume that your bank has to process a transaction in USD involving your branch (Branch Code 001) and another branch (Branch Code 002). If you maintain the customer accounts for the branch pair 001-002 and currency USD, system will accordingly determine the settlement route.

Branch1 and Branch2

To specify a branch pair for which you want to define the customer accounts, you can choose from a list of maintainable branch pairs displayed by the System. The description of Branch 1 and Branch 2 are displayed below the respective branch codes.

7.1.2.1 Specifying General Ledger Details

Specify the customer accounts which are involved in the inter-branch transaction, in the respective branches

To maintain customer accounts for the branch pair specified, the following parameters should be maintained:

Inter Bank Currency

For each branch, you have the option of specifying whether the inter-branch entries must be posted in the transaction currency or the settlement account currency.

For the booking branch, if the Inter-branch Transaction Currency option specified is Transaction Currency, inter-branch entries are posted in the transaction currency only if:

- The local currency of both branches involved in the transaction is the same
- One of the accounts in the entries belongs to the booking branch

Due To Branch 2

This field identifies the customer account maintained in Branch 1 into which the credit accounting entry is passed.

To specify the customer account, select the appropriate account from the picklist of all the customer accounts maintained at Branch 1.

Due From Branch 2

This field identifies the customer account maintained in Branch 1 into which a debit entry will be passed.

Due to Branch 1

This identifies the customer account maintained at Branch 2 into which a credit entry will be passed.

Due From Branch 1

This account identifies the customer account maintained at Branch 2 into which a debit entry will be passed.

System uses the customer accounts specified in this screen and determines the settlement route for a transaction between two different branches of your bank.

Inter-Branch Transactions through Customer Accounts with Currency – An Example

Assume that Friendly Neighborhood Bank has three branches:

- Los Angeles Branch, which is the Head Office Branch (Branch Code 000)
- Houston Branch (Branch Code 001),
- Chicago Branch (Branch Code 002)

Ms. Sally Williams has an account in branch 002 and wants to withdraw USD 20,000 from her account in Branch 001.

If the inter-branch scheme is 'Through HO', this inter-branch will be routed through the Head Office.

For this inter-branch withdrawal, you need to specify the following:

- Currency Code: USD
- Customer Accounts at Branch 1:
 - Due From – Sally Williams' account in Branch 001.
 - Due To – Account of Branch 002 maintained at the Head Office (Branch 000).
- Customer Accounts at Branch 2:
 - Due From – Account of Branch 002 maintained at the Head Office (Branch 000).
 - Due to – Sally Williams' account in Branch 002.

Therefore, by specifying the customer accounts involved in an inter-branch transaction, you are indicating the settlement route for the transaction.

Accounting Entries in Inter-Branch Accounting - An example

Suppose the University Savings Bank in Headington, Oxford has three branches:

1. Roosevelt Avenue Branch, which is the Head Office branch (Branch code 000)
2. Foxlake Drive Branch (Branch Code 001)
3. Mountainwood Road branch (Branch Code 002)

Branch 000 has a nostro account with Citibank, USA bearing a balance of USD 1 million. Branch 001 and 002 do not maintain USD nostro accounts, but are authorized to operate the nostro account maintained by the Head Office.

Suppose Ms. Tina Shenoy has an account with branch 001. She makes a request to her branch manager, to pay one Mrs. Tanya Agnihotri, in New York, 1000 USD from her account.

Thus, Branch 001 will instruct Citibank, New York to make the payment to Mrs. Agnihotri and debit the nostro account of it's Head Office.

If the 'preference' specified is 'Through HO' then this inter-branch transaction will be routed through the main branch 000.

The following movement of funds will be involved:

1. At branch 001, the customer's account will be debited and the 'due to branch 000' account will be credited.

- At branch 000, the Nostro account will be credited and the 'due from branch 001' will be debited.

At branch 001	Debit Ms. Shenoy's account Credit 'Due to Branch 000' account
At branch 000	Debit 'Due from Branch 001' account Credit Nostro account

7.2 Defining accounts for Inter-Branch fund transactions

A fund transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch.

As mentioned earlier, if you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the IB Entity will be defaulted as General Ledger. The GL that will be used will be based on the maintenance in the Fund Inter Branch Accounts Maintenance screen, for the fund id.

To invoke this screen, type 'IADIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

For a fund ID, specify all the details necessary to define the Inter branch GL that will be used. The option list against the field Fund ID includes all the valid funds maintained in the system.

For an explanation on each of the other fields, refer to the previous section.

7.2.1 Accounting entries in inter-branch accounting - An example

The following is an example of entries passed when the IB Currency is Transaction Currency:

A customer ABC invests USD 1,000,000 in Fund A. The currency of Fund A is BHD.

The following set of entries will get passed if the IB Currency is Transaction Currency.

The following entries will be posted as part of the transaction in corporate branch

Dr	Customer	USD 1,000,000
Cr	Inter branch account – Fund A	BHD 750,000

The following entries will be posted as part of the transaction in fund branch

Dr	Inter branch Account – Fund A	BHD 750,000
Cr	Mudarabah Fund A – Customer ABC	BHD 750,000

The following is an example of entries passed when the IB Currency is Account Currency:

The following entries will be posted as part of the transaction in corporate branch

Dr	Customer	USD 1,000,000
Cr	Inter branch account – Fund A	USD 1,000,000

The following entries will be posted as part of the transaction in fund branch

Dr	Inter branch Account – Fund A	USD 1,000,000
Cr	Mudarabah Fund A – Customer ABC	BHD 750,000

7.2.2 Maintaining Netting Group

You may want to net off inter-company payables and receivables between subsidiaries of an organisation. To accomplish this you need to maintain netting groups in Oracle FLEXCUBE. You can capture netting group details in the 'Netting Group Maintenance' screen. You can invoke this screen by typing 'STDNETGR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software window titled "Netting Group Maintenance". At the top, there are input fields for "Group Code *" and "Description". Below these are sections for "Netting Center" (with a sub-field "Netting Center Branch") and "Netting Entries" (with a sub-field "Transaction Code"). A "Details" section contains a table with two rows, each starting with a checked checkbox, followed by "Branch Code *" and "Customer Account Number *". The bottom of the window features a status area with fields for "Maker", "Checker", "Date Time", "Mod No", "Record Status", and "Authorization Status", and a "Cancel" button.

Using this screen, you can set up netting groups to net off FT (local account-to-account transfer), Retail Teller and Data Entry transactions.

Here you can capture the following details:

Group Code

Specify a unique code to identify the group for netting of transactions across customers.

Description

Enter a brief description about the organization.

Netting Center

Here you can specify the following details:

Netting Center Branch

The system displays the netting centre branch. This branch will be defaulted to the current branch code and cannot be changed.

Netting Entries

Here you can specify the following details:

Transaction Code

Specify the transaction code for posting netted entries by the netting centre.

Details

Here you can specify the following details:

Branch Code

Specify the branch code of the netting group member.


Customer Account No

Specify the netting group member account number. The adjoining option list displays all valid savings and current accounts of corporate customers maintained in the system. You can select the appropriate one.

Note that you will not be able to close the customer account record if there are any non-netted transactions of the netting group awaiting netting under the netting batch.

7.2.2.1 Executing Batch Process for Netting

You can run a batch for netting of transactions from the designated branch for the netting group as maintained, using the 'Netting Group Batch Processing' screen. You can invoke this screen by typing 'STDCSNET' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.




The screenshot shows a dialog box titled "Netting Group Batch Processing". It features a title bar with a diamond icon and a close button. The main area contains three input fields: "Group Code" with a dropdown arrow, "Description", and "Number of Unnetted Entries". A "Branch" label is followed by a blank line. A "Process" button is located below the "Number of Unnetted Entries" field. A "Cancel" button is in the bottom right corner.

You can run this batch before making end of transaction input. It will consolidate the entries posted and post one net entry for each account involved in the batch.

Group Code

Specify the netting group code to run the batch. The adjoining option list displays all the valid group codes maintained in the system. You can choose the appropriate one.

 The option 'ALL' is also available for execution of batch for all the groups under the current branch.

Branch

The system displays the branch of netting group.

Description

The system displays the description of netting group.

Number of Unnetted Entries


The system displays the number of current unnetted entries for the selected Netting Group.

On clicking the 'Process' button all the transactions available under the current netting batch are considered for processing.

All book dated transactions are considered for netting. Note that accounting entries will be passed for netting only if both legs of the transaction are customer accounts. If any of the legs contains a GL, netting entries will not be posted.

7.2.3 Querying on Netting Batch

You can view all netted and non-netted transactions of the netting process from the 'Netting Batch Query' screen. You can invoke this screen by typing 'STDNETQY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query on the basis of one or more of the following parameters:

- Netting Group Code
- Account Number

- Date

On clicking a 'Plus' button, the system displays the following details:

- Netting Reference Number
- Date
- Branch Code
- Account
- Module
- Event
- Reference Number
- Transaction Code
- Amount Tag
- Debit/Credit Transaction
- Account Currency
- Foreign Currency Amount
- Local Currency Amount

8. Currency Maintenance

8.1 Introduction

In the 'Currency Definition' screen, you define the attributes of the currencies in which your bank can deal. For each currency, you can define attributes like, the SWIFT code for the currency, the country to which the currency belongs, the interest method, the spot days, the settlement days, etc.

Currencies can be maintained only at the Head Office. The list of currencies will be made available to all the branches of your bank.

Invoke this screen by typing 'CYDCDEFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Currency Definition' window with the following fields and options:

- Currency Code * (text field)
- Alternate Currency Code (text field)
- Currency Name (text field)
- Currency Type (text field)
- ISO Numeric Currency Code (text field)
- Country (dropdown menu)
- Position General Ledger (text field)
- Position Equivalent General Ledger (text field)
- Tolerance Limit (text field)
- Index Base Currency (dropdown menu)
- Decimals (text field)
- Interest Method: 30(Euro)/360 (dropdown menu)
- Spot Days (text field)
- Foreign Exchange Netting Days (text field)
- Settlement Days (text field)
- Cut-Off Time: Days, Hour, Minute (text fields)
- Generate 103- (checkbox)
- CLS Currency (checkbox)
- Index Flag (checkbox)
- Euro Conversion (checkbox)
- New COV format Required (checkbox)
- Validate Tag-50F (checkbox)
- Rounding: Rule (Truncate dropdown), Unit (text field)
- Amount Format Mask: 99,999,999,999 (radio), 9999,99,99,999 (radio)
- Euro Type: EURO Currency (radio), IN Currency (radio), OUT Currency (radio), EURO Closed (radio)

Bottom status bar: Input By DOC7, Date Time, Modification Number, Authorized, Open, Cancel

8.2 Maintaining Currency Details

Currency Code

Currencies are identified in Oracle FLEXCUBE by the SWIFT codes assigned to them. The currency will be identified by this code in all transactions that involve it.

Currency Name

You can enter the detailed name of the currency in not more than thirty-five alphanumeric characters.

Currency Type

As per your bank's requirement you can choose to classify currencies into different currency types. The bank can use its own discretion to decide the basis of classifying currencies into different currency types. A currency type can consist of a maximum of three characters.

Depending on the customer account mask maintained, the value in the currency type field would be used during the generation of customer account numbers through the Customer Accounts Maintenance screen.

If you have decided to include currency type as part of the customer account number (in the account number mask), then at the time of creating a new customer account number, you will need to select the currency of the account number being generated. In the option-list provided for currency, the currency code is displayed along with the associated currency type say, USD – 1, GBP – 2 etc. When the account number gets populated, it is the currency type that forms a part of the customer account number.

ISO Numeric Currency Code

Specify the currency code specified by the International Standardization Organization.

Country

After you have identified the currency, you should indicate the country to which the currency belongs. You can select a country code from the option list available.

Decimals

You can indicate the number of decimal units up to which the currency can be denominated. The number of decimals allowed for any amount in the currency can be:

- 0 - Currency with no decimals
- 2 - Currency with two decimals
- 3 - Currency with three decimals

Interest Method

You can indicate the interest rate to be used for transactions that involve this currency. The interest options available are:

- Actual/Actual
- 30(US)/360
- Actual/360
- 30(Euro)/365
- 30(US)/365
- Actual/365

- 30(Euro)/Actual
- 30(US)/Actual
- Actual/Actual

Select the interest method that should be used by default whenever the currency is used in transactions. While processing a transaction that involves this currency, the interest method defined for the currency is defaulted. You have the option to change it for a specific transaction.

However, if you do not specify an interest method for a transaction, the method defined for the currency will be used (For details refer to Annexure on Page 140).

Spot Days

The number of spot working days applicable for the currency is specified here. Payment advices for FX and MM contracts will be generated on a date, which is calculated as the number of spot working days before the Maturity Date of the contract.

Example

The tenor of an MM contract is as follows:

Value Date - 01/01/99

Maturity Date - 31/01/99

Contract Currency - USD

Contract Amount - 5000

For USD, the number of Spot Days is specified as: **Spot Days** - 3

For this contract, the payment advices will be sent on 28/01/96.

Foreign Exchange Netting Days

Oracle FLEXCUBE provides a facility wherein all transactions relating to a customer, meant to be settled on a particular day and are made before a specific cut off day are collated, netted and a single payment message is sent instead of individual messages for each payment. This cut off day can be parameterized and is called 'Netting Days'. The number of FX netting days applicable for the specified currency is maintained here.



The system will validate that the FX Netting days are lesser than or equal to the spot days.

Settlement Days

In this screen, you can specify the 'Settlement Days' for a currency. Settlement messages for the components of a contract (in the LC, BC, LD, MM, FX, and FT modules) will be generated according to the settlement days specified for the currency of the settlement account. The following example illustrates this.

Example

When maintaining the details of USD in the Currency screen, you specify the 'Settlement Days' as '2'. This implies that two working days prior to the settlement of a component through a USD account, a settlement message will be automatically generated if specified (when you run the Settlement Messages function at the end of day).

The settlement details of a contract are as follows:

Settlement Date: 06 May 1999

Settlement Account Currency: USD

Component: Principal

Settlement Message: **Yes**

Component Currency: GBP

When you generate the Settlement Messages function, at the end of day, on 04 May 1999, a settlement message for the Principal component of the contract will be generated.

You can run Settlement Messages function as part of EOD operations from the Application Browser to automatically generate settlement messages for contracts marked out for automatic liquidation.

The settlement day specification for a currency will determine the contracts that are picked up for settlement message generation.

Cut-off Time

The Currency Cut-off time refers to the time by which all transactions involving a currency should be generated. For a currency, you can indicate the cut-off hour and minute. This time should be expressed in the local time of the bank.

The maintenance of a cut-off time for a currency has particular reference to outgoing funds transfers involving it.



Holidays are handled based on the currency holiday preferences specified for your bank.

Cut-off days

You can also specify the cut-off days and time for payment transactions involving the currency.

Example

The value date of a funds transfer transaction (incoming payment) involving USD, is 3rd June 2001. The number of cut-off days specified for the currency is 2. This means that the payment must be received on or before 1st June 2001. If the payment is received on 1st June, it must be received before the cut-off time specified for USD.

If the USD cut-off time is 1200 hrs, then, if the payment is received on 1st June 2001, it must be received before 1200 hrs.

The cut-off time (in hours and minutes) that you maintain to be applicable for payment transactions involving a currency are applicable to the head office branch of your bank.

If the branches are in time zones other than the head office branch time zone, you must maintain the offset time applicable for each branch, in the Branch Parameters screen.



Even when cut-off days and cut-off time for a currency have both been specified, the cut-off checks are performed for a funds transfer transaction only if specified as applicable for the product involved in the transaction.

Position or Position Equivalent GL for a currency

If you have opted for position accounting in your bank, you should indicate the Position GL and the Position Equivalent GL, when maintaining a foreign currency, in the currency screen (the Currency Definition screen).

When maintaining the GLs in your bank, you can opt to link the different foreign currencies, associated with the GL to either of the following:

- The Position GLs that you specify here (for the corresponding currency)
- Position GLs of your choice

Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

The implication:

During the transition period, settlement of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

Example

In the SWIFT messages (MT 100 and MT 202) that are generated towards settlement, the value of the component can be reported both in Nostro account currency (in Field 32A) and in an ERI currency that you specify (in Field 72). In Oracle FLEXCUBE, this information is captured in the European Related Information (ERI) fields in the Settlement Message Details screen.

Assume the following scenario:

- The settlement account is an EUR account
- You have to settle an amount of DEM 10000
- You have defined the ERI currency for DEM as DEM
- The Tolerance Limit for DEM as 0.05%
- The exchange rate: 1 Euro = 1.30 DEM

The settlement amount in Euro would therefore be 7692.36 (rounded to nearest higher cent). This amount will be reported in Field 32A of the settlement messages. Now, if you want to furnish the settlement amount in the ERI currency (in this case, DEM) you have to manually enter the DEM value in the ERI Amount field. You may enter DEM 10000. (EUR 7692.36 actually converts into DEM 10000.068.)

The value that you have entered is well within the Tolerance Limit of 0.05% defined for DEM. Therefore, this value will be reported in Field 72 of the settlement messages.

Since the Tolerance Limit for DEM is 0.05%, you can specify an ERI Amount between DEM 9995 and DEM 10005 ($DEM\ 10000 * 0.05/100 = DEM\ 5$). If you enter an ERI value exceeding DEM 10005 or less than DEM 9950, the system recalculates the ERI Amount at the time of generating the settlement messages. The recalculation will be on the basis of the pegged rates between the Settlement Currency and the ERI currency.



The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

Index Base Ccy

Specify the currency that should be used to handle index-based securities traded by the banks, wherein the deals are done in index currency and their settlement is done through the local currency.

Generate 103+

You can enable the MT 103 + format option only if you would like to generate outgoing MT 103 messages in the MT 103 + format.

If you are enabling this option for a specific currency, ensure to also enable this option:

- For your bank branch in the Branch Parameters Maintenance
- For the customer of the contract, in the BIC Code Maintenance
- For the product used by the contract, in the Product Preferences

Consequently, while processing transactions in the specified currency for such a customer, branch and product, for which the MT 103+ option is enabled, the system generates outgoing payment messages in the MT 103 + format.



Since the system is also capable of processing incoming MT 103 messages in the MT 103 + format. Therefore, during the upload process for your branch, the system considers an MT 103 payment message to be of MT 103+ format for those customer, currency and product combinations, for which the MT 103+ option has been enabled.

CLS currency

To allow customers of your bank to settle their FX deals via the CLS (Continuous Linked Settlements) Bank, you can identify the currency to be a 'CLS Currency'. FX deals in the CLS currency only will be eligible to be routed through the CLS bank.

From the available list of CLS currencies, you can further maintain a list of 'allowed' or 'disallowed' currencies for a specific customer. Every customer who is a 'CLS Participant' will be allowed to trade in all the available CLS currencies unless specifically mentioned.

Refer the 'Continuous Linked Settlements' chapter of the Foreign Exchange User Manual for details on maintaining currency restrictions and other maintenances required for processing CLS deals in Oracle FLEXCUBE.

New COV Format Required

Check this box to indicate that cover message needs to be sent in the new format, for transactions involving the currency specified here.

For more details on new cover message formats, refer settlements user manual.

Validate Tag 50F

Check this box to indicate that validations need to be performed for the 50F details captured for the ordering customer during contract input.

For more details on 50F validations, refer the chapter titled 'Maintaining Addresses for a Customer' in Messaging System user manual.

8.2.1.1 Indicating Rounding Preferences

Rule

This refers to the method to be followed for rounding off fractional units of a currency. The rounding preferences available are:

- Truncate — The amount is truncated to the number of decimals specified for the currency
- Round Up — The amount is rounded up based on the number of decimals and the nearest rounding unit
- Round Down —The amount is rounded down based on the number of decimals and the nearest rounding unit

Example

Amount before Rounding	Rounding Method	No. of Decimals	Rounding Unit	Amount after Rounding
1234.678	Truncate	2	-	1234.67
1234.678	Round up to the nearest rounding unit	2	.01	1234.68
1234.678	Round down to the nearest rounding unit	2	.01	1234.67

Unit

If you have selected Round Up or Round Down in the Rule field, you need to indicate the nearest unit to which the rounding should take place. The number of units specified here should not be greater than the number of decimals allowed for the currency.

Example

The decimal points specified for currency 'A' is 2. Rounding unit is .05

Amount for transaction is USD 100.326, which will be rounded off depending upon the decimals specified and the rounding rule and rounding unit.

For Rounding Rule 'Up', the amount available for transaction would be USD 100.35. For rounding rule 'Down', the transaction amount would have been rounded down to 100.30

If the rounding rule was specified as 'truncate' then, the amount would have rounded off to 100.32 (simply, knock off all decimal points beyond the stated decimals places to be rounded off). Thus whenever you specify a 'truncate' option you need not state the 'Rounding unit'.

8.2.1.2 Specifying Amount Format Mask

Specify the format in which amounts in this currency are to be displayed for contracts in this currency. Two options are available:

999,999,999

9,999, 999, 99

The system defaults to the 999,999,999 format.

Euro Type

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency with relation to transition phase of the European Economic and Monetary Union (EMU). You can do this in the 'Euro Type' field.

Your specifications in this field enable you to handle the *first phase* of the EMU, which commenced on 01 January 1999.

For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro'.

By choosing the appropriate option, you can indicate if the currency is:

- The Euro
- An 'In' currency
- An 'Out' currency
- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.


When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

- Closing all 'In' currencies, and
- Choosing the 'Euro Closed' option (for the Euro)

8.2.2 Specifying Exchange Rate Limits

Click 'PC' button in the Currency Definition screen to invoke 'Limits' screen.




You can specify the credit limit and the debit limit for the exchange rate in this screen.

8.2.3 Mapping Currency to Country

Click 'Currency Country Mapping' button in the Currency Definition screen to invoke 'Clearing Zones Country Codes for Currency' screen.

The screen appears as shown below:




You can map a currency code to a country in this screen.

8.2.4 Specifying User Defined Fields

You can associate values to all the User Defined fields created and attached to the Currency Definition Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:



You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

8.2.5 **Annexure**

The treatment for interest calculation varies with each of the interest calculation methods. Each method is dealt with individually below:

Actual/Actual Method

$$10,000 \times 10 / 100 \times (31 / 365 + 84 / 366)$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

$$\text{Total} = 31 + (31 + 29 + 24 = 84) = 115$$



When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

Therefore, the denominator for the 31 days in December is 365 as it is a non-leap year and the denominator for the 84 days in 2000 is 366 as it is a leap year.

Actual /365 Method

$$10,000 \times 10 / 100 \times 115 / 365$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

Total=31+31+29+24=115

Actual/360 Method

$10,000 \times 10 / 100 \times 115 / 360$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

Total=31+31+29+24=115

30 Euro/Actual Method

$10,000 \times 10 / 100 \times (30 / 365 + 84 / 366)$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 114 days



When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

30 Euro/365 Method

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 114 days

30 Euro/360 Method

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 114 days

30 US/Actual Method

$10,000 \times 10 / 100 \times (30 / 365 + 84 / 366)$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 114 days



When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

30US/365 Method

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 114 days

30US/360 Method

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 114 days

8.2.6 Specifying Currency Cut-Off Parameters

You can choose to restrict the time within which (or before which) funds transfer transactions involving a specific customer, product, and a currency, must be received for processing. For a specific customer, product, and a currency, you can specify a certain number of days before which a transaction involving the combination must be received, as well as a cut-off time before which transactions must be received. These parameters are known as currency cut-off parameters, and you maintain these parameters in the 'Value Dated Spread' maintenance screen.

Invoke this screen by typing 'FTDVDSR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software window titled "Value Date Spread Maintenance". It is divided into several sections. The top section, "Value Date Spread", contains fields for "Customer Identification *", "Customer Name", "Product Code *", and "Description". To the right of these are fields for "Currency Code *" and "Description". Below this is the "Spread Details" section, which includes "Debit Value Date Spread *" and "Credit Value Date Spread *". To the right of this is the "Cut Off Details" section, which includes "Days", "Cut Off Time HR", and "Minutes". At the bottom of the window, there is a "Fields" section with checkboxes for "Input By DOC7", "Date Time", "Modification Number", "Authorized", "Authorized By", "Date Time", "Open", and a "Cancel" button.

In this screen, you can maintain the cut-off time, cut-off days and the value spreads to be applicable for:

- Each customer, for a product and currency combination
- All customers, for each product and currency combination

These currency cut-off parameters are validated in respect of a funds transfer transaction only if currency cut-off checks are specified as applicable in the product preferences, for the product involving the transaction.

For details about how the currency cut-off checks are applied on a funds transfer transaction, refer the chapter 'Processing a Funds Transfer Contract' in the Funds Transfer User Manual.

8.3 Handling Euro

On 1 January 1999, eleven countries that are part of the European Union embarked on the first phase of economic integration, called the 'Economic and Monetary Union' (EMU). In Oracle FLEXCUBE, the eleven countries participating in the first phase of the EMU are referred to as 'In' countries and the respective national currencies as 'In' currencies. All other countries are referred to as 'Out' countries.

The first phase of the EMU, referred to as the 'transition period', ushered in a new, single European currency: the **Euro (EUR)**. During this phase, the National Currency Denominations of 'In' countries would co-exist with the Euro. That is, transactions involving an 'In' currency would, typically, be routed through the Euro during this phase. At the end of the transition period, in mid 2002, however, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in 'In' countries.

In Oracle FLEXCUBE, you can handle the Euro and the attendant implications for your bank, by capturing additional currency and settlements related information. This chapter details how this information is to be captured, and its implications.

8.4 **Maintaining Euro Related Information**

In Oracle FLEXCUBE, the details that you need to maintain in order to handle the EMU include:

- Maintaining Euro as a valid currency
- Indicating if a currency is 'In', 'Out', 'Euro', or 'Euro Closed'
- Maintaining Currency Redenomination details
- A common conversion GL and a transaction code to identify the redenomination entry
- Maintaining a 'Tolerance Limit' for a currency (to check against ERI information)
- Capturing additional settlement details (Euro related information for the MT 100 and MT 202 SWIFT messages)

You can maintain currency related information in the Currency and the Currency Pair Definition screens. 'Settlement' details can be captured in the Settlement Instruction Details screen.

8.4.1 **Maintaining Currency Details**

Your specifications for a currency in the Currency Definition screen determine the manner in which transactions in the currency are handled in Oracle FLEXCUBE. Invoke this screen by typing 'CYDCDEFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Type

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency. You can do this in the 'Euro Type' field. Choose the appropriate option from the following:

- The Euro itself
- An 'In' currency
- An 'Out' currency
- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.

When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

- Closing all 'In' currencies, and
- Choosing the 'Euro Closed' option (for the Euro)

Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

The implication:

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

The following example illustrates the application of the Tolerance Limit.

Example

In the SWIFT messages (MT 100 and MT 202) that are generated towards settlement, the value of the component can be reported both in Nostro account currency (in Field 32A) and in an ERI currency that you specify (in Field 72). In Oracle FLEXCUBE, this information is captured in the European Related Information (ERI) fields in the Settlement Message Details screen.

Assume the following scenario:

- The settlement account is an EUR account
- You have to settle an amount of DEM 10000
- You have defined the ERI currency for DEM as DEM
- The Tolerance Limit for DEM as 0.05%
- The exchange rate: 1 Euro = 1.30 DEM

The settlement amount in Euro would therefore be 7692.36 (rounded to nearest higher cent). This amount will be reported in Field 32A of the settlement messages.

Now, if you want to furnish the settlement amount in the ERI currency (in this case, DEM) you have to manually enter the DEM value in the ERI Amount field. You may enter DEM 10000. (EUR 7692.36 actually converts into DEM 10000.068.) The value that you have entered is well within the Tolerance Limit of 0.05% defined for DEM. Therefore, this value will be reported in Field 72 of the settlement messages. Since the Tolerance Limit for DEM is 0.05%, you can specify an ERI Amount between DEM 9995 and DEM 10005 (DEM 10000 * 0.05/100 = DEM 5). If you enter an ERI value exceeding DEM 10005 or less than DEM 9995, the system recalculates the ERI Amount at the time of generating the settlement messages. The recalculation will be on the basis of the pegged rates between the Settlement Currency and the ERI currency.



The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

Currency pairs

In the Currency Pair Definition screen, you can specify a 'Through Currency'. When maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'.



You cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.

8.4.2 Maintaining Conversion GLs

To facilitate the currency conversion process, two additional parameters need to be maintained in the 'Branch Parameters' screen. Invoke this screen by typing 'STDBRANC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You have to maintain a common Conversion GL and a Transaction Code that identifies redenomination entries.

The screen is as shown below:

The screenshot shows the 'Branch Parameters Maintenance' window. At the top, there are fields for 'Branch Code *', 'Branch Name *', and a checked 'Branch Available Status'. Below this are three tabs: 'General Details', 'Financial Details', and 'Duplication Check Details'. The 'General Details' section includes fields for 'Parent Branch', 'Regional office', 'Country Code', 'Customer Identity', and 'Local Currency', each with a small 'EK' icon. The 'Financial Details' section has three 'Description' fields. The 'Duplication Check Details' section has three 'Description' fields. The 'Time Zone Offset' section includes 'Hours', 'Minutes', 'Time Level', and checkboxes for 'Ahead' (checked), 'Fund Branch', and 'Allow Corporate Access'. The 'ATM Details' section has 'ATM Branch', 'Institution Identification', and 'Inter Branch Transaction Code' fields, with a 'Customer Transfer' checkbox. The 'CutOff Offset Time' section has 'Hours' and 'Minutes' fields. The 'Local Payments' section has a 'Clearing Branch *' field. The 'Address' section has three 'Branch Address Line' fields. The 'BIC', 'Telex', and 'Host Name' fields are on the right. The bottom section has 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status' fields, and a 'Cancel' button.

8.4.2.1 Indicating Euro Redenomination General Ledger

Conversion GL

The conversion GL that you specify will be identified as the common Suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

Transaction Code

In addition to the conversion GL, you have to indicate a Transaction Code, which identifies conversion related entries.

8.4.3 Implications of Currency Redenomination

In the IC Product Accounting Role Definition screen

For the purpose of currency conversion, an accounting role called 'Acquired' is available.

End of day processes

Maintaining a Conversion GL and Transaction Code simplifies the End of day process. Basically two important things happen when the End of day processes are run. Firstly interest is liquidated to the Acquired Interest GL and secondly all balances will be reduced to zero.

When you run the Beginning of day processes the next day the change in the currency conversion will be in place. In addition balances will get restored.

Example

You decide to re-denominate the account 'BOAB001BNKCUFINRA2' of Customer Number 'SP1000' from Deutsche Mark (DEM) to EURO.

You have specified that the liquidation cycle is to be monthly. The currency conversion is carried out on the 17th of the month.

The interest liquidated from the 1st to the 17th will be put in the Acquired Interest GL. On the next liquidation date (i.e. the 30th of the month) the interest liquidated from the 1st to the 17th is converted to Euro and transferred from the Acquired Interest GL to account 'BOAB001BNKCUFINRA2'.

Additionally the interest calculated from the 17th to the 30th is also credited or debited to the account depending upon the type of account.

An example of the EOD/BOD processes

The following example illustrates the accounting entries passed when currency conversion is made.

Account Name BOAB001BNKCUFINRA2

Account Currency Deutsche make (DEM)

The Bank's LCY	USD
The Standard Exchange Rate between DEM and EURO	2.5

Requirement:

The account currency has to be converted from DEM to EURO.

The Value Dated balances as of the 17th of the month are as follows:

17th Jan 99	18th Jan 99	19th Jan 99
100,000 Cr.	120,000 Cr.	80,000 Cr.

The following are the accounting entries passed as of the 17th for the Account BOAB001BNKCUFINRA2.

Account	CCY	Dr/Cr.	FCY	LCY	Txn Code	Val. Date
BOAB001BNKCUFINRA2	DEM	Dr.	100,000	33333.33	ECV	17 th
BOAB001BNKCUFINRA2	DEM	Dr.	20,000	6666.67	ECV	18 th
BOAB001BNKCUFINRA2	DEM	Dr.	40,000	13333.33	ECV	19 th
CNV GL	DEM	Cr.	80,000	26666.67	ECV	17 th

The following are the entries passed on the 18th of the month:

Account	CCY	Dr./Cr.	FCY	LCY	Txn Code	Val. Date
BOAB001BNKCUFINRA2	EURO	Cr.	48000	40000	ECV	18 th
BOAB001BNKCUFINRA2	EURO	Dr.	16000	13333.33	ECV	19 th
CNV GL	EURO	Dr.	32000	26666.67	ECV	18 th

Change in field values due to conversion

The change in currency re-denomination impacts amount based fields pertaining to Accounts, Collaterals, Credit Lines and Customer Limits. The change in the value of these fields is reflected when you run the beginning of day processes.

The amount-based fields, which are affected by the change in currency denomination, will be updated with the equivalent value in the new currency

Accounts

The following fields will reflect the new values:

- Temporary Over Draft limit
- Sub-limit
- Uncollected Funds limit
- Offline limit
- Account Currency

These fields can be found in the Customer Accounts Maintenance screen.

Collateral

In the Limits Maintenance Collaterals screen the following fields will be updated:

- Collateral Currency
- Collateral Value

- Limit Contribution
- Issuer Exposure Amount

Credit Lines

In the Limits screen of the Limits Maintenance module the following fields will reflect the new values:

- Credit Line Currency
- Tenor limits
- Tenor utilization
- All Related Amounts

Customer Limits

In the Customer Maintenance screen of the Core Services module the following fields will be updated at BOD.

- Limit Currency
- Liability Risk Limit
- Customer Risk Limit



Note the following:

- Once the conversion process is complete the advices generated for your customer will carry the following information:
 - The Old Value
 - The New Value
 - And the Exchange Rate used for the conversion
- As a consequence of currency re-denomination you will not be able to pass entries where the value date falls before the currency conversion date.

8.4.4 Specifying Preferred ERI Currency for Counterparty

For a counterparty and currency (combination), you can maintain a preferred ERI currency. You can state this preference in the 'Settlement Instructions' screen.

The implication

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You can maintain this ERI currency (for a counterparty and currency combination) in the 'Settlement Instructions Maintenance' screen.

In the SWIFT messages that are generated towards settlement of a component (involving the counterparty and the currency), the component value will be expressed in this (ERI) currency, by default. Invoke this screen by typing 'ISDINSTR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

8.4.5 Specifying Settlement Message Details

SWIFT messages (MT 100/MT202) generated towards settlement can furnish the value of the settlement amount in both the settlement account currency, and an 'ERI' currency. If you opt to furnish the ERI value of the amount, you have to enter the following in the 'Settlement Details' screen:

- The ERI currency
- The ERI Amount

The screen appears as shown below on clicking 'Settlements' button in the contract screen:

The screenshot shows a window titled "Settlement Details". At the top, there are two input fields: "Contract Reference *" and "Component". Below these are several tabs: "AccountDetails", "Message Details", "Parties", "Parties", "Clearing Details", and "Local Clearing". A table is displayed with the following columns: Component, Currency, Branch, Account, Description, Account Currency, Debit/Credit, Original Exchange Rate, and Exchange. The table is currently empty. Below the table is a "Signature Verification" button. At the bottom right of the window are "Ok" and "Cancel" buttons.

The system defaults to the ERI currency specified for the customer and currency combination. You can change the default ERI currency. The ERI amount that you specify will be validated against the Tolerance Limit specified for the ERI currency.

8.4.6 **Settlements of Foreign Exchange Deals**

Oracle FLEXCUBE allows cross currency settlements of foreign exchange deals that involve an 'In' currency. You can settle the 'In' currency leg in another 'In' currency or in 'Euro'.

Example

Assume you enter into the following Foreign Exchange deal. You sell 1,00, 000 FRF against USD.

The scenario:

You specify the exchange rate: 1 USD = 5.2 FRF

The bought amount is therefore: 19230.769 USD

The settlement account is in EUR

The exchange rate between EUR/FRF: 1 EUR = 6.475 FRF


Since FRF is an 'In' currency, you can settle the *sell* leg of the deal through EUR (in this example). The settlement amount would be EUR 15444.015.

8.4.7 Reports and Advices

The following reports furnish the equivalent Euro values of amounts in an 'In' currency. The 'locked in' exchange rates defined for the Euro against the 'In' currency will be used for currency conversions.

The reports with this feature are the:

- Currency Position report
- Cash Flow report
- FX Maturity report

 These reports will not furnish the 'In' currency and equivalent Euro values when you close the 'In' currencies, and choose the 'Euro Closed' option (for the Euro) in the Currency Definition screen.

All advices that provide 'In' currency details will also provide the equivalent Euro values

Account Statements

Statements provided for accounts in an 'In' currency provide the Euro equivalent values of the following:

- The opening balance
- The closing balance
- Every transaction

8.4.8 Maintaining Limits Type

You can maintain various limit types and their values through the 'Limits Types Maintenance' screen. For example, you can define and maintain various Limit types like price codes, collateral types and price through this screen.

You can invoke this screen by typing 'LMDTYPES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software window titled "Limit Types". At the top, there are two input fields: "Type *" and "Description". Below these is a section titled "Values" which contains a table with two columns: "Value" and "Code". The table has one row with empty input fields. Above the table are icons for adding (+), deleting (-), and refreshing (list) items. At the bottom of the window is a "Fields" section with labels for "Input By", "Date Time", "Authorized By", "Date Time", "Modification Number", and "Number". There are also checkboxes for "Authorized" and "Open", and a "Cancel" button.

Type

Specify the limit type for which you want to maintain values

Description

Specify the description for the limit type you are maintaining

Values

The values for the limit type that you are maintaining can be listed here. To add a value to the list of values, click on the 'Add' icon, and type the value. To remove a value from the list of values, check the box against that value and click on the 'Delete' icon.

Value

Specify the list of supported values. For example, MAIL, COURIER, BRANCH and so on.

Code

Specify the codes for the list of value. For example, CO, ML and so on.

8.4.9 Maintaining Transaction Limits

This section explains in detail about maintaining transaction limits, level of authorisations required for the transaction amounts and minimum user authorisation limit required for a transaction.

Oracle FLEXCUBE offers you a facility, whereby, each time a particular transaction processed in the system exceeds a certain limit; an override will be generated by the system.

You can maintain transactional limits for a module and product combination through the 'Product Transactional Limits Maintenance' screen. Invoke this screen by typing 'CSDPLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Transaction Limit *	Level Of Authorization	Minimum Authorization Limit	Cumulative
			<input type="checkbox"/>

Module Code

Each module in Oracle FLEXCUBE is identified by a code. First, you have to identify the module for which the currency-wise transactional limit is to be maintained. A list of all the modules operational at your bank will be displayed in the option list. You can choose the appropriate module code.

Description

The description associated with the module will be defaulted in the adjacent field.

Product Code

Each module contains a number of products within it. After you identify the module, indicate the product within the module for which you would like to maintain a currency-wise transactional limit. You can select the appropriate product code from the option list.

In the Product Transactional Limits screen, you can maintain the limits for:

- A specific module and a specific product
- A specific module and all products (select 'ZALL' as the Product Code)
- All modules (Select 'AL' as the Module Code) and all products

Description

The description associated with the module will be defaulted in the adjacent field.

Transaction Limit Currency

The transaction limit currency is the currency in which you would like to maintain the amount limit.

Transaction Amount Limit

Each time you process a transaction, the system will check the transaction amount against the limit maintained for the module, product and currency combination, involved in the contract.

Customer Type

Select the type of customer for whom you are maintaining the transaction limits from the adjoining drop-down list. The following are the options available:

- Corporate
- Individual
- Bank
- All

Product Transaction Limit Details

Specify the following transaction limit details:


Transaction Limit

Specify a transaction limit. Each time you process a transaction, the system checks the transaction amount involved in the contract against the limit specified here. If the contract currency is different from the transaction limit currency, then the system converts the contract amount using the standard mid rate to the transaction limit currency and check against the transaction limit amount maintained for the product

The system displays an appropriate message indicating the levels of authorization if the transaction amount booked is in excess of the maintained transaction limit.

Level Of Authorization

Specify the number of authorisers to be involved in the authorising a particular transaction amount.

 The level of authorization should be greater than one.

Cumulative


Check this option to indicate that multiple authorisers are allowed to authorise a transaction. The authorisers must have equal or greater than the minimum authorization limit maintained in this screen. The system displays an appropriate error message if the authoriser tries to authorise a transaction having transaction amount greater than the minimum authorising limit.

Minimum Authorization Limit

This option is enabled only if the 'Cumulative' option is checked. Specify the minimum authorization limit required for a transaction. The authorization limit cannot be greater than the transaction limit. This amount is used to validate authorizer limit while authorizing the contract.

8.4.9.1 Validating Transaction Amount during Contract Processing

While saving a contract, the system will check the transaction amount against the cut-off amount maintained for the module and product currency involved in the transaction. If both the transaction currency and the limits currency are same, the comparison will be done directly. If different currencies are involved, the system will first convert the transaction amount into the cutoff amount currency using the STANDARD mid rate and then perform the validations.

 To perform the check, the System will look for the limits maintained, in the following order:

1. The System looks for the limits maintained for a specific module and specific product combination
2. If the first option is not available, it checks the limits maintained for a specific module + ZALP (all products) combination
3. It checks the maintenance for AL (all modules) + ZALP (all products) combination

If the third option is also not available, the system displays an error message

When a transaction exceeds the amount limit, the system displays an override message while saving the transaction

8.5 Maintaining Sequence Generation Format

Every contract in Oracle FLEXCUBE is identified by a unique Contract Reference Number that is generated internally by the system. You are not allowed to modify this number. In addition, a contract is also identified by a unique User Reference Number. By default, the Contract Reference Number will be taken as the User Reference Number. But you have the option to change the User Ref Number.

Oracle FLEXCUBE also provides you the facility to generate the user reference number in a specific format.

To maintain a specific format, you need to identify the various components that would be part of the user reference number including details such as the length, order, value etc. of each component.

You can maintain a unique format through the 'Sequence Generation Input' screen. You can invoke this screen by typing 'CSDSEQGN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Component Order	Component	Component Type	Use in Sequence Generation	Component Length	Component Value

You can maintain the following details of the sequence format:

Sequence Code

Each sequence format is identified by a unique sequence code. You can devise a code comprising a maximum of 20 alphanumeric characters.

Branch Code and Module Code

You can maintain the format for a specific branch and module combination. Select the branch code and the module code from the option-list. All authorized and active records will be displayed in the list.

Alternatively, you can maintain a sequence format that will be applicable to all the branches (ALL) and all the modules (AL) available in your bank.

Reset Frequency

You need to specify the frequency at which the system will drop and recreate the sequence numbers once again. At the reset frequency that you specify, all sequence numbers of the sequence format will be dropped and recreated again during the End of Day processing.

The options available are:

- None
- Daily
- Monthly
- Yearly

For example, let us assume that the running number in the sequence format is 4 characters long (starting from 0001) and the reset frequency is Monthly. Further, let us assume that the sequence number of the last contract processed on the last day of the month is 0199. At EOD of the last day of the month, the sequence numbers generated till date will be dropped and the system will begin regeneration starting from 0001 once again for all subsequent contracts.

Range

You can specify a range of sequential reference numbers. If you specify such a range, then no additional details need be specified. If you do not specify a range, you can specify additional details specific to each component of the sequence format.

In addition to the above details, you should also maintain details specific to each component of the sequence format. The details are as follows:

Component Order

Each component is assigned an order number based on which they would appear in the user reference number. The component order is automatically generated by the system and is non-editable.

Component

Each component in the sequence format is identified as one of the following:

- An Oracle FLEXCUBE Component – If your sequence format uses an Oracle FLEXCUBE column directly, you can specify it as an Oracle FLEXCUBE Component. For instance, you may want to include the product group associated with the product code involved in a contract, as a component in sequence number generation. To achieve this, you will use the Oracle FLEXCUBE column PRODUCT_GROUP (available in the table CSTM_PRODUCT) as an Oracle FLEXCUBE Component.
- A User Component – You may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. You can define it as a user component. In addition, if you want to use the manipulated value of an Oracle FLEXCUBE Column in the sequence format, you can specify it as a User Component. For eg, you may want to include ONLY the first four characters of the product group in the sequence number. In this case, the component would be defined as a User Component.

- A Separator – To separate the various components from one another, you can use the component known as the separator. Eg: a back slash, a hyphen etc.
- A Running Number – Each contract is identified by a unique sequence number. It is mandatory to maintain a running number as a component in the sequence format. If not included, you will not be allowed to save the details of the format. A running number is internally generated by the system.

Component Type

You need to identify the type of each component in the sequence format. A component can be constant throughout or change for every contract processed at your bank. You can associate a component with one of the following types:

- Static – To include any hard coded component in the sequence format, you will specify the type to be static. For instance, you may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. The component type would be static in this case.
- Dynamic – You will specify the component to be of the dynamic type if its value is picked up from the Oracle FLEXCUBE table. Eg: Product Group. A running number would always be dynamic in nature.

Use in Sequence Generation

You need to indicate whether the component being defined should be used in sequence generation or not. Specify 'YES' or 'NO' as per your choice.

You can also choose to display the reference number in the advices that are generated for a contract.

Component Length

You can also specify the length of each component in the sequence format. The component value is dependent on the component length maintained. For instance, if you specify 2 as the component length, the value should comprise of only two characters.

Component Value

As stated earlier, the component value is dependent on the component length. Based on the length, you can specify a value comprising of as many characters as specified in the Component Length field. However, this field is used only if the value of the component is required to be constant (static type) in all the user reference numbers generated at your bank. If the component value is changing constantly (Dynamic type) for every contract, the system will automatically pick up the value from the DB table based on the SQL query that you maintain for the purpose.

Component Column and Component Table

If your component is of the dynamic type, you will need to mention the name of the Oracle FLEXCUBE column from where the system will pick up the component value. Further, if you wish to include a manipulated column value in sequence generation, you will need to include 'SUBSTR' as well in the column name. For eg, to include only the first four characters of the product group associated with the product code involved in a contract, you will specify the following in the Component Column field:

SUBSTR (PRODUCT_GROUP, 1, 4)

You need to mention the table name also, if the component type is dynamic. The following table names are available in the option-list provided.

- DUAL
- STTM_BANK
- STTM_BRANCH
- CSTM_PRODUCT

For our example, the table name would be CSTM_PRODUCT.

Component Where Clause

The condition or the 'where clause' of the SQL code is specified here. In the example discussed above, the system will pick up the appropriate product group depending on the product code involved in the contract being processed. You can specify the following where clause as an extension of the SQL statement specified earlier:

```
WHERE PRODUCT_CODE = SUBSTR (P_CRN, 4, 4);
```

Click add icon to define each subsequent component in the format. Use the navigating icons to move between the various components of a sequence format.


8.6 Message delivery In Oracle FLEXCUBE

Messages generated in Oracle FLEXCUBE can be sent to external delivery channels. As a branch level parameter you can indicate whether delivery of messages through multiple channels is required. You must also designate a default delivery channel to which messages would be delivered.

If you enable the Multiple Channels option you can maintain the various delivery channels that would be used through the Delivery Channel Maintenance screen.

8.6.1.1 Maintaining Delivery Channels

At the Head Office branch, you can maintain the various Delivery Channels through which messages are delivered from FLEXCUBE. You can invoke this screen by typing 'CSDZDLCH' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



The screenshot shows a window titled "Delivery Channel Maintenance". It has a blue header bar with a diamond icon on the left and standard window controls (minimize, maximize, close) on the right. The main area contains two text input fields: "Delivery Channel *" (with a red asterisk) and "Description". At the bottom, there are four text labels: "Maker", "Checker", "Date Time:", and another "Date Time:". A "Cancel" button is positioned in the bottom right corner.

You can maintain the following details here:

Delivery Channel

Specify the delivery channel.

Description

Provide the brief description of the specified delivery channel.

9. Maintaining Currency Denomination

9.1 Introduction

In the Data Entry module, you can specify a break up of a transaction amount for Teller transactions by denomination. The system also maintains a break-up of the till balances by denomination.

9.2 Maintaining Currency Denomination Details

In the 'Currency Denomination' screen, you maintain the standard currency denominations for each currency that your bank deals with. You can invoke this screen by typing 'CSDDEMAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Denomination Details' application window. At the top, there are input fields for 'Denomination Type *' (set to 'Cash'), 'Currency Code *', 'Currency Description', 'Issuer Code *', and 'Issuer Description'. Below these is a table with the following columns: 'Denomination Id *', 'Denomination Description', 'Denomination Value *', 'Sequence Number', and 'Type *'. The table is currently empty. At the bottom of the window, there are fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

To maintain the denominations of a currency, you need to specify the following:

- The code of the currency for which you are defining denominations
- A unique code to identify each denomination of the currency. For example, you can assign D1, D10, D50 for USD 1, 10, 50.
- A description of the denomination unit
- The denomination type coin or note
- The value of the denomination in relation to one unit of the currency. It could be a fraction for coins

Example

For the currency USD you can maintain the denominations as follows:

CURRENCY CODE	DENM CODE	DESCRIPTION	VALUE	NOTE / COIN
USD	D100	100 dollars	100.00	NOTE
USD	D50	50 dollars	50.00	NOTE
USD	D20	20 dollars	20.00	NOTE
USD	D10	10 dollars	10.00	NOTE
USD	D5	5 dollars	5.00	NOTE
USD	D1N	1 dollar Note	1.00	NOTE
USD	D1C	1 dollar Coin	1.00	COIN
USD	C25	25 cents	0.25	COIN
USD	C10	10 cents	0.10	COIN
USD	C5	5 cents	0.05	COIN
USD	C1	1 cent	0.01	COIN

Denomination type Millionaire certificate is used to facilitate MC/LMC (Millionaire Certificate) transactions. You can have only one denomination with denomination type as 'Notes' and the currency code should be the LCY code of each country..

9.2.1.1 Operations Allowed in the Currency Denomination screen.

Following standard maintenance operations are possible in the 'Currency Denomination' screen:

- Add
- Modify
- Delete
- Authorize
- Close
- Re-open
- Inquiry
- Logs all maintenances in the Audit Trail.

10. Expressing Amounts in Words

10.1 Introduction

You can describe the amounts printed on account statements, messages, advices, etc., in words, for the benefit of your customers. To describe 'amounts' in a specific language, you have to maintain the verbal equivalents of numerals in the language. You can maintain verbal equivalents of numerals in the 'Amount Text Maintenance' screen.

You can invoke this screen by typing 'STDAMTRN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Amount *	Description	Prefix One
		<input checked="" type="checkbox"/>

Currency *	Pre Decimal	Post Decimal	Final Text	Text Before	Fractions
				<input checked="" type="checkbox"/>	<input type="checkbox"/>

Fields

Input By DOC7 Date Time Modification Number Authorized
Authorized By Date Time Open Cancel

Amount translation details can be maintained as one time maintenance at the time Oracle FLEXCUBE is installed at your bank. Once maintained, the amount descriptions printed on account statements, and other messages, will be described according to your specifications in this screen.

Language

You can maintain verbal equivalents of numerals in any language that Oracle FLEXCUBE supports. This means that you can maintain the verbal equivalents of numerals in as many languages as you generate messages.

Text

You must describe the following numerals in the Description field (in the language that you specify in the Language field):

- 1, 2, 3, up to 10
- 20, 30, 40, 50, 60, 70, 80, and 90
- 100
- 1,000
- 10,000
- 100,000
- 1,000,000
- 10,000, 000, and so on

In certain languages, One thousand, One million, and so on are expressed, simply, as 'thousand', and 'million'. If you are defining verbal equivalents of amounts in such a language, do not choose the 'Prefix One' option. Statements and messages printed in such a language will describe amounts such as '1000', simply, as 'thousand'.

Choose the 'Prefix One' option, if you would like amounts such as '1000' described as 'One thousand'.

Currencies

In this screen, you can also describe the pre-decimal and the post-decimal units of a currency in different languages. Enter the verbal equivalent of the 'pre' and 'post' decimal units of a currency in the Pre-Decimal and Post-Decimal fields respectively. For example, if you would like to describe the decimal units of USD, enter:

- The currency in the Currency field
- The pre-decimal description as 'Dollars'
- The post-decimal description as 'Cents'
- Final Text to be attached to the currency.

You can opt to prefix, or suffix, an amount with its currency. If you would like the suffix an amount with its currency, do not choose the 'Text Before' option. If you would like to prefix an amount with its currency, choose the 'Text Before' option.

For example, if you would like to describe USD 1000, as Dollars One Thousand, choose the 'Text Before' option.

11. Defining Currency Pairs

11.1 Introduction

In the foreign exchange markets, the exchange rates for some currency pairs such as the USD-GBP or USD-JPY are easily obtainable, since these are frequently traded. The exchange rates of other currencies such as the ZAR-INR (South African Rand - Indian Rupee), which is not traded very often, is determined through a third currency. This third currency is usually the US dollar, since the US dollar is quoted in all trading centres.

In the Currency pair definition screen, you define the static attributes of currency pairs for which a regular market quote is readily available. For other pairs, which do not have a regular market quote, you need to specify the third currency through which the system should compute the exchange rate.

The currency pair screen is maintained at the bank level by your Head Office branch using the 'Currency Pair Maintenance' screen.

You can invoke this screen by typing 'CYDCPAIR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Pair Maintenance

- Currency Pair

Currency1 *

Currency2 *

Through Currency

Description

Description

- Through Currency

Code

Description

Quotation Method Direct Indirect

Points Multiplier

Number Of Units One Hundred Thousand

Spread Definition Percentage Points

Fields

Input By DOC7 Date Time Modification Number Authorized

Authorized By Date Time Open

11.2 System Features

From among the currencies maintained in the currency screen, the system builds all possible combinations of currencies in pairs. For example, if you have maintained the following currency codes: USD, YEN. The system will give you a choice of defining parameters for the following pairs.

- USD-INR
- USD-YEN
- INR-USD
- INR-YEN
- YEN-USD
- YEN-INR

It is however, not obligatory to define parameters for all these pairs. A currency pair needs to be maintained only if:

- You want to define a direct exchange rate for the pair: for frequently traded currencies like INR-USD or USD-GBP or USD-JPY for which market quotes are available.
- You want to define a through currency for the pair: for those currencies which are not so well traded, market quotes may not be available. Therefore you can route the conversion rate for the pair via a 'through currency'. For example, in the case of GBP-NLG, for which a direct exchange rate may not be available, you can define a through currency say, USD. The exchange rate between GBP-USD and NLG-USD will be picked up by the system to compute the exchange rate between GBP-NLG.

In the absence of a direct exchange rate, the system will look for a through currency to compute the rate. If a 'through currency' has not been maintained then the default local currency will be picked up as the through currency to compute the rate for a currency pair.

11.3 Maintaining Parameters for Currency Pair

Currency Pair

A currency pair (specified as Currency1 and Currency2, in the Currency Pair screen) represents the two currencies for which you need to maintain exchange rates.

To specify the pair, choose from the list provided against Currency1. Select the pair for which you want to maintain parameters.

The pair should be selected according to the quotation method followed by the market, which could be direct or indirect (for details refer to the field 'quotation method'). Exchange rates can be defined for currency1 against currency2 or currency2 against currency1.


The descriptions of the respective currencies are displayed below.

Through Currency

If the exchange rate for a particular currency pair is not to be maintained, specify the 'Through Currency' via which the exchange rate between the currencies should be calculated.

To maintain a through currency for a currency pair, check against the box 'Through Currency'.

Then choose from the list codes provided against Code, Select the currency code, which you want to specify as the 'through currency'. The exchange rate for the currencies involved in the pair will be calculated using the through currency.

 While maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'. Please note that you cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.

For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro' in this manual.

Whenever, you define a through currency for a currency pair, you will not be allowed to specify the following for the pair:

- Number of units
- Spread definition

Quotation Method

This is the method to be followed for quoting the exchange rate. There are two methods direct and indirect.

In the Direct method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate - buy spread

Sell rate = mid rate + sell spread

Ccy 1 = Rate x Ccy 2

In the Indirect method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate + buy spread

Sell rate = mid rate - sell spread

Ccy 2 = Rate x Ccy 1

Example

The market follows the direct quote convention for the currency pair USD-DEM e.g., 1USD=1.6051DEM. To maintain this pair, you would specify currency 1 as USD and currency 2 as DEM, and specify "direct" in this field.

For the USD-GBP pair, which is quoted indirectly (1 GBP = 1, 5021 USD), the USD will be defined as currency 1 and the GBP as currency 2, with the quotation method "indirect".

Number of Units

This indicates the number of units of currency to be used for currency conversion

Example

Quotation Method	No. Of Units	Formula for calculating conversion rate
Direct	1	1ccy1 = rate x ccy2
Direct	100	100 ccy1 = rate x ccy2
Direct	1000	1000 ccy1= rate x ccy2
Indirect	1	1ccy2 = rate x ccy2
Indirect	100	100ccy2 = rate x ccy1
Indirect	1000	1000ccy2 = rate x ccy1

Spread Definition

You need to indicate the method in which the spread for a currency pair needs to be defined. There are two ways of defining the spread -- in points and in percentage.

The effective spread can be calculated using any of the following two methods:

- In points — spread x points multiplier
- In percentage — spread/100 x mid rate

Example

We shall examine the impact of each of these spread definition methods on the currency pair USD: DEM.

Mid rate = 1.6040

Spread = 10

In points the buy rate and sell rate would be calculated as:

Buy rate = Mid rate - spread x points multiplier

Sell rate = Mid rate + spread x points multiplier

If points multiplier = .0001 then

Buy rate would be = $1.6040 - 10 \times .0001$

Sell rate would be = $1.6040 + 10 \times .0001$

In percentage the buy rate would be calculated as:

Buy rate = Mid rate - spread x points multiplier

Sell rate = Mid rate + spread x points multiplier

Buy rate would be = $1.6040 - 10/100 \times 1.6040$

Sell rate would be = $1.6040 + 10/100 \times 1.6040$

The default-spread definition is through the points method.

The method of spread definition that you specify here applies to two instances:

- While maintaining exchange rates for this currency pair
- While maintaining Customer Spread for this currency pair

11.3.1 Specifying Points Multiplier

Points are the smallest unit of measurement in the exchange rate of a currency pair. If you have opted for a points system of defining spread, you should specify the multiplication factor for the points to compute effective spread.

Suppose for the currency pair USD-DEM your rates are as follows:

Mid-Rate: 1.6045

Buy rate: 1.6040

Sell rate: 1.6051

The effective buy spread is 0.0005 ($1.6045 - 1.6040$) and the effective sell spread is 0.0006 ($1.6051 - 1.6045$).

In the Rates screen, where you define rates and spreads for a currency pair, you can specify the buy and sell spreads as 5 and 6 instead of as 0.0005 and 0.0006 (i.e., as spread points), and specify here the points multiplier as 0.0001.

The effective spread, buy and sell rates are then computed as follows:

Effective buy spread = Buy spread x Points multiplier = $5 \times 0.0001 = 0.0005$

Buy rate = Mid rate - Buy spread = $1.6045 - 0.0005 = 1.6040$

12. Maintaining Exchange Rates

12.1 Introduction

In the Currency Rates screen, you can maintain exchange rates for a currency pair, the rates at which you buy and sell one currency for another.

A bank determines its buy and sell rate for a currency pair by applying a spread (i.e., its profit margin) to the mid-rate of the currency pair. Mid rate is the basic rate at which a currency pair is exchanged.

The spread applied for a currency pair varies with the transaction type, while the mid-rate usually remains constant. Consequently, different rates are applicable to different transaction types. For instance dollars in currency are purchased at a certain rate, while USD traveler's checks are bought at a different rate. In Oracle FLEXCUBE, you can define a rate type which you would like to associate with a transaction type e.g., 'CASH', 'TRAVCHKS', etc., in the Rates screen.

In the Currency Rates Maintenance screen, you define the mid-rate, buy and sell spread applicable to each rate type; the buy and sell exchange rates are computed by the system.

Buy rates and sell rates can either be maintained by individual branches or can be input by the HO and propagated to all the branches. If in the Bank-wide parameters - Preferences screen you have specified your preference as 'copy exchange rates to branches' then the 'currency rates maintenance' screen is maintained at the bank level by your Head Office. These rates are then propagated to the branches. The branches can only view the rates but cannot make changes to them.

In the Bank-wide Preferences screen, if you have not specified 'copy exchange rate to branches' then the 'Currency Exchange Rates Input' screen is maintained at the branch level by the different branches.

You can invoke this screen by typing 'CYDRATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

The screenshot shows a software window titled "Currency Exchange Rates Input". At the top, there are two text input fields labeled "Currency1*" and "Currency2*". Below these is a table with the following columns: "Rate Type*", "Mid Rate", "Buy Spread", "Sale Spread", "Buy Rate", "Sale Rate", "Rate Date", and "Rate Serial". The table is currently empty. Below the table is a button labeled "Enrich". At the bottom of the window, there is a "Fields" section with several labels: "Input By", "Date Time", "Modification Number", "Authorized", "Authorized By", "Date Time", "Open", and an "Exit" button.

In this screen you maintain the following parameters for each rate type of a currency pair:

- Mid rate
- Buy spread and Sale spread
- Buy rate and Sale rate

Specify the currency pair for which you want to compute the exchange rates. The pair should be selected keeping in mind the quotation method for exchange rates as followed by the market. The system offers the choice of maintaining both the currencies as currency1 or currency 2 -- USD against DEM and DEM against USD.

For the pair specified the following parameters need to be maintained to arrive at the buy and sell rate of currencies:

- Rate Type
- Mid Rate
- Buy Spread
- Sell Spread
- Buy Rate
- Sell Rate

Rate Type

This is the rate type for which you are maintaining exchange rates for a currency pair. For different transaction categories your bank would like to maintain different exchange rates. For example, traveller's check is purchased at a certain rate whereas a bill of exchange is bought at a different rate.

In the front-end-modules, where you define products to cater to the various transaction types of your bank, you can link an appropriate rate type to the product. For instance, you create a product to cater to outgoing cross currency transfers by SWIFT. For this product, if you define the rate type to be STANDARD then for all contracts linked to this product, the Standard Rate Type would be applied.

Mid Rate

Mid rate is an indicative exchange rate for a currency pair. It is the average of the buy and sell rate quoted by the market for a currency pair.

Example

Suppose, currency 1 = USD

Currency 2 = INR

Buy rate -- 1 USD = 1.7020 INR

Sell rate -- 1 USD = 1.7040 INR

Mid-Rate = 1.7030

Buy Spread

This is the buy spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you buy currency 1 for currency2. You can define the buy spread in two ways -- either in points or in percentage. The system computes the effective buy spread for you.

Sale Spread

This is the sell spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you sell currency 1 for currency 2. You can define the sell spread either in points or in percentage. The system computes the effective sell spread for you.

Buy Rate

Buy rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

Sale Rate

Sell rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

You can also input the buy and sell rate for a currency pair. In which case, the system will compute the spread for the rate type.

Rate Date

This is a display field. When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date. The rate date will always be less than or equal to the application date.

Rate Serial

This is a running serial number for the Rate Date. You need to specify the serial number. Your entry will be validated for uniqueness. For example, there could be only one exchange rate between USD and EUR for 31/07/2003 with Rate Type STANDARD with Rate Serial as 0001. Thus, this will be a unique rate serial for a currency pair, rate type combination for a given rate date.

When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date and the Rate Serial as the latest available serial for the currency pair + 1. The Rate Serial Number will be system generated. However, you can modify it if required. This number takes into account the Rate Serial Number present in the Currency Rates History screen too. The Rate Serial Number and the Rate Date will be displayed during authorization of the Rate in the Currency Authorization screen.

12.1.1 Authorizing Exchange Rates

Authorization of exchange rates is done from the Currency Exchange Rates input screen. Details like old value, new value for each field (buy rate, mid rate etc) are displayed. Click authorise icon to authorize the record.

12.1.2 Revising Exchange Rates


For revising the exchange rates for your bank or the branches invoke the 'Currency Maintenance' screen. Click the currency pair whose exchange rate you want to revise and click unlock icon on the toolbar. Input/modify the new rates for the pair.

12.1.3 Viewing Exchange Rates

You can view the exchange rates in the 'Currency Exchange Rates View' screen. You cannot input any values. You also have the option of specifying whether you want to view authorized rates or the unauthorized rates for any currency pair.

You can invoke this screen by typing 'CYSRATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:



If the branches pick up the exchange rates maintained by the HO, then each time you invoke the 'currency view' screen from a branch it is advisable to update this screen with the latest rate input, from the HO. To do this, click on 'Refresh'. Refresh updates the screen with the last exchange rates input.

12.1.4 Specifying Limits for Cross Currency Transactions

Typically, the exchange rates applicable for cross currency funds transfer or teller transactions is defaulted by the system depending upon the preference indicated in the product preferences, for the product involving the transaction.

In your bank, for high-value cross currency transactions, you may want the user to manually enter the exchange rate involved, rather than let the system automatically pick up a default rate during transaction input.

You can define such a preference to be applicable to cross currency transactions involving:

- A currency pair
- A specific product, or all products
- A specific module, or all modules
- A specific branch, or all branches
- A specific rate code

The transaction amount limit, above which the exchange rate must be entered, for a high value transaction, could be defined in terms of currency pair where the currency of the transaction is currency1 in the CCY pair defined in the maintenance.

Example

In the San Francisco branch of your bank, you do not wish to allow default of exchange rates automatically for funds transfer payments for the currency pair USD GBP exceeding 10000 USD.

So this Limit Amount of 1000 USD will be maintained as follows:

Branch – 000, Module – FT, CCY1 – USD, CCY2 – GBP

Rate Code – Standard, Limit CCY– USD, Limit Amount – 100000

When an FT transaction with transaction currency as USD happens where the offset currency is GBP, the system will check for the Limit Amount defined for the currency pair USD-GBP. If the transaction amount is more than the limit amount defined here, the system will not default the exchange rate for the pair. Instead, it will force the User to enter the rate manually for the transaction.

To ensure that users manually enter exchange rates for high-value cross currency transactions in Oracle FLEXCUBE, you must specify the limit amounts that must be validated for each transaction in terms of currency pair, product, module, and branch combination. You can use the 'Product Limits Maintenance' screen to specify the limits.

When you have specified these limits, the system automatically validates the amount with each transaction for the currency pair, product, module and branch combination, and accordingly, if the limits are exceeded, enforces the manual entry of exchange rates.

In case, the limit between ccy1 and ccy2 is given in ccy2, the system will automatically convert the transaction amount to an amount in ccy2 using standard mid rate and check against the limit amount whether or not manual entry of exchange rates is required. You can invoke the 'Product Limits Maintenance' screen, by typing 'CSDPXMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

The screenshot shows the 'Product Limits Maintenance' window. At the top, there are five input fields: 'Branch Code*', 'Module Code*', 'Product Code*', 'Currency1*', and 'Currency2*', each with a selection icon. Below these is a 'Limit Details' section containing a table with three columns: 'Rate Code*', 'Limit Currency*', and 'Limit Amount*'. The table is currently empty. At the bottom of the window, there is a 'Fields' section with checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

Branch Code

You must specify the branch for which the limit amount will be applicable. You can specify that the limits must be applicable for all branches.

Module Code

You must specify the module for which the limit amount will be applicable. You can indicate that these limits must be applicable for both the Data Entry (DE) and Funds Transfer (FT) modules.

Product Code

You must specify the product, transactions involving which the limit amount will be applicable. You can specify that the limits must be applicable for all products.

Currency 1

You need to specify the currency1 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. This currency is always the transaction currency of the contract.

Currency 2

You need to specify the currency2 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. The Currency2 should be part of a Currency Pair Maintenance in which the Currency1 defined here is the first currency. Currency 2 can be specified as ALL.

12.1.4.1 Specifying Limit Details

Rate Code

You need to specify the Rate Type (code) for the Exchange Rate Limit

Limit Currency

You need to specify the currency in which the Limit Amount should be expressed. All valid currencies defined in the system will be applicable for selection. There will be a validation for the limit currency as either Currency1 or Currency2.

Limit Amount

You need to specify the maximum amount up to which the system should default the Exchange Rate or perform the Rate Variance validation.

12.1.4.2 Validating Exchange Rate Limits

The Funds Transfer Contract Input will default the Rate only if the Transaction Amount is less than the Maximum Amount defined for the Rate Code maintained at the product level for FT. If the amount is more than the specified amount, then the system will not default the Rate. Instead, it will force the user to enter the Rate. Once the user enters the Rate, the system will not add the Customer Spread etc. as this will be final Exchange Rate for the contract.

The Rate Variance validation will also be done only if the amount is less than the maximum amount defined for the Rate Code maintained at the product level for FT. If the amount is more than the specified amount, the system will not perform the Rate Variance validation. Instead, there will be an override to specify that the transaction amount is greater than the maximum amount for Rate Variance check.

For details about how limits are applied when a transaction is entered, refer the chapter 'Processing a Funds Transfer', in the Funds Transfer User Manual.

12.2 Maintaining Index Currency Rates

You can specify details of index currency using 'Index Currency Rates Maintenance' screen. To invoke the screen, type 'CYDIDXRT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Index Rates Input' application window. At the top, there are two input fields: 'Index Ccy' and 'Base Ccy'. Below these is a 'Default Settlements' section with a table. The table has two columns: 'Rate Date' and 'Rate'. The table is currently empty. At the bottom of the window, there are fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Specify the following details:

Index Currency

Specify the index currency.

Base Currency

Based on the index currency selected, the system displays the corresponding base currency.

Rate Date

Specify the date on which the exchange rate has been provided. This can be the current date or a future date of the current month.

Rate

Enter the exchange rate for the index currency as of the rate date. The rate can have up to eight decimal places. The index rates are maintained date-wise. As of a specific date, you can have only one rate.



You cannot modify or delete the rate maintained for a past date.

13. Maintaining Currency Spread for Customer

13.1 Maintaining Customer Spread Details

For a customer and currency pair, you can maintain tenor-wise spread details in the 'Customer Spread Maintenance' screen.

You can invoke this screen by typing 'CYDCUSPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Spread Details	Buy Spread	Sale Spread
<input type="checkbox"/> Tenor *		
<input type="checkbox"/>		

In this screen, for a customer and currency pair, you can maintain buy and sell spreads for different tenors.

You need to maintain customer spreads in each branch. Transactions initiated in a branch will pick up the spread(s) maintained for that branch.



Note the following:

- Funds Transfer, Loans and Deposit contracts have tenor = 0 (zero). Therefore, you need to maintain Customer Spreads for zero tenor also.
- The tenor is specified in days

13.1.1.1 Specifying Spread Details

When processing an FX deal involving a customer (for whom you have maintained spread details), the system picks up the customer spread corresponding to the tenor of the deal and builds it into the exchange rate. If spread details are unavailable for a specific tenor, the system picks up the spread defined for the nearest lower tenor.

For example, assume for a customer and currency pair you maintain spread details for the following tenors: '3', '5', and '10' days. When processing a deal with a tenor of '4' days (involving the customer and the currency pair), the system picks up the spread details defined for a tenor of three days. This is because spread details for a '4' day tenor is unavailable for the customer and currency pair.



You can also maintain customer spreads for the wildcard entry – ALL. If spread details for a specific counterparty (for the currency pair) are unavailable, the System looks for the customer spread maintained for the wildcard ALL entry. If even that is not available, then the customer spread defaults to zero.

13.1.2 Computing Buy and Sell Spreads

Using percentage system -- suppose the bank wants to make a profit of 5% over and above the mid rate quoted. Suppose the dealing currencies are USD and AUD. 1USD = 1.4166 AUD for Standard rate type. (Mid rate being 1.4166). Now to arrive at the spread the bank will use the following formula:

$$\text{Spread} = 5 / 100 \times \text{Mid rate (1.4166)} = 0.07083$$

Example

Currency Code 1	Currency Code 2	Rate Type	Mid Rate	Buy Spread	Sale Spread
USD	AUD	STD	1.4166	0.07083	0.07083
USD	AUD	TT	1.3666	0.06833	0.06833
USD	AUD	CASH	1.2666	0.06333	0.06333

Using the points system -- suppose the point quoted by the bank is 708.3. The points multiplier in this case would be 0.0001 (depends on the decimal points that the mid rate extends to. Usually it is 4 decimal places).

$$\text{Spread} = \text{Points (708.3)} \times \text{Points Multiplier (0.0001)}$$

Now coming to the buy and sale rate computing, there are two ways of computing the buy and sale rates -- Direct and Indirect. Depending upon the quotation method you have specified in the Currency pair screen, the system computes the spreads.

In the **Direct** method, the buy and sell rates are calculated as follows:

$$\text{Buy Rate} = \text{Mid-Rate} - \text{Buy Spread}$$

$$\text{Sell Rate} = \text{Mid-Rate} + \text{Sell Spread}$$

For cross currency contracts, the rate for the currency pair is:

1 unit of Ccy 1 = Rate * 1 unit of Ccy 2

In the **Indirect** method, the buy and sell rates are calculated as follows:

Buy Rate = Mid-Rate + Buy Spread

Sell Rate = Mid-Rate - Sell Spread

For cross currency contracts, the rate for the currency pair is:

1 unit of Ccy 2 = Rate * 1 unit of Ccy 2

Example

You have entered into a Buy contract and the currency pair involved is USD/AUD (where 1 USD = 1.4166 AUD). In the Currency Rate Maintenance screen, the following details are maintained:

Mid-Rate - 1.4166 (from the Currency screen)

Rate Type - STD

Buy Spread - 0.07083

Sell Spread - 0.07083

You have specified the Quotation method for this currency pair as Direct in the Currency Pair screen. In this method, the Buy Rate is calculated as -- Mid-Rate - Buy Spread. So the Buy Rate for this contract is:

$$\text{Buy Rate} = 1.34577 = (1.4166 - 0.07083)$$

In addition, you have the option of defining the fields that should be computed and those that should be input. You can either input the buy and sale rates and get your spreads computed by the system or define the spreads and let the system compute the rates.

The method of spread definition – percentage or points – that you have maintained for the currency pair is displayed on this screen.

13.1.3 Maintaining Currency Margins for Customer

For each customer of your bank you can define buy and sell margins for a specific currency. This spread is applied to floating interest components that involve the customer and currency combination.

You can define buy and sell margins for a customer in the Customer Spread Maintenance screen invoked from the Application Browser. You can invoke this screen by typing 'CFDCUMRG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The margin that you define will be appropriately picked up and applied to arrive at the final rate that is applied to floating components of contracts that involve the customer - currency combination.

The buy and sell margins that you define are for a customer and currency combination. You can select the customer and currency combination from the option lists available.

For the selected currency – customer combination, you can define amount slabs and specify a Borrow and Lend margin for each slab. To add a slab to the list click add icon and enter the slab details. To remove a slab from the list, highlight it and click delete icon.

Whenever you enter a contract in Oracle FLEXCUBE that involves the customer and currency combination, the appropriate spread is applied to arrive at the floating rate to be charged. The slab is selected based on the contract amount and depending on the nature of the contract, the Borrow or Lend spread is applied.

Amount Slab	Spread
-------------	--------

13.1.3.1 Making Margin Applicable to All Customers

For a given currency, you can define borrow and sell margins to be applied to All customers. At the customer field choose ALL. However, if you have maintained currency margins for a specific customer and currency combination, it takes precedence over the margin defined for all customers.

Currency margins can be maintained for customers across branches. In effect, a branch can maintain margins for a customer belonging to another branch. These margins are propagated across branches of your bank.

14. Defining Currency Rate Types

14.1 Introduction

Banks quote different exchange rates for different transaction types. For instance, traveler's checks are purchased at a certain rate; a different rate is applicable for buying of foreign currency notes, and so on.

In the 'Currency Rate Type Definition' screen, you define the rate types applicable to the different transaction categories of your bank. Each rate type is assigned a code. For instance, you could define a rate type called CASH, which will be applicable for all cash transactions in foreign currency; TRAV-CHKS for traveler's checks buying and selling, and so on. The buying and selling rates for each rate type are defined in the 'rate definition screen'.

In the front-end-modules, where you define products to cater to the various transaction types of your bank, you can link an appropriate rate type to the product. For instance, you create a product to cater to outgoing cross currency transfer by SWIFT. For this product if you define the rate type to be STANDARD then for all contracts linked to this product the Standard Rate Type would be effective.

The currency Rate Type Definition screen is maintained at the Bank level by your Head office branch. You can invoke this screen by typing 'CYDCRTYP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Currency Rate Type Maintenance". The window contains a form with the following elements:

- A label "Currency Rate Type" followed by a horizontal line.
- A text input field labeled "Type*" with a red asterisk.
- A text input field labeled "Description".
- A "Fields" section at the bottom containing a table of fields:

Input By DOC7	Date Time	Modification Number	<input type="checkbox"/> Authorized
Authorized By	Date Time		<input checked="" type="checkbox"/> Open

A "Cancel" button is located at the bottom right of the window.

In this screen you can maintain the following:

Type

Currency types in which your bank may be dealing with -- like cash, traveller's cheque, telegraphic transfer etc.

Description

Specify a description of the rate type.

15. Maintaining Rate Template

15.1 Rate Template

The Source Rate, Spread and Destination Rate is developed to maintain their respective characteristics in the 'Rate Template' screen. You can invoke this screen by typing 'CSDRTTMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Rate Template' application window. It features several input fields and dropdown menus. At the top, there are fields for 'Template Id *' and 'Description'. Below these are two dropdown menus for 'Read Destination Rate Characteristics From' and 'Read Source Rate Characteristics From', both set to 'Contract'. The window is divided into three main sections: 'Characteristics of Source Rate', 'Characteristics of Spread', and 'Characteristics of Destination Rate'. Each section contains fields for 'Type *' (set to 'Effective Annual'), 'Year Basis' (set to 'Actual'), and 'Period'. Below these sections is the 'Rate Converter' section, which includes 'Source Rate' and 'Spread' input fields, a 'Calculate Destination Rate' button, and a 'Destination Rate' output field. At the bottom, there are fields for 'Maker', 'Checker', 'Mod No', 'Date Time', 'Record Status', and 'Authorization Status', along with 'Ok' and 'Cancel' buttons.

The screen contains multiple sections to fill in the data and convert the required rates for different source and destination rates selection. All the mandatory fields have to be filled in the screen.

Specify the following details:

Template ID

Specify the Unique Id to identify Rate conversion parameters.

Description

Specify the template description.

Read Destination Rate Characteristics From

Select the values from the adjoining drop down list. The list displays the following values.

- Contract
- Template

Read Source Rate Characteristics From

Select the values from the adjoining drop down list. The list displays the following values.

- Contract
- Template

Characteristics of Source Rate

Type

Select the source rate type from the adjoining drop down list. The list displays the following values.

- Bearing
- Discounted
- Effective
- Annual

Year Basis

Select the year basis from the adjoining drop down list. The list displays the following values.

- 360
- 365 or Actual

Period

Specify the source rate period in days.

Characteristics of Spread

Type

Select the spread rate type from the adjoining drop down list. The list displays the following values.

- Bearing
- Discounted
- Effective

- Annual

Year Basis

Select the year basis from the adjoining drop down list. The list displays the following values.

- 360
- 365 or Actual

Period

Specify the spread rate period in days.

Characteristics of Destination Rate

Type

Select the destination rate type from the adjoining drop down list. The list displays the following values.

- Bearing
- Discounted
- Effective
- Annual

Year Basis

Select the year basis from the adjoining drop down list. The list displays the following values.

- 360
- 365 or Actual

Period

Specify the destination rate period in days.

Rate Converter

Source Rate

Specify the source rate value for simulation.

Spread Rate

Specify the spread rate value for simulation.

Destination Rate

The system displays the Converted Rate Value based on Rate parameters, source and spread rate for simulation.

Click the 'Calculate Destination Rate' button in order to calculate the value.

16. Maintaining Floating Rates

16.1 Floating Rates

A Floating Rate corresponds to the market rates for the day. These rates are maintained and updated daily (or whenever they change), in the 'Floating Rates Maintenance' screen. The rates can be applied on a loan with or without a spread.

You can invoke this screen by typing 'CFDFLTRI' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'LD MM Floating Rate Input' window. It is divided into several sections:

- Rate Code:** Includes fields for Branch Code (set to 'PKS'), Rate Code, and Rate Description.
- Currency:** A table with columns for Currency Code. The first row is checked.
- Effective Date and Amount Slab:** A table with columns for Amount Slab, Effective Since, and Effective Un. The first row is checked.
- Tenor and Interest Rate Details:** A table with columns for Tenor To, Interest Rate, Maximum Rate for Term Deposits, and Pre-Closure Differential for Term Deposits. The first row is checked.
- Fields:** A section at the bottom with labels for Maker, Checker, Mod No, Date Time, and Record Status.
- Buttons:** A 'Cancel' button is located in the bottom right corner.

A Floating Rate Code identifies a set of rates defined, for a combination of Currency, Amount Limit, Tenor and Effective Date. The initial criteria for the rate calculation to happen successfully is that there should be a Zero tenor/Non zero tenor based rate slab existing for the particular Buy/Sell Indicator with Effective date less than/equal to the Value date.

You can associate a Floating Rate to a contract by linking the Rate Code to the contract. The rates defined for the Rate Code will be applied to the contract based on the application preferences that you set up here.

Branch and Rate Code

Specify the branch and rate for which the preferences (effective date, amount slab etc) are being set up

16.1.1.1 Specifying Currency Details

You can associate several currencies with a Rate Code. For example, you can have a Rate Code 'TERMLON45' (with a description of Rates for a Term Loan of 45 days). You can define rates for the same Rate Code in different currencies. Thus, you can define a set of rates, for contracts in USD and another set for contracts in GBP.

Click add icon and select a currency code, from the option list available.

When you link a contract in USD to the Rate Code TERMLON45, the rates defined for this currency will be applied. Similarly, if the contract is in GBP, the rates defined for that currency would be applied.

16.1.1.2 Specifying Effective Dates and Amount Slab

Amount Slab

A floating rate can be defined as per an amount slab structure. You should specify the upper limit of the slab to which a particular rate should be applied.

Example

Suppose the following is the slab structure you want to maintain for the Rate Code – FL01 and Currency – USD.

Amount Slab
250 Thousand
1 Million
3 Million
3 Million

The Basis Amount To for the first slab or tier should be indicated as 250,000 that for the second slab as 1,000,000, and so on.

In case component amount is greater than the highest slab, the appropriate rate for highest amount slab is picked up and applied. Similarly, if the component amount is lesser than the lowest amount slab, the appropriate rate for lowest slab is picked up and applied.

Effective Since

Each rate that you define for a Rate Code and Currency combination should have an Effective Date associated with it. This is the date on which the rate comes into effect. Once a rate comes into effect, it will be applicable till a rate with another Effective Date is given, for the same Rate Code and Currency combination.



The revised rates will be applied on specific effective dates depending on whether it has been defined, with Auto Rate Code Usage or Periodic Rate Code Usage. You can specify this in the Product ICCF Details screen.

Effective Until

Specify the Effective Until It indicates the date until which reference rate will be effective.



Note the following:

When loan is created with rate codes DTF, IPC, IBR and LIBOR; Code usage is selected as Periodic for UDE. Additionally, rate revision is maintained to trigger rate revision on desired dates (rate revisions are in scope only for bearing loans on the schedule due date only, not on any desired date).

After conversion if 'Spread Rate' is in 'EA' denomination, the system will check the 'Spread treatment' defined at product level and use the method to calculate the final value either it can be "Conventional Method" or "Addition Method". If "Spread Rate" is not in "EA" denomination then system will ignore the spread treatment defined at product level and always use the "Addition Method" to calculate the final value.

Borrow Lend Ind

Here you indicate the type of contracts to which the floating rate should be applied. Select one of these options from the picklist:

- Borrow
- Lend
- Mid

Typically, a floating rate maintained as Borrow can be applied on Deposits. Rates marked with Lend can be made applicable to Loans and Bill contracts.

Tenor

For each amount slab that you define for a Floating Rate Code, you can define tenors and indicate the rates applicable to each tenor. The rate will be applied to contracts based on the slab into which it falls and the reset tenor defined for the component.

17. Maintaining Packet Templates

17.1 Introduction

Oracle FLEXCUBE allows you to customize various products and services as a single package to be offered to your customers. These packages will also provide benefits pertaining to commissions and charges.

17.2 Maintaining Packet Templates

You can maintain the parameters that are required for creation/association of products as part of a package in the 'Packet Template Maintenance' screen. To invoke this screen, type 'STDPATEM' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Account Class	Currency	Count	Cheque Type	Cheque Book Code	No C
			Regular		

You can specify the following details in this screen:

Template ID

Specify the template identification number.

Scheme ID

Specify the relationship pricing scheme ID. The adjoining option list displays all the scheme id's that are maintained in the system. You can choose the appropriate one.

Customer Type

Select the customer type for which the template is applicable. The list displays the following values:

- All
- Individual
- Corporate
- Bank

17.2.1 Specifying Account Details

You can specify the account details by clicking 'Account Details' tab in the 'Packet Template Maintenance' screen.

Specify the following details:

Account Class

Specify the account class that you wish you to associate to the template. The adjoining option list displays all the account classes that are maintained in the system. You can choose the appropriate one.

While maintaining a template, it is mandatory to associate it with the current account class.

Currency

Specify the currency of the account class. The adjoining option list displays all the currencies that are maintained in the system. You can choose the appropriate one.

Count

Specify the count of account numbers that needs to be created.

Cheque Type

Select the cheque type from the drop-down list. The list displays the following values:

- Regular
- Continuous
- Magnetic
- Continuous Form
- Special Form
- Not required

Cheque Book Code

Specify the cheque book code.

No of Leaves

Specify the number of leaves.

Optional

Check this box to indicate that the corresponding item is optional as a part of package.

STOP If this check box is not selected, it will be displayed as such details in the 'Packet Creation' screen. If packet is saved with optional checked, the account will not be created on save, else, at package level on save account would be created.

17.2.2 Specifying Limit Details

You can specify the limit details by clicking 'Limit Details' tab in the 'Packet Template Maintenance' screen.

The screenshot shows the 'Packet Template Maintenance' window with the 'Limit Details' tab selected. The window contains the following fields and controls:

- Template Id * (text input)
- Scheme Id * (text input with a dropdown arrow)
- Customer Category (dropdown menu set to 'All')
- Account Details | **Limit Details** | Debit Card Details (tabbed interface)
- Navigation controls: 1 of 1, search icon, and list icons.
- Table with columns: Limit Template, Limit Type, Limit Amount, and Optional.
- Table content: One row with a checked checkbox in the 'Limit Template' column, a dropdown arrow in the 'Limit Type' column, a text input in the 'Limit Amount' column, and an unchecked checkbox in the 'Optional' column.
- Footer fields: Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status.
- Buttons: Ok and Cancel.

Specify the following details:

Limit Template

Specify the template id for the limits. The adjoining option list displays all the limit templates that are maintained in the system. You can choose the appropriate one.

Limit Type

Select the type of limit from the drop-down list. The list displays the following values:


- Uncollected Fund Limit
- Over Draft Limit
- Collection Type Limit

Limit Amount

Specify the limit Amount.


Optional

Check this box to indicate that the corresponding item is optional as a part of package.

 If this check box is not selected, it will be displayed as such details in the 'Packet Creation' screen. If packet is saved with optional checked, the account will not be created on save, else, at package level on save account would be created.

17.2.3 Specifying Debit Card Details

You can specify the debit card details by clicking 'Debit Card Details' tab in the 'Packet Template Maintenance' screen.



The screenshot shows the 'Packet Template Maintenance' window with the 'Debit Card Details' tab selected. The window contains the following fields and controls:

- Template Id *
- Scheme Id *
- Customer Category: All
- Account Details | Limit Details | **Debit Card Details**
- Table with columns: Card Type, Card Product, Card BIN, Brand, Status
- Maker, Checker, Mod No
- Date Time: (two instances)
- Record Status, Authorization Status
- Ok, Cancel buttons

Card Type	Card Product	Card BIN	Brand	Status

Specify the following details:

Card Type

Specify the type of cards. The adjoining option list displays all the card types that are maintained in the system. You can select the appropriate one.

Brand

Specify the brand or issuer who issued the debit card. The adjoining option list displays all the brands that are maintained in the system. You can select the appropriate one.

Status

Select the status of the debit card. The adjoining option list displays all the status that are maintained in the system. You can select the appropriate one.

Fee Code

Select the fee code which is associated to the transaction fee. The list displays the following values:

- Transaction Fee Paid
- Transaction Fee Not Paid

External Service

Specify the external service. The adjoining option list displays all the external services that are maintained in the system. You can select the appropriate one.

Renewal Code

Select the renewal code for the debit card from the drop-down list. The list displays the following values:

- Cancel with Renewal
- Cancel without Renewal
- Renew without Cancellation

Pin

Specify the pin number for the card.

Optional

Check this box to indicate that the corresponding item is optional as a part of package

If you do not check this box, it will be displayed as such details in the 'Packet Creation' screen. If packet is saved with this option checked, the account will not be created on save. Instead, at package level, the system creates the account on save.

Card Product

Specify the debit card product. The option list displays all valid debit cards maintained in the system. Choose the appropriate one.

Card Bin

Specify the debit card bin. The option list displays all valid card bins maintained in the system. Choose the appropriate one.

17.2.4 Viewing Packet Template Details

You can view the details of the packet template in the 'Packet Template Maintenance Summary' screen. To invoke this screen, type 'STSPATEM' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows a web application window titled "Packet Template Maintenance Summary". The window contains several search filters: "Authorization Status" (dropdown), "Record Status" (dropdown), "Template Id" (text input with a red 'X' icon), "Scheme Id" (text input with a red 'X' icon), and "Customer Category" (dropdown). Below these filters are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A pagination bar shows "Records per page" set to 15, with "1 of 1" records displayed. Below the pagination is a table with the following columns: "Authorization Status", "Record Status", "Template Id", "Scheme Id", and "Customer Category". The table currently contains no data rows. At the bottom right of the window is an "Exit" button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Template Id
- Record Status
- Scheme Id

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Template Id
- Record Status
- Scheme Id

17.3 **Creating Packets**

You can use the 'Packet Creation' screen for creation of required items based on the template id selected. To invoke this screen, type 'STDPAQUT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Packet Creation' window. At the top, there are input fields for 'Template Id *', 'Customer Number *', 'Scheme Id', 'Activation Date', 'Closure Date', 'Active', 'New Request', and 'New Template Id'. Below these is a tabbed interface with 'Account Details', 'Limit Details', and 'Debit Card Details'. The 'Account Details' tab is active, showing a table with columns: Branch Code, Account Class, Currency, Account Number, Cheque Type, Cheque Book Type, and Cheque Book Name. The table is currently empty. At the bottom, there is a 'Benefit Details' section with fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status. 'Ok' and 'Cancel' buttons are located in the bottom right corner.

You can specify the following details in this screen:

Template ID

Specify the template identification number. The adjoining option list displays all the templates that are maintained in the system. You can select the appropriate one.

Customer No

Specify the customer identification number. The adjoining option list displays all the customer numbers that are maintained in the system. You can select the appropriate one.

Scheme ID

The system displays the scheme ID that has been linked with the template ID in 'Template Maintenance' screen.

Active

Check this box to activate the package. If you do not check this, the packet will be created in inactive status. However, you can activate the packet later by unlocking and checking this box or by activating any of the products (cheque book, debit card) which is associated with the packet.

Activation Date

The system displays the application date when active check box is selected and clicked 'Default' button.

New Request

Check this box to indicate that the item selected is to be created as a part of package for the template id chosen.



If this check box is not selected, you can associate an existing item with the template ID chosen.

Closure Date

The system displays the date on when the packet got closed.

New Template ID

Specify a new template ID if you wish to change the benefits of the template id chosen. The adjoining option list displays all the template ID's that are maintained in the system. You can choose the appropriate one.

Mandatory items associated to the New template will be created as part of template change, if it does not exist in the old template.

For instance, if you wish to change the packet of ABC to DEF, you need to unlock the old packet, specify the new template id, and click 'Default' button. The benefits that are associated to the template ID will be displayed. If the new template has any mandatory items which are not part of previous package, then these items will be triggered based on the template maintenance.

When you click 'Default' button after specifying the template id, scheme id and customer id, the items that are maintained in the 'Packet Template Maintenance' screen will be displayed in the respective tabs.

On clicking 'Default' button, the system will validate whether:

- The customer type of the customer selected and the customer type maintained for the template are the same.

- The package already exists for the customer. If it exists, the system will display an error message.

17.3.1 Specifying Account Details

You can specify the account details by clicking 'Account Details' tab in the 'Packet Creation' screen.

Specify the following details:

Branch Code

The system displays the branch code in which the account details are maintained.

Account Class

The system displays the account class based on the template id chosen.

Currency

The system displays the currency based on the template id chosen.

Account Number

If you have checked the 'New Request' box, the system will display the customer account number on saving. If not, the system displays the customer account number based on the account class chosen.

On saving the packet, the system displays the account number as DUMMY1, 2, 3 etc. On authorization of the packet, the system creates the account and updates the field accordingly.

Cheque Type

Select the cheque type from the drop-down list. The list displays the following values:

- Regular
- Continuous
- Magnetic
- Continuous Form
- Special Form
- Not required

Cheque Book Name

Specify the cheque book name.

No of Leaves

Specify the number of leaves.

First Cheque No

Specify the first cheque leaf number of the cheque book.

Cheque Book Code

The system displays the cheque book code based on the template.

Cheque Book Status

Select the cheque book status from the drop-down list. The list displays the following values:

- Requested
- Issued

Optional

Check this box to indicate that the corresponding item is optional as a part of package.

Cancel

Check this box to cancel the corresponding item which is a part of package. You can cancel an item only after the creation of the packet. You can cancel only the products that are marked as 'Optional' in the template.

Cancellation Date

The system displays the date on which the item is cancelled.

Status

The system displays the status of the corresponding item.

Dormancy Status

The system displays the dormancy status of the corresponding item.

17.3.2 Specifying Limit Details

You can specify the limit details by clicking 'Limit Details' tab in the 'Packet Creation' screen.

The screenshot shows the 'Packet Creation' application window. At the top, there are input fields for 'Template Id *', 'Scheme Id', 'Activation Date', and 'Closure Date'. To the right, there are fields for 'Customer Number *', 'Active' (checkbox), 'New Request' (checkbox), and 'New Template Id'. A 'Default' button is located below the date fields. Below these fields are three tabs: 'Account Details', 'Limit Details' (which is selected), and 'Debit Card Details'. Under the 'Limit Details' tab, there is a table with the following columns: 'Limit Template', 'Liability ID', 'Line Code', 'Serial No', 'Limit Type', 'Line Currency', 'Limit Amount', and 'Revolving Line'. The table is currently empty. At the bottom of the window, there is a 'Benefit Details' section with fields for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. 'OK' and 'Cancel' buttons are located in the bottom right corner of this section.

Specify the following details:

Limit Template

The system displays the limit template based on the template id chosen.

Liability ID

The system displays the liability identification number.

Line Code

The system displays the line code.

Serial No

The system displays the serial number.

Limit Type

The system displays the limit type based on the template id chosen.

Line Currency

The system displays the line currency.

Limit Amount

Specify the limit amount.

Revolving Line

Check this box to indicate that the facility line needs to be a revolving line or non revolving Line.



For uncollected fund limit line and collection type limit, revolving Line has to be checked.

Optional

Check this box to indicate that the corresponding item is optional as a part of package.



If you have checked the box 'Optional' on the 'Packet Template Maintenance' screen, it will display the packet details here. You can modify it.

17.3.3 Specifying Debit Card Details

You can specify the debit card details by clicking 'Debit Card Details' tab in the 'Packet Creation' screen.

The screenshot shows the 'Packet Creation' application window. At the top, there are input fields for 'Template Id *', 'Scheme Id', 'Activation Date', and 'Closure Date', along with a 'Default' button. To the right, there are fields for 'Customer Number *', 'Active' (checkbox), 'New Request' (checkbox), and 'New Template Id'. Below these fields is a tabbed interface with three tabs: 'Account Details', 'Limit Details', and 'Debit Card Details'. The 'Debit Card Details' tab is selected. Below the tabs is a table with the following columns: 'Card Issue Reference', 'Debit card Number', 'Optional', and 'Status'. The table is currently empty. At the bottom of the window, there is a 'Benefit Details' section with fields for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. 'Ok' and 'Cancel' buttons are located in the bottom right corner.

Specify the following details:

Card Issue Reference


The system displays the card issue reference number based on the template id chosen.

Debit Card Number

The system displays the debit card number based on the template id chosen.

Optional

Check this box to indicate that the corresponding item is optional as a part of package.


 If the 'Optional' check box is selected in the 'Packet Template Maintenance' screen, it will display the packet details here and you can modify it.

Status

The system displays the debit card status based on the template id chosen.

17.3.4 Viewing the Benefit Plan Details

Select an item of the scheme and click 'Benefit Details' button to view the benefit plans associated with the selected scheme.



The screenshot shows a software window titled "Benefit Details". At the top, there is a navigation bar with "1 of 1" and a "Go" button. Below this is a form with several input fields, each with a label and a red asterisk indicating it is required: "Customer Number", "Scheme Id", "Benefit Plan Id", "Benefit Plan Description", "Module", "Priority Number", and "Template Id". Below the form is a table with the following columns: "Product", "Price Component Type", "Price Components", "Benefit Type", "Variance Type", "Variance Currency", and "Variance V". The table is currently empty. At the bottom of the window, there is a section labeled "Account Scheme Details" and two buttons: "Ok" and "Cancel".

You can also modify the benefit details of the scheme ID chosen and view it in "Relationship Pricing Benefit Plan" screen.

For more details on the benefit details, refer the section 'Maintaining Benefit Plan' in this user manual.

17.3.5 Viewing Packet Creation Details

You can view the details of items that are created in the 'Packet Creation' screen. To invoke this screen, type 'STSPAQUT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows a software application window titled "Packet Creation Summary". At the top, there are four search criteria: "Authorization Status", "Record Status", "Template Id", and "Customer Number", each with a corresponding dropdown or input field. Below these are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A table below the search area shows a list of records with columns for "Authorization Status", "Record Status", "Template Id", "Customer Number", and "Scheme Id". The table currently displays 15 empty rows. At the bottom right of the window is an "Exit" button.

You can query for records based on any one or all of the following criteria:

- Authorization Status
- Template Id
- Scheme Id
- Record Status
- Customer Number

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Template Id

- Customer Number
- Scheme Id

18. Period Code Maintenance

18.1 Introduction

Banks, like all business houses compute their profits and losses and assess their financial position at the end of each financial year, which typically extends to 12 months -- from January to December or from March to April. However, this could be changed, depending upon the Bank's policies and regulatory requirements.

For interim reporting needs, the financial year is further divided into accounting periods, the duration of which is again determined by the bank's accounting requirements. For example, your bank's Board of Directors meets once a month therefore, you would divide the financial cycle into monthly periods.

The financial year and the accounting periods are referred to in the Oracle FLEXCUBE system as the 'Financial Cycle' and the 'Financial Periods' respectively and are maintained at the bank level by your Head Office branch.

At the end of each financial period and financial cycle you can generate profit and loss statement and a balance sheet. The system also offers you the flexibility of keeping a financial period/financial cycle open, allowing you to post adjustments to it and obtain a revised profit or loss statement/balance sheet. You can maintain these details in the 'Period Code Maintenance' screen.

18.2 Invoking Period Code Maintenance Screen

You can invoke this screen by typing 'STDACPER' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

The screenshot shows the 'Period Code Maintenance' window. The 'Financial Cycle' section includes fields for 'Cycle *', 'Description', 'Start Date *' (set to 2010-01-01), and 'End Date *'. Below this is a 'Period Group *' section with a table for 'Period Code *', 'Start Date', and 'End Date *'. At the bottom, there is a 'Fields' section with checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

In this screen you define the following:

- The financial cycle of your bank giving the start date and end date of each financial year
- The period group - financial periods into which each financial cycle is to be divided

The following are the features of the Period Code screen

Financial Cycle

For each financial cycle you maintain the following parameters:

Cycle

This is a code for the financial cycle. It acts as an identifier for the cycle. For example, while posting adjustments into a previous financial cycle -- you would identify the year through this code.

Input the code using a maximum of 9 characters, alphanumeric.

Example

The financial cycle extends from 1st April to 31st March in India. A bank here could define its code for the year 1996-97 as FY 1996-97.

Description

This describes the financial cycle. Enter description using a maximum of 35 characters, alphanumeric. Taking the above example, you could enter Financial Year - 1996-97.

Start Date

This is the first day of this Financial Cycle

End Date

This is the last day of this Financial Cycle

Period Group

The financial cycle defined above, can be divided into different accounting periods. To define individual accounting periods click on the first row under period code. A period called 'FIN' is created by the system. This is an open ended period coinciding with the last day of the financial cycle (for details refer to the section 'System Functions').

You can maintain the following parameters for each accounting period within a financial cycle:

Period Code

This code identifies the accounting period. Enter a code using a maximum of 3 characters, alphanumeric. For example, if your period length is a quarter you can enter - Q1 for the first period; Q2 for the second; Q3 for the third and so on. If your period length is a bimonthly you can enter BM1, BM2. If your period length coincides with a month you can input M1, M2.

Start Date

This is the first day of the corresponding period

End Date

This is the last date of the corresponding period. 'End date' of a period should always end on a month end. Please note:

- The period codes could be of varying lengths but no gaps should be left between periods
- The duration of two periods should not overlap
- You can modify the period code of the current or a future period; however, a past period cannot be modified even if it has not been closed
- All details maintained in the 'Period Code Screen' will automatically apply to any new branch opened by you in the Branch Parameters Screen
- The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

Period Code Status

After authorisation, you can view whether a financial period is open or it has been closed. Each branch can view the status of a period in every other branch. Click the period whose status you want to view.

Branch

Displays the codes of the different branches of your bank

Status

Displays the corresponding status of the period code highlighted. 'O' - indicates open status; 'C' - indicates closed status



The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

All details maintained in the 'Period Code Screen' will automatically apply to any new branch if incorporated to your bank post maintenance of this screen. The status of all periods in the new branch will be open.

18.3 System Functions

The system offers you the flexibility of posting transactions into a previous accounting period which has passed its due end date. For example, let's assume your bank's financial cycle extends from 1st January to 31st December; the first period starts on 1-01-96 and ends on 31-03-96. Even beyond 31-03-96 you can keep the period open to be able to post for example, expense bills you expect to receive in April. After you have posted all adjustments, you can close the period.

Even after you have closed the last accounting period of a year, the system offers you the flexibility of posting adjustments to the financial year.

For each financial year the system generates an open status period called FIN. Its start and end dates coincide with the last date of the financial cycle. Into this one day period you can post the accumulated profits and loss for the financial cycle, general reserves, and statutory reserves for the current year after paying off the dividends. After this one day period is closed the status of the financial cycle in the made by field 'status' is displayed as closed. With this the financial year stands closed and no adjustments can be posted to it.

Closure of a period/financial cycle can be invoked through the General Ledger/ Core Services module. The branches of the bank should close this period/financial cycle.

19. Status Code Maintenance

19.1 Introduction

Loans and bills, which are past their due maturity date of installment re-payment, but remain unpaid, are defaulted contracts. In the Oracle FLEXCUBE system these defaulted contracts can be assigned to different statuses, based on the number of days for which the contract is outstanding.

Each status can be assigned a code. For instance, you can define a status code PDO to represent 'past due obligation', and specify a period of 15 days after which an outstanding contract should be marked as 'PDO'. If they are due for more than 60 days, you could assign a 'doubtful' status; 'sub-standard' if due for 6 months, and so on. Contracts for which no installments are due, or which are regularly paid on their due dates are assigned the status 'Active' by the system. According to the number of days of default defined for each status, a loan would be moved from 'Active' to PDO status, then to doubtful and finally to sub-standard status.

Similarly, you can define status codes for current and savings accounts also. Current and Savings accounts that have not generated any interest over a specific period or have remained inactive with interest overdue may be identified as 'NPAs' (Non-Performing Asset). In Oracle FLEXCUBE, you can assign these accounts different status codes and define status criteria based on which the status movement will occur.

Refer the 'Core Entities' user manual for details on associating status codes with a customer account class /account.

These status codes are maintained in the 'Status Codes Maintenance' screen.

19.2 Invoking Status Maintenance Screen

You can invoke this screen by typing 'STDSTCOD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

In this screen you can maintain the following to user defined status of a loan or bill/account status:

- A unique code for the status
- A brief description for the status
- A sequence number for the status
- The type of status – Indicate whether the status codes are maintained for an ‘Account’ or for a ‘Contract’, or for ‘Both’

The type of status you choose depends on the status processing basis for your branch, which is defined in the Branch Parameters Preferences maintenance. If status processing basis is at individual account / contract level, you can choose the applicable status types as ‘Account’ or ‘Contract’. The status codes that have been maintained of type ‘Account’ are available for association in the Account maintenance and those maintained with type ‘Contract’ can be associated with contracts.

If status processing basis is at Group / CIF level, you can only maintain status codes of type ‘Both’ (that is, applicable for both accounts and contracts). In such a case, you must associate the statuses at both the Account maintenance as well as for contracts.



Note the following:

- It is mandatory to maintain the status code ‘NORM’ (Normal) with the sequence number as ‘0’, for all the status types. The sequence number must not be repeated for a status type.
- The sequence number associated with the status will be used for determining the hierarchy of statuses, i.e., higher the number, worst the status and this will be unique for the status codes.

19.2.1 Maintaining Status Codes for Contracts

The following parameters need to be maintained for defining a status code:

Status Code

This is the code, which identifies the status to which the contract belongs

Example

Assign a code using a maximum of 3 characters, alphanumeric. For example, if your contract has past its due obligation status you can input code PD1. PD representing post due obligation. The number 1 stands for stage 1 of the post due obligation status

Status Description

This is the description of the status, Enter a description using a maximum of 35 SWIFT characters.

Example

Taking the above example, you can input here - Past Due Obligation 1 for Loan if you are maintaining status codes for Loans.

Link to

This represents the category of the product - asset or liability to which the contract status is applicable

Example

If you are maintaining status codes for loans or any money market placements, click on 'assets type of product'. If you are maintaining status codes for deposits, click on 'liability type of products'.

Effective days from Maturity


This indicates the number of days after the due date when this status becomes applicable to the contract. You can specify any number of days from 0-999.

The effective days defined here is defaulted to the product level in the Bills and Loans modules. You have the option of redefining the number of days at the product level.

19.2.2 Viewing Restrictions

The system checks whether you are authorized to do a signature or balance query on an account. Only the user of that specific role which is defined in 'Status Code Maintenance' screen can query the signature and balance for that status.

You can attach the user role to a status in the 'View Restriction' screen. You can invoke this screen by clicking 'View Restriction' button in the 'Status Code Maintenance' screen.



Here, you can capture the User Role.

User Role

Specify the user roles which have the rights for querying signature and balance for that status. The adjoining option list displays a list of user roles maintained in the system. You can choose the appropriate one.

19.2.3 Maintaining Status Codes for OD Account


Oracle FLEXCUBE provides a facility to maintain status codes for Charge-off and Write-off status of the OD account. These status codes are maintained in 'Status Code Maintenance' screen and the details of the same are as follows:

Status Code	Description	Status Sequence	Status Type
CROF	Status code for Charge-off of OD accounts.	Should be less than SUSP status sequence	Account
SUSP/WOFF	Status code for suspended status of OD accounts.	Should be greater than CROF status sequence	Account

19.3 Maintaining Dormancy Parameter Details

You can maintain the dormant statuses for the customer account in the 'Dormancy Parameter Maintenance' screen. To invoke this screen, type 'STDSTDOR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Click the 'New' button on the Application Tool bar. The system will display 'Transaction Branch' screen. Here you can select the transaction branch.

A screenshot of a dialog box titled "Transaction Branch Code". The dialog has a blue header bar with a white diamond icon on the left. Below the header, the text "Transaction Branch Code" is followed by a text input field containing "E01" and a small dropdown arrow icon to its right. Below the input field is a single "Ok" button.

Here you are allowed to book other branch transactions from the logged in branch. Also, you can query other branch transactions from the logged in branch. The system defaults the logged-in branch by default as the transaction branch.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This screen will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.



The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'Dormancy Parameter Maintenance' screen.

You need to specify the following details:

Branch Code

Specify the branch code. The adjoining option list displays all the branch codes that are maintained in the system. You can choose the appropriate one.

Customer A/C

Specify the customer account for which you are maintaining the dormant status. The adjoining option list displays all the customer account numbers that are maintained in the selected transaction branch. You can choose the appropriate one.

Debit

Check this box to indicate that no debits should be posted to the selected customer account.

Credit

Check this box to indicate that no credits should be posted to the selected customer account.

Frozen

Check this box to indicate that the customer account is frozen due to some unavoidable reason.

Dormant

Check this box to indicate that the account is in dormant status which means not used for along time.

Dormant Param

Select valid dormant parameter you need for re-activating the dormant account. You can select one of the following options:

- Debit
- Credit
- Any
- Manual


Remarks

Specify the remarks, if any.

19.4 Maintaining CR\DR Statistics Details

You can maintain the credit\debit statuses for the customer account in the 'CrDrStat Maintenance' screen. To invoke this screen, type 'STDSTCDM' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Click the 'New' button on the Application Tool bar. The system will display 'Transaction Branch' screen. Here you can select the transaction branch.



Here you are allowed to book other branch transactions from the logged in branch. Also, you can query other branch transactions from the logged in branch. The system defaults the logged-in branch by default as the transaction branch.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.



The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'CrDrStat Maintenance' screen.

CrDrStat Maintenance

Branch Code * 000

Customer A/C *

No Debit

No Credit

Posting Allowed

Remarks

Change Log

Maker [] Date Time: [] Mod No [] Record Status []

Checker [] Date Time: [] Authorization Status []

Exit

You need to specify the following details:

Branch Code

Specify the branch code. The adjoining option list displays all the branch codes that are maintained in the system. You can choose the appropriate one.

Customer A/C

Specify the customer account for which you are maintaining the credit\debit status. The adjoining option list displays all the customer account numbers that are maintained in the selected transaction branch. You can choose the appropriate one.

No Debit

Check this box to indicate that no debits should be posted to the selected customer account.

No Credit

Check this box to indicate that no credits should be posted to the selected customer account.

Posting Allowed

Check this box to indicate that the account class being created is to be used while creating IRA monetary accounts. Monetary accounts used for IRA need to be distinguished from the other accounts in Oracle FLEXCUBE, so that these accounts do not come up for posting in the other Oracle FLEXCUBE screens.

Remarks

Specify the remarks, if any.

20. Transaction Code Maintenance

20.1 Introduction

In the 'Transaction Codes Maintenance' screen you define transaction codes to representing various types of transactions, for example, transfer charges, incoming mail transfer, incoming telex transfer, reserve, incoming clearing transfer etc. All similar transactions can be grouped under a common transaction code with a description. This description will be printed on the account statements, reports and advices generated.

For a transaction type you also maintain other related processing details which will be applicable to all transactions posted under a common code. Details about availability of funds for liability checking, SWIFT code for the transaction type, preferences regarding charges to be levied on turnovers, payment to be made through cheques etc.

20.2 Maintaining Transaction Code

You can invoke 'Transaction Code Maintenance' screen by typing 'STDTRNCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Transaction Code Maintenance' window with the following sections:

- Transaction Details:** Fields for Transaction Code *, Description *, and SWIFT Code. MIS Head and External Code fields are also present.
- Availability Information:** Radio buttons for Immediate, On Value Date, After Days with New Value Date, and After X Days. A Days input field is located below.
- Anti Money Laundering Monitoring:** Includes checkboxes for Anti Money Laundering Required, Intraday Release, Available Balance Check Required?, Interests and Charges Penalty Inclusion, Inter Branch in Local Currency, Acumen Transaction Code, Exempt Advance Interest (checked), Escrow Processing, Available Balance Update Through PPC, Include Linked Account Balance, Include Linked OD, and Apply City Compensation. It also features dropdowns for Product Category, Statement Day Basis (Current Working Day), and Salary Credit.
- Preferences:** A list of checkboxes including Cheque Mandatory, Interest and Charges Transaction Count, Interest and Charges Turnover Inclusion, Consider For Account Activity, Interest and Charges Balance Inclusion, Consider for Turnover Limit, and Consider For Cover Account.
- Fields:** A tabbed interface with 'Transaction Tax' selected.
- Footer:** Fields for Maker and Checker, each with a Date Time field, and a Cancel button.

In this screen you maintain the following for a transaction:

- A code representing the transaction type
- Description of the transaction type
- The interval after which funds should be made available after the transaction
- Preferences regarding charges to be levied or not on number of transaction counts and total turnover amounts
- Preference stating whether a transactions booked under this code should cause an account marked as 'dormant' by the system to be re-instated to 'active'
- Preference whether payment for a transactions posted under this code should be made through cheque
- Preference indicating whether payment for a transaction booked under this code should be considered for Escrow transfer processing

20.2.1 Maintaining Transaction Details

The following parameters need to be maintained for a transaction type:

Transaction Code

This is the code you assign to a transaction type. This code identifies the type of transaction.

Enter 3 characters, Alphanumeric. For example, for all transfer charges transaction you can give the code as TCT; for incoming telex transfer you can input - ITT. In case, you want to assign numeric codes only, then for ease of operation similar transaction types should be grouped into a range. For example, you can set a range for all Money Market transactions say, A1-A30; a different range for Bills and Collections B1-B30 and so on.

Description

This is the description of the transaction type

Enter the description using a maximum of 35 characters, alphanumeric. For example, for TCT code you can enter 'Transfer Charges Transaction'.

SWIFT Code

This is the SWIFT code to which this transaction code is linked. It is used for posting transaction details on SWIFT format.

Select from the option list. It will display a list of SWIFT formatted codes representing transaction types. The following list is displayed:

SWIFT CODES	TRANSACTION TYPE
BOE	Bill of Exchange
BRF	Brokerage fee
CHG	Charges and other Expenses
CHK	Cheques
CLR	Cash Letter/Cheque Remittance
COL	Collections
COM	Commission
DCR	Documentary Credit (for Principal Amount)
DIV	Dividends - Warrants
EQA	Equivalent Amount
ECK	Euro checks
FEX	Foreign Exchange
INT	Interest
LBX	Lock Box
LDP	Loan Deposit
MSC	Miscellaneous
RTI	Returned Item
SEC	Securities
STO	Standing Order
TCK	Travelers Cheques
TRF	Transfer
VDA	Value Date Adjustment

The codes COL -Collections, DCR - Documentary Credit and SCC- Securities are used when entering a principal amount.

MIS Head

Each Transaction Code that is created can be linked to an MIS Head. An MIS Head indicates the manner in which the type of entry should be considered for profitability reporting purposes.

20.2.1.1 Indicating Availability Information

This states the different time intervals after which funds will be available for withdrawal in case of all transactions posted under this transaction code.

The system defaults to immediate, which means that funds will be immediately available for withdrawal (the immediate option on the screen). Example: Teller Transaction. For all Clearing transactions you have the option to specify as to when will funds be made available for withdrawal. Click the desired option.

Click 'On Value Date' option if you want funds to be available on the date the transaction became effective. Example: A loan or a deposit

Incase you want to specify the number of days after which funds should be available for withdrawal, click on the option After Days. Enter the number in the box. It could be any two digit positive integer from 1 to 99. This option will make funds available for all transactions posted under this code, on the specified date from the value date. Example: Demand Draft

When you click the last option that is, After Days with New Value Date and enter the number of days in the box; then the original value date of the contract will take a new value date. This new value date = old value date + the number of days input by the user in the box against the option. Example: Future dated funds transfer.

The difference between the third and fourth option being that in the latter case the old value date changes; while in the former the value date does not change.

Intra-day Release

If you want uncollected funds on a transaction posted using the transaction code, to be manually released intra-day (that is, within the day), select the Intraday Release option. The Intraday Funds Batch, when manually executed during the day, picks up those transactions that are due for release on or before the system date, which have been posted with the transaction code (with the Intraday Release option enabled), for release of uncollected funds.

The Intraday Release option cannot be enabled if the Availability specified for the transaction code is Immediate.

You can use the Intraday Funds Release batch process to perform the intra-day release of uncollected funds in respect of transactions posted using a transaction code for which the Intraday Release option has been enabled.

For details about invoking the batch process, refer the Current and Savings Account user manual.

20.2.1.2 Specifying Preferences

This field indicates your preferences regarding transactions booked against this transaction code. The preferences marked relate to the following:

Interest and Charges Transaction Count

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C transaction count' then all entries made under that code would be picked up by the system as chargeable transaction counts which would be used by the I&C system to compute charges.

Therefore, you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

Example

Your bank has a policy of limiting savings withdrawals without additional charges to only 8 in a month. Beyond which all withdrawals would be charged. For the ninth and onward withdrawals in the month from any account the system will maintain a count for computing charges. However, care should be taken to exclude all bank-induced transactions from the count.

Interest and Charges Turnover inclusion

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C turnover inclusion' then the debit turnover/ credit turnover balance under that code would be picked up by the system as chargeable depending upon the option specified in the I&C module. Therefore you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

Interest and Charges Balance Inclusion

Check this box to indicate that the transactions posted under this code should be considered for the purpose of computation of Remuneration (Interest). By default this option is checked. Uncheck this box for such loan transactions or any other transactions for which you wish to exclude computation of remuneration (interest).



Once the transaction code is authorized, you cannot change your preference.

Include Linked Account Bal

Check this box to indicate that the system will include the account balance of the linked Line of Credit (LOC) account while performing balance calculations for retail teller transactions. The system will process a transaction if the sum of the current account balance and LOC account balance is greater than the transaction amount. If the current account balance is less than the transaction amount then the difference amount will be blocked from the LOC account.

Include Linked OD

Check this box to indicate that the system will include the overdraft linked to the account while performing balance calculations for retail teller transactions. The system will process a transaction if the sum of the current account balance and overdraft balance is greater than the transaction amount.



If both 'Include Linked Account Bal' and 'Include Linked OD' are not checked, then at the time of processing a transaction, the system will check the balance only against the current account. The system will not process a transaction if the current account balance is less than the transaction amount.

Consider for Turnover Limit

Check this box to indicate that all transactions posted under this code should be considered as part of the turnover limit processing.

Consider for Cover Account

Check this box to consider easy saver processing using cover accounts for transaction.

Only if you check this box, the system will consider the transactions with transaction code for processing.

The above field is applicable only for clearing and teller modules.

Consider for Account activity

If you check the field 'Consider for A/C activity' for a transaction code, then any debit or credit posted under this code would reinstate the status of an account from dormant to active and accounting activity shall be considered.

Cheque Mandatory

If for a transaction code you check 'Cheque Mandatory' then, for all transactions posted under this code, transaction will take place through cheque. For example: Incoming Clearing transfer.

Cheque Mandatory should be checked only for SB cheque withdrawals and Cash Account Cheque withdrawals.


Example

Transaction Code Maintenance Model Screen

TRANS CODE	DESCRIPTION	SWIFT CODE	AVAIL INFO	I & C TRANS COUNT	I & C TURN INCL	UPDATE ACTIVITY STATUS	CHEQUE MAND
A01	ACCOUNT TO ACCOUNT TRANSFER	MSC	I	Y	Y	Y	Y
A02	ACCEPTANCE	MSC		Y	Y	Y	Y
B01	BANK WIRE TRANSFER	TRF		Y	Y	Y	Y
B02	BANK WIRE TRF- OWN ACC	TRF		Y	Y	Y	Y
B03	BILL C/ A ENTRY	BOE		Y	Y	Y	Y
B04	BILLS REDISCOUNTED	BOE		Y	Y	Y	Y
C01	CANCEL CLEAN CREDIT	RTI		Y	Y	Y	Y
C02	CANCEL GUARANTEE	RTI		Y	Y	Y	Y
D01	DEBIT INTEREST	MSC		Y	Y	Y	Y
D02	DEMAND DRAFT ISSUED	MSC		Y	Y	Y	Y
E01	ENDORSED BILLS SOLD	BOE		Y	Y	Y	Y
F01	FEES ACCRUAL	BRF		Y	Y	Y	Y
G01	GL CREDIT	MSC		Y	Y	Y	Y
G02	GL DEBIT	MSC		Y	Y	Y	Y

Available Balance Check Required

Select this option if you want the system to check for the availability of funds before posting a debit entry to a customer account. The system will check for the available balance in all customer accounts associated with the Transaction Code for which the option is enabled. If the available balance check fails i.e. if the system detects insufficient funds in the customer account, it will display a warning message.


 However, the system will check for the available balance only if you have selected the 'Available Balance Check required' option for both the transaction code associated with the accounting entry and the Customer Account Class to which the customer's account that is being debited, belongs. The check will not be performed if the option is not selected in both places.

Interest and Charges Penalty Inclusion

In the transaction code that you use for debit entries to time deposit accounts, you must indicate the computation of penalties on debit entries due to withdrawals from the account before the maturity date. You must select the IC Penalty Inclusion check box to indicate this.

Inter Branch in Local Currency


This indicates whether inter branch entries passed with this transaction code should be in Local currency. If this option is checked, the inter branch transactions would be passed in local currency. This way, the Treasury would be able to track its profit and the branch's profit by passing a single consolidated entry (Position transfer from one branch to the Treasury branch) at the treasury rate.

 Note the following:

- This option is applicable only if the local currency of the different branches is the same. This option is applicable only for Fcy1- Fcy1 transactions. For other transactions, namely, Fcy1-Fcy2, Lcy-Fcy, Fcy-Lcy, IB entries would be based on IB Parameters Maintenance.
- For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen should be checked to avoid creating position due to IB posting.

Acumen Transaction Code

You need to check this option in order to eliminate the deals/transactions uploaded from the Acumen in the Hand-off of transactions affecting FCY Position to Acumen from Oracle FLEXCUBE.

 This is applicable where Oracle FLEXCUBE interfaces with Acumen. Acumen is an Integrated Turn-key solution for Treasury, Derivatives and Capital Markets Covering Front, Risk Control, Middle Office from Login SA.

Exempt Advance Interest

Check this box to indicate that all the postings with this transaction code should not be considered for penalty interest calculation.

Escrow Processing

Check this box to indicate that all the payments related to this transaction code should be considered for Escrow sweeps. If this box is checked and the credit account (Project account) is Escrow enabled then the system will automatically compute predefined percentage of transaction amount and places an amount block on the credit account (Project account).



Escrow processing is possible only if the trust account and escrow account are of the same currency and are with-in Oracle FLEXCUBE.

Available Balance update through PPC

Check this box to update the available balance on the project through PPC.

Apply City Compensation

Check this box to apply the city compensation to the transaction code. If you check this option, the system compares the city compensation code of account branch and transaction branch to determine whether commission should be collected or not. If the city compensation code for both branches are found to be the same, the system will not collect the commission.

Salary Credit

Select the type of salary credit from the adjoining drop-down list. This list displays the following values:

- Normal Salary
- Bulk Salary

By default, the system selects null value.



Note the following:

- The value 'Bulk Salary' can be selected only if the 'Availability Information' is 'Immediate'.
- This applies when you use the option 'Bulk Salary' along with a transaction code. When a credit is made to an account through salary upload table along with a bulk salary enabled transaction code, the system blocks the entire credit amount on that account with effect from the date of upload. This block remains active for the period maintained in CSTB_PARAM against the parameter 'BULKSALARY_BLOCK_DAYS'. The number of days for expiry is mentioned terms of calendar days. The system does not allow manual operations on the amount block for these accounts.

Apply City Compensation

Check this box to indicate that city compensation is applied for the transaction code.

Statement Day Basis

You need to specify when the transaction associated with the selected Transaction Code should appear in the account statement. The available options are:

- Current Working Day
- Previous Working Day

20.2.1.3 Accounting Entry Processing to Calculate Statement Date

The accounting entry processing will be enhanced to calculate the Statement Date based on the Transaction Code Maintenance and the Statement Status at the Branch level. The following illustration explains the calculation of Statement Date.

Assume two Transaction Codes TXN1 and TXN2 have been defined with Statement Date Basis as Current Working Day and Previous Working day respectively. The Statement Date would be derived as follows:

For a transaction C1 posted on say 25th Jan, 2004 with TXN1, the Statement Date would be derived as 25th Jan, 2004 irrespective of the Branch Statement Status.

For a transaction C2 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as the Previous Working Day of 25th Jan, 2004 if the Branch Statement Status is set to 'N' specifying that the Branch is not yet ready for periodic statements processing.

For a transaction C3 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as 25th Jan, 2004 if the Branch Statement Status is set to 'Y' specifying that the Branch is ready for periodic statements processing.

The Statement Date would be stored as part of the archived data also

The Statement Date would be recomputed during the reversal entry in the same logic

20.2.1.4 Monitoring Anti Money Laundering

Anti Money Laundering Required

Check this box to indicate that AML monitoring is required for all accounting entries linked to the particular transaction code. Leave it unchecked to indicate otherwise.

Product Category

If you indicate that AML tracking is required for all transactions linked to the particular transaction code you have to identify the product category for which AML tracking is necessary.

20.2.2 Maintaining Transaction Tax Details

You can maintain the transaction tax details by clicking on the 'Transaction Tax' button in the 'Transaction Code Maintenance' screen. The following screen is invoked:

✓ Tax Scheme	Tax Borne By	Tax Applicability
✓		Both Transactions

Tax Scheme

Specify the tax scheme details. This tax scheme is attached to a tax rule for tax calculation.

Tax Borne By

Select the tax borne by details from the drop-down list. Following are the options available in the drop-down list:

- Bank Account
- Customer Account

Tax Applicability

Select the tax applicability details from the drop-down list and the options available are:

- Debit Transactions
- Credit Transactions
- Both Transactions

20.3 Maintaining GMF Tax Preferences

Oracle FLEXCUBE allows you to maintain GMF Tax preferences at the branch level using 'Transaction Tax Maintenance' screen. You can invoke the 'Transaction Tax Maintenance' screen by typing 'STDTRNTX' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Transaction Tax Maintenance". It has a header bar with a diamond icon and window control buttons. Below the header, there are four input fields: "Branch Code *", "Currency Code *", "Tax Scheme *", and "Tax Class". Each of these fields has a dropdown arrow icon. Below these fields is a section labeled "Tax Details" which contains three more input fields: "GL Code", "Description", and another "Tax Class" field. At the bottom of the window, there are fields for "Maker", "Checker", "Date Time:", and another "Date Time:" field. A "Cancel" button is located in the bottom right corner.

Branch Code

Specify the branch code.



You can type '*' whenever a particular maintenance is applicable to all branches in a bank.

Currency Code

Specify the currency code.



You can type '*' whenever a particular maintenance is applicable to all branches in a bank.

Tax Scheme

Specify the tax scheme. This tax scheme is used to define the rule for tax calculation.

20.3.1 Specifying Tax Details

Tax Class

Specify the tax class. This tax class is used to define accounting entry.

GL Code


Specify the GL Code which needs to be debited when the 'Tax Borne By' in Transaction Tax Details' maintenance is 'Bank Account'.

Description

Once you select the GL code, the system displays the description of the GL code.

20.3.2 Maintaining Country Name Details

You can define country name through the 'Country Code Maintenance' screen. You can invoke this screen by typing 'STDCOUNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Here, you can capture the following details

Country Code

You can capture a unique three-character code to identify the country. For example: you can maintain USA as the country code for United States of America.

Alternate country code

You can also associate an alternate country code. This is for information purposes only and will not be printed on any customer correspondence.

For example you can have US as the alternate code for USA

Country Name

After you define an alphanumeric code to identify the country for which you would like to assign a name, you have to specify the name of the Country.

Overall Limit

This is the maximum credit exposure that a bank is willing to take for a country. That is, the sum of all utilization's under this country liability cannot exceed the amount specified here.

Blacklisted

Further, in the 'Country Name Maintenance' screen you can black list a country for further usage. You are not allowed to deal in countries that are blacklisted.

You can only deal with countries that are *not* blacklisted

IBAN Mandatory for Payment Messages

If this is checked, it indicates that for every payment message an IBAN is mandatory. This is automatically checked if you have checked the 'EU Member' box.

If this option is unchecked for a country, the system will not process the outgoing payments wherein the ordering customer or the beneficiary customer belongs to that country.

EU Member

This indicates whether the country is recognized by Swift as a part of the Intra European countries.

If you check this flag the instructed amount field should be mandatory in the generated 103, 103+ and 102 messages. The instructed amount field is mandatory in the incoming messages.

Clearing Code in BIC+

Check this box to indicate that the National ID in the BIC plus file is the clearing code. During upload of clearing codes from BIC plus file, the records that belong to countries against which this box is checked will be selected.

Generate 205

Check this box to indicate that the cover message 205COV or 205 need to be generated for transactions involving this country. If you do not select this option, RTGS, 202 or 202COV message will be generated.

For more details on 202COV and 205COV cover message formats, refer settlements user manual.

Default Clearing Network

Once the National ID from BIC plus directory is uploaded into clearing codes, the network will be populated as the default clearing network for that country. This is mandatory when clearing code in BIC+ is chosen as 'Y'.

21. Reason Code Maintenance

21.1 Introduction

In the 'Block Reason Code Maintenance' screen, you can maintain various reason codes for blocking an account. An account could be blocked for a variety of reasons such as internal, legal, process of closure, address verification, and so on. You can maintain a reason code for each of these reasons.

While blocking an account, you can specify the reason code in 'Customer Accounts Maintenance' screen.

21.2 Maintaining Reason Code

You can maintain the reason code using 'Block Reason Code Maintenance' screen. You can invoke the 'Block Reason Code Maintenance' screen by typing 'STDRACBK' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Block Reason Code Maintenance". Inside the window, there are two text input fields. The first is labeled "Block Reason Code *" and the second is labeled "Description". Below these fields is a section titled "Fields" which contains labels for "Maker", "Checker", "Date Time:", and "Date Time:". A "Cancel" button is positioned in the bottom right corner of the window.

Here you can specify the following details:

Block Reason Code

Specify the reason code.

Description

Enter a brief description for the reason code.



Note the following:

- You can delete a reason code before authorization. An unauthorized reason code can only be deleted by the person who created it. The system disallows deleting an authorized reason code.
- The maker and the checker (authorizer) of a reason code cannot be the same. The system displays an error message if you try to authorize a reason code created by yourself.

21.3 Maintaining Reversal/Reason Code

You can maintain the reason for rejection of cheques using 'Reversal/Reason Code Maintenance' screen. You can invoke this screen by typing 'CADRVCOD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "ChequeType - Reversal / Reason Code Maintenance". At the top, there are two input fields: "Reversal / Reason Code *" and "Reversal / Reason Code Description". Below these is a "Fields" section with a dark header. Underneath, there are labels for "Maker", "Checker", "Mod No", "Date Time:", "Date Time:", "Record Status", and "Authorization Status". At the bottom right, there are "Ok" and "Cancel" buttons.

You need to specify the following details:

Reversal/Reason Code

Specify a unique code that identifies the reversal/reason.

Reversal/Reason Code Description

Enter a brief description of the reversal/reason.

22. Account Revaluation Maintenance


22.1 Introduction

Account revaluation is a process by which the LCY equivalent of balances in the FCY accounts is marked to market.


In all foreign currency accounts, the FCY current balance is displayed along with the LCY equivalent of the current balance. The LCY equivalent current balance is the aggregate of the LCY equivalent of the various transactions that have been posted to the account.


In the 'Chart of Accounts - GL Details' screen you specify whether a GL should be revalued or not.


In the 'Account Revaluation Maintenance' screen, you specify parameters for account revaluation such as rate type, the GL to which the profit or loss from revaluation should be posted, etc. You can invoke this screen by typing 'RVDSETUP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.





Account Revaluation Setup


General Ledger Code * 
Description _____


Transaction Code * 
Description _____


Rate Type * 
Description _____

Profit General Ledger 
Description _____

Loss General Ledger 
Description _____



Revalue into 
Description _____

Trading Profit Account 
Description _____

Trading Loss Account 
Description _____

Netting of Offset Entries

Entry Based Revaluation

Rate Type 
Transaction Code 

Fields

Input By: DOC1 Date Time Modification Number Authorized
Authorized By Date Time Open

In this screen you can maintain the following parameters to define the revaluation parameters for a GL account:

- The general ledger accounts to which the profit or loss on revaluation is to be posted
- The account to which the revaluation profit is to be debited or loss credited
- The rate type to be used to revalue the GL
- The transaction code for posting the revaluation entries
- The rate type to be used for accounting entry-based revaluation of profit and loss GLs
- The transaction code that would be used to post revaluation entries due to accounting entry-based revaluation of profit and loss GLs

General Ledger Code

This is the code of the GL account for which you are specifying revaluation parameters.

Transaction Code

This is the transaction code under which the accounting entries would be posted to the defined revalued GL account

Rate type

This is the rate type to be used for revaluation of this GL

Profit General Ledger

If the result of revaluation is a profit, the profit amount is credited to this profit GL. If, for a GL, you have opted for revaluation split, then Revaluation Profit (as opposed to Trading Profit) is posted into this GL.

Revaluation split segregates revaluation profit / loss into:

- Trading Profit / Loss – Profit / Loss due to revaluation of FCY entries posted into the GL during the current day.
- Revaluation Profit / Loss – Profit / Loss due to revaluation of opening FCY balances (excludes current day's turnover).

Loss General Ledger

If the result of revaluation is a loss, the loss amount is debited to this loss GL. If, for a GL, you have opted for revaluation split, then Revaluation Loss (as opposed to Trading Loss) is posted into this GL.

Revalue into

This GL account is debited if the result of revaluation is a profit; and credited if the result of revaluation is a loss

This would typically be the GL code being revalued. For all non-contingent GLs belonging to the asset or liability categories, the system defaults to the GL being revalued.

If you wish to specify a different account for posting these entries specify by selecting from the list of maintained GLs. A list of all GLs would be displayed. Select.

Trading Profit Account/Trading Loss Account

This indicates the GL for posting profit/loss due to trading revaluation (Trading Profit / Loss) if you have indicated that revaluation split is required for a GL.

Netting of offset entries

A check against this indicates whether the offset entries for all accounts linked to the GL code need to be netted or not. If checked, a single consolidated entry would be passed (one for profit and one for loss).



Netting of offset entries is applicable only for normal account revaluation and not for accounting entry-based revaluation of Income/Expense GLs.

Accounting entry-based revaluation of Income / Expense GLs

Income/expense GLs that are marked for entry-based revaluation are picked up by the EOD revaluation batch process, which executes before the account revaluation batch process on a given business day.

In the Account Revaluation Maintenance, you must specify the following parameters that would be used by the batch revaluation process, for revaluing FCY entries in Income/Expense GLs:

- Rate type
- Transaction code for posting entry-based revaluation entries

You can maintain these parameters for specific Income/Expense GLs. If you wish to maintain these parameters for all Income/Expense GLs, you can specify the 'STDPNL' option in the GL Code field. The 'STDPNL' option signifies that the entry-based parameters being maintained are applicable for all Income/Expense GLs.

When the revaluation batch revalues an Income/Expense GL, it uses the rate type and transaction code maintained for the GL in the Account Revaluation screen. If no maintenance exists for the specific GL, the parameters maintained for the 'STDPNL' GL Code option are used.

23. Maintaining Branch Holidays

23.1 Introduction

For a year, you need to define your weekly holidays and your calendar year annual holidays. This is done in the 'Local Holiday Calendar' screen.

The system uses the information maintained in this screen to do the following:

- To check that the 'value date' of no Data Entry transaction falls on a holiday
- To check that the start date / maturing date and schedule date of a loans and deposit contract does not fall on a holiday
- To effect a date change on the system -- today's date and the next working date

For any schedule / contract maturing at a future date, say, 5 years hence, you can input a future date, only if the calendar for that year has been maintained. It is not necessary to maintain the list of all annual holidays, for future, you can merely define all regular weekly holidays.

This screen is maintained for each branch, of your bank, from the respective branches; thus making it possible to have a different set of holidays for different branches of the bank.

23.2 Invoking Local Holiday Screen

Invoke the 'Local Holiday Calendar' screen, by typing 'STDLCVOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

In this screen you can specify the weekly and also the annual holidays, for your branch, for any year between 1 AD and 4000 AD.

23.2.1 Steps to Define Yearly Holidays

To define holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Select 'New' from the Actions menu in the Application tool bar or click new icon

Step 2

Enter the year -- 2000 or move to the year 2000 using the arrows

Step 3

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays. This is the default setting of the system

- For identification, the working days are marked in black and the holidays in red
- All unauthorized records appear against a blue background. On authorisation of that record, the background is cleared.

23.2.2 Defining Holidays

To define any other weekly holiday, other than the default, double click the day of the week, listed on the top row of the screen. For instance, if you double click on 'F', all Fridays in the year would be marked as holidays.

To clear off the default weekly holidays — Saturdays and Sundays, double click on 'sa' and 's' written on the top row.

To specify, other annual holidays, double click on the date — the date would be marked as a holiday.

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black. Because the change is yet unauthorized, it appears against a blue background.

23.2.3 Annual Holidays

These are the holidays you have defined for the year calendar on display

You will observe that all holidays are marked in red, while working days in black. (All unauthorized holiday dates appear against a blue background). To mark a date as a holiday, double click on it. In case you wish to undo a date marked off as a holiday, double click on it once again. It changes back to a working day.

With each modification you make, the Modification Number in the made by column below moves up serially

23.2.4 Designating Unexpected Holidays for Branch

The holiday calendar for your branch is maintained in the Branch Holiday Calendar screen.

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Branch Holiday Maintenance' screen. You can invoke this screen by typing 'CGDUNHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software interface for managing branch holidays. The main form includes the following elements:

- Branch Code ***: 000
- Branch Name**: BANK FUTURA - HEAD OFFICE
- Holiday / Working Type**: Radio buttons for HOLIDAY (selected) and WORKING.
- Holiday Date From ***: [Date Picker]
- Holiday Date To ***: [Date Picker]
- Holiday Reason**: [Text Field]

Below the main form is a table titled "Type Exceptions":

Holiday / Working Date	Reversed Flag
<input type="checkbox"/>	

At the bottom of the window, there is a "Fields" section with the following controls:

- Input By**: DOC1
- Date Time**: [Date Time]
- Modification Number**: [Field]
- Authorized**:
- Open**:
- Cancel**: [Button]


In this screen, for the current branch, you can maintain a range of dates, every date within which will be designated as holidays for the branch. You can also provide a reason for the designation.

Every unexpected holiday you designate must be authorized for it to be effective

23.2.4.1 Reversing Designated Holiday

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for any transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.

 For the release of uncollected funds, the original transaction date is considered for availability calculations

24. Maintaining Currency Holidays

24.1 Introduction

You need to maintain a yearly list of holidays, for the currencies, defined in the currency screen. This is done in the 'Currency Holiday Calendar' screen.

The system uses the information maintained in this screen to check whether any settlement, involving a foreign currency (in the foreign Exchange, Money market, Funds Transfer, Loans & Deposit modules) falls on that currency's holiday. If yes, then the system will display a message stating so, and ask the user for an override

For any schedule or contract maturing at a future date say, 5 years hence, you can input the future date, only if the calendar for that year has been maintained.

The currency holiday screen is maintained at the Bank Level by the Head Office

24.2 Invoking Currency Holiday Screen

You can invoke this screen by typing 'STDCCHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Currency Holiday Calendar Maintenance' window. It features a grid for entering holidays for each month of the year. The months are arranged in a 4x3 grid: January, February, March; April, May, June; July, August, September; October, November, December. Each month header is followed by a row of days (S, M, T, W, Th, F, Sa) and then several rows of input fields. At the bottom of the window, there is a 'Currency Code' field, a 'Year' field set to '2007', and a 'Refresh' button. A 'Fields' section at the bottom left shows 'Input By: DOC1', 'Date Time', 'Authorized By', and 'Date Time'. A 'Modification Number' field is also present. On the right, there are checkboxes for 'Authorized' and 'Open'. A 'Cancel' button is located at the bottom right.

In this screen, you can maintain a list of holidays for each of the currencies maintained in the 'currency screen', for any year between 1 AD and 4000 AD.

24.2.1 Steps to Define Currency Holidays

To define currency holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Select 'new' from the Actions menu in the Application tool bar or click new icon. A blank screen appears and the cursor moves to the field 'Year'

Step 2

Enter the year -- 2000 or move to the year 2000 using the arrows

Step 3

To build the calendar for the year, 2000 click on the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you

Step 4

Select the currency for which you are defining holidays. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays for the currency. This is the default setting of the system.
- For identification, the working days are marked in black and the holidays in red.
- All unauthorized records appear against a blue background. On authorisation of that record the background disappears.

24.2.2 Defining Currency Holidays

To define any other weekly holiday for the currency, other than the default, double click the day of the week, listed on the top row of the screen. For instance, if you double click 'F', all Fridays in the year would be marked as holidays.


To clear off the default weekly holidays — Saturdays and Sundays, double click on 'sa' and 's' written on the top row

To specify, other holidays, double click on that date — the date would be marked as a holiday

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black. Because the change is yet unauthorized, it appears against a blue background

24.3 Uploading Holiday file

SWIFT provides a country-wise holiday file that can be uploaded into Oracle FLEXCUBE. For all countries where 'EUR' is not the local currency, the respective holidays can be uploaded into the currency holidays tables. For European countries, where 'EUR' is the currency, you can upload the TARGET holidays. Oracle FLEXCUBE allows you to upload these currency holidays through the 'BIC/BICPLUS – Upload' screen. You can invoke this screen by typing 'ISDBICPU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a web-based form titled "BIC Upload". The form includes a "Source Code" dropdown menu, three text input fields for "File Name", "File Path", and "Intraday Sequence Number". At the bottom of the form, there are three buttons: "Submit Params", "Submit Batch", and "Cancel".

Here you need to choose the source code as 'CCH' from the drop-down list. For further details about this screen, refer the section titled 'Uploading the BIC/BICPLUS files into Oracle FLEXCUBE' in the 'Settlements' User Manual.

The holiday file gets uploaded with two records:

- HF Record – wherein 'EUR' is not the local currency
- HS Record - wherein 'EUR' is the local currency

For more details on the file formats of these records, refer the chapter titled 'Annexure – B – File Formats'.

25. Maintaining Clearing Holidays

25.1 Introduction

You need to maintain a yearly list of holidays of your Clearing House. This is defined in the 'Clearing House Holiday Calendar' screen.

This set of holidays is maintained at the bank level, by the Head Office. You can invoke this screen by typing 'STDCLHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Clearing House Holiday Maintenance' application window. The window title is 'Clearing House Holiday Maintenance'. The main area is a grid of 12 months, each with a header row containing day abbreviations (S, M, T, W, Th, F, Sa) and a table of horizontal lines for data entry. The months are arranged in a 4x3 grid: January, February, March; April, May, June; July, August, September; October, November, December. At the bottom of the window, there are fields for 'Clearing House *' and 'Year *', a 'Populate' button, and a 'Fields' section with checkboxes for 'Authorized' and 'Open'. A 'Cancel' button is also present.

In this screen, you maintain a list of holidays of the Clearing House with which your bank is associated with.

25.1.1 Steps to Define Clearing House Holidays

To define Clearing House holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Click new icon.

Step 2

Enter the year — 2000 or move to the year 2000 using the arrows.

Step 3

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- Your clearing house can be identified with the name -- SYS, given to it by the Oracle FLEXCUBE system. This is displayed in the field 'Clearing House'
- Saturdays and Sundays are marked as weekly holidays for the Clearing House. This is the default setting of the system
- For identification, the working days are marked in black and the holidays in red
- All unauthorized records appear against a blue background. On authorisation of that record the background disappears

25.1.2 Defining Clearing House Holidays

To define an additional holiday, click the particular date which you need to be considered as holiday. The system will mark that date as a holiday. The system will change the color of the date to red.

If you click a date that is already marked as a holiday, the system will clear the holiday and treat that date as a working day. The color of the date text is changed to black, indicating that it is no more a holiday.

25.1.3 Designating Unexpected Holidays for Clearing House

The holiday calendar for your clearing house is maintained in the Clearing House Holiday Calendar screen

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Holiday Maintenance' screen.

You can invoke this screen by typing 'CGDCLHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Input By	Date Time	Modification Number	Authorized
Authorized By	Date Time		Open

In this screen, for a clearing house, you can maintain a range of dates, every date within which will be designated as holidays for the clearing house. You can also provide a reason for the designation.

Every unexpected holiday you designate must be authorized for it to be effective

25.1.3.1 Reversing Designated Holiday

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for clearing transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.



For the release of uncollected funds, the original transaction date is considered for availability calculations

26. Document Maintenance

26.1 Introduction

Before opening an account, the customers are expected to furnish the documents to the bank.

The following sections in this chapter discusses about the various document categories, type of document to be submitted, and the document checklist to be maintained.

26.2 Maintaining Document Category Details

You can maintain the various document categories in the 'Document Category Maintenance' screen. To invoke this screen, type 'CSDDOCMT' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows a software window titled "Document Category Maintenance". The window contains the following fields and controls:

- Document Category ***: A text input field.
- Document Description ***: A text input field with a small icon to its right.
- Maker**: A text input field.
- Checker**: A text input field.
- Date Time:**: Two text input fields.
- Mod No**: A text input field.
- Record Status**: A text input field.
- Authorization Status**: A text input field.
- Cancel**: A button on the right side of the window.

Specify the following details:

Document Category

Specify the document category.

Document Description

Specify a brief description for the document.

26.3 Viewing Document Category Details

You can view the document category details in the 'Document Category Summary' screen. To invoke this screen, type 'CSSDOCMT' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screen is as shown below:

The screenshot shows a web application window titled "Document Category Summary". At the top, there are search filters: "Authorization Status" (dropdown), "Record Status" (dropdown), "Document Category" (dropdown), and "Document Description" (text input). Below these are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A table below has columns for "Authorization Status", "Record Status", "Document Category", and "Document Desc". The table is currently empty. At the bottom right, there is an "Exit" button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Document Category
- Document Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Document Category
- Document Description

26.4 Maintaining Document Type

You can maintain the various document types in the 'Document Type Maintenance' screen. To invoke this screen, type 'CSDDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows a window titled "Document Type Maintenance". Inside the window, there is a section labeled "Document Type" with three required fields: "Document Category *" (with a dropdown arrow), "Document Type *" (text input), and "Document Description *" (with a text area icon). Below this section, there are several other fields: "Maker", "Checker", "Date Time:" (two instances), "Mod No", "Record Status", "Authorization Status", and a "Cancel" button.

Specify the following details:

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.


Document Description

Specify a brief description for the document.

26.5 Viewing Document Type Details

You can view the document type details in the 'Document Type Summary' screen. To invoke this screen, type 'CSSDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screen is as shown below:



You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Document Type
- Document Category
- Document Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Document Type
- Document Category
- Document Description

26.6 Maintaining Document Checklist Details

You can maintain the various document checklist details in the 'Document Checklist Maintenance' screen. To invoke this screen, type 'CSDDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button

Document Category *	Type *	Mandatory
<input checked="" type="checkbox"/>		Mandatory

Specify the following details:

Process Code

Specify the process code. The adjoining option list displays the process codes that are maintained in the system. You can select the appropriate one.

Stage

Specify the stage in which you need to maintain the checklist details.

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.

Mandatory

Indicates whether the document is needed for checklist.

26.7 Viewing Document Type Details

You can view the document type details in the 'Document Checklist Summary' screen. To invoke this screen, type 'CSSDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Authorization Status	Record Status	Process Code

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Process Code
- Stage

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Process Code
- Stage

27. Configuring Overrides

27.1 Introduction

The system displays messages in respect of errors that occur when you execute operations during a work session, in any module. These error messages are also displayed in respect of automatic or batch processes, such as end of day processes.

Depending upon your requirements at your installation, you might require some of the errors to be ignored, and others to result in an override being sought from the user for the operation to proceed. For still others, you might require an online authorization for the operation to proceed. Accordingly, the implementers at your installation configure the sensitivity of such errors. Subsequently, you might also need to configure errors to suit your requirements.

27.1.1 Types of Overrides

In Oracle FLEXCUBE, you can assign a level of sensitivity to each override that arises or occurs during system operation. This level of sensitivity that you assign to an override indicates the action that will result when that specific override occurs. Accordingly, you can assign any of the following sensitivity levels to an override:

Ignore

This would mean that no override message would be displayed and the exception would be ignored

Override

This sensitivity indicates that an override message should be displayed, seeking confirmation from the user. If the user confirms or accepts the override, processing of the transaction would proceed; if not, the exception would have to be corrected before transaction processing can proceed.

For such overrides, you can assign an additional parameter to indicate whether an online authorization is required if the override is accepted. If you have assigned online authorization to be required, then, for transactions involving such overrides, an online authorization is requested as a mandatory procedure. The online authorization limit specified for the authorizer would be checked during authorization, in addition to the time level of the authorizer, which should be greater than the user who is input the transaction.

For such overrides, if you have specified that no online authorization is required, the user can accept the override, and it will not require any online authorization.

Error

This would indicate that, when an exception occurs, an override message would be displayed, and the transaction cannot be processed further, that is, it would stop being processed until the exception is corrected.

Online Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted.

Dual Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted. Also, at least two authorizers would be needed to authorize the transaction.

Override Types for Batch Functions

For exceptions occurring during execution of automatic or batch processes, you can assign the Ignore, Override or Error sensitivities.

27.2 Specifying Override Type

In the 'Overrides Maintenance' screen, all the error messages that would appear in each module, with their respective error codes, are displayed. The functions, with respect to which the error messages could be encountered, are also displayed. You can invoke this screen by typing 'CSDOVDMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Overrides Maintenance' window. It has a title bar with a diamond icon and a close button. The window is divided into several sections:

- Language:** Language * ENG, Description
- Error details:** Error Code * AC-LM-00117, Message: Amount exceeds limit for liability \$1. Limit = \$3 \$2, Utilisation = \$4 \$2, Overdraft = \$5 \$2 %, Overdraft = \$6. There is a checkbox for 'Confirm'.
- Type:** A dropdown menu showing 'Override'.
- Function:** BCCONONL
- Param:** 5
- Batch Type:** A dropdown menu showing 'Override'.


At the bottom, there are two tabs: 'Fields' and 'Conversion'. Below the tabs, there is a status bar with the following information:

- Input By: SYSTEM
- Date Time: 2005-03-10
- Modification Number: 1
- Authorized:
- Open:
- Authorized By: SYSTEM
- Date Time: 2005-03-10
- An 'Exit' button is located on the right side of the status bar.

In the Type field, you can specify, for each error message, the appropriate sensitivity level – Ignore, Override, Error, Online Authorization or Dual Authorization.


For error messages in respect of automatic or batch functions, you can specify the appropriate level in the Batch Type field – Ignore, Override or Error.

For certain overrides, (to which you have assigned the level Override, Online Authorization or Dual Authorization), you can indicate whether the authorizer must also confirm the override, by checking the Confirm box.

 You can make changes to configurable overrides in the Error Codes Maintenance screen only after consulting the support team at your installation.

27.2.1 Maintaining Override Conversion

Click 'Conversion' button on the 'Overrides Maintenance' screen to maintain the conversion error codes for the override error code using 'Overrides Conversion' screen.



<input type="checkbox"/>	Branch Code *	Function Id *	New Error Code
<input type="checkbox"/>			
<input type="checkbox"/>			

You can enter the following details:

Branch Code

Specify the branch code. If ALL is specified, in all the branches the conversion will be done. However if it is maintained for a specific branch, only in that branch the conversion will be done.

Function Id

Specify function Id for which the override should be treated as error.

New Error Code

You can map an already existing error code as the conversion error code or can use the 'Override Maintenance' screen to define the same.

You are not allowed to maintain/map conversion error codes for the error code which is a conversion error-code.



Note the following:

- If you encounter overrides while processing, the system will check if any conversion error code mapped for the override for the combination of branch and function Id. If available then the system will raise the mapped error code instead of the original error code.
- The system will allow you to map conversion codes only for the error codes with type as 'Override'.
- If a modifiable error code is changed from 'Override' to 'Error', then the system will delete all the conversion error codes maintained for the same.


28. Maintaining Features

28.1 Introduction

In order to improve the performance of the system during online or batch processes, you can install some features on need basis on the system. This chapter explains the process of installing features.

28.2 Maintaining Feature ID

You can maintain required features using the 'Feature ID Maintenance' screen. You can invoke this screen by typing 'CSDFEAMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a software window titled "Feature ID Maintenance". The window has a blue header bar with a close button (X) on the right. Below the header, there are three input fields: "Branch Code *" with a dropdown arrow, "Branch Name" with a dropdown arrow, and "Feature Id *" with a dropdown arrow. Below these fields is a checkbox labeled "Installed". At the bottom of the window, there is a "Fields" tab and a status bar. The status bar contains several fields: "Input By DOCS", "Date Time", "Modification Number", "Authorized" (with a checkbox), and "Open" (with a checked checkbox). A "Cancel" button is located in the bottom right corner of the status bar.

You can specify the following details:

Branch Code

Specify the branch where the feature needs to be installed. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Branch Name

The branch name is displayed here based on the chosen branch code.

Feature ID

Specify the feature that should be installed in the branch. You can also choose any of the following values from the adjoining option list:

Feature Id	Description	Mode - Online/Batch
ACCRESTR	Account Restriction feature which need to be enabled for replace amounts in overrides with wild char (*)	Online
ACSTHAND	Account Statement Handoff during EOD	Batch
APY	Movement of Annual Percentage Yield to history	Batch
CCYPOS	CCY position entries updation during EOD	Batch
CUSTOMIS	building of Customer MIS details Transaction/Composite/Fund	Online
DDRECLOG	During Demand Draft creation - update of record log and field log	Online
DEFERLIQ	IC Deferred Liquidation	Batch
DORMUPD	Dormancy update during EOD	Batch
DRINTDUE	Dr. Interest Due	Batch
FCTDSTATS	Financial cycle wise account statistics update	Batch
GLCUSTSTATS	Period/Financial cycle wise customer GLs statistics update	Batch
GLFCTDSTATS	Financial cycle wise GL statistics update	Batch
GLPTDSTATS	Period wise GL statistics	Batch
ICINTSTMT	IC Interest Statement generation	Batch
ICRATECHG	Rate change Advice	Batch
IRASTMT	IRA Statement generation during EOD	Batch
LDSTMT	Loan Statements generation during EOD	Batch
LINKSTMTAC	Update of Previous Statement	Batch

Feature Id	Description	Mode - Online/Batch
	Date and No during statement generation	
PRODTXNREST	Product and Transaction code restrictions applicability	Batch
PTDSTATS	Period wise account statistics update	Batch
RAC	Account entry serial number derivation logic when multiple FCUBS instances exists	Online/Batch
REGCC	Regulatory CC update for customer account during EOD	Batch
TRACKACCRINT	Tracking of Accrued interest	Batch
USREGCHGS	US Regulatory changes	Batch
VDBALINIC	VD balance update. This is equivalent to flag at bank parameters level	Online

Installed


Check this box to indicate that the feature should be installed in the branch.

Click save icon in the Application tool bar to save the changes.

28.2.1 Specifying UDF Values

All User Defined Fields (UDFs) linked to the function ID 'CSDFEAMT' are displayed in the 'User Defined Fields' screen. Invoke this screen by clicking 'Fields' button on the 'Feature ID Maintenance' screen.

The screen is as shown below:




Here you can specify values for each UDF.

Refer the User Manual titled 'User Defined Field' for details about defining UDFs.

28.3 Viewing Feature ID Summary

You can view summary of all feature IDs installed across branches, using the 'Feature ID Summary' screen. To invoke this screen, type 'CSSFEAMT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screen is as shown below:



You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Feature ID
- Installed

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Feature ID
- Installed

Double click on a record to invoke the detailed screen for that record.

29. Purging Data

29.1 Introduction

Purging is a process by which you remove unwanted data from the system. For example, you may find the interest rates that you have maintained for a financial cycle useless a couple of years later. You would want to remove such data from the system. You can achieve this by 'purging' the system of the data.

The purge function of Oracle FLEXCUBE allows you to purge:

- Contracts and transactions that you have entered into,
- Data relating to transactions (such as, interest rates)
- Limits history (Liability, Lines and Line Utilization history)
- GL Average Balance and Customer Account statistics

You can purge the contracts (or transactions) that you have entered into in the following modules of Oracle FLEXCUBE:

- Foreign Exchange
- Money Market
- Loans
- Deposits
- Data Entry
- Standing Instructions
- Letters of Credit
- Bills and Collections

You can purge data from the following modules:

- Accounting
- Currency
- General Ledger
- Interest and Charges
- Messaging
- MIS
- Reconciliation
- Receivable Liquidation

You can also purge data relating to transactions. For example, you can purge the currency rates that you have maintained, the messages in the messaging system of Oracle FLEXCUBE, the User Data Elements that you used to compute interest, interest statement details, user information maintained in the Security Management System of Oracle FLEXCUBE, customer information, and so on.

The system will automatically purge data according to the parameters that you define in the Purge Details Maintenance screen.

29.2 Maintaining Purge Details


In the 'Purge Details Maintenance' screen, you can define the parameters for purging data from the system. For instance, you may want to purge the contracts entered into in the previous financial cycle. Or, you may want to retain exchange rates in the system for a specific period. These are examples of parameters that you can define in the Purge Details Maintenance screen. You can invoke this screen by typing 'CSDPURGE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Purge Details Maintenance' window. It has a blue title bar with the text 'Purge Details Maintenance' and a close button. The main area is divided into two sections: 'Module Selection' and 'Purge Criteria'. The 'Module Selection' section has a 'Module Identification *' field with a search icon and a 'Description' field with a help icon. The 'Purge Criteria' section has a 'Status *' dropdown menu and a 'Retention Period' text field. At the bottom, there is a 'Fields' section with a grid of fields: 'Input By DOC7', 'Date Time', 'Modification Number', 'Authorized' (checkbox), 'Authorized By', 'Date Time', 'Open' (checkbox), and a 'Cancel' button.

29.2.1.1 Specifying Module

In the Purge Details Maintenance screen you must first specify the module for which you are defining parameters. All parameters that you define subsequently will only apply to the module that you specify.

You can enter a description of the module for which you are maintaining purge details.

 For purging limits history which is Liability, Lines, and Lines Utilization history, you must specify LM as the module code. Limits history data is purged for the current branch only.

29.2.1.2 Specifying Nature of Data to be Purged

You can opt to purge contracts (of the module you specified) along the following criteria. You may either choose to purge any of the following:

- Liquidated contracts
- Closed (applicable only to the BC and LC modules)
- Reversed contracts

When you run the purge process, only those contracts that are in the status that you specified will be purged. That is, only contracts (in the module you specified) that are liquidated, closed, and/or reversed, depending on your specification, will be purged from the system.

Similarly, if you want to purge

- Exchange rates (from the Currency module), you should choose the 'None' option.
- Data from the Reconciliation module, you should choose any of the following options, depending on the data that you want to purge. The options available are:
 - System Date Relative
 - Match Relative
 - Closed Match
 - Closed External Statement

Retention Period

The retention period, as the term suggests, is the period for which data is stored in the system. For each module in Oracle FLEXCUBE, you can specify the retention period.

When you run the purge process on any given day, only the data that is beyond the retention period that you specified will be purged. The following example illustrates this concept.

Example

The requirement:

You would like to retain foreign exchange contracts that were liquidated 60 days prior to the running of the purge process, in the system. (That is, if the current system date is 30 June 1999 and you do not wish to purge the foreign exchange contracts that were liquidated between 1 May 1999 and 30 June 1999).

Solution:

In the Retention Period field enter '60' (note this value is expressed in days), and in the 'Status' field choose the 'Liquidated' option.

Result:

If this setup is authorised, and you run the purge process on 30 June 1999, the current system date, all foreign exchange contracts that you liquidated prior to 1 May 1999 will be purged. Contracts that were liquidated on or after 1 May 1999 will not be purged.

30. Tanking of Maintenance Records

30.1 Introduction

The maintenance records that are created or modified in the system can be tanked till they get authorized, so that it is possible to undo the modifications, if needed, before the records are authorized. The maintenance log also will store the changes till they get authorized. The new or the modified records are written to the static tables only after authorization.

30.2 Tanking New and Modified Maintenance Records

You can enable tanking of the creation and modification of maintenance records by selecting the 'Tanking Required' option provided at the function Id level. You need to enable the 'Tanking Required' option in RAD tool as well.

You can enable 'Tanking Required' option for individual function Ids in 'Function Description Maintenance' screen. You can invoke this screen by typing 'SMDFNDS' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Function Description Maintenance' window. It features a form with the following fields and options:

- Function Id *
- Module List *
- User Function Id
- Name
- Type: Form
- Menu Head: MODULE
- Type String: Maintenance
- Checkboxes:
 - Tanking Required
 - Dual Authorization
 - Remarks Required
 - Excel Export Required
 - Available
 - Automatic End of Day aware
 - Log Event
 - Customer Access
 - Auto Authorization
 - Head Office Function
 - Duplicate task check

The 'Function Description' table has the following columns: Language Code, Main Menu, Sub Menu 1, Sub Menu 2, Balloon Help, and Description.

The 'Field Properties' section includes: Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, and an EXIT button.

To enable tanking of maintenance records for a function Id you need to select the function Id in this screen and then select the 'Tanking Required' checkbox.

For more details on this screen, refer Security Management System user manual.



Tanking of records has been enabled only for the following function Ids:

- STDCIF

- STDCUSAC

30.2.1 Tanking New Records

During the creation of a new record, if 'Tanking Required' option is enabled, the system tanks the details of the newly created record till the record gets authorized. Any query on this data retrieves this stored information.

30.2.2 Tanking Modified Records

All modifications to unauthorized records get tanked and the modified data gets written to actual tables only after authorization. In this case, the record remains in 'Authorized' status in the actual table and the unauthorized modifications will be kept pending for un-tanking. The most recent modifications will be shown in both summary and detailed screens with the Authorization status as 'Unauthorized'.

30.2.3 Closing a Record

You can close a record only if it is in 'Authorized' state, without any unauthorized modifications pending for un-tanking. Closure is possible only for records that are in 'Open' status. When you close a record, the system tanks this and the record gets actually closed only after the closure gets authorized.

30.2.4 Re-opening a Record

You can re-open a record only if it has been closed and the closure is authorized. Re-opening of a record gets tanked till it gets authorized and the actual re-opening happens after the authorization.

30.2.5 Authorizing a Record

All unauthorized modifications get displayed when you click 'Authorize' menu option. You can select a modification number and the records get authorized till that modification. These records are un-tanked and their status gets updated as 'Authorized'. You can authorize the modifications partially, if required.

30.2.6 Deleting a Record

All unauthorized records will be available for deletion. You can select a modification number and system deletes all unauthorized modifications from the selected modification number. If the modifications getting deleted are made by a user other than the current user, the system displays an error message.

30.2.7 Viewing Summary of Records

All summary screens display data retrieved from both the summary data source and the table that contains the unauthorized tanked records.

30.2.8 Modifying Tanking Preferences

You can modify the tanking preferences specified for a function Id, if required. This modification is possible only if all records related to that function Id are in 'Authorized' status.

31. External Deal Maintenance

31.1 Introduction

You can capture the details of a deal booked in an external system using 'External Deal' maintenance screen. You can invoke this screen by typing 'STDEXLIN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "External Deal Linkage Detail". The window contains the following fields:

- FLEXCUBE Reference *
- Account Number
- External Deal Reference
- Deal Currency
- Deal Amount
- Exchange Rate
- Deal Booking Date
- Deal Expiry Date
- Account Currency
- Equivalent Amount
- Remarks

At the bottom of the window, there are several fields and a button:

- Maker
- Checker
- Date Time:
- Date Time:
- Mod No
- Record Status
- Authorization Status
- Exit button

You can specify the following details in this screen:

FLEXCUBE Reference Number

This reference number is automatically generated by the system.

Account Number

Select the account number associated with the external deal from the option list which displays all valid account numbers in the system.

External Deal Reference Number

Specify a unique identification number for the external deal.

Deal Currency

Specify the currency in which the external deal was carried out or select the deal currency from the option list provided.

Account Currency

The account currency gets defaulted once you select the account number.

Deal Amount

Specify the amount associated with the external deal in terms of deal currency.

Equivalent Amount

The deal amount in terms of the account currency gets displayed here.

Equivalent Amount = Deal Amount * Exchange Rate

Exchange Rate

Specify the exchange rate to convert the deal currency in terms of the account currency.

Remarks

Specify any remarks associated with the external deal, if required.

Deal Booking Date

Specify the booking date of the external deal or select the deal booking date by clicking the 'Calendar' icon.

Deal Expiry Date

Specify the expiry date of the external deal or select the deal expiry date by clicking the 'Calendar' icon.

After specifying the above details you can save the record. An amount block equivalent to the deal amount is automatically created once these details are authorized.



You cannot modify a record in this screen, after it has been authorized.

For more details related to amount block maintenance, refer the chapter 'Maintaining Amount Blocks' in Current and Savings Account User Manual.

32. Annexure B - File Formats

32.1 Introduction

As mentioned earlier, SWIFT provides a country-wise holiday list that can be uploaded into Oracle FLEXCUE using the 'CCH' source code. This file consists of the 'HF' and 'HS' records. HF and HS are the tag identifiers through which the currency code can be obtained.

32.2 Upload File Formats

HF – Non-European countries

As mentioned before, the HF record comprises the holiday details for countries where 'EUR' is not the local currency. The currency code is obtained from the country code present in this record. The holiday record is then uploaded into the Oracle FLEXCUBE holiday upload table.

The HF record has the following format:

Position	Description	Length	Type	Mandatory	Data
1	Tag Identifier	2	VARCHAR2	Y	'HF'
3	Modification Flag	1	VARCHAR2	Y	'A' addition 'M' modification 'D' deletion 'U' unchanged
4	Country Code	2	VARCHAR2	Y	ISO Country Code
6	Country Name	35	VARCHAR2	Y	Country Name (first part)
41	Country Name	35	VARCHAR2	N	Country Name (second part)
76	Date	8	VARCHAR2	Y	Date of a Holiday
84	Holiday type	1	VARCHAR2	Y	Code indicating type of Holiday (see below)

Position	Description	Length	Type	Mandatory	Data
85	Special holiday info.	320	VARCHAR2	N	Restrictions applicable if a holiday is not applicable country-wide, or is not a full day

HS – For European countries

The HS record comprises the Target holiday details for countries where 'EUR' is the local currency. The holiday record is uploaded into the Oracle FLEXCUBE holiday upload table.

The HS record has the following format:

Position	Description	Length	Type	Mandatory	Data
1	Tag Identifier	2	VARCHAR2	Y	'HS'
3	Modification Flag	1	VARCHAR2	Y	'A' addition 'M' modification 'D' deletion 'U' unchanged
4	Service Code	3	VARCHAR2	Y	Value Added Service Code
7	Date	8	VARCHAR2	Y	Date of a Holiday
15	Holiday type	1	VARCHAR2	Y	Code indicating type of holiday(see below)
16	Special holiday info	320	VARCHAR2	N	Restrictions applicable if a holiday is not applicable country-wide, or is not a full day

33. Anti-Money Laundering Reporting

33.1 Guarding Against Money Laundering

In Oracle FLEXCUBE you can guard against Money Laundering by using the anti-money laundering option wherein you will be required to maintain certain basic information as a safeguard against Money Laundering activities that customers may indulge in.

The information that you need to maintain includes the maintenance of:

- Product Categories
- Limit Codes
- Customer Groups

33.1.1 Creating Product Categories in Oracle FLEXCUBE

You have to create product categories in Oracle FLEXCUBE, for the purpose of grouping common transactions. A product is a specific service that you offer your customers. Each transaction that you process in Oracle FLEXCUBE should be linked to a product. By maintaining amount limits at the product level, each time you link a transaction with a product the system verifies the amount limit maintained for the product. If the transaction amount exceeds the amount maintained at the product level the system intimates you with an override.

You can invoke the 'AML Product Categories Maintenance' screen by typing 'CSDAMLPC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'AML Product Categories Maintenance' window. It features several input fields: 'Product Category *', 'Description *', 'Limit Currency *', 'Exchange Rate Code', and 'Exchange Rate Type *' (set to 'Buy Rate'). There are radio buttons for 'Product Type' (Cash, Non Cash) and 'Debit/Credit Indicator' (Debit Indicator, Credit Indicator, Both (Aggregate Together), Both (Aggregate Separately)). Below these are tabs for 'Individual', 'Daily', 'Monthly', 'Online', and 'Online Daily'. A 'Limit Details' table is visible with columns for 'Limit Code *', 'Limit Amount', and 'Limit Currency'. At the bottom, there are checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

Product Category

You should identify each product category with an identification code by giving it a unique name.

Description

With each product category you have to associate a brief description. This description is meant for information purposes and will not be used for any processing.

Limit Currency

You have to identify the currency in which limits have to be tracked for transactions associated with the product category.

A list of all the currencies maintained in Oracle FLEXCUBE is available in the option list positioned next to this field. You can select the appropriate.

Product Type

Transactions grouped under a product can either be cash based or non-cash based. Therefore, you would have created products catering to cash based and non-cash based transactions.

While creating a product category, you have to indicate whether the products grouped under the respective category cater to cash based or non-cash based transactions. You can select the appropriate option.

Exchange Rate Code and Rate Type

The rate associated with this rate code will be used to derive the exchange rate when the currency of the transaction is different from the limit currency of the product category.

Similarly, you have to select the Rate Type that is to be associated with the rate code. The options available are as follows:

- Mid
- Buy
- Sell

The rate code along with the rate type will determine the exchange rate that is to be used.

Debit/Credit Indicator

As part of Anti-Money Laundering you can indicate the manner in which the system should track the Debit and Credit turnover limits for any of the limit types, for the product category. The options available are:

- Both (Aggregate Together) – absolute values of debits and credits will be aggregated together
- Both (Aggregate Separately) – debits and credits will be aggregated separately
- Debits alone or Credits alone

Limit Code and Limit Amount

At the product category level, you can specify the limit amount that should be associated with each limit code for a limit type.

A list of all the limit codes maintained for the specific limit type (Online, Individual, Daily turnover Batch, Daily turnover Online and Monthly turnover), in the Limit Codes Maintenance screen, will be displayed in the option list positioned next to this field. You can select the appropriate limit code and specify the limit amount that is to be linked with the code.



For a particular product category you can choose to maintain Limit Code and Amount combinations for all of any of the five Limit types. They are:

- The Online transaction limit
- Individual limits
- Daily turnover limits
- Monthly turnover limits
- Online daily turnover limits

The transaction limits that you specify will be tracked online on a daily basis, whenever you process a transaction involving the product category. However, individual, daily and monthly turnover limits will be tracked only when the after the End of Day processes have been run successfully.

33.2 Maintaining Limit Codes

Before you begin the maintenance of product category records, you should necessarily maintain limit codes through the Limit Code Maintenance screen. While linking a limit amount with a limit code in the product category screen, only valid limit codes that you have maintained through this screen will be made available for mapping.

You can invoke this screen by typing 'CSDAMLLM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Limit Codes Maintenance". It features two text input fields: "Limit Code *" and "Description". To the right, under the heading "Limit Type", there are five radio button options: "Online Limit" (which is selected), "Online Daily Turnover", "Daily Turnover", "Monthly Turnover", and "Individual Transaction". At the bottom of the window, there is a "Fields" tab and a status bar containing several fields: "Input By DOC7", "Date Time", "Modification Number", "Authorized", and "Open". A "Cancel" button is positioned in the bottom right corner of the window.

Limit Code

You can maintain limit codes for the various types of limit types like online tracking limits, individual tracking limits, daily turnover limits and monthly turnover limits.

You have to specify a unique name to identify each Limit Code that you would like to define. Subsequently, you can assign a brief description with each limit code that you define.

Limit Type

Since you can maintain separate limit codes for each limit type, you have to associate a limit code with each limit type. The options available are:

- Online Limit – tracks the limits of all online transaction that exceed limits
- Individual Transaction – during the batch processed executed at EOD the limit maintained for this type is used to tack all individual transactions that exceed the limit

- Online Daily Turnover –all transactions processed during the day are considered for an online tracking and an online reporting is done when the specified limit exceeds
- Monthly Turnover – all transactions processed during the month that have exceeded the specified limit will be reported
- Daily Turnover – during the batch processes executed at EOD all transactions for the business day that have exceed the limit will be reported

You can select the appropriate type from the list.


33.3 Maintaining Anti Money Laundering Customer Groups

Since you need to define transaction online, individual, daily and monthly limits for each customer, each product category that you maintain should be linked with a customer. To facilitate this linking, you are required to maintain AML Customer Groups. You have to link one of the limit codes of the respective type attached to the product category to the customer group

You can define product categories applicable to customer groups through the 'AML Customer Group Maintenance' screen. You can invoke this screen by typing 'CSDAMLCG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Group

This is the AML group to which the particular customer belongs. You can select from the available option list and identify the AML group to which the customer belongs.

 In the CIF maintenance screen when you capture the customer code of a customer, the same will be defaulted in the AML Customer Group field since the system recognizes each customer code as a customer group. You can either choose to categorize the customer under the same group or choose another customer group.


You can capture a brief description that should be associated with every AML group

Next Review Date

While maintaining customer group and product category records you can specify the next date on which you would like to review the limits maintained for the various limit types.

Tracking

You have to specify whether the AML tracking is required for a customer or for all customers within a group. The system performs a group level tracking if you select Customer group. Conversely if you select Customer, the AML reporting, online tracking and data collection is done only at the customer level.

 If you fail to indicate your preference specifically the system will perform a customer group level tracking by default

Risk Profile

You can identify the risk profile of the customer group by selecting any one of the following options:

- High – indicating that the limits for the customer group need to be tracked regardless of the amount involved since the customer group is meant for high-risk customers.
- Low – indicating that the customer group is meant for low risk customers therefore amount limits need not be tracked if the amount involved falls within the limit amount.

You can select the required specification.

33.3.1.1 Linking Product Category with Customer Group

You have the option of selecting and linking as many limit codes as required for each limit type from the product categories maintained in the system. After you select the product category that is to be linked to the customer group, you have to identify the limit code associated with the limit type and in turn link it with the customer group.

Given below is a sample of the Customer Group maintenance record:

The Main details of the record are as follows:

Customer Group	AMLCUS01
Description	AMLCUSTOMER GROUP 1
Next Review Date	10-FEB-2003
Risk Profile	High

The Product Category linkage details are as follows:

Product Category	Description	Online Limit Code	Individual Limit Code	Daily Limit Code	Monthly Limit Code	Online Daily Turnover
PDT01	Product 1	LIM31	LIM01	LIM11	LIM21	LIM41
PDT02	Product 2	LIM36	LIM06	LIM16	LIM26	LIM46



Note the following:

- Consequently, while processing transactions for all customers linked to the Customer Group AMLCUS01, the system does an online verification of transaction limits based on the amount limits maintained for the limit code LIM31 (linked to the product category PDT01) and LIM36 (linked to the product category PDT02) respectively.
- It is mandatory for you to maintain a generic Customer Group called ALL for the customers of your bank. When product categories have not been linked to a specific customer or a customer group, the system picks up the limits maintained at the generic level for AML tracking purposes. Also, any new product category created and associated to the transaction code should be mandatorily associated with the ALL group.

33.4 Monitoring AML Accounting

For AML reporting purposes, while maintaining a transaction code you need to indicate whether AML monitoring is required for all accounting entries linked to the transaction code.

You can invoke this screen by typing 'STDTRCOD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot displays the 'Transaction Code Maintenance' window. It is divided into several sections:

- Transaction Details:** Includes fields for Transaction Code, Description, SWIFT Code (set to MSC), MIS Head, and External Code.
- Availability Information:** Features radio buttons for 'Immediate', 'On Value Date', 'After Days with New Value Date', and 'After "X" Days', along with a 'Days' input field.
- Anti Money Laundering Monitoring:** Contains a checkbox for 'Anti Money Laundering Required', a 'Product Category' dropdown, a 'Statement Day Basis' dropdown (set to 'Current working day'), and an 'Intraday Release' checkbox.
- Preferences:** A list of checkboxes for various settings, including 'Cheque Mandatory', 'Interest and Charges Transaction Count', 'Interest and Charges Turnover Inclusion', 'Consider for Account Activity', 'Interest and Charges Balance Inclusion', 'Consider For Turnover Limit', 'Available Balance Check Required?', 'Interests and Charges Penalty Inclusion', 'Inter Branch in Local Currency', 'Acumen Transaction Code', 'Exempt Advance Interest', and 'Escrow Processing'.
- Fields:** A section at the bottom with checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

If you indicate that AML tracking is required for transactions linked to the transaction code you have to identify the product category with which the transaction code is to be linked.

Consequently, the system does a check for every accounting entry passed during online processing. The system checks the transaction amount of the entry with the transaction online limit maintained for the specific customer group (of the customer to whose account the entry has been posted) and the product category (for the transaction code of the entry). If the system finds that the limit amount has been exceeded an override message informing you of the same will be displayed.

During the End of Day (EOD) processing, the system identifies all accounting entries posted during the day, which have been marked for AML monitoring, and verifies the individual amount limit for the customer group and product category combination and stores this data in the system. You will be able to view this data when you generate an AML report using Business Objects.

As part of the EOD processes the system also updates the daily turnover limits for the particular customer group and product category combination. Monthly turnovers are updated for the Customer Number, Product Category and Currency combination.

34. Developer and Developer Project Maintenance

34.1 Introduction

In Oracle FLEXCUBE, you can maintain details of the real-estate developer and developer projects. You can link the developers to loan accounts.

34.2 Maintaining Developer Details

You can maintain contact and project details of the developer in the 'Developer Maintenance' screen. You can invoke this screen by typing 'CSDDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Developer Maintenance" with a close button (X) in the top right corner. The window contains two columns of input fields. The left column includes: "Developer Code *" (with a red asterisk), "Address" (with three stacked text boxes), "Zip", "Country" (with a small "E/c" icon to its right), and "Country Name". The right column includes: "Developer Name", "Telephone", "Email ID", "Fax", "Mobile", and "Website". At the bottom of the window, there is a "Project" tab and a "Fields" tab. Below these tabs is a table with columns: "Maker", "Date Time:", "Mod No", "Record Status", "Checker", "Date Time:", "Authorization Statu", and "s". A "Can" button is located at the bottom right of the table.

Here, you can specify the following details:

Developer Code

Specify the unique code of the developer.

Address

Specify the address of the developer.

Zip

Specify the ZIP code of the developer.

Country

Specify the code of the country to which the developer belongs. The adjoining option list displays all valid country codes maintained in the system. You can choose the appropriate one.

Country Name

The system displays the corresponding country name based on the specified code of the country.

Developer Name

Specify the name of the developer.

Telephone

Specify the telephone number of the developer.

Email ID

Specify the Email ID of the developer.

Fax

Specify the fax number that should be linked with the specified developer.

Mobile


Specify the mobile number of the developer.

Website

Specify the URL of the website linked to the developer.

34.2.1 Viewing Project Details


You can view the details of the projects linked to the developer by clicking 'Project' button in the 'Developer Maintenance' screen.



Here you can view the project names and descriptions that are linked to the specified developer.

34.2.2 Viewing UDF Details


You can view the UDF details by clicking 'Fields' button in the 'Developer Maintenance' screen.



Here you can view the field names and its value.

34.3 Viewing Developer Maintenance Summary

You can view the summary of developer maintenance in the 'Developer Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status
- Record Status
- Developer Code
- Website
- Address
- Developer Name
- Country
- Email ID
- Zip

34.4 Maintaining Developer Project Details

You can maintain the details of real estate development projects in the 'Developer Project Maintenance' screen. You can invoke this screen by typing 'CSDDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Unit Id	Unit Holder Name
<input checked="" type="checkbox"/>	<input type="text"/>

Here you can specify the following details:

Project Name

Specify the name of the project.

Project Description

Specify a brief description about the project.

Address

Specify the address of the project location.

Status

Specify the status of the project.

Developer Code

Specify the unique code of the developer. The adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Unit Details

Specify the following details.

Unit ID


Specify the unit ID of the developer project.

Unit Holder Name

Specify the name of the unit holder of the developer project.

34.4.1 Viewing UDF Details

You can view the UDF details by clicking 'Fields' button in the 'Developer Project Maintenance' screen.



The screenshot shows a window titled "User Defined Fields" with a close button (X) in the top right corner. Below the title bar, there is a navigation bar with "1 of 1" and "Go to Page" buttons. The main area is titled "UDF Details" and contains a table with two columns: "Field Name" and "Value". The table is currently empty. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

Here you can specify values for the UDF.

34.5 Viewing Developer Project Maintenance Summary

You can view the summary of developer project maintenance in the 'Developer Project Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Developer Project Maintenance Summary". At the top, there are search filters: "Authorization Status" (dropdown), "Record Status" (dropdown), "Developer Code" (text input), and "Project Name" (text input). Below these are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A table below the search area has columns for "Authorization Status", "Record Status", "Developer Code", "Project Name", "Project Description", "Address", and "Status". The table is currently empty. At the bottom right of the window is an "Exit" button.

In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status
- Project Name

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status
- Record Status
- Developer Code
- Project Name
- Project Description
- Address

- Status

35. Project Financing

35.1 Introduction

Project financing is the financing of long-term infrastructure and industrial projects involving a number of equity investors and a group of banks.


Project financing is a credit facility sanctioned to the contractors who execute large infrastructure projects, residential complexes, commercial complexes, etc. These contractors are awarded the contracts (projects) based on a BID system. Once the project is awarded to a contractor, he approaches the bank seeking for finance.

The contractor can avail financing from the bank against PPC (Project Progress Certificate/ Project Payment Certificate) or Invoice or TD or a clean line. PPCs are one type of backing against which OD is provided. The contractor can be a single entity or a joint venture (JV). In case of a joint venture, the share of the overdraft for each contractor will depend on their share in the joint venture.



35.2 Processing Finance for Project

The process of project financing is as follows:



1. A customer or a joint venture approaches the bank for project financing
2. The bank creates the customer in the system
3. If it is a joint venture, the bank creates the joint venture customer and enters the party/customer details linked to the joint venture in the joint venture button screen.
4. The bank then creates the project account for the created customer/joint venture customer.
5. The bank captures the following details in the 'Project Maintenance' screen:

- Project header details
 - Sponsor/Pay-master details
 - Project milestone details
 - Joint Venture Parties Details (In case of Joint Venture Limit Tracking)
 - PPC Limits Details
 - Non PPC Limits Details
6. Link the Non PPC lines defined in project to the project account using Limits tab
 7. The customer will utilize this clean limit line until he furnishes a PPC against part or full completion of a milestone.
 8. On receiving the PPC, the bank does the following:
 - Captures the PPC details
 - If it is a joint venture then the system will default the joint venture details to this screen based on the details captured in the project maintenance venture details screen.
 - If 'Auto Line Creation for PPC' field is unchecked,
 - You should manually create the line whenever a PPC is received.
 - The line currency can be other than project currency also, but the PPC CCY should be either project currency or line currency.
 - You should manually enter the limit line details in the project maintenance screen limits tab, if the project lines are created manually and in the PPC maintenance screen Joint Venture tab if PPC lines are created manually. If joint venture party limits tracking is not required, then the system will attach one line for the project customer with 100% tracking.
 - The system will also update the project ID and the PPC ID in the 'Facility Maintenance' screen, once the linkage between a line and a PPC/ Project is established manually during PPC maintenance
 - If 'Auto Line Creation for PPC' field is checked,
 - On authorizing the PPC, the system will create the limit lines for each of the PPC for liability ID of the project customer
 - You should allocate the limit to the project line equal to the lendable value of the respective PPC
 - You should allocate the limit to an individual customer limit lines based on the share each has in the joint venture if 'JV Limit Tracking Required' is checked
 - On authorizing the PPC, the system will automatically create line commitment contracts during the EOD. The rates used in the commitment are taken from project maintenance.
 - For each PPC authorized and if 'Limits tracking through Commitment' is checked, then the system will create the following line commitment contracts:
 - Project line commitment contract, regardless of whether there is a joint venture or not
 - Customer line commitment contract for each customer only in case of joint venture

9. The bank will view the details of a project and the status of its collaterals from a Dashboard screen
10. You should manually mark the PPC as CLOSED, if the payment against it has been received
11. You should manually close the project account, if the system receives the payment towards all the PPC's and all the PPC's are marked as CLOSED
12. When multiple lines are available and system has to utilize the lines, the priority will be determined based on the lowest interest rate + spread defined in the linkages screen.
13. Using the PPC liquidation screen, you can choose the payment of the loan or credit to the project account. This transaction will be logged under the PPC.
14. PPC liquidation will be allowed even without the 'Entry No.', say, in case the contractor did not receive money due to contractual terms elapse etc. The system will display an override message when such an input is made.
15. Partial liquidation of PPC is allowed and they will be tracked. In case 'Entry No' is provided, loan payment will be considered only to the extent of PRINCIPAL payment and other component payments will not be considered.
16. Project closure activities include:
 - Liquidating PPCs
 - Marking PPCs as closed
 - All PPCs should be liquidated before they are closed
 - Closing all lines associated with the project
 - Manually created lines can be closed using the close button in the facility screen
 - Auto created lines (created by system) will be auto closed on the event of complete repayment and complete PPC liquidation
 - Manually closing project account
 - All lines associated with the project account should be closed
 - All PPCs should be closed
 - Manually closing project
 - All lines associated with the project should be closed
 - Commitment contracts will be auto closed on commitment maturity date through CL batch (Event: CLOC). Closure of commitment contracts before closure of project will have to be operationally controlled.

35.3 Maintaining Project Financing Transaction

Oracle FLEXCUBE allows you to maintain the project finance transaction in a bank with the details of the project undertaken with the contract. You can maintain these details using 'Project Detail and Maintenance' screen. To invoke this screen, type 'STDPJMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Project Detail and Maintenance

Project Details

Customer Number * Branch Code 000

Project ID * Currency *

Project Name * Number Of PPCs *

Project Account Branch * Default PPC Clearance Days *

Project Account * Start Date *

Liability No. * End Date *

Project Value * Sponsor Retention Margin (%)

Remarks Bank Margin (%)

Ratio Change Allowed Auto Line Creation for PPC

JV Limit Tracking Required Limit Track Required through Commitment

Main Milestones Venture Details PPC Limits Non PPC Limits

Sponsor

<input checked="" type="checkbox"/>	Sponsor ID	Sponsor Name *	Sponsor
<input checked="" type="checkbox"/>	<input type="text"/>	<input type="text"/>	

Consultant

<input checked="" type="checkbox"/>	Consultant ID	Consultant Name *	Consultant
<input checked="" type="checkbox"/>	<input type="text"/>	<input type="text"/>	

UDF

Maker Date Time: Mod No
Checker Date Time: Record Status
Authorization Status

35.3.1 Specifying the Project Details

Customer Number

Specify the customer number.

Project ID

Specify the project identification number.

Project Name

Specify the name of the project.

Project Account Branch

Specify the project account branch details.

Project Account

Specify the project account details.

Liability ID

Specify the liability ID.

Project Value

Specify the value of the project.

Remarks

Specify remarks, if any.

Ratio Change Allowed

Check this box if the joint venture ratio change is allowed during the course of the project.

This field is enabled only for new loans under the project financing.

JV Limit Tracking Required

Check this box if joint venture limit tracking is required.

Branch Code

The system displays the branch code.

Currency

Specify the currency details.

Number of PPCs

Specify the number of PPCs in the project.

Default PPC Clearance Days

Specify the default PPC duration for the payment.

Start Date

Specify the start date of the project.

End Date

Specify the end date of the project.

Sponsor Retention Margin (%)

Specify the retention margin for the sponsor while paying the PPC.

Bank Margin (%)

Specify the margin retained by the bank for the PPC..

Auto Line Creation for PPC

If you check this box, then the system will automatically create the credit lines while authorizing the PPC. Else, you need to manually create the line and link them in the PPC screen.

By default, this field will be checked.

Limit Track Required through Commitment

If you check this box, then the system will create the commitment contracts for every automatic line creation.

35.3.2 Specifying the Main Details

You can specify the main details of the project such as sponsor details and consultant details to validate the PPC and to recommend the sponsor for the payment.

The screenshot displays the 'Project Detail and Maintenance' window. The 'Project Details' section includes the following fields and options:

- Customer Number *
- Project ID *
- Project Name *
- Project Account Branch *
- Project Account *
- Liability No. *
- Project Value *
- Remarks
- Branch Code 000
- Currency *
- Number Of PPCs *
- Default PPC Clearance Days *
- Start Date *
- End Date *
- Sponsor Retention Margin (%)
- Bank Margin (%)
- Ratio Change Allowed
- JV Limit Tracking Required
- Auto Line Creation for PPC
- Limit Track Required through Commitment

Navigation tabs include Main, Milestones, Venture Details, PPC Limits, and Non PPC Limits. Below the main form are two data grids:

- Sponsor Grid:** Columns include Sponsor ID, Sponsor Name, and Sponsor. It shows one record with a checkmark in the first column.
- Consultant Grid:** Columns include Consultant ID, Consultant Name, and Consultant. It shows one record with a checkmark in the first column.

At the bottom, the 'UDF' section contains fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an Exit button.

35.3.2.1 Maintaining Sponsor Details

Sponsor ID

Specify the sponsor identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Sponsor Name

Specify the name of the sponsor.

The system will display the sponsor name, if you had specified the CIF ID in the 'Sponsor ID' field.

Sponsor Address

Specify the address of the sponsor.

The system will display the sponsor address, if you had specified the CIF ID in the 'Sponsor ID' field.

35.3.2.2 Maintaining Consultant Details

Consultant ID

Specify the consultant identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Consultant Name

Specify the name of the consultant.

The system will display the consultant name, if you had specified the CIF ID in the 'Consultant ID' field.

Consultant Address

Specify the address of the consultant.

The system will display the consultant address, if you had specified the CIF ID in the 'Consultant ID' field.

If the sponsor or consultant is not a customer of the bank, then the system will display only the name and address of the sponsor or the consultant.

35.3.3 Specifying Milestones Details

You can specify the records of the various milestones in the project and percentage of completion with respect to the project.

The screenshot shows the Oracle Project Detail and Maintenance form, specifically the Milestones tab. The form is divided into several sections:

- Project Details:** This section contains various input fields for project information, including Customer Number, Project ID, Project Name, Project Account Branch, Project Account, Liability No., Project Value, and Remarks. It also includes fields for Branch Code (001), Currency, Number Of PPCs, Default PPC Clearance Days, Start Date, End Date, Sponsor Retention Margin (%), and Bank Margin (%). There are checkboxes for Ratio Change Allowed, JV Limit Tracking Required, Auto Line Creation for PPC (checked), and Limit Track Required through Commitment.
- Navigation:** Below the Project Details section are tabs for Main, Milestones (selected), Venture Details, PPC Limits, and Non PPC Limits.
- Milestones Table:** This section displays a table with the following columns: Milestone No., Description, Percentage Completion, Start Date, and End Date. The table is currently empty, and there are navigation controls (back, forward, search, and Go to Page) above it.
- UDF Section:** At the bottom of the form, there is a User Defined Fields (UDF) section with fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status. An Exit button is located in the bottom right corner.

Milestone No

Specify the milestone number.

Description

Specify the description of the milestone.

Percentage Completion

Specify the percentage of completion with respect to the milestone.

Start Date

Specify the start date of the milestone.

End Date

Specify the end date of the milestone.

35.3.4 Specifying the Venture Details

You can maintain the details of the joint venture. You can also change the joint venture ratios during the course of the project, but these ratios are effective only for future loans. Each loan created for the project can store the ratios at the loan level which is defaulted based on the application ratio at the time of loan creation. All limits tracking for joint venture parties will be based on this ratio.

The system will create the limit lines for each of the project venture parties when joint venture limit tracking is required at the project level. The line ID maintained at the limits is used to create the limits automatically. Each time the PPC is created, the system will create a new limit line using the same line for each of the liability of each joint venture. Different joint venture parties will have the same commitment product which can have different interest rate.

The screen is as shown below:

The screenshot displays the 'Project Detail and Maintenance' application window. The 'Venture Details' tab is active, showing a 'Default' button and two data grids. The first grid is for 'Effective Date *' and the second is for 'Party Id *', 'Party Name', 'Liability No. *', 'Ratio *', 'Rate *', and 'Margin *'. The bottom section contains user-defined fields (UDF) for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status', with an 'Exit' button.

Effective Date

Specify the effective date of the joint venture. For each effective date, the system maintains the ratio among the joint venture partners. The sum of ratios for each effective date must be equal to 100.

Party ID

The system displays the joint venture details of the project.

Party Name

The system will display the party name.

Liability ID

Specify the liability ID.

Ratio

Specify the percentage share of the joint venture party. The sum of all the ratios must be equal to 100.

Default Interest Rate

Specify the default interest rate that is used for the external component in the commitment product. The system will default this value to PPC.

Margin

Specify the margin applicable on the interest rate.

35.3.5 Specifying PPC Limits Details

You can create the clean limit (ToD) manually using the line ID for the amount. You should then link this limit to the project account. The system creates the joint venture lines on authorization of the PPC maintenance with joint venture tracking required.

In case of manual line creation, the system will create the lines in project currency. Whenever there is a cross currency, the system will use a standard mid rate to convert from limit currency to project currency to track utilization. The LCY difference that may arise due to exchange rate differences will be handled by the ELCM CCY revaluation EOD batch.

You can view the limits detail such as line ID to create the project limits. There are two types, namely, PPC Limits and Non PPC Limits.

The screenshot for PPC Limits is as follows:

The screenshot displays the 'Project Detail and Maintenance' window with the 'PPC Limits' tab selected. The window is divided into several sections:

- Project Details:** A form with fields for Customer Number, Project ID, Project Name, Project Account Branch, Project Account, Liability No., Project Value, Remarks, Branch Code (001), Currency, Number Of PPCs, Default PPC Clearance Days, Start Date, End Date, Sponsor Retention Margin (%), and Bank Margin (%). There are also checkboxes for 'Ratio Change Allowed', 'JV Limit Tracking Required', 'Auto Line Creation for PPC' (checked), and 'Limit Track Required through Commitment'.
- Navigation:** Tabs for 'Main', 'Milestones', 'Venture Details', 'PPC Limits', and 'Non PPC Limits' are visible.
- Table:** A table with columns: Limit Type, Limit Description, Credit Line, Serial No, Commitment Product, Rate, and Margin. The table is currently empty.
- UDF Section:** A section for User Defined Fields (UDF) with fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an 'Exit' button.

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Credit Line

Specify the credit line.

Serial No

The system displays the serial number for the limit created.

Commitment Product

Specify the commitment product details used when the respective limit line is created.

Rate


Specify the rate.

Margin

Specify the margin.

35.3.6 Specifying Non PPC Limits Details

The screenshot for Non PPC Limits is as follows:



35.3.6.1 Maintaining Joint Venture Line Details

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Customer No

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

Rate

Specify the rate.

Margin

Specify the margin.

JV Line

This box will be checked by default.

35.3.6.2 Maintaining Party Line Details**Customer No**

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

35.4 Maintaining PPC

Oracle FLEXCUBE allows the executor to maintain the PPC during the course of the project, i.e. during the course of the project, once the executor completes the milestone should inform the sponsor. The sponsor in turn, will inspect and confirms the completion of the milestone. The executor is then allowed to raise the PPC with start date and the expiry date. The system calculates the expiry date based on the default PPC clearance days. However, the sponsor can change the expiry date. The system will accept the PPC in any currency. If there is a cross currency, then the system uses a standard mid rate for converting from limit currency to project currency.

You can maintain the PPC using 'PPC Maintenance' screen. To invoke this screen, type 'STDPPCMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'PPC Maintenance' window. It features a top navigation bar with a 'Go to Page' button and a '1 of 1' indicator. The main area is divided into two columns of input fields. The left column contains: Project ID * (with a search icon and 'P' button), PPC ID, PPC Description *, Start Date *, End Date *, Milestone No. *, and Currency *. The right column contains: PPC Amount *, Sponsor Retention Margin (%) *, Sponsor Amount *, Bank Margin (%) *, Lendable Amount *, Amount Paid, and Remarks. A 'CALC' button is positioned below the Remarks field. Below the input fields is a table with a header row:

Party Id *	Ratio *	Credit Line	Serial Number	Currency
------------	---------	-------------	---------------	----------

. At the bottom, there is a 'UDF' section with fields for: Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status. An 'Exit' button is located in the bottom right corner.

35.4.1 Specifying PPC Maintenance Details

Project ID

Specify the project ID.

PPC ID

The system displays the PPC ID.

PPC Description

Specify the description of the PPC.

Start Date

Specify the PPC start date.

End Date

Specify the PPC end date.

Milestone No

Specify the milestone sequence number.

Currency

Specify the currency of the PPC.

PPC Amount

Specify the amount of the PPC. If the sum of the PPC amounts for all the PPCs presented for the specific milestone is greater than the milestone percentage calculated amount an error message is displayed.

The system will create the automatic limit lines for the lendable amount arrived at after applying the sponsor retention margin and the bank margin.

Sponsor Retention Margin

The system displays the margin retained by the sponsor for this PPC. However, you can amend this field while creating the PPC.

Sponsor Amount

The system displays the sponsor amount after applying the sponsor retention margin.

Bank Margin

The system displays the margin retained by the bank for this PPC. However, you can amend this field while creating the PPC.

Lendable amount

The system displays the lendable amount after applying the bank margin.

Amount Paid

The system displays the amount that has been paid against this PPC.

Remarks

Specify remarks, if any.

35.4.2 Specifying Joint Venture Details

In case of manual line linkage, you need to operationally ensure the following points:

- Synchronization of Line End date and PPC end date
- Limit lines should have amounts equivalent to that of PPC lendable amount. In case line currency is different from PPC currency, lines should be created for the equivalent of PPC lendable amount by applying the rate conversion. If there is any mismatch in the amounts, while linking the manual lines, the system will display an override message

Party ID

The system defaults the party ID from the project maintenance.

Ratio

The system defaults the joint venture share ratio from the project maintenance.

Credit Line

The system defaults the line ID. The system uses this limit line for tracking the exposure of specific joint venture party.

If joint venture limit tracking is not required at project level, the system will not create the lines. In case auto creation of lines is not chosen, then you need to manually create limit lines and link them in this screen.

Serial Number

Specify the line serial of the credit line.

Currency

The system displays the line currency.

After specifying the PPC amount, click on 'CALC' button. The will calculate the sponsor margin and the bank margin and arrive at the sponsor amount and the lendable amount respectively.

35.4.3 Maintaining PPC Liquidation

You can maintain the liquidation details in the PPC screen, where in you can choose the payment of the loan or credit to the project account. This transaction is logged in the PPC. To invoke the PPC Liquidation screen, type 'STDPPCLQ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "PPC Liquidation" with a close button (X) in the top right corner. The main area contains two columns of input fields:

Project ID *	_____	Branch Code *	_____
Project Name	_____	Loan/Account Number *	_____
PPC ID *	_____	Entry Number	_____
PPC Description	_____	Currency	_____
Serial No	_____	Amount	_____

Below the input fields is a blue bar with the text "UDF". At the bottom of the window is a light blue toolbar containing the following labels: "Maker", "Date Time:", "Mod No", "Checker", "Date Time:", "Record Status", "Authorization Status", and an "Exit" button.

Project ID

Specify the project ID.

Project Name

The system displays the name of the project ID selected.

PPC ID

Specify the PPC ID.

PPC Description

The system displays the description for the PPC ID selected.

Loan/Account Number

Specify the loan or the account number.

Entry Number

Specify the entry number. If you have not specified the entry number, then the system will display an override message.

Amount

The system displays the amount for liquidation. However, you can amend this field.

Branch Code

Specify the branch code.

Currency

The system displays the currency details.

35.5 Viewing Dashboard Details

Oracle FLEXCUBE allows you to view the details of the PPC available in the project such as joint venture ratios, balance in the project account, the project lines and their limits for each project line, etc. You can view these details using 'Dashboard Details' screen. To invoke this screen, type 'STDPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows the 'Dashboard Detail' window with the following fields:

Project ID	Customer Id	Account No
Project Name	Customer Name	Account CCY
Project Amount	Available Balance	Current Balance
Project Utilization	Currency	

Navigation tabs: PPC Details (selected), Limit Details, Commitment Details, Loan Details

Table 1 (PPC Details):

Collateral Type	Sequence	Collateral Description	Amount	Currency	Out Standing	Status
-----------------	----------	------------------------	--------	----------	--------------	--------

Table 2 (Party Details):

Party ID	% Share	Currency	Limit	Available
----------	---------	----------	-------	-----------

Exit button is located at the bottom right.

You can view the following details:

- Project ID
- Project Name
- Customer ID
- Customer Name
- Available Balance
- Account Number
- Account Currency
- Project Limit
- Project Utilization
- Current Balance

35.5.1 Viewing PPC Details

You can view the PPC details by clicking on the 'PPC Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows a software interface titled "Dashboard Detail". At the top, there are several input fields for project and customer information: Project ID, Project Name, Project Amount, Project Utilization, Customer Id, Customer Name, Available Balance, and Currency. Below these fields are four tabs: "PPC Details", "Limit Details", "Commitment Details", and "Loan Details". The "PPC Details" tab is selected and active. It contains two data tables, both of which are currently empty. The first table has columns: Collateral Type, Sequence, Collateral Description, Amount, Currency, Out Standing, Status. The second table has columns: Party ID, % Share, Currency, Limit, Available. At the bottom right of the window, there is an "Exit" button.

You can view the following details:

- Collateral Details
 - Collateral Type
 - Sequence
 - Collateral Description
 - Amount
 - Outstanding
 - Status
- Venture Details
 - Party ID
 - % Share
 - Limit CCY
 - Limit
 - Available

35.5.2 Viewing Limit Details

You can view the limit details by clicking on the 'Limit Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows the 'Dashboard Detail' application window. At the top, there are input fields for Project ID, Project Name, Project Amount, Project Utilization, Customer ID, Customer Name, Available Balance, Currency, Account No, Account CCY, and Current Balance. Below these fields are four tabs: PPC Details, Limit Details (selected), Commitment Details, and Loan Details. The main area displays two empty data tables. The first table has columns: Credit Line, Line Serial, Currency, Limit, Utilized, and Paid. The second table has columns: Party ID, % Share, Credit Line, Line Serial, Currency, Limit, Utilized, and Paid. Both tables have a search icon and a 'Go to Page' field. An 'Exit' button is located at the bottom right of the window.

You can view the following details:

- Project Line Details
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid
- Customer Line Details
 - Party ID
 - % Share
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid

35.5.3 Viewing Commitment Details

You can view the commitment details by clicking on the 'Commitment Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows a software window titled "Dashboard Detail". At the top, there are several input fields arranged in a grid:

Project ID	Customer ID	Account No
Project Name	Customer Name	Account CCY
Project Amount	Available Balance	Current Balance
Project Utilization	Currency	

Below these fields are four tabs: "PPC Details", "Limit Details", "Commitment Details" (which is selected and highlighted in blue), and "Loan Details".

Under the "Commitment Details" tab, there is a table with a header row and an empty body. The header row contains the following columns:

<input type="checkbox"/>	Contract Reference	Currency	Amount	Outstanding Amount	Maturity Date
--------------------------	--------------------	----------	--------	--------------------	---------------

At the bottom right of the window, there is an "Exit" button.

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

35.5.4 Viewing Loan Details

You can view the loan details by clicking on the 'Loan Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows a software window titled "Dashboard Detail". At the top, there are several input fields arranged in three columns: Project ID, Project Name, Project Amount, Project Utilization; Customer Id, Customer Name, Available Balance, Currency; and Account No, Account CCY, Current Balance. Below these fields is a tabbed interface with four tabs: "PPC Details", "Limit Details", "Commitment Details", and "Loan Details". The "Loan Details" tab is selected and active. It displays a table with a header row containing the following columns: "Contract Reference", "Currency", "Amount", "Outstanding Amount", and "Maturity Date". The table body is currently empty. Above the table, there is a navigation bar with "1 of 1" and a "Go to Page" field. An "Exit" button is located in the bottom right corner of the window.

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

35.6 Querying Dashboard Details

Oracle FLEXCUBE allows you to query the dashboard details based on the Project ID, Project Name, Customer ID, Customer Name, Account Number. You can view these details using 'Dashboard Summary' screen. To invoke this screen, type 'STSPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Project ID	Project Name	Customer Id	Customer Name	Account No	Account CCY

You can query the record based on the following details:

- Project ID
- Customer ID
- Account Number
- Project Limit
- Project Name
- Customer Name
- Account Currency

You can double-click on a specific record to view the detailed screen.

35.7 Querying Accounting Entries

Oracle FLEXCUBE allows you to view the accounting entry serial number which can be used in PPC liquidation screen for marking a specific credit entry for query. You can view these details using 'Customer Account Transaction Query' screen.

The screen is as shown below:

Contract Reference Number	Entry Serial No	Module Code	Transaction Code	Event Code	Transaction Date	Value
0000011080910001	401460	DE	000	INIT	2008-03-31	200

You can query the record based on the following details:

- Contract Reference Number
- Debit/Credit
- Transaction Code
- Currency
- Event Code
- Module Code
- Value Date
- Transaction Date
- Related Reference
- Related Account

- From Date
- To Date
- Branch Code
- Starting Balance
- Currency
- Debit Credit Balance
- Account Number

Clicking on the 'Query' button, the system displays the transaction details. You can double-click on a specific record to view the detailed screen.

36. Error and Error Codes for Project Financing

36.1 Error and Error Codes

Validation	Error Code	Description
System should not allow entering PPCs if the total # of PPC's already entered exceeds the # allowed	ST-PPC-001	Max limit for number of PPCs exhausted.
Whenever there is a change in the # of PPC's, the system should validate whether the change is an increase or decrease. It should only allow an increase in the # of PPC's	ST-CON003	Decreasing number of PPCs not allowed
At the project maintenance, whenever there is a change in the project amount, the system should validate and only allow an increase in the project amount and not allow a decrease	ST-CON005	Decrease of project amount not allowed
In case of a JV, the total of the % share of individual customers should be 100%	ST-PROJ-009	Total share should be 100%
In case of a JV, each customer should have a separate Liability ID it is operational control. At the project maintenance, each project should have unique Line ID for PPC lines.	ST-PROJ-028	Liability ID already in use
The milestone start date and end date should be validated against that of the project	ST-PROJ-004	The milestone start date/end date should be equal to or within the range of project start and end date

Validation	Error Code	Description
The project status when changed to CLOSED should be allowed only when all PPC's associated with the respective project are in CLOSED status	ST-PROJ-024	OPEN PPC's exist. Project status cannot be closed
In case of auto created lines, system should not allow amendment on these lines	ST-CON012	Amendment of auto-created lines not allowed
The number of milestones cannot exceed the number of PPCs	ST-PROJ-027	Number of milestones cannot be greater than the number of PPCs
The sum of the milestone percentage completion should be 100	ST-PROJ-010	The sum of milestone completion should be 100
PPC end date is different from PPC start date + PPC clearance days. Configurable override	ST-PROJ-031	PPC End Date is different from Project Start Date + PPC Clearance days.

37. Reports

37.1 Introduction

You can generate the following reports:

- List of deleted transactions
- Accounting journal
- Cash flow report
- Balances of future dated transactions
- Current Rates Report
- Account Opening Confirmation
- Account Closing Confirmation
- Activity Journal Report
- Core Exception Report

37.2 List of Deleted Transactions

This report lists out the deleted transaction details pertaining to each product under each module pertaining to every user. You can invoke this screen by typing 'ACRDLTXN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Deleted Transactions Listing' window. It features a blue title bar and a white background. On the left side, there are four sections: 'Module', 'Products', 'User', and 'Batch'. Each section has a label and a set of radio buttons. 'Module' has 'Single' selected and 'All' unselected. 'Products' has 'Single' selected and 'All' unselected. 'User' has 'Single' selected and 'All' unselected. 'Batch' has 'From' and 'To' input fields with dropdown arrows. On the right side, there is a 'Transactions' section with radio buttons for 'All' (selected), 'This Branch', 'Posted To Other Branch', and 'This branch acted as bridge'. Below this is a 'Print Copies' checkbox. At the bottom right, there are 'OK' and 'Exit' buttons.

Specify the following details.

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch
- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the date from which the transactions need to be considered for report generation.

To

Specify the date until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Click 'OK' to generate the report.

37.2.1 Contents of Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the report

This report is sorted module-wise. For every module the following details are displayed.

- Module
- Product
- User ID

The following transaction details are displayed.

Reference No	This is the reference number of the account for which deleted transaction details is being reported.
Ac Br	This is the branch where the account resides.
Account Number	This is the account number.
Ccy	This is the currency of the transaction.
Dr/Cr	This indicates the nature of the transaction – debit or credit.
Trn Code	This is the transaction code.
Account description	This is the account description.
Fcy Amount	This is the transaction amount in foreign currency.
Trn Description	This is the transaction description.
Narrative	This is the narrative text associated with the transaction.
Instrument No	This is the instrument number linked to the transaction.
Total Debits	Total amount debited under the product

Total Credits	Total amount credited under the product
User ID	This is the user ID of the user who entered the transaction.

37.3 Accounting Journal

This report gives details of every journal entry transaction. You can invoke this screen by typing 'ACRJRNAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details:

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch
- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the date from which the transactions need to be considered for report generation.

To

Specify the date until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Position Entries

Check this box to indicate that the report needs to cover position accounting entries.

Report Date

Specify the date as on which the report needs to be generated.

Click 'OK' to generate the report.

37.3.1 Contents of Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the report

The report is sorted by modules. Under every module, it lists out product-wise transaction details.

The following transaction details are displayed.

Product	This is the product code of the transaction.
User Id	This is the user ID of the user who entered the transaction.
Reference No	This is the transaction reference number.
Ac Br	This is the account branch.
Account Number	This is the account number.
Ccy	This is the currency of the transaction.
Dr/Cr	This is the nature of the transaction – either debit or credit.
Trn Code	This is the transaction code while posting the journal entry.
Description	This is the transaction description.
Status	Status of the transaction.
Value Date	This is the value date of the transaction.
Account Description	This is the description of the account.
Event	This is the event triggered on the transaction.
Fcy Amount	This is the transaction amount in a foreign currency
Exch Rate	This is the exchange rate used if the transaction is in any other currency.
Lcy Amount	This is the transaction amount in local currency.
Auth ID	This is the user ID of the user who authorized the transaction.
Total Debits	This is the total amount debited under the product.
Total Credits	This is the total amount credited under the product.

37.4 Cash Flow Report

The 'Cash flow report' gives details of the cash flow by accounts or by account class. The report contains details of the Account Number or Account Class, and the list of Accounts or Account Classes. You can invoke this screen by typing 'ACRPCASH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a dialog box titled "Cash flow report". It has a "Report Name" field with a dropdown arrow. Under "Report Type", the "Summary" radio button is selected. The "Include Call - Notice Contracts" section has two unchecked checkboxes: "Notice Contracts" and "Call Contracts". The "Select Account Class/Account" section has the "Account Class" radio button selected. Below this are two empty list boxes, one labeled "Account Class" and one labeled "Account". At the bottom right, there are "Ok" and "Exit" buttons.

Specify the following details.

Report Name

Specify the name of the report. The option list provided displays all valid reports maintained in the system. You can select the appropriate one.

Report Type

Indicate whether the report should be a detailed report or a summary report.

Notice Contracts

Check this box to indicate that notice contracts should be covered in the report.

Call Contracts

Check this box to indicate that call contracts should be covered in the report.

Select Account Class/Account

Indicate whether the reports should be generated based on account class or account.

All/Specific Records

Indicate whether the reports should be generated for all records in an account class/account or for specific records.

Account Class

If you have indicated 'Account Class' as the basis for report generation, specify the account classes that should be considered. Click add icon to add rows. You can select a valid account class from the adjoining option list.

Account

If you have indicated 'Account' as the basis for report generation, specify the accounts that should be considered. Click add icon to add rows. You can select a valid account from the adjoining option list.

Click 'OK' to generate the report.

37.4.1 Contents of Report

The contents of the cash flow report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report and the date and time at which it was generated.

Body of the report

The report is sorted on the currency of the cash flow.

Contract Reference Number	This is the reference number of the account for which transaction details is being reported.
Due Date	When the maturity of a deposit is being reported the Due Date will indicate the Maturity date. For a Call contract this will be Call. Similarly for a notice contract this will be Notice.
Amount In	This is the amount debited into the particular account for the particular period.
Amount Out	This is the amount credited from the account during the specified period.

37.4.2 Cash Flow (Summary) Report

The Cash Flow summary report summarizes the details of cash flow for particular Accounts or Account Classes.

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report and the date and time at which it was generated.


Body of the report

The report is sorted on the currency of the cash flow for different account classes and their accounts. The following details are displayed.

Amount In	This is the amount debited into the particular account for the specific period
Amount Out	This is the amount credited from the account during the specified period
Net Flow	This is the net amount available in the account for the specified period

37.5 Future Dated Account Balance Report

This report gives balances of future dated transactions. You can invoke the screen by typing 'ACRPFVBL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.


Body of the report

The following details are displayed.

Date	This gives the date for which the report is generated.
Reference No	This is the reference number for the report.
Inflow	This is the inflow amount.
Outflow	This is the outflow amount.
Balance	This is the available balance.
Currency	This is the type of currency.
Customer	This is the name of the customer.
Account	This is the account number of the customer.
Account Class	This is the account class.
Opening	This is the opening balance.

37.6 Current Rates Report

This report gives details on rates for currency pairs. You can invoke the screen by typing 'CYRTCURR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Specify the following details.

Selection

Indicate whether the report should be generated for all currency pairs or for a given currency pair.

Currency 1

If you have chosen, 'Selected Currency Pair', then specify the first currency that forms a pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Currency 2

If you have chosen, 'Selected Currency Pair', then specify the second currency that forms the pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Click 'OK' to generate the report.

37.6.1 Contents of Report

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report and reporting options.


Body of the report

The report is sorted by currency pairs. The following details are displayed.

Currency Pair	This gives the currency pairs for which rate report has been generated.
Quotation	This indicates the quotation type – either direct or indirect.
No. of Units	This indicates the number of units of one currency being quoted against the other.
Rate Type	This is the rate type.
Mid Rate	This is the mid rate used for conversion.
Buy Rate	This is the buy rate used for conversion.
Sale Rate	This is the sell rate used for conversion.

37.7 Rate History Report

This report gives details on history of rates for currency pairs. You can invoke the screen by typing 'CYRTHIST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report, reporting options, currency pair, from date and to date .


Body of the report

The report is sorted by currency pairs. The following details are displayed.

Currency Pair	This gives the currency pairs for which rate report has been generated.
Quotation	This indicates the quotation type – either direct or indirect.
No of Units	This indicates the number of units of one currency being quoted against the other.
Rate Type	This is the rate type.
Date	The effective date of the rates applied.
Mid Rate	This is the mid rate used for conversion.
Buy Rate	This is the buy rate used for conversion.
Sale Rate	This is the sell rate used for conversion.

37.8 Account Opening Confirmation

Account opening confirmation report provides information on the details of the customer account number and first account holder details. To invoke the screen, type 'CSRPACKO' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



37.8.1 Contents of the Report

The contents of account opening confirmation have been discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, date and time at which it was generated, the modules covered in the report and customer number of the account holder for whom the report is being generated.

Body


You can find the following details in the body of the report:

Customer Account Number	The account number of the customer
Client Account Number	The account number of the client.
First Account Holder Details	Name, Address, Date of Birth, Telephone, E-mail, FAX, Account Opening Date and alternate Account Number of the first account holder

37.9 Account Closing Confirmation

This report gives details about closing confirmation of an account in 'Account Closing Confirmation' screen. To invoke this screen, type 'CSR PACCC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:



37.9.1 Contents of Report

The contents of account closing confirmation have been discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report and customer number of the account holder for whom the report is being generated.


Body

You can find the following details in the body of the report:

Client Number	The account number of the client
---------------	----------------------------------

37.10 Activity Journal Report

This report gives details about activity journal in 'Core Activity Journal' screen. To invoke this screen, type 'CSRFACTJ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



37.10.1 Contents of Report

The contents of account activity journal have been discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:


Module	The module for which the report is being generated
Product Type	The type of product for which the report is being generated
Contract Ref No	The reference number of the contract being reported
Counter Party No	The CIF ID of the customer involved
Counter Party Name	This is the name of the customer involved
User Def. Status	The status if the user defined elements
Event Date	The date on which the event took place

Seq. No	The sequence number of the event
Event Description	The description of the event
Contract Status	The status of the contract i.e., active, closed etc.
Maker ID	The identification number of the maker
Checker ID	the identification number of the checker
Reversed Seq. No.	The reversed sequence number

37.11 Core Exception Report

This report gives details about core exception in 'Core Exception' screen. To invoke this screen, type 'CSRPEXCP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:



37.11.1 Contents of Report

The contents of core exception have been discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:

Module	The module for which the report is being generated
Contract Ref No	The reference number of the contract being reported
Counter Party	The name of the counter party
Counter Party Name	The name of the counter party involved
Date	The branch date
Event Description	The description of the event
Exception	The description about the exception

37.12 Uncollected Funds Report

This report gives details of all the uncollected funds. You can invoke this screen by typing 'ACRUNCOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Uncollected Funds Print". The window contains the following elements:

- Accounts:** A radio button group with "All" selected and "One" unselected.
- Date Option:** A radio button group with "Present Date" selected and "Between Dates" unselected.
- Account:** A text input field with a dropdown arrow icon.
- From Date:** A text input field with a calendar icon.
- To Date:** A text input field with a calendar icon.
- Buttons:** "Ok" and "Exit" buttons at the bottom right.

Specify the following details.

Accounts

Select the type of account.

Account

Specify the account from the option list.

Date option

Select either Present Date or Between Dates option.

From Date

Specify the From date.

To Date

Specify the To date.

37.12.1 Contents of Report*Header*

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.


Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

Account	This is the account for which transaction details is being reported
Trn Refno	This is the reference number of the account for which transaction details is being reported
Amount	This is the amount debited into the particular account for the particular period
Total Amount	This is the total amount debited into the particular account during the specified period

37.13 Revaluation Report

This report gives details of the memo revaluation funds. You can invoke this screen by typing 'ACRREVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

**Memo or Normal**

Specify the type of account revaluation report.

37.13.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.


Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

Currency	This is the currency for which transaction details is being reported
Revaluation Rate	This is the revaluation rate
Account	This is the account for which transaction details is being reported
Description	This is the description provided
Account Revalued	This is the revalued account
Account Balance	This indicated the account balance
Lcy Eq (before reval)	This indicates the local currency before revaluation
Lcy Eq (after reval)	This indicates the local currency after revaluation
Profit/ Loss	This is the profit or loss incurred
Profit/ Loss Amount	This is the profit or loss amount
Pnl Account	This is the profit or loss account
Currency	This is the currency for which transaction details is being reported
Rate	This is the revaluation rate
Category	This is the category

37.14 Accounts Movement Report

This report gives details of the movement of the accounts for that particular day. You can invoke this screen by typing 'ACRPMOVE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a dialog box titled "Accounts Movement Report". It contains several input fields and radio buttons. On the left, there are two date pickers labeled "From Date" and "To Date". Below them, under the heading "Single Account", are two more pickers: "Account Number" and "Currency". On the right side, there are two groups of radio buttons. The first group, under "Account Selection", has "Value Dated" (unselected) and "Booking Dated" (selected). The second group has "Single Account" (unselected) and "All Accounts" (selected). At the bottom right, there are "Ok" and "Exit" buttons.

From Date

Specify the From Date from the option list.

To Date

Specify the From Date from the option list.

Account Number

Specify the account number from the option list.

Currency

Specify the currency from the option list.

Account Selection

Specify the type of account selection.

37.14.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report


The details of the uncollected funds that would be displayed in the report are as follows:

Trn Date	This is the transaction date
Trn Refno	This is the reference number of the account for which transaction details is being reported
Value Date	This is the value date on which transaction details is being reported
Fcy Amount	This is the Foreign Currency debited into the particular account for the particular period
Rate	This is the revaluation rate
Lcy Amount	This is the Local Currency debited into the particular account for the particular period

37.15 Customer Details Report

This report gives details of the customer and you can generate this report using the 'Customer Details' screen.

You can invoke this screen by typing 'STRCIF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



37.15.1 Contents of Report

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer information details that would be displayed in the report are as follows:

Customer	Customer Identification Number of the customer
Customer Name	Customer name
Address line	Displays the address of the customer.
Country	The country the customer belongs to.
Nationality	The nationality of the customer.
Type	Type of the customer (individual or Corporate or Bank).
Unique ID Name	Displays the customer's unique id name.
Unique ID Value	Displays the customer's unique id value.
Creation Date	Displays the date of customer's number creation.
Input By	The Login ID of the user that created the customer record.
Input Date	The date the customer record was created.
Auth By	The Login ID of the user that has authorized the record.
Auth Date	The date of the authorization.
Mod No	Displays the number of times the record was modified.
Auth Stat	Displays the current status of the customer record.
Record	Displays the record status.
Exposure Country	Displays the exposure country details.

Frozen	Displays the frozen status of the customer's account.
Local Branch	Displays the customer's local branch details.
Whereabouts Unknown	Gives the customer's details regarding the whereabouts.
Deceased	Indicates whether the customer is fit or deceased.
Short Name	Customer's abbreviated name.
Liability	This is the customer Liability ID number for which credit facility granted to the customer.
Language	Language.
Category	Category of the customer of the bank.

37.16 Customer Accounts Report

This report gives details of the customer account and you can generate this report using the 'Customer Accounts' screen.

You can invoke this screen by typing 'STRCUSAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

37.16.1 Contents of Report

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer accounts details that would be displayed in the report are as follows:

Customer Account No.	Details about customer account Number
----------------------	---------------------------------------

Account Class	Details about account class
Ac Desc	Account Description
Ac open date	The opening date of the account.
Ac Stat Dormant	The account status as dormant
Ac Stat Frozen	Account status as frozen.
Ac Stat No Cr	Gives the credit account number status.
Ac Stat No Dr	Gives the debit account number status.
Ac Stat Stop Pay	Gives the accounts stop pay status.
Ac Stmt Cycle	Gives the account statement cycle.
Ac Stmt Day	Gives the account statement day.
Ac Stmt Type	Gives account statement type.
Alt Ac No	Gives an alternative account number.
Branch Code	Gives the branch code.
Ccy	Currency
Cust No.	Gives customer number.
Nominee1	Gives the first nominee details
Nominee2	Gives the second nominee details
Account Type	Gives the account type.
Dr Gl	Gives all debit balances within a specific account class
Cr Gl	Gives all credit balances within a specific account class.
Dr Ho Line	In this, all accounts belonging to account class will report, if they move to the status being defined.
Cr Ho Line	In this, all accounts belonging to account class will report, if they move to the status being defined.

Dr Cb Line	This is a GL to which all debit accounts belonging to an account class should report to.
Cr Cb Line	This is a GL to which all credit accounts belonging to an account class should report to.
Atm Facility	Availability of ATM facility.
Cheque Book Facility	Availability of cheque book facility.
Passbook Facility	Availability of passbook facility.
Previous Statement Date	Gives the date of the previous statement.
Previous Statement Balance	Gives the balance of the previous statement.
Previous Statement No.	Gives the number of the previous statement
Tod Limit	The temporary overdraft limit facility granted to the customer account
Sublimit	It the overdraft facility maximum permitted to this account associated and tracked against the line id maintained for the liability.
Tod Limit Start Date	The start date for the temporary overdraft facility
Tod Limit End Date	The end date for the temporary overdraft facility.
Uncoll Funds Limit	The funds hit the account which are debited / credited to the account with effect from the mentioned value days
Line ID	The line code is associated with the liability ID against which the overdraft facility is being tracked.
Tanked Status	It is the status of the transaction that hit the account in a specific branch once the branch is marked for EOTI.
Account Balance	Gives the total account balance
Maker ID	The identification number of the maker
Maker Dt Stamp	This is the date on which the contract was uploaded.
Checker ID	This is the Login ID of the user who authorized the product.
Checker Date Stamp	This is the date on which the product was authorized.

Mod No.	Displays the number of times the record was modified.
Record Stat	Displays the current status of the external account record.
Auth Stat.	Displays the current authorization status of the record.

38. Screen Glossary

38.1 Function ID List

The following table lists the function id and the function description of the screens covered as part of this User Manual.

Function ID	Function Description
ACDIBMNT	Inter Branch Parameters Maintenance
ACRDLTXN	Deleted Transactions Listing
ACRJRNAL	Accounting Journal
ACRPCASH	Cash Flow Report
ACRPFVBL	Future Dated Account Balances Report
ACRPMOVE	Accounts Movement Report
ACRREVAL	Account Revaluation Report
ACRUNCOL	Uncollected Funds Print
CFDCUMRG	Customer Spread Maintenance
CFDFLTRI	LD MM Floating Rate Input
CSDACRHM	Branch level Role To Head Mapping
CSDAMLCG	AML Customer Group Maintenance
CSDAMLLM	Limit Codes Maintenance
CSDAMLPC	AML Product Categories Maintenance
CSDDEMAN	Denomination Details
CSDDEVDT	Developer Maintenance
CSDDEVPR	Developer Project Maintenance
CSDPLMNT	Product Transaction Limits Maintenance
CSDPXMNT	Product Limits Maintenance
CSDRAMDN	Ramadan Day Maintenance
CSDRTTMT	Rate Template

Function ID	Function Description
CSDSEQGN	Sequence Generation Input
CSRPACKO	Customer Account Opening Confirmation
CSRFACTJ	Core Activity Journal
CSRPEXCP	Core Exception
CSSACRHM	Branch level Role To Head Mapping Summary
CSSDEVDT	Developer Maintenance Summary
CSSDEVPR	Developer Project Maintenance Summary
CYDCDEFN	Currency Definition
CYDCPAIR	Currency Pair Maintenance
CYDCRTYP	Currency Rate Type Maintenance
CYDCUSPR	Customer Currency Spread Maintenance
CYDRATES	Currency Exchange Rates Input
CYRTCURR	Currency Rates
CYRTHIST	Currency Rate History Report
CYSRATES	Currency Exchange Rates View
FTDVDSPR	Value Date Spread Maintenance
IADIBMNT	Fund Inter Branch Parameters Detailed
ISDINSTR	Settlement Instructions Maintenance
LMDTYPES	Limit Types
STDAMTRN	Amount Text Maintenance
STDBANKP	Bank Parameters Maintenance
STDBRANC	Branch Parameters Maintenance
STDBREST	Batch Restriction Maintenance
STDCSNET	Netting Group Batch Processing
STDDATES	System Dates Maintenance
STDDEALR	Dealer Maintenance

Function ID	Function Description
STDNETGR	Netting Group Maintenance
STDNETQY	Netting Batch Query
STDPJDSH	Dashboard Detail
STDPJMNT	Project Detail and Maintenance
STDPPCLQ	PPC Liquidation
STDPPCMN	PPC Maintenance
STDTRNCD	Transaction Code Maintenance
STDTCYCL	Tax Cycle Maintenance
STRCIF	Customer Details
STRCUSAC	Customer Accounts
STSPJDSH	Dashboard Summary
STDTRNTX	Transaction Tax Maintenance
STDRACBK	Block Reason Code Maintenance
CYDIDXRT	Index Rates Input
STDPATEM	Packet Template Maintenance
STSPATEM	Packet Template Maintenance Summary
STDPAQUT	Packet Creation
STSPAQUT	Packet Creation Summary
SMDPTMT	Department Maintenance
DEDTPREF	Till Preference Maintenance
MSDADVSQ	Advice Sequence Maintenance
STDNTCHG	Notary Charge Maintenance
CYDIDXCD	Index Maintenance
CYDXCDRT	CPI Rate Maintenance



Core Services
[November] [2016]
Version 11.3.83.03.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © 2005, 2016, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.