

FLEXCUBE Enterprise Limits and Collateral Management
User Guide

Oracle FLEXCUBE Universal Banking

Release 12.87.06.0.0

Part No. F22925-01

May 2020

FLEXCUBE Enterprise Limits and Collateral Management User Guide
November 2019
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India
Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © 2007, 2019, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction.....	1-1
1.2 Audience.....	1-1
1.3 Documentation Accessibility.....	1-1
1.4 Organization	1-1
1.5 Acronyms and Abbreviations.....	1-2
1.6 Related Documents	1-3
1.7 Glossary of Icons.....	1-3
2. Limits & Collaterals	2-1
2.1 Introduction.....	2-1
2.2 Maintaining Credit Score	2-1
2.3 Maintaining Agency Details for Credit Rating.....	2-2
2.4 Maintaining User Defined Status	2-3
2.5 Liability Maintenance	2-3
2.5.1 <i>Specifying Liability Scores</i>	2-7
2.5.2 <i>Specifying Liability Credit Rating</i>	2-8
2.6 Maintaining Customer to Liability Link.....	2-8
2.6.1 <i>Viewing Customer to Liability Link Summary</i>	2-10
2.7 Covenant Maintenance.....	2-11
2.8 Collateral Types Maintenance	2-12
2.9 Collateral Category Maintenance	2-13
2.9.1 <i>Maintaining Covenant Details for Collateral Category</i>	2-15
2.10 Issuer Maintenance	2-16
2.11 Securities Maintenance	2-18
2.12 Collaterals Maintenance	2-21
2.12.1 <i>Specifying Details for Market Value Based Type</i>	2-25
2.12.2 <i>Specifying Details for Guarantee Based Type</i>	2-26
2.12.3 <i>Specifying the Insurance Details</i>	2-26
2.12.4 <i>Specifying Covenant Details</i>	2-28
2.12.5 <i>Specifying Shared Details</i>	2-29
2.12.6 <i>Linking Contracts as Collaterals</i>	2-30
2.12.7 <i>Maintaining UDE Values</i>	2-32
2.12.8 <i>Maintaining Source Restrictions</i>	2-35
2.12.9 <i>Maintaining Haircut Schedules</i>	2-35
2.13 Collateral Pool Maintenance.....	2-36
2.13.1 <i>Creating Collateral Pool Linkages</i>	2-38
2.14 Facilities Maintenance	2-40
2.14.1 <i>Maintaining Limit Schedules</i>	2-49
2.14.2 <i>Specifying Covenant Details</i>	2-51
2.14.3 <i>Maintaining Value Dates Details</i>	2-52
2.14.4 <i>Tracing Exposure for a Line</i>	2-52
2.14.5 <i>Capturing UDE Details</i>	2-54
2.14.6 <i>Maintaining Collateral Pool Linkages</i>	2-59
2.14.7 <i>Maintaining Restrictions for a Line</i>	2-60

2.14.8	<i>Defining Tenor based Restrictions</i>	2-64
2.14.9	<i>Maintaining Source Restrictions</i>	2-67
2.14.10	<i>Maintaining Mandate Details</i>	2-68
2.14.11	<i>Including Netting Amount in Facility's Netting Contribution</i>	2-68
2.14.12	<i>Viewing Previous Credit Limit Changes</i>	2-69
2.14.13	<i>Specifying Power Pocket Limit</i>	2-72
2.15	Track Exposure Maintenance	2-73
2.15.1	<i>Maintaining Value Date Exposure Details</i>	2-75
2.16	Ear Marking Maintenance	2-75
2.17	Global Block Exposure Maintenance	2-77
2.17.1	<i>Additional Information</i>	2-78
2.18	Exception Queue Maintenance	2-78
2.19	Exception Queue Slab Maintenance	2-79
2.20	Limits & Collaterals Parameter Details	2-81
2.21	Facilities Amount Transfer Maintenance	2-84
2.22	Force Collateral Revaluation	2-86
2.23	Multi Authorization Maintenance	2-86
2.24	Dual Authorization of Utilization Transaction	2-89
2.25	Merging Liabilities	2-90
2.25.1	<i>Liability Merger Maintenance</i>	2-90
2.25.2	<i>Liability Merger Process</i>	2-91
2.26	Maintaining Future Dated Amendment or Renewal of Facility	2-92
3.	ELCM Data Replication	3-1
3.1	Introduction	3-1
3.2	Online Data Replication	3-1
3.2.1	<i>Replicating Data from Oracle FLEXCUBE to ELCM</i>	3-2
3.2.2	<i>Processing ELCM Data Replication</i>	3-2
3.2.3	<i>Replicating Data from ELCM to Oracle FLEXCUBE</i>	3-3
3.2.4	<i>Processing Oracle FLEXCUBE Data Replication</i>	3-4
3.3	Data Replication Process	3-5
3.3.1	<i>Automatic Data Replication</i>	3-6
3.3.2	<i>Viewing Successfully Replicated Records</i>	3-6
3.4	Batch Replication	3-7
3.4.1	<i>Replicating Data from Oracle FLEXCUBE to ELCM</i>	3-7
3.4.2	<i>Replicating Data from ELCM to Oracle FLEXCUBE</i>	3-7
4.	Queries	4-1
4.1	Introduction	4-1
4.2	Liabilities Query	4-1
4.3	Liability History	4-3
4.4	Utilization Transaction Query	4-4
4.5	Covenants Queries	4-5
5.	Reports	5-1
5.1	Introduction	5-1
5.2	Generating Reports	5-1
5.3	Generating Covenant History Reports	5-1
5.3.1	<i>Contents of the Report</i>	5-2
5.4	Collateral Review Report	5-3
5.4.1	<i>Contents of the Report</i>	5-3
5.5	Ear Mark Transaction Inner Limit Report	5-4

5.5.1	Contents of the Report	5-4
5.6	Expired Limits Report	5-5
5.6.1	Contents of the Report	5-5
5.7	Foreign Exchange Clean Risk Report	5-6
5.8	Bank wide Clean Risk Tracking Report	5-7
5.9	Country Exposure Report	5-9
5.10	Collaterals Details	5-11
5.11	Collateral Utilization of Collateral Party Report	5-13
5.12	Collateral Utilization of Credit Lines Report	5-15
5.13	Credit Movements Report	5-17
5.14	Exposure Details	5-19
5.15	Issuer Exposure Report by Collateral Type	5-21
5.16	Issuer Details Report	5-23
5.17	Liability Summary Report	5-25
5.18	Limit Details Report	5-26
5.19	Line Details Report	5-28
5.20	Line Summary Rep	5-30
5.21	Movements to Non-Revolving Lines	5-32
5.22	Pool Linkage Report	5-34
5.23	Pool Utilization Report	5-36
5.24	Overdrawn Lines	5-38
5.25	Product Exposure Report	5-40
5.26	Securities Details Report	5-43
5.27	Limits – Tenor wise Details Report	5-44
5.27.1	Contents of the Report	5-45
5.28	Utilization Report	5-47
5.29	Issuer Exposure by Security Report	5-49
5.30	Limit Tenor Restriction Details Report	5-51
5.31	Date Wise Utilisations Report	5-53
5.32	Credit Lines by Maturity Dates	5-54
5.33	Country Utilization Report	5-57
5.33.1	Contents of the Report	5-57
5.34	Credit Rating Report	5-59
5.34.1	Contents of the Report	5-59
6.	Annexure 1 - Utilization Transactions	6-1
6.1	Introduction	6-1
6.2	New Utilization	6-1
6.2.1	Input Utilization	6-1
6.2.2	Validations for a New Utilization Process	6-4
6.2.3	Authorize Utilization	6-6
6.2.4	Delete Utilization	6-6
6.2.5	Technical Undo (Special Delete)	6-7
6.3	Increase/Decrease Utilization	6-7
6.3.1	Validations for Modify Utilization Process	6-8
6.4	Alter Utilization	6-9
6.4.1	Input Alter Utilization	6-9
6.5	Reverse Utilization	6-12
6.5.1	Input Reverse Utilization	6-12
6.6	Set Balance of Utilization Transaction	6-13
6.7	Query Utilization	6-15

6.8	Mature Utilization Transaction	6-16
6.9	Utilization Transaction Screen	6-17
6.10	Reconciliation of Utilization Transactions	6-19
6.11	Increasing/Decreasing Utilizations	6-20
6.12	Linking an Utilization Transaction to a Facility.....	6-21
	6.12.1 Collateral Pool Utilization Transaction Process.....	6-23
	6.12.2 Utilization Transaction Status	6-23
7.	Annexure 2 - Value Dated Facility	7-1
7.1	Introduction.....	7-1
7.2	Value Date Based Facility Maintenance.....	7-1
7.3	Value Date Based Utilization Processing	7-2
	7.3.1 Back Valued Transactions.....	7-2
	7.3.2 EOD Processing.....	7-2
8.	Annexure 3 – Revaluation	8-1
8.1	Introduction.....	8-1
8.2	Currency Revaluation	8-1
	8.2.1 Facility Currency and Utilization Currency.....	8-1
	8.2.2 Facility Currency and Collateral Currency	8-3
8.3	Collateral Revaluation	8-4
	8.3.1 Collateral Revaluation of Market Based Securities	8-5
	8.3.2 Collateral Revaluation of Non-Market Based Securities.....	8-8
9.	Annexure 4 - Gateway Processes & Interfaces	9-1
9.1	Introduction.....	9-1
9.2	Gateway Online Process	9-1
	9.2.1 Maintenance Transactions	9-1
	9.2.2 Utilization Transactions	9-2
	9.2.3 Batch Process	9-2
	9.2.4 Reprocessing Locked Online Transactions.....	9-2
	9.2.5 Technical undo (Functional Rollback)	9-2
9.3	Gateway Batch Process	9-2
	9.3.1 Batch Inbound Process	9-3
	9.3.2 Batch Outbound Process.....	9-4
9.4	Interfaces.....	9-4
10.	Function ID Glossary	10-1

1. Preface

1.1 Introduction

This manual is designed to help you to quickly get acquainted with the Oracle FLEXCUBE Enterprise Limits and Collateral Management (hereafter referred to as Oracle FLEXCUBE ELCM) system. It provides an overview and takes you through the various steps involved setting up and maintaining the Oracle FLEXCUBE ELCM system.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office data entry clerk	Input functions for funds
Back office managers/ officers	Authorization functions
Product Managers	Product definition and authorization
End of day operators	Processing during end of day/ beginning of day

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This manual is organized into the following chapters:

Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Limits & Collaterals</i> explains a series of maintenance options facilitated by Oracle FLEXCUBE for Enterprise Limits and Collateral Management.
Chapter 3	<i>ELCM Data Replication</i> describes the process of replicating data between ELCM and Oracle FLEXCUBE which are hosted in two separate database, using the Replication Mode Maintenance options.
Chapter 4	<i>Queries</i> explains about the query functions and helps you to query records on Liabilities, Transactions, Collateral Covenants, and so on.

Chapter 5	<i>Reports</i> provide a list of reports that can be generated in this module and also explains their contents.
Chapter 6	<i>Annexure 1 - Utilization Transactions</i> explains how to maintain all utilization transactions in Oracle FLEXCUBE ELCM.
Chapter 7	<i>Annexure 2 - Value Dated Facility</i> describes how to track and maintain all facility utilizations based on the value date of the transaction.
Chapter 8	<i>Annexure 3 – Revaluation</i> describes how to maintain the fluctuating exchange rates of marketable securities such as currency and collateral, over a period of time.
Chapter 9	<i>Annexure 4 - Gateway Processes & Interfaces</i> details on how an external system can be integrated with Oracle FLEXCUBE ELCM system for communication.
Chapter 10	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Acronyms and Abbreviations

You may find the following acronyms/abbreviations in this manual.

UI	User Interface
ELCM	Enterprise Limits and Collateral Management
FCUBS	Oracle FLEXCUBE Universal Banking Solution
GW	Gateway
HTTP	Hyper Text Transfer Protocol
XML	eXtensible Mark-up Language
XSD	XML Schema Definition
XSLT	eXtensible Stylesheet Language Transformations
BPEL	Business Process Execution Language
SMS	Security Services
ID	Identification Number
PK	Primary Key
RDBMS	Relational Data Base Management System
VD	Value Date
Mark EOTI	Mark End of Transaction Input
Mark TI	Mark Transaction Input
TD	Term Deposits

CIF	Customer Information File
-----	---------------------------

1.6 Related Documents

- The Procedures User Manual

1.7 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Limits & Collaterals

2.1 Introduction

The functions and actions provided by the Oracle FLEXCUBE Enterprise Limits and Collateral Management are explained below. All functions explained below, come under Limits & Collaterals in the Menu Browser.

2.2 Maintaining Credit Score

Before creating a Liability in the system, your Bank will assess the credit score of individual liabilities. You can create and maintain Credit Score names in the 'Credit Score Maintenance' screen. These credit scores can later be linked to Liability Maintenance (GEDMLIAB) for assessing the liability score.

Credit Score Maintenance is a bank level maintenance and will be accessible in all Branches. You can invoke the 'Credit Score Maintenance' screen by typing 'GEDCRSCR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Credit Score Maintenance". At the top left, there are icons for "New" and "Enter Query". Below these are two text input fields: "Score Name *" and "Score Description". At the bottom of the window, there is a "Fields" section with a table-like structure. The fields listed are: Maker, Date Time, Mod No, Record Status, Checker, Date Time, and Authorization Status. An "Exit" button is located in the bottom right corner of the window.

Enter the following details:

Score Name

Specify a unique credit score name here.

Score Description

Give a brief description of the score.

Note

This is only for information and not for processing.

2.3 Maintaining Agency Details for Credit Rating

You can maintain details regarding credit rating agencies in the 'Credit Rating Agency Maintenance' screen. Using this maintenance you can record the credit rating codes published by each credit rating agency. This can later be linked to Liability Maintenance (GEDMLIAB) for specifying customer rating published by an agency.

You can invoke the 'Credit Rating Agency Maintenance' screen by typing 'GEDCREDIT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Credit Rating Agency Maintenance' application window. At the top, there are buttons for 'New' and 'Enter Query'. Below these are two text input fields: 'Agency Name *' and 'Agency Description'. The main area is titled 'Credit Rating Details' and contains a table with two columns: 'Credit Rating *' and 'Credit Rating Description'. The table is currently empty. At the bottom of the window, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Enter the following details:

Agency Name

Specify the name of the credit rating agency here.

Agency Description

Give a brief description of the credit rating agency here.

Credit Rating Details

Specify the following here:

Credit Rating

Specify the unique Credit Rating code/ID.

Credit Rating Description

Give a brief description of the Credit Rating code/ID.

Note

This is only for information and not for processing.

2.4 Maintaining User Defined Status

You may wish to specify certain statuses for liabilities such as Normal, Partially Defaulting, Defaulting etc. Such statuses can be maintained first in the 'User Define Status Maintenance' screen. You can name and describe statuses here. This can later be linked to Liability Maintenance (GEDMLIAB) & Facilities Maintenance (GEDFACTL) for choosing the status of the liability or facility respectively.

You can invoke the 'User Define Status Maintenance' screen by typing 'GEDUDFNS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Enter the following details:

User Defined Status

Provide a name/ID for the status here.

Description

Give a brief description of the status.


2.5 Liability Maintenance

Every customer of your bank who enjoys credit facilities should be assigned or linked to a Liability Code category. Several customers can be linked to the same Liability Code. Liability linkage can be in two ways.

- Single Liability linked to multiple customers (i.e. a Customer Group)
- Single Liability linked to only one customer


Single Liability Linked To Multiple Customers

Here multiple customers are linked to same the Liability Code and all restrictions/facilities maintained at liability level are shared to all the customers.



Single Liability Linked To Only One Customer

Here a liability is linked to only one customer and all restrictions/facilities maintained at liability level are applicable to that customer alone.



Liability with Single Customer

You can create or modify the Liabilities using the 'Liability Maintenance' screen.

You can invoke the 'Liability Maintenance' screen by typing 'GEDMLIAB' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Liability Maintenance' application window. The title bar reads 'Liability Maintenance'. Below the title bar, there are two buttons: 'New' and 'Enter Query'. The main area contains a list of fields for data entry, each with a corresponding input box. The fields are: Liability No *, Liability Name *, Main Liability Number, Main Liability Name, Liability Branch *, Liability Currency *, Overall Limit, Utilization Amount, Revision Date, Credit Rating, Overall Score, User Defined Status, Liability Category, Liability Clean Risk Limit, Secondary Clean Risk Limit, Secondary PSTL Risk Limit, Access Group Code *, UnAdvised (checkbox), Netting Required (checkbox), and User Reference. At the bottom of the window, there is a status bar with the text 'Score | Credit Rating | Fields'. Below the status bar, there are several fields: Maker, Checker, Date Time, Date Time, Mod No, Record Status, Authorization Status, and an 'Exit' button.

Liability No

Specify the Liability Number. If the Liability Number is customer group then all customers under this group should have same Liability Number.

Liability Name

Specify the Liability Name here. A maximum of 35 characters are allowed in this field.

Main Liability Number

Specify the main liability number. The adjoining option list displays a list of liability numbers maintained in the system. Choose the appropriate one.

The child liability's overall limit amount should not exceed the parent liability's overall limit amount.

During Utilization transaction, the utilization is tracked for both the specified Liability and also the parent Liability to which it is linked.

Main Liability Name

Specify the main liability name.

Liability Branch

Specify the branch in which liability is associated.

Liability Currency

Specify the currency with which the liability is associated. If Liability currency is different from Limit currency specified in Global Exposure Parameter then the Liability amount is converted to the limit currency.

System displays an override message, if the LCY equivalent of overall limit of the customer liability is greater than 35000 USD.

Overall limit amount \$1 of the customer liability exceeds the maintained Internal Lending Limit Equivalent Amount \$2.

Note

You can modify the Liability Currency after authorization if:

- There are no lines, collaterals or collateral pools linked to the liability.
 - The liability is not utilized.
 - The liability is not the parent liability for another child liability
-

Utilization Amount

This field displays the utilized amount for that liability Id at any point in time. You cannot edit this display.

Revision Date

Specify the date on which your bank would wish to revise the limit for the liability. The limit check will continue irrespective of the date maintained here. The revision date must be greater than the start date and can also be left blank.

Credit Rating

The primary credit rating maintained in the credit rating sub screen is displayed here.

Note

These details are maintained only for information and have no processing impact.

Overall Score

Specify the overall credit score for the liability. The given credit score is supplemented by the multiple credit score details, if any entered in the Credit Score sub screen.

Note

These details are maintained only for information and have no processing impact.

Overall Limit

Specify the overall limit amount for that liability. Value entered in the field will be in the currency stated above. If liability is of customer group then overall limits stated will be common to all the customers.

Note

System validates the overall limit amount against the internal lending limit equivalent amount. If the overall limit amount is greater than the Internal Lending Limit Equivalent Amount then the system displays an override message as 'Overall limit amount \$1 of the customer liability exceeds the maintained Internal Lending Limit Equivalent Amount \$2.'

Liability Category

Select the Liability Category from the list available here.

User Defined Status

Specify status of the liability (e.g. NORM for normal, BLOCKED etc).

Access Group Code

Specify the access group code. Alternatively, you can select the access group code from the option list. The list displays all valid access groups maintained in the system.

Unadvised

Select this check box if the Liability is unadvised.

For any transaction involving an unadvised liability, you will be notified so.

Netting Required

Select this check box to indicate that the netting amount defined in the 'Account/Contract Balance for Netting' screen will be updated in the 'Netting Contribution' field for the specific facility for which 'Netting required' checkbox is enabled.

This is only for information and not for processing.

You can have the Facility to display the Netting Amount in the 'Netting Contribution' screen. For more details on this feature, refer the section 'Including Netting Amount in Facility's Netting Contribution' in this document.

User Reference

Specify the User Reference number for the liability.


Note

Limits tracking at liability level is based on liability tracking at the parameterization level.

- If the liability tracking is enabled, then the system allows you to track the limit at the liability level.
 - Disabling liability tracking does not allow tracking limits at liability level.
-

2.5.1 Specifying Liability Scores

When a Liability is created, Bank will assess the credit score for the liability. You can link score parameters in the Liability Score screen. Here you can also assign a score value to each. You can maintain multiple score parameters for the single Liability. To invoke the Liability Score screen, click 'Score' button.



The screenshot shows a window titled "Liability Score" with a table interface. The table has three columns: "Score Name", "Score Description", and "Score". The table is currently empty. Above the table, there is a navigation bar with "1 Of 1" and a "Go" button. Below the table, there are "Ok" and "Cancel" buttons.

Score Name

Select the score name from the adjoining option list.

Score Description


Give a brief description on the liability score.

Score

Specify the liability score here.

2.5.2 Specifying Liability Credit Rating

When Liability is created, Bank will assess the credit rating for the liability. You can link all the rating parameters to which the liability is associated to in the Liability Credit Rating screen. Click 'Credit Rating' button to invoke this screen.



The screenshot shows a window titled "Credit Rating" with a table. The table has three columns: "Agency Name", "Credit Rating", and "Primary". The table is currently empty. The window includes a search bar at the top with "1 Of 1" and a "Go" button. There are also "Ok" and "Cancel" buttons at the bottom right.

Here you can select the Credit Rating Agency its Credit Rating for the liability. Out of all the Credit Ratings, you may select one as the primary rating for the Liability. You can maintain multiple score parameters for a single Liability.

Agency Name

Select the credit rating agency name from the adjoining option list.

Credit Rating

Select the credit rating from the adjoining option list.

Primary

Select one of the Credit ratings as the primary rating for liability.

2.6 Maintaining Customer to Liability Link

You can link customers to liabilities using the 'Customer to Liability Link Maintenance' screen.

Multiple customers can be linked to a liability. But a customer cannot be linked to multiple liabilities. You can invoke the 'Customer to Liability Link Maintenance' screen by typing

'GEDCULIK' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Customer To Liability Link Maintenance' application window. The window title is 'Customer To Liability Link Maintenance'. The interface includes a toolbar with 'New' and 'Enter Query' buttons. Below the toolbar are four input fields: 'Branch Code *', 'Customer No *', 'Liability No *', and 'Liability Name'. A section titled 'Customer Exposure' contains a table with columns 'Exposure Name *', 'Exposure Description', and 'Exposure Type'. The table is currently empty. At the bottom, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Branch Code

The branch code of the branch in which the Customer to liability link Maintenance is done gets defaulted here.

Customer No

Specify customer's number to whom the liability has to be linked.

Liability No and Liability Name

Specify the number and name of the Liability to be linked to the customer.

Customer Exposures

Here you can specify different Exposure Types for the customer. This allows you to track the exposure of a customer. Multiple exposure names can be linked (e.g. IT for Sector exposure, INDIA for country exposure) to track exposures.

- Exposure Type - The exposure type for the exposure, as maintained in the 'Track Exposure Maintenance' screen gets defaulted here based on the 'Exposure Name' chosen.
- Exposure Name - Specify an exposure name which is maintained in the 'Track Exposure Maintenance' screen.
- Exposure Description - The description for the exposure, as maintained in the 'Track Exposure Maintenance' screen gets defaulted here based on the 'Exposure Name' chosen.

Note

- The Customer to Liability Link Maintenance is mandatory, when limits tracking are required under any of the Oracle FLEXCUBE modules.
- In the 'Customer Exposures' section, the 'exposure name' LOV will display the exposures having utilization type as 'Customer' maintained in the 'Track Exposure Maintenance' (GEDTREXP) screen.

- The Customer to Liability Link Maintenance is mandatory, when account for the customer is created using account class, for which limit check flag is set as Y at preference sub-system screen.
- When account for the customer is created without maintaining liability and later the liability is created and linked to the customer, the 'Limits tracking' option at the customer level would be automatically selected by the system.

2.6.1 Viewing Customer to Liability Link Summary

You can view the summary of customer to liability link in the 'Customer to Liability Link Summary' screen. To invoke this screen, type 'GESCULIK' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Customer No
- Liability No
- ID
-

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- ID
- Branch Code
- Customer No

- Liability No
-
- ID

2.7 Covenant Maintenance

As a part of maintaining Collaterals/Facilities, you may collect certain required information and documents from the customer regularly. Based on the information you may revise the collateral/facility details. The information or documents collected from the customer is termed as a 'Covenant'.

You can maintain Covenant details in the 'Covenant Maintenance' screen. You can invoke the 'Covenant Maintenance' screen by typing 'GEDCOVNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Covenant Name and Description

Specify the Covenant Name for which information is entered. A maximum of 50 alpha numeric characters are allowed in this field. You may also provide a brief description of the covenant maintained.

Mandatory

Indicate whether covenant defined is mandatory as part of the process or not. You may change this preference when this covenant is linked to a Collateral/Facility.

Frequency

Select a frequency according to which the Covenant has to be collected/revisted. You may select any one of the following frequencies:

- Yearly
- Half Yearly
- Quarterly
- Monthly
- Weekly
- Daily

Start Month

If the Frequency select is Yearly, Half Yearly, Quarterly or Monthly, then specify the start month here.

Due Date On

Specify the number of days after which the covenant needs to be reviewed.

Grace days

Specify the Grace days past the next due/revision date allowed for renewal of the covenant.

Notice days

Specify the number of days in the notice period. The notice period will start this many days prior to the revision date of the covenant.

Remarks

Specify the remarks about the covenant maintenance.

This can be linked to 'Collateral Category Maintenance' screen (GEDCOLCA), 'Collaterals Maintenance' screen (GEDCOLLT) and 'Facilities Maintenance' screen (GEDFACTL) for choosing the covenant that is to be linked to the Collateral Category, Collaterals and Facilities respectively. On choosing the covenant in these screens the values maintained for the covenant is defaulted. You can modify these defaulted values.

2.8 Collateral Types Maintenance

Collateral Types maintenance is used to capture all types of Collateral which your bank accepts. Collateral Types information would be required when creating a new collateral in the system.

You can maintain Collateral Types in the 'Collateral Types Maintenance' screen. You can invoke the 'Collateral Types Maintenance' screen by typing 'GEDCOLTY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

This maintenance is at done at the bank level and all branches would be able to access this information.

The screenshot shows a software window titled "Collateral Types Maintenance". At the top, there is a menu bar with "New" and "Enter Query" options. The main workspace contains three input fields: "Collateral Type *" (with a red asterisk), "Description", and "Interest Rate". Below the workspace is a "Fields" section with a grid of labels: "Maker", "Checker", "Date Time:", "Date Time:", "Mod No", "Record Status", "Authorization Status", and an "Exit" button.

Collateral Type

Specify the Collateral Type. A maximum of 20 characters are allowed in this field.

Description

Give a brief description of Collateral Type. A maximum of 50 characters are allowed in this field.

Interest Rate

Specify the interest rate to be applied on the customer account when customer uses the overdraft facility against the collateral type.

This can later be linked to 'Collateral Category Maintenance' screen (GEDCOLCA), 'Issuer Maintenance' screen (GEDISSUR) and 'Securities' screen (GEDSECTY) for choosing the collateral type.

2.9 Collateral Category Maintenance

You can define the category to which collateral belongs to using the 'Collateral Category Maintenance' screen.

You can invoke the 'Collateral Category Maintenance' screen by typing 'GEDCOLCA' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Collateral Category Maintenance

New Enter Query

Collateral Category *

Collateral Type *

Revision Date

Corporate Deposits Category Type Maintenance

Sovereigns

Banks

Corporates

Reval Frequency Yearly ▼

Due Date On

Reval Start Month

Type

Category Description

Collateral Description

Collateral Exposure Type

Secured

UnSecured

Liquid

Asset Type

Tangible

Untangible

Collateral Haircut Category

1 Of 1 Go

Type Name *	Description	Haircut Percentage *	Primary

Covenant | Fields

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

Collateral Category and Category Description

Specify the Category name and a brief category description of the category.

Collateral Type and Collateral Description

Specify the collateral type. Collateral description will default from the 'Collateral Types Maintenance' screen based on Collateral type chosen.

Corporate Deposits Category Type Maintenance

Indicate the category type from the following:

- Sovereigns
- Bank
- Corporate

Revision Date

Specify the date on which the Collateral Category has to be revised

Secured Type

Indicate the Collateral Exposure Type from the following:

- Secured
- Unsecured
- Liquid Type

Tangible Type

Specify the asset type here - Tangible or intangible

Reval Frequency

Select the frequency with which the collateral has to be revaluated. You can select one of the following:

- Yearly
- Half Yearly
- Quarterly
- Monthly
- Weekly
- Daily

Reval Start Month

If the Frequency select is Yearly, Half Yearly, Quarterly or Monthly, then specify the start month here.

Due Date On

Specify the number of days after which the covenant needs to be reviewed.

Collateral Haircut Category

Here you can maintain several collateral haircut categories for use in the credit risk mitigation process. Multiple haircut records for same collateral category can be maintained.

Specify the following haircut details for each record:

- Type Name and Description
- Haircut Percentage - Specify the final Haircut (offset margin)
- Primary – Select a haircut as the primary haircut value for the Collateral Category

Type


Specify the remarks about the collateral category maintenance.

2.9.1 Maintaining Covenant Details for Collateral Category

To maintain the Covenant details for the Collateral Category, use the 'Collateral Category' screen. Invoke this screen by clicking 'Covenant' button.

The Revision Date for the covenant is generated based on the Frequency and Due date.

For example, if the collateral category covenant for a particular covenant name the frequency is monthly and the due date is 15. Based on the date of creation of the collateral covenant category (say 20 JAN 2008) the revision date will be 15-feb-2008.



Covenant Name

Specify a covenant name which is maintained in the 'Covenant Maintenance' screen.

Description

The description for the covenant, as maintained in the 'Covenant Maintenance' screen gets defaulted here based on the 'Covenant Name' chosen.

Revision Date

The system defaults the Revision Date for the covenant, on save of the collateral category record, based on the Frequency and Due Date of the covenant, maintained in the 'Covenant Maintenance' screen.

Covenant Reference No

Specify the covenant reference no for the collateral category being maintained.

Mandatory

The mandatory field for the covenant, as maintained in the 'Covenant Maintenance' screen gets defaulted here based on the 'Covenant Name' chosen.

Grace Days

The grace days for the covenant, as maintained in the 'Covenant Maintenance' screen gets defaulted here based on the 'Covenant Name' chosen.

This can later be linked to 'Collaterals Maintenance' screen (GEDCOLLT) for choosing the collateral category while maintaining the collateral.

2.10 Issuer Maintenance

A customer is granted credit on the basis of his/her credit worthiness. The credit worthiness of a customer depends on the assets constituting the customer's portfolio. The type of collateral that a customer offers can be in the form of marketable or non-marketable securities.

Marketable collaterals, driven by market forces, tend to fluctuate unpredictably. You may hence need to monitor your bank's exposure to issuers of such collateral. The details of the issuer and limit for his securities can be defined using the 'Issuer Maintenance' screen.

You can invoke the 'Issuer Maintenance' screen by typing 'GEDISSUR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Issuer Maintenance' application window. At the top, there are buttons for 'New' and 'Enter Query'. Below these are several input fields: 'Issuer Code *', 'Issuer Details', 'Overall Limit Currency *', and 'Overall Limit'. To the right, there is a field for 'Issuer Identification Number'. Below the input fields is a table titled 'Issuer Limits'. The table has three columns: 'Collateral Type *', 'Limit Currency *', and 'Limit Amount'. The table currently shows 1 of 1 records. At the bottom of the window, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Limits for the issuers of Collateral can be setup at the following two levels:

- Overall limit for each Issuer
- Limit for the Securities issued by an Issuer

Issuer Code

Each Issuer whose securities the bank accepts should be assigned a unique code. The Issuer will be identified by this code. This code can also be used to retrieve information about the Issuer. Specify the Issuer Code here.

Overall Limit

Specify an Overall Limit for the issuer here. This limit indicates the maximum limit beyond which your bank would not like to expose itself to the Issuer.

An issuer can issue different types of market based securities; these could be debentures, shares, bonds etc. By defining an overall limit for an Issuer, the bank can limit its exposure to the issuer.

When the total of all the collateral given by the customer in the form of market- based securities exceeds the overall limit specified for the Issuer, the system will show an appropriate message indicating that the limit has been exceeded.

Overall Limit Currency

Specify the currency in which the Overall Limit is specified.

Issuer Identification Number

Select the Issuer Identification Number if any, from the adjoining option list.

The option list for 'Issuer Identification Number' displays only those customers that belong to the bank and those that have been created in the application using the screen 'Customer Maintenance' (STDCIF) with the checkbox 'Issuer Customer' enabled.

Issuer Details

Specify in brief any additional details of the issuer.

Issuer Limits for Collateral Types

An Issuer of Securities may issue different types of securities. These can be used by a customer as collateral for credit availed from the bank. The securities used as collateral can be debentures, shares, bonds, commercial papers etc. These securities can therefore be classified under different Collateral Types too.

For each security type that your bank accepts as collateral from the issuer, you can specify a limit indicating the maximum exposure amount (in value) to the issuer for this security type.

When the total of the collateral given by the customer in the form of a particular collateral type exceeds the limit set for the Issuer, the system will show you a notification.

You can define Issuer Limits for different collateral types under Issuer Limits. You can maintain several collateral types here, with their respective Limit Currencies and Limit Amounts.

Collateral Type

Select the collateral type for which issuer limits are being specified.

Limit Currency

Select the limit currency from the adjoining option list.

Limit Amount

Specify the limit amount for that collateral type in the limit currency.

This can later be linked to 'Securities Maintenance' screen (GEDSECTY) for choosing the issuer code while maintaining the security.

2.11 Securities Maintenance

The credit facilities granted to the customers of the bank under a credit line can be backed by the securities that the customer offers as collateral. You can maintain the details of all such securities in the Oracle FLEXCUBE ELCM system. These details can then be used for determining the:

- Limit granted under a particular security
- Credit worthiness of a security when it's used as collateral

Since market based securities (Marketable Securities) are driven by market forces, the price of such securities tends to rise or fall in value. These fluctuations have a direct effect on the collateral value of the security. You can update the value of the collateral if the value of the security that backs it fluctuates beyond the increase and decrease sensitivity that has been specified.

You can capture details of marketable securities in the 'Securities' screen as shown below. You can invoke the 'Securities Maintenance' screen by typing 'GEDSECTY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Details of the marketable security that your bank accepts as collateral can be specified in the above screen.

Security Code

Assign a unique ID to identify the security. This ID is called the Security Code. This ID is used while maintaining Collateral for a market value based Security.

Description

Describe in brief the security maintained.

Equity Base

Here you can specify the equity base for the security i.e. the total amount raised by the issue of this security. This entry is for information purposes only.

For example, Gem granites have come out with Debentures 98 and have raised US \$1 Million through this issue. This US \$1M that Gem Granites has raised constitutes the equity base for Debentures 98.

Price Increase Sensitivity and Price Decrease Sensitivity

If the value of collateral is backed by a marketable security (whose value is driven by market forces) you may want to revalue the collateral, so that its value reflects the current market price of the security, which backs it. To do so, you should specify your sensitivity to the security.

The price sensitivity of a security is expressed as a percentage. You should specify the percentage increase or decrease (the upper and lower limits) above or below the current market price, which should trigger the revaluation process. The revaluation process revalues the collateral if the price of the securities that backs it fluctuates above or below the sensitivity you have defined.

Price Increase Sensitivity denotes the percentage increase in the market price that should trigger a revaluation of the Collateral. This means, if the current market price of the security rises above the old market price by the percentage you have defined as the Increase sensitivity for the security, then the revaluation process happens.

For example, Consider a case wherein you have specified the price increase sensitivity for Debentures 98 to be 15%. If the market price of the security has increased from \$100 to \$125. At this rise in the market price of the security (which is 25% above the old market value), the revaluation process will be triggered off, so that the Collateral value of the security reflects its current market value.

Price Decrease Sensitivity denotes the percentage decrease in the market price of the security that should trigger a revaluation of the Collateral. This means, if the current market price of the security falls below the old market price by the percentage you have defined as the decrease sensitivity for the security, the revaluation process happens.

For example, Consider a case wherein you had specified the price decrease sensitivity of Debentures 98 to be 15%. If the market price of the security has decreased from US \$100 to US \$75. At this fall in the market price of the security (which is 33.33% below the old market value of the security), the revaluation process will be triggered off, so that the Collateral value of the security reflects its current market price.

Currency

Specify the currency to be associated with the Security using the list available here. Once authorized this entry cannot be changed.

Face Value

Specify the face value of the security. A maximum of 50 numeric characters are allowed here.

Type

Specify the collateral type here.

Issuer Number

Specify the issuer code for the customer for whom the securities are collected. The list of issuers is available here.

Start Date and Expiry Date

Specify Start date and Expiry Date of the security in these fields

Limit Amount

Specify the limit amount for the particular security.

Nominal Value Based

Select this check box if the collateral value is to be calculated on the nominal value based for a particular security.

Security Price

If the security is quoted in different markets, its value would differ in different markets. You can maintain the various market prices of the security under the Security Price table.

You can specify the following details here:

- Market Price Code - Indicates the market place for which the price is quoted
- Market Price - Price of the security in that market
- Last Price Change - Date on which the price was last changed

This can later be linked to 'Collaterals Maintenance' screen (GEDCOLLT) for maintaining market value based collaterals.

2.12 Collaterals Maintenance

In the 'Collaterals Maintenance' screen, you can maintain the details of collateral offered by customers for the credit that the bank grants under a credit line. The collateral can either be market value based or non market value based.

You can invoke the 'Collaterals Maintenance' screen by typing 'GEDCOLLT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Collateral Details

Liability No * Branch *
Collateral Code * Lendable Margin
Collateral Description Charge Type
Remarks User Reference Number
Collateral Currency * Secured Type Secured
Collateral Value * Unsecured
Limit Contribution Liquid
Start Date Available
End Date Sharing Required
Revision Date Auto Pool Create
Revaluation Date Revaluate Collateral
Grace Days Haircut Percent *
Collateral Category * Collateral Type Market Value Based
Utilization Amount Guarantee Based
Available Amount Normal
Liability Name Mortgage Initiated
Block Amount Interest Rate
 Taken Over

Market Value Based

Security Id
Number Of Units/Nominal Value
Cap Amount
Price Code
Last Revaluation Price
Next Revaluation Date

Guarantee Based

Guarantor Id
Rating
 Revokeable
Revoke Date

Issuer Details

Issuer Name Issuer Reference Number
Source

Insurance | Covenant | Shared | Link Contract | UDE Values | Source Restrictions | Collateral Haircut | Fields

Input By: Date Time
Authorized By: Date Time
Modification Number: Authorized Open
Exit

In the above screen you can specify the contribution that the collateral should make to the limit assigned to a customer under a credit line.

The collateral details which are associated with a collateral code can be picked up during collateral pool maintenance.

Liability Number

Collaterals issued have to be linked to a liability. Specify the liability Number for which the collateral is linked.

Collateral Code

Specify the Collateral Code here. A maximum of 20 alphanumeric characters are allowed in this field. Each Collateral code should be unique.

Collateral Description

Give a brief description of the collateral here.

Collateral Type

Indicate the type of collateral - Market Based Type, Guarantee Type or Normal Type.

Secured Type

Indicate the Collateral Exposure Type here. A particular collateral category can be of a Secured or Unsecured or Liquid Type.

Auto Pool Create

Check this box if you wish to automatically create a collateral pool as and when you create collateral. To facilitate this, it is essential that the 'Available' option be checked for the collateral. The system then creates a collateral pool with the following characteristics when you save the record:

- The Pool Code, Pool Description and Pool Currency are the Collateral Code, Collateral Description and Collateral Currency respectively.
- The Collateral Linked Percentage is set at 100%.

Note

You cannot modify this option after you authorize the collateral.

Mortgage Initiated

On authorizing a mortgage loan account, the system creates collateral and collateral pool based on the property details maintained in the Mortgage Tab and 'Mortgage Initiated' option will be checked automatically.

For more information about the 'Mortgage Initiated' field please refer to the section, 'Linkages Tab' under the Chapter 'Account Creation' of the 'Mortgages' user manual.

Collateral Currency

Specify the currency in which the Collateral has to be maintained. Once authorized you cannot change this entry.

Charge Type

Select the charge type from the following list:

- Lien
- Pledge
- Hypothecation
- Mortgage
- Assignment
- This is only for information and not for processing.

Haircut (%)

Specify the bank's margin (Haircut) to be assigned for Collateral. Haircut% applied by the system as per the Haircut schedule would be displayed here

Collateral Category

Specify a collateral category which is maintained in the 'Collateral Category Maintenance' screen.

Available Amount

The system defaults the available amount for the collateral, on save of the collateral record.

Utilization Amount

The system computes and displays the utilization amount to the Collateral, if a collateral is directly linked to a contract or account and not through a pool.

Grace Days

The grace days for the covenant, as maintained in the 'Covenant Maintenance' screen gets defaulted here based on the 'Covenant Name' chosen.

Liability Branch

The liability branch for the Liability Number specified, as maintained in the 'Liability Maintenance' screen gets defaulted here based on the 'Liability Number' chosen.

User Reference Number

Specify the User Reference Number for the collateral.

Issuer Name

Specify the Issuer Name for the collateral in the case of a Market Value Based collateral.

Issuer Reference Number

Specify the Issuer Reference Number for the collateral in the case of Market Value Based collateral.

Available

This check box will be checked by default, indicating that the collateral is available for linking to the collateral pool. You can uncheck this so as to manually freeze this collateral.

If the 'Available' check box is unchecked then the collateral will be frozen i.e. it will not be available for subsequent linkages to new collateral pools. The collateral's current links to collateral pools will not be affected.

Note

- As a part of Collateral Pool creation for a Liability, only those collaterals which are checked as 'Available' will be displayed in the list for collateral pool linkage.
 - Collateral which was 'Available' and which has been linked to pool/pools can modified as unavailable later on. Unavailable collateral will not be available for subsequent new collateral pool linkages, but the old linkages will not be affected.
-

Sharing Required

Check this box to indicate that the collateral can be shared among several liabilities. If you choose this option, you can specify the details of such liabilities in the 'Shared Details' screen.

If this option is chosen then in collateral maintenance for a collateral pool, the list of collaterals will include shared collaterals too. As part of Collateral Revaluation, pools with the shared collaterals will be considered for revaluation.

Branch

By default, the branch code in which collateral is created is displayed here and you cannot modify this value.

Lendable Margin

On save of the collateral, system calculates the lendable margin for the collateral This value will be:

100 – Haircut (%).

Collateral Value

The collateral value depends on whether the security is Market Value based or Non-Market Value based.

If it is market value based then the collateral value is calculated as shown in the following examples.

Example

Input in case of a nominal quoted security:

Nominal Amount	Price Code	Market Price	Collateral Value [(Market price/100) * Nominal Amount]
10,00,000	BOM1	65	(65/100) * 10,00,000=650000
5,00,000	BOM2	70	(70/100) * 5,00,000= 350000
7,00,000	BOM3	80	(80/100) * 7,00,000= 560000

Input in case of a unit quoted security:

Number of Units	Price Code	Market Price	Collateral Value (Number of Units x Market price)
65	BOM1	120	7800
70	BOM2	130	9100
40	CAL1	95	3800

If it is Non-Market Value based then the user has to enter the collateral value manually.

Limit Contribution

On save of the collateral, system calculates the amount contribution that will be applicable for the collateral after applying the hair cut percentage on the collateral value.

Example

Collateral is valued at \$1000, and you wish to offer the customer credit only worth \$ 980. This amount is 98% of the collateral contribution.

$(1000 - 980) / 1000 = 2\%$ is the Hair cut percentage

This means you want to have a lendable margin of 98%.

For instance, if you enter the lendable margin percentage, then based on the value you enter, the hair cut will be calculated as described above and the limit contribution will be calculated.

Start Date and End Date

Specify the tenor of the collateral using the Start Date and End Date fields. The collateral is considered effective only during this period.

The start date indicates the date from which the collateral becomes effective. The end date that you specify indicates the date on which the collateral ceases to exist. On the end date, the credit limit, of the credit line backed by the collateral, will be reduced by the amount that the collateral contributes to the credit line.

Revalue Collateral

Select the check box if the collateral is to be revaluated.

Revaluation Date

Specify the date on which the next revaluation has to be done.

Revision Date

Specify the date on which this collateral has to be revisited for review.

Taken Over Collateral

Taken Over Collateral is checked if the collateral linked to CI/CL account is taken over.

Interest Rate

The interest rate to be applied if the customer uses overdraft facility against the collateral gets defaulted here when you select the 'Collateral Category'.

Block Amount

When the collateral is linked to the collateral pool, the system computes and displays the amount to be blocked. The blocked amount is computed based on the linked percentage or linked amount specified when a collateral is linked to a Collateral Pool.

For example, Collateral 'Collat1' is created with collateral value of 10000 USD. And 60% of Collat1 is linked to a Collateral Pool, then the blocked amount of the collateral is updated as 6000 (i.e., 60% of 10000). The available amount of collateral is updated as 4000(10000-6000). The available amount of the collateral is arrived by using the below mentioned calculation

Available amount = Collateral value – utilization – blocked amount.

The available amount of pool is increased to the extent of linked amount in the pool currency. Any utilization to the pool will only impact the available amount and the utilization of the pool and not the collateral.

2.12.1 Specifying Details for Market Value Based Type

For a market value based security you must maintain the following security related details.

Security Id

Specify the security Id for which the collateral is linked. On specifying the security Id, the price details and Market where security is traded are displayed.

Number of Units/Nominal Value

The collateral value of Marketable Securities will be computed by multiplying its market value (which is picked up from the Securities maintenance screen) by the number of units of the security that constitutes the collateral. Therefore, while maintaining details of Marketable Collateral, it is mandatory to specify the number of units of the marketable asset that constitutes the collateral.

If the security is nominal value based, input the nominal value of the security.

If it is a units quoted security then enter the number of units of the security that the bank accepts as collateral.

Cap Amount

As the price of marketable securities tend to fluctuate based on the forces of demand and supply, specify an upper limit on the contribution of this security to the collateral value, as a result of an increase in the price of the security. This upper limit is called the Cap Amount. The Cap Amount indicates that at any point in time the limit contribution of the collateral cannot

exceed this amount, even though its actual computed value is much higher. However, if the actual computed value of the collateral is lower than the Cap Amount, then the system picks up the collateral value as the actual computed value.

Price Code

Specify the market price code (E.g. NYSE, NASDAQ) based on which the revaluation price for collateral value calculation should be considered.

Last Revaluation Price

The last market price based on which the collateral value was revaluated will be displayed here.

Next Reval Date

Select the next revaluation date for the security.

2.12.2 Specifying Details for Guarantee Based Type

Guarantor

Specify the customer number (CIF ID) of the guarantor. This field is alpha numeric and a maximum of 50 characters can be entered.

Rating

You can assign a credit rating to each Guarantor. Here specify the rating assigned to the Guarantor. This Field is of numeric and maximum of 50 digits can be entered.

Revocable


Indicate whether the Guarantor can revoke (withdraw) this guarantee provided or not.

Revoke Date

Indicate the date when the Guarantor will revoke the guarantee. This field is enabled only when the Revoke check box is selected.

2.12.3 Specifying the Insurance Details

You may enter the Insurance details for a Collateral via the 'Insurance Details' screen. Click 'Insurance' button to invoke this screen .



You can specify the following details:

Insurance Name

Specify the name of the Insurance/Insurance Company associated with the collateral.

Insurance No

Specify the insurance number under which that insurance has been issued.

Insurance Owner

Select the owner of the insurance policy from the adjoining drop-down list. This list displays the following values:

- Bank
- Customer

Insurance Type

Specify the type of the insurance (e.g. FIRE, DAMAGE, THIEFT etc) that has been associated for that collateral.

Start Date

Specify the start date for that insurance.

End Date

Specify the end date for that insurance.

Revision Date

Specify the date of revision of the insurance.

Notice Days

On choosing a covenant name, system defaults the Notice Days details i.e. the number of days prior to next revision date of the covenant. You can modify this value. The period during the notice days will be the notice period.

Insurance Premium Periodicity

Select the premium periodicity of the insurance. The list displays the following values:

- Daily
- Weekly
- Monthly
- Quarterly
- Half Yearly
- Yearly

Premium Status

Specify the insurance premium status, where in the premium status like normal, overdue, premium payment failure status etc can be specified.

Premium End Date

Specify the end date of the premium payment.

Insurance Amount

Specify the insured amount of the policy.

Insurance Currency

Specify the insurance currency of the policy.

Cover Date

Specify the date from which the insurance policy is valid. The insurance cover date cannot be greater than the collateral expiry date.

Insurance Code

Specify the insurance code of the policy for which you want to capture insurance details.

Premium Currency

Specify the currency of the premium to be paid.

Premium Amount

Specify the amount of the premium to be paid.

Remarks

Specify the remarks about the insurance details.


Coverage

Specify the coverage details of the insurance.

2.12.4 Specifying Covenant Details

The covenant details can be captured for a collateral in the 'Covenant Details' screen. Click 'Covenant' button to invoke this screen.

Multiple covenants can be entered in the screen shown below. You can customize the details of each covenant recorded here.

**Covenant Name**

Select the covenant name from the list available here. The list displays the covenant names maintained in Covenant Maintenance screen. Based on the covenant selected, all other details of the covenant maintenance will be brought here.

Description

Description of the specified covenant is displayed here based on the details maintained at 'Covenant Maintenance' level.

Mandatory

Mandatory/Non mandatory details will be shown on choosing a covenant name. You may change this.

Frequency

You may change the frequency shown here on choosing a covenant name.

Grace Days

You can change the Grace Days details which are displayed here on choosing a covenant name.

Notice Days

Once you select the covenant name, system defaults the Notice Days details i.e. the number of days prior to next revision date of the covenant. You can modify the value.. The period during the notice days will be the notice period.

Revision Date

System defaults the Revision Date for the covenant, on save of the collateral category record, based on the Frequency and Due Date of the covenant, maintained in the 'Covenant Maintenance' screen..

Due date

Due date of the specified covenant is defaulted here based on the details maintained at 'Covenant Maintenance' level.

Start Month


Starting month of the specified covenant is defaulted here based on the details maintained at 'Covenant Maintenance' level..

Remarks

Remarks if any specified for the covenant at the 'Covenant Maintenance' level are defaulted here.

2.12.5 Specifying Shared Details

The details of the liabilities sharing the collateral can be captured for a collateral in the 'Shared Details' screen. Click 'Shared Details' button to invoke this screen.



Liability Number

Specify the liability number of the liability that is sharing the collateral. Each liability mapped here cannot be more than 100% of the total collateral value.

Shared Percentage

Specify the percentage share of the liability in the collateral.

Liability Name

Specify the Liability Name here. A maximum of 35 characters are allowed in this field.

You can modify the above retails post authorization. However the modification must be authorized.


2.12.6 Linking Contracts as Collaterals

The Oracle FLEXCUBE ELCM system supports linking of Term Deposit Accounts or Contracts as collaterals. You can link the Term Deposit Account Number or Contract Reference Number as collateral to a Liability in the Collateral Maintenance screen. The system subsequently blocks/marks Lien on the linked Term Deposit.

Note

Once a Term Deposit has been linked as collateral, the system will generate an output batch file to block/mark Lien on the linked Term deposits Accounts/Contracts. This output batch file will be generated as a part of Out Bound Batch Transaction.

For linking a contract as collateral, click 'Linked Contract'. The following screen appears where in you can link the Term Deposit Contract Reference Numbers of all Term Deposits you wish to link.



Modification of existing linked contracts can also be done in the above screen.

Contract Reference

You can link the Term Deposit Account Number or Contract Reference Number as collateral for a Liability by specifying the 'Contract Reference No' here. The adjoining list of options in this field displays all contract types other than Contract Type 'AC'.

Note

- The Term Deposit contract needed for Collateral Linkage must be maintained in Netting Maintenance with any contract type other than 'AC'
- Once the contract is linked as collateral, then its collateral value cannot exceed its contract amount as maintained in the Account Netting screen.

- The start date of the collateral should be later than the value date of the respective contract netting maintenance. Likewise, the expiry date of the collateral should be earlier than the expiry date of the respective contract netting maintenance.
 - The system blocks/marks Lien on the linked Term Deposit contract.
-

Contract Contribution

Specify here the amount being contributed from the contract as a collateral for the liability.

On saving the above maintenance, the system computes the sum of all the collateral values (specified under 'Contract Contribution') and updates the same in the 'Collateral Value' field of the 'Collaterals Maintenance' screen.

Note

You are allowed to link contracts associated to LC, BC and MM modules as part collateral maintenance in ELCM. The amount which is contributed to the collateral is the sum of the contract amounts (specified under 'Contract Contribution') of the contracts linked. ..

2.12.7 Maintaining UDE Values

You can capture UDE values details for a collateral in the 'UDE Value Details' screen. Click 'UDE Values' button in 'Collateral Maintenance' screen to invoke the below screen.

The screenshot shows the 'UDE Maintenance' window. It contains the following fields and controls:

- Commitment Branch (text input)
- Commitment Product (text input)
- Commitment Settlement Account (text input)
- Commitment Settlement Branch (text input)
- Commitment Reference Number (text input)
- Populate (button)
- Primary Customer Id (text input)
- Interest Calculation Method (dropdown menu)
- UDE Details section with a table:

User Data Elements Id *	Value	Rate Code	Code usage	Effective Date
-------------------------	-------	-----------	------------	----------------
- Ok (button)
- Exit (button)

Commitment Branch

Select the branch from the adjoining option list in which the commitment contract needs to be created.

Commitment Product

Select the product code from the adjoining option list to be used for creating the commitment contract.

Note

If the commitment contract is created in FCUBS, then the system will not allow modify the product code.

Commitment Settlement Account

Select the settlement account number from the adjoining option list used in commitment contract for passing the accounting entries.

Commitment Settlement Branch

Specify the commitment settlement branch code used in commitment contract for passing the accounting entries.

Commitment Reference Number

Specify the Commitment reference number.

Note

If a commitment reference number is maintained in the system, then the same is auto populated upon selecting the particular commitment.

Primary Customer ID

Specify the Primary customer ID which is to be used for commitment account. Alternatively, you can select the Primary customer ID from the option list. The list displays all valid customer ID's which in-turn are linked to the liability number used for creating a facility in the system.

Note

The customer ID selected here is displayed as the default customer ID in the Commitment Account Details screen (CLDCMTMT).

Interest Calculation Method

You can specify the following preference to calculate the interest by including or excluding the start and/or the end date of the contract. Select the type of interest calculation method to be used from the drop-down list. The list displays the following values:

- Start Dates Only (Kataha Ato Otoshi) - To include only start dates and exclude end dates.
- End Dates Only (Kataha Mae Otoshi) - To include only end dates and exclude start dates.
- Both Dates + End for Inter (Ryoha Mae Otoshi) - To include start and end date of the contract and to exclude start date of intermediate schedules.
- Both Dates + Start of Inter (Ryoha Ato Otoshi) - To include start and end date of the contract and to exclude end date of intermediate schedules.

Note

The Interest Calculation Method defined here will overwrite the default value if maintained in the Preferences tab of Commitment Account Details screen (CLDCMTMT).

UDE Details

You can specify the user defined element values details in the following fields:

User Defined Element ID

Specify the unique identification for the user defined element. The adjoining option list displays all valid IDs maintained in the system. You can choose the appropriate one.

Value

Specify the value for the user defined element.

Rate Code

Specify the rate code. The adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Code Usage

Select the type of code usage from the adjoining drop-down list. The list displays the following values:

- Periodic
- Automatic

Effective Date

Select the effective date from the adjoining calendar.

Component Grace Days

You can specify the Component Grace Days details in the following fields:

Note

You can also auto populate the default Component Grace Days details maintained at product level by clicking on Populate button after specifying the commitment details.

Component Name

Select the component name for the commitment product. The adjoining option list displays all component names maintained in the system. You can choose the appropriate one.

Grace Days

Specify the number of grace days for the selected component.

Holiday Treatment for All Schedules

You can define the following holiday preferences for all repayment schedules. The preferences defined here will be defaulted to commitment level and also overwrites the holiday preferences defined at product level.

Ignore Holidays

Check this box to freeze the schedule dates without considering the holidays into account.

If this option is not selected and the schedule date falls on a holiday, the automatic processing of such a schedule is determined by your holiday handling specifications for automatic processes, as defined in the 'Branch Parameters' screen.

Holiday Check

Select the type of holiday check to be maintained from the drop-down list. The list displays the following values:

- Local - To consider the local holiday to adjust the overlapping holiday schedule.
- Currency - To consider the currency holiday to adjust the overlapping holiday schedule.
- Both - To consider both currency as well as local holiday to adjust the overlapping holiday schedule.

Move Across Month

Check this box to allow the schedule date to be moved to the next or previous month when the schedule due date is either on first or last working day of the month and is a holiday.

Cascade Schedules

Check this box to cascade the current schedule change across all the remaining schedules. If not checked, then only the current schedule is changed.

Schedule Movement

If you have opted to move the schedule date across months by selecting the 'Move Across Month' check box, then select the type of movement. The options are as follows:


- Move Forward - if the schedule date is to be moved to first working day of next month.
- Move Backward - if the schedule date is to be moved to last working day of previous month.

Note

The above UDE details can be used to upload commitment details to Oracle FLEXCUBE as part of Collateral maintenance. INIT, VAMI and CLOC events will be triggered only on authorization of Collateral. For LINK and DLINK events, 'ELBCOMNT' batch needs to be configured as part of EOD process.

2.12.8 Maintaining Source Restrictions

You can specify which sources are allowed or restricted to access the collateral in 'Source Restrictions' screen. Click on 'Source Restrictions' button to invoke this screen.



Restriction Type

Choose the 'Allowed' option to maintain an allowed list of liability restrictions. Choose the 'Disallowed' option to maintain a disallowed list of liability restrictions.


Default value of this field will be 'Disallowed'. If you select restriction type as 'allowed', then you need to input at least one record.

Source

Specify the source from the adjoining option list.

2.12.9 Maintaining Haircut Schedules

You can specify the hair-cut revisions for the collateral in 'Haircut' screen. Click on 'Haircut Schedules' button to invoke this screen.



Effective Date

Specify the date on which the Haircut % will become effective from the adjoining option list.

Haircut Schedule Percentage

Specify the Hair cut % of the Collateral. You can enter values between 1 to 100

Note

System applies the haircut% to the collateral on the schedule effective date during the BOD process of the collateral batch (GEBCOLAT).

The following validations are performed during save,

For New operation,

- Effective date should be greater than the application date and start date of the collateral
- Multiple Haircuts for the same effective date will not be allowed.
- Haircut % chosen at the main screen gets defaulted as the first schedule with collateral start date as the effective date, in the Haircut schedules sub screen..

For Modify operation,

- Effective date should be greater than the application date and start date of the collateral
- Effective date should be less than the end date of the collateral.
- Deletion or Modification of existing Haircuts whose effective date are less than application date would not be allowed.
- Haircut schedules maintained in this sub screen would be applied on the effective date in the existing collateral batch process.
- Existing field Haircut % would show the latest haircut of the collateral.

2.13 Collateral Pool Maintenance

You may group together two or more collaterals to create a Collateral Pool. You can create and maintain collateral pools in the 'Collateral Pools Maintenance' screen.

You can invoke the 'Collateral Pools Maintenance' screen by typing 'GEDMPOOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Liability No

Specify the liability to which the collaterals need to be linked.

Liability Name

Specify the Liability Name here. A maximum of 35 characters are allowed in this field.

Pool Code

Specify the Pool Code here. The pool code assigned to each collateral pool can be linked to a Liability while creating credit limits.

Pool Description

Specify a brief description of the collateral pool here.

Pool Currency

Specify the currency in which the Collateral Pool has to be maintained.

Available Amount

On save of the collateral pool record, system defaults the available amount for the collateral pool. It is the difference between Pool Amount and Pool Utilized.

Block Amount

When the collateral is linked to the collateral pool, the system computes and displays the amount to be blocked. The blocked amount is computed based on the linked percentage or linked amount specified when a collateral is linked to a Collateral Pool.

For example, Collateral 'Collat1' is created with collateral value of 10000 USD. And 60% of Collat1 is linked to a Collateral Pool, then the blocked amount of the collateral is updated as 6000 (i.e., 60% of 10000). The available amount of collateral is updated as 4000(10000-6000). The available amount of the collateral is arrived by using the below mentioned calculation

Available amount = Collateral value – utilization – blocked amount.

The available amount of pool is increased to the extent of linked amount in the pool currency. Any utilization to the pool will only impact the available amount and the utilization of the pool and not the collateral.

Liability Branch

Specify the branch in which liability is associated.

Collateral Description (Collateral Pool Linkages)

The description for the collateral, as maintained in the 'Collaterals Maintenance' screen gets defaulted here based on the selected 'Collateral Code'.

Order Number

Specify the order for collateral utilization.

Type

The type for the collateral, as maintained in the 'Collaterals Maintenance' screen gets defaulted here based on the selected 'Collateral Code'

Branch Code

The branch code for the branch where the collateral is maintained in the 'Collaterals Maintenance' screen gets defaulted here based on the selected 'Collateral Code'.

Collateral Utilization

System updates the collateral utilization for each of the collateral codes linked in the 'Collateral Pool Linkages', based on the utilization, when the collateral pool comprising the collateral is linked to the facility.

Mortgage Initiated

This option will be checked automatically for collateral and collateral pool created as a result of authorization of mortgage account and you cannot modify it.

Auto Facility Create

Check this box to indicate that a facility should be created automatically for the given Liability number with line code as pool code.

Note

This automatically created line code can be used to maintain limits for customer account in 'Account Limits' screen, if required.

For more details on maintaining Account Limits, refer Core Entities User Manual.

2.13.1 Creating Collateral Pool Linkages

Under 'Collateral Pool Linkages' you can add the different collaterals pooled in for the particular Liability.

To add a new collateral click 'Plus' button, specify the relevant details and save the record.

To delete an existing collateral, select it and then click 'Minus' button and save the record.

While creating collateral pools, remember the following:

- Collateral can be linked to more than one pool if the collateral amount available is not zero.
- A credit line can be backed by only one pool but a single pool can back multiple credit lines.

You must maintain the following details for each of the collateral.

Collateral Code

Select the collateral code from the adjoining option list.

If the 'Linked Percent Number', is specified, on save of the record, system defaults the 'Linked Amount' calculated as Linked Percentage of 'Collateral Contribution'.

If the 'Linked Amount' is specified, on save of the record, system defaults the 'Linked Percent' calculated as percentage of 'Linked Amount' out of the 'Collateral Contribution'.

Collateral Currency

The currency in which the collateral has been maintained will be displayed when a collateral code has been picked.

Limit Contribution

The collateral amount which has been maintained will be displayed when a collateral code has been picked.

Linked Amount

When a collateral pool comprising the collateral is linked to the facility, the system computes and displays the amount to be linked. The linked amount of Collateral pool is computed based on the pool percentage or pool amount specified when a collateral pool is linked to a Facility.

For example, Collateral Pool 'Pool1' is created with pool amount of 6000 USD. And 60% of Pool1 is linked to a Facility, then the linked amount of the collateral pool is updated as 3600 (i.e., 60% of 6000). The available amount of collateral pool is updated as 2400 (6000-3600). The available amount of the collateral pool is arrived by using the below mentioned calculation

Available amount = pool amount – pool utilization – linked amount.

The available amount of facility is increased to the extent of linked amount in the facility currency. Any utilization to the facility will only impact the available amount and the utilization of the facility and not the collateral pool or the underlying collateral.

Pool Amount

The system computes and displays the utilization amount to the Collateral Pool, if a collateral Pool is attached to a contract or account and not through a facility.

Pool Utilized

This field displays the pool amount that has been linked to a various credit lines, hence displaying the total pool amount utilized at any point in time.

Linked Amount Pool Currency

.System defaults the 'Linked Amount Pool Currency' for each of the collaterals added in the 'Collateral Pool Linkages' as the linked amount in the pool currency.

For Example, you have linked the pool 'LOANP001' to the liability 'BIRLA0001'. LOANP001 is in turn backed by the following collaterals:

Collateral Code	Ccy	Collateral Amount	Linked Amount
ISDP16924	DEM	100,000	75,000
AC777228	GBP	55,000	55,000
COLSHRS15	INR	2,000,000	1,500,000
COLHS819	USD	1,500,000	1,500,000

Now the pool currency specified is USD. Therefore the system does the necessary calculations and converts the linked amount into the currency of the pool and displays the pool amount in the respective field.

Linked Percent Number

The part of the collateral amount which has to be linked to the pool can be specified as a percentage here. On save of the record, if Linked Percent Number is specified, system defaults the 'Linked Amount' calculated as Linked Percent Number Percentage of 'Collateral Contribution'.

Available Interest Rate

The interest rate maintained for the collateral code in 'Collateral Type Maintenance' screen gets defaulted here,

Interest Spread

Specify the interest spread to be applied on the customer account. The interest spread can be zero. However, if the collateral attached is a term deposit, then on rollover of the term deposit the interest spread is defaulted to the spread applicable for the term deposit on rollover.

Rate of Interest

The rate of interest applicable on the customer account when customer uses the overdraft facility against the collateral type is derived as follows:

Rate of Interest = Available Interest Rate + Interest Spread + Customer spread

Expiry Date

On save of the record, system defaults the expiry date based on the end date of the collateral maintained. However, if the collateral attached is of a deposit then on rollover of the term deposit the maturity date of the term deposit is updated as the expiry date of the collateral.

Note

- The batch program 'CASABAT' is used to update the overdraft utilization at collateral level.
 - If a rollover happens for a TD linked as collateral, during BOD, the interest rate applied on the TD gets updated to the interest rate value maintained at the collateral pool level.
-

2.14 Facilities Maintenance

You can maintain credit limits for a Line Code - Liability Code combination in the 'Facilities Maintenance' screen. You can invoke the 'Facilities Maintenance' screen by typing

'GEDFACTL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details:

Branch Code

By default, the branch code in which facility is maintained is displayed here and you can modify this value.

Liability No

Specify the Liability number here.

Liability Name

Specify the Liability Name here. A maximum of 35 characters are allowed in this field.

Line Code

Specify the Line Code to which the liability ID is to be associated with. Allocating credit limits for the Line-Liability combination can be done. The customer(s) who fall under this Liability Code will in turn avail credit facilities under this Credit line.

By linking a Credit Line to a Liability code the customer also gets linked to the Credit Line. This is true because a Liability code has been assigned to every credit seeking customer and the credit facilities granted to the customer are defined and tracked against this code.

Serial No

Each time a customer - line code combination is specified, Oracle FLEXCUBE ELCM system assigns a unique serial number to the combination. This serial number is unique to the line-liability code combination. Thus, for every new record entered for a Line-Liability combination, a new serial number is generated. The Line - Liability - Serial number forms a unique combination.

Facility Branch

By default, the system displays the branch code in which facility has been created. You can change the branch code from the adjoining option list before saving the facility. Once the facility is saved, you cannot modify the branch code.

Description

Give a brief description of the facility here.

Main Line Code

Specify the main line code if the created facility is a sub line.

If the main line code is not specified, then the system defaults the facility code as the main line code.

Line Currency

Specify the currency in which the facility is defined. The currency that has been selected will have the following implications:

- The limit amount that has been specified for this Line-Liability combination is taken to be in this currency.
- The line that has been defined will be available for Utilization only in the line currency, unless specified otherwise under Currency Restrictions in this screen.

Once the entry is authorized you cannot change the currency.

If the limit allotted to this Line-Liability combination can be utilized by accounts and transactions in currencies other than the limit currency, the limit utilization will be arrived at by using the mid rate for the currency pair as of that day.

Main Line Currency

By default, the system displays the currency of the main line for the Main Line Code selected.

Main Line Exchange Rate

Specify the exchange rate for conversion between sub-line and main-line.

- The system checks the consistency of currency of the sub-line and allowed currencies at the main-line.
- The system checks that the loan currency is among the allowed currencies of the facility /facilities attached, including main-line. If the loan is attached to sub-line and the loan currency is not among the allowed currencies of the main line, the system displays an error message stating 'Loan currency is not an allowed currency at the Facility Level'.

The system performs the following validations while managing multi-currency at facility level:

- The system checks the consistency of currency of the sub-line and allowed.
- The system ensures that the loan currency is among the allowed currencies of the facility or facilities attached, including main-line. If the loan is attached to sub-line and

the loan currency is not among the allowed currencies of the main line, the system displays an error message stating 'Loan currency is not an allowed currency at the Facility Level'. The system adds the Exchange Rate field at the Facility level. In case of sub-line, this shall be used to convert all the amounts with respect to the main-line, in case the currencies are different. These include sub-line v/s main-line limit amount check.

- You can change the exchange rate after the sub-line is created. The system uses the latest rate for amount conversions.
- If the exchange rate field is null at sub-line level, the system uses the maintained rates for conversion between sub-line and main-line.
- If the Sub-line Limit Amount exceeds the Main-line, the system displays an error message (configurable as an override) stating, 'The Sub Line Limit Amount cannot exceed the Main Line Limit' if the currencies are different.
- For commitment-linked facilities, the system displays an error message if a loan is directly linked to commitment and the loan utilization exceeds the commitment available amount.
- If the loan is attached to a line which is not linked to commitments, system displays an error which can be configured as an override. If the loan utilization exceeds the facility available amount, the system displays an error message stating 'Linkage amount cannot be greater than amount available'.
- You cannot remove currency at the facility level. Once a sub-line or loan is linked to a facility using a currency. The system will display an error message stating 'Sub-line or loan exist with the Currency. It cannot be removed from the allowed currencies'.

Category

Select the facility category from the list available here. The list displayed here is based on maintenance done in 'Category Maintenance' screen.

Revolving Line

Check this box to indicate that the credit line is Revolving. A revolving credit line indicates that a repayment of the utilized credit should reinstate the credit limit of the customer. You can modify the preference, as required.

Netting Required

This check box will be unchecked by default, indicating that netting is not required for the facility. You can check this box to enable netting for the facility.

Unadvised

Check this box to indicate that the facility is unadvised.

Note

Charges can be collected on the utilization transactions for facilities that are unadvised. For this purpose SDEs ADVISED_LINE and COMMITMENT_CUR_UTIL can be used while setting up the charge rule at the CL product creation level.

Fund

Indicate whether the line is fund based or non fund based.

Shadow Limit

Select this check box to indicate that utilization amounts should be updated only for the facility and mainlines for the facility. Thus, when a utilization request is processed, the system

updates the utilization amount only at the facility level and leaves the utilization amount at the liability level untouched.

The mainline and sub-lines of a facility need to have the same preference. This implies that you can enable this option for a sub-line only if the mainline has this option already enabled. Similarly, you cannot create a sub-line as a 'Shadow Limit' if the mainline does not have this facility.

Note

You cannot modify this option after you authorize the facility.

Bulk Payment Required

Check this box to indicate if bulk payment is required. If you specify here that bulk payment is required for the liner, then the same is maintained at the 'Bulk Payments' screen.

For more information about the 'Bulk Payments' screen please refer to the section, 'Making Bulk Payments against loan or commitment' under the Chapter 'Operations' of the 'Retail Lending' user manual.

User Defined Status

Specify status of the facility (e.g. NORM for normal, BLOCKED etc) from the list available here. The list displayed here is based on maintenance done in 'User Define Status Summary' screen.

Status Changed On

Specify the date on which you wish to change the status. You can specify a date before the line start date to block the line till the specified date. Also, you can set a date prior to the application date.

Internal Remarks

Specify the internal remarks as limits terms and conditions.

Renewal

Check this box to renew current dated amendments

Amounts

Specify the following details:

Limit Amount

Specify the limit for the facility. If you have maintained schedules for limits, the system automatically updates the limit amount here on the dates specified for each limit in the schedule.

Note

The charges can be collected on facility limit amount change. In this case commitment contract created should be capable of charging the customer on the facility limit amount change. For this purpose SDE INCREASED_PRINCIPAL can be used while setting up the charge rule at the CL product creation level.

LIMIT_AMOUNT can be used while setting up the IC rule for interest calculation based on facility limit amount.

Collateral Amount

System defaults the Collateral Amount on save, based on the pools linked in the 'Pool Links' sub screen.

Transfer Amount

System displays the transfer amount resulting from 'Facilities Amount Transfer' transactions. The value displayed has either the sign "-" or "+", indicating whether the amount is transferred from or to the line. If the sign is "-", then the amount is transferred from the line and if it is "+", then the amount is transferred to the line.

Effective Line Amount

The system displays the effective line amount.

Effective Line Amount Basis

For defining drawing power of line the elements mentioned below are treated as the basis for the effective line amount calculation.

- Line Amount + Collateral
- Line Amount
- Minimum of Line Amount and Collateral

Note

EFF_LIMIT_AMOUNT can be used while setting up the IC rule for interest calculation based on facility effective limit amount.

Uncollected Amount

The system displays the uncollected amount.

Approved Limit Amount

This is the maximum limit amount allowed for the facility and must be specified whenever you maintain schedule limits. System ensures that neither the 'Limit Amount' maintained here nor the schedule 'Limit Amount', maintained as part of the limits schedule is greater than the limit specified here".

Block Amount

Specify the block amount.

Daily Light OD Limit

Specify the daily light limit.

Daily Light Limit

Specify the daily light limit.

Utilization

This section contains the following details:

Available Amount

The system displays the available amount.

Date of First OD

The system displays the date of first OD.

Date of Last OD

The system displays the date of last OD.

Netting Contribution

The system displays the netting contribution if:

- the facility is linked in the 'Netting Account' screen.
- 'Netting Required' is checked at Liability level, Facility level and Netting Account level.

Last New Utilized Date

The system displays the last date when a utilization increase was done for a particular facility. The utilization can be either a new utilization or an increase in the existing utilization.

Amount Utilized Today

The system displays the amount utilized on the current date.

Utilization Amount

The system displays the utilization amount.

Tanked Utilization

The system displays the tanked utilization.

Availability

Specify the following details:

Line Start Date

Specify the line start date. If not specified, system defaults the line start date as the current application date.

Note

The system accepts the Line Start Date as back valued. The commitment contract booked will be back value dated with the value date being the line start date specified as part of Facility Maintenance. The utilization of the facility will always be with the current application date.

Expiry Date

Specify the expiry date for the facility. If the limit amount assigned to the facility is not utilized within the specified expiry date then the Available check box will remain un-selected. This freezes the line for the respective liability.

The freezing of the line code will be part of the Oracle FLEXCUBE ELCM EOD Batch.

The Oracle FLEXCUBE ELCM system will not allow the expiry date of a facility to exceed the expiry date of linked collateral(s).

When a Facility record is saved, the system will compare the expiry date of all the collaterals in the Pool which is linked to the Facility. An error message will be shown if any expiry dates are less than the expiry date of the Facility.

If the expiry date falls on a holiday maintained in the branch, then system displays the error message 'Facility Expiry Date falls on a branch Holiday'.

The facility shall not be available on the maturity/expiry but you can modify the facility on the expiry date if required.

Expiry Allowance Date

Specify the final expiry date for the facility.

Note

If you maintain this date, system does not close the Facility till this date is reached. When the 'Expiry Allowance Date' is maintained at the Facility level, system validates the loan maturity date with respect to Expiry Allowance Date.

If the loan maturity date is beyond this date, system does not allow the transaction to proceed. System displays error that 'Loan Maturity Date is beyond the Facility Expiry Allowance Date'.

During transaction input, system performs the following validations:

- System compares the loan account maturity date with the Expiry Allowance Date of the linked limit. If the maturity date is less than the Expiry Allowance Date of all the linked limits, transaction becomes successful. However if it is more than the Expiry Allowance Date of any of the linked limits, then transaction fails. If Expiry Allowance Date is not present, system shall continue to validate the loan maturity date against the Line Expiry Date and show the existing override if the maturity date is beyond the line expiry date.
- You cannot link an expired limit to a new loan.
- If Expiry Allowance Date is less than Line Expiry Date, system displays an error stating Expiry Allowance Date cannot be less than the Expiry Date.
- If there are active loans linked to a facility and if the Facility Expiry Date is modified to be less than the maturity date of the linked loans, system displays an error stating 'Active Loans Exist with Maturity Date Greater than the Expiry Allowance Date'.

Available

If the Line facility is available then this check box will be checked.

The Oracle FLEXCUBE ELCM system tracks the status of both the Contract and the Facility. When the status of the Contract changes to PDO, then the Facility will become unavailable.

The product processor will give an ASCII file including all the facilities which need to be frozen. Oracle FLEXCUBE ELCM will initiate an amendment event and then un-checks the 'Available' check box.

Availment Date

Specify the availment date on which the first utilization should take place. If the limit amount assigned to the facility is not utilized within the specified availment date then the available check box will be disabled. This freezes the line for the respective liability.

Note

- The system does not allow utilization post availment date even if the facility has been utilized before the availment date.
 - The system does not allow new loan contracts to be linked to a facility post the availment date.
 - The system allows payment, hence available amount of the facility will not become zero, it can increase even after the availment date is crossed.
 - The system allows the amendment of the loans as long as they do not result in utilization of the facility.
-

Exception

Specify the following details:

Exception Transaction Amount

Specify the Exception Txn Amount. During utilization transaction when utilization amount crosses the specified Exception Txn Amount, BEPL process is triggered for Credit Exception Management to authorize the credit utilization amount. The limit transaction amount specified should be below the total effective line amount specified for that facility.

Note

The utilization transaction can also be authorized or rejected using the "Multi Authorization Maintenance screen based on the system configuration.

Exception Breach Percentage

Specify the Exception Breach Percentage. During utilization transaction when utilization amount crosses the specified Exception Breach Percentage, BEPL process is triggered for Credit Exception Management to authorize the credit utilization amount. The limit transaction amount specified should be below the total effective line amount specified for that facility

Note

The utilization transaction can also be authorized or rejected using the 'Multi Authorization Maintenance' screen based on the system configuration

Interest Fee Required

Specify the following details:

Interest Fee Required

Check this box to indicate the facility is applicable for interest calculation.

Fee Calculation Account

Specify the account which is linked with the above facility. Then the same account will be applicable for interest calculation based on ELCM facility.


Note

The following SDEs will not be applicable for ELCM based interest calculation.

- ELCM based interest calculation SDEs,
 - Limit_Amount, Eff_Limit_Amount
 - Matured_Amount - If you repay the already utilized amount, then the repay credit will update on the Matured_Util field of the 'Getm_facility' table.
-

2.14.1 Maintaining Limit Schedules

The limit assigned to a customer under a revolving line can be reduced. You can define these details while maintaining limits for a customer. From the Limits Maintenance screen, click 'Schedules' button.



For a liability code and credit line combination, you can define limit schedules and indicate the limit that is applicable for the period. You can enter a negative limit amount. However, the 'Limit Date' should not be earlier than the 'Limit start date' and later than the 'Limit Expiry Date'.

The Facility batch which runs at BOD checks the limits schedule for a facility and if a schedule is due on the current date in the branch. If so, it updates the limit amount for the facility for which the schedule is due with the schedule limit amount.

For example, you have defined a limit schedule for a facility for your client ABC Corporation where the Limit Amount initially is USD 1 million and the start date for the facility is Jan 01, 2009. The schedule is as shown below:

Limit Date	Schedules Limit Amount
Feb 01, 2009	500000
Mar 02, 2009	800000
April 03, 2009	400000
May 04, 2009	900000

In this case, during BOD on Feb 01, 2009, the limit amount will be updated to USD 500,000 and on Mar 02, 2009 it will be modified again to USD 800,000. If the batch does not run on Mar 02, 2009, it will be run on Mar 03, 2009. Accordingly, the 'Scheduled Limit Amount' defined for Mar 02, 2009 Schedule will be updated as Facility Limit Amount.

During EOD, the system processes limits schedules and revision process takes place for the facilities as per the scheduled date. It processes the limit schedules till next working day and marks all the schedules till date as processed.

When the Facility Start Date and Schedule Date falls on the same day, then on save of Facility record, you will get an override message for confirmation on updating the limit amount of Facility as per the schedule amount.

While processing, if there are any errors or overrides, it should be logged. The following are the possible errors:

- Available amount is negative for the facility.
- The Tenor Limit Amount exceeds the Line Approved Limit Amount as the validation of the Tenor Limit Amount is against the Approved Limit Amount.
- The amount cannot exceed the overall limit specified for the liability id.
- The Main Line Limit cannot be less than any of its Sub Line Limit.
- The Sub Line Limit cannot exceed the Main Line Limit.
- Example
- Assume the following:
- Liability - GROUPLIAB
- Line - SHTLLIMIT
- Serial - 1
- Start Date - 01-Jul-2009
- Limit Currency - USD
- Limit Amount - 50000
- Schedules:

Limit Date	Schedules Limit Amount
15-Jul-2009	60000
28-Jul-2009	65000
30-Jul-2009	75000
15-Aug-2009	80000

- System Date - 14-Jul-2009
- Limit Amount - 50000
- On 14-Jul-2009 EOD, limit revision process picks the 15-Jul-2009 schedule and update 60000 as limit amount. The revised limit is enforced or effective on 15-Jul-2009.
- System Date - 15-Jul-2009
- Limit Amount - 60000
- Schedules:

Limit Date	Schedules Limit Amount
15-Jul-2009	60000
28-Jul-2009	65000
30-Jul-2009	75000

15-Aug-2009	80000
-------------	-------


- System Date - 27-Jul-2009
- Limit Amount - 60000
- Next working Day - 30-Jul-2009
- On 27-Jul-2009 EOD, the limit revision process picks 28-Jul-2009 and 30-Jul-2009 schedules and update 75000 as limit amount. The revised limit is enforced / effective on 30-Jul-2009.
- System Date - 30-Jul-2009
- Limit Amount - 75000
- Schedules:

Limit Date	Limit Amount
15-Jul-2009	60000
28-Jul-2009	65000
30-Jul-2009	75000
15-Aug-2009	80000

2.14.2 Specifying Covenant Details

The covenant details can be captured for facility in the 'Covenant Details' screen. Click 'Covenants' to invoke this screen.

Multiple covenants can be entered in the screen shown below. You can customize the details of each covenant recorded here.



Covenant Name

Select the covenant name from the list available here. The list displays the covenant names maintained in Covenant Maintenance screen. Based on the covenant selected, all other details of the covenant maintenance will be brought here.

Mandatory

Mandatory/Non mandatory details will be shown on choosing a covenant name. You may change this.

Periodicity

You may change the frequency shown here on choosing a covenant name.

Grace Days

You can change the Grace Days details which are displayed here on choosing a covenant name.

Notice Days


Specify the notice days i.e. the number of days prior to next revision date of the covenant. The period during the notice days will be the notice period.

Revision Date

On save of the collateral record ,the Revision Date for the covenant is defaulted based on the Frequency and Due Date maintained in the 'Covenant Maintenance' screen.

2.14.3 Maintaining Value Dates Details

To maintain details regarding value dates, click 'Value Date' button.



The screenshot shows a window titled "Value date Details" with a close button (X) in the top right corner. Below the title bar, there is a navigation bar with "1 Of 1" and a "Go" button. A table is displayed with the following columns: "Value Date Limit Amount", "Value Date", and "Main Line Code". The table is currently empty. At the bottom right of the window, there are "Ok" and "Exit" buttons.


Value dated limits for a particular facility are automatically populated in the above screen when you save the Facility. The following are the details available:

- Value date Limit Amount
- Value Date after which the mentioned amount is valid – You may modify this when required.
- Main Line to which the limit amount is linked to

2.14.4 Tracing Exposure for a Line

The facility defined can be tracked for particular exposures.

The exposure details can be captured for facility in the 'Exposure Details' screen. Click 'Exposure' to invoke this screen.




Exposure Name

Select the exposure name from the list available here. The list displays the exposure names maintained in Exposure Maintenance screen. Based on the exposure selected, all other details of the exposure maintenance will be displayed here.

Capturing Facility Maintenance Charges Details

To capture facility maintenance charge details, click 'Charges' button.



Admin Charge Type

Administrations charges as a part of creation of new line can be specified here. Charge can be a fixed amount or a percentage of the Limits amount.

Unutilized Charge Amount

Specify the charge amount that has to be collected on a certain frequency (daily, monthly etc) based on the unutilized amount. Charge can be a fixed amount or a percentage of the unutilized amount.

Utilized Charge Amount

Specify the charge amount that has to be collected on a certain frequency (daily, monthly etc) based on the utilized amount. Charge can be a fixed amount or a percentage of the utilized amount.

2.14.5 Capturing UDE Details

To capture the UDE details, click 'UDE Details' button.

The screenshot shows the 'UDE Details' window with the following fields and tables:

- Commitment Branch
- Commitment Product
- Commitment Settlement Account
- Commitment settlement Branch
- Populate
- Interest Calculation Method
- PPC Reference No
- PPC Project Id
- Commitment Reference Number
- Primary Customer Id
- Days in Month
- Days in Year

UDE Values

User Defined Element Id	UDE Value	Rate Code	Code usage	Effective Date
-------------------------	-----------	-----------	------------	----------------

Component Grace Days

Component Name	Grace Days
----------------	------------

You need to capture the following details here:

Commitment Branch

Specify the branch in which the commitment contract needs to be created. By default, it will be the same branch in which the facility has been created.

Commitment Product

Specify the product details of the commitment.

Commitment Settlement Branch

Specify the settlement branch details of the commitment.

Commitment Settlement Account

Specify the settlement account details of the commitment.

Note

You can the specify or select the settlement accounts and GLs attached to the liability as Commitment Settlement Account. This is applicable to facility future dated amendment or renewal.

PPC Project Id

The system displays the PPC Project ID to which the facility is linked to.

PPC Reference No

The system displays the PPC reference number to which the facility is linked to.

Commitment Reference Number

Specify the reference number of the commitment.

Note

If a commitment reference number is maintained in the system, then the same is auto populated upon selecting the particular commitment.

Primary Customer ID

Specify the Primary customer ID which is to be used for commitment account. Alternatively, you can select the Primary customer ID from the option list. The list displays all valid customer ID's which in-turn are linked to the liability number used for creating a facility in the system.

Note

The customer ID selected here is displayed as the default customer ID in the Commitment Account Details screen (CLDCMTMT).

Interest Calculation Method

You can specify the following preference to calculate the interest by including or excluding the start and/or the end date of the contract. Select the type of interest calculation method to be used from the drop-down list. The list displays the following values:

- Start Dates Only (Kataha Ato Otoshi) - To include only start dates and exclude end dates.
- End Dates Only (Kataha Mae Otoshi) - To include only end dates and exclude start dates.
- Both Dates + End for Inter (Ryoha Mae Otoshi) - To include start and end date of the contract and to exclude start date of intermediate schedules.
- Both Dates + Start of Inter (Ryoha Ato Otoshi) - To include start and end date of the contract and to exclude end date of intermediate schedules.

Note

The Interest Calculation Method defined here will overwrite the default value if maintained in the Preferences tab of Commitment Account Details screen (CLDCMTMT).

Days is Month

Select the days in month calculation method from the drop-down list. The list displays the following values:

- Actual
- 30-(Euro)
- 30-US

Note

The system by default populates the value maintained from product. You may change it.

Days in Year

Select the days in year calculation method from the drop-down list. The list displays the following values:

- 360
- 365
- Actual

Note

The system by default populates the value maintained from product. You may change it.

UDE Values

You can specify the user defined element values details in the following fields:

User Defined Element Id

Specify the unique identification for the user defined element. The adjoining option list displays all valid IDs maintained in the system. You can choose the appropriate one.

UDE Value

Specify the value for the user defined element.

Rate Code

Specify the rate code. The adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Code Usage

Select the type of code usage from the adjoining drop-down list. The list displays the following values:

- Periodic
- Automatic

Effective Date

Select the effective date from the adjoining calendar.

Component Grace Days

You can specify the Component Grace Days details in the following fields:

Note

You can also auto populate the default Component Grace Days details maintained at product level by clicking on **Populate** button after specifying the commitment details.

Component Name

Select the component name for the commitment product. The adjoining option list displays all component names maintained in the system. You can choose the appropriate one.

Grace Days

Specify the number of grace days for the selected component.

Note

The above UDE details can be used to upload commitment details to Oracle FLEXCUBE as part of Facility maintenance. INIT,VAMI and CLOC events will be triggered only on authorization of Facility. For LINK and DLINK events, 'ELBCOMNT' batch needs to be configured as part of EOD process.

Holiday Treatment for All Schedules

You can define the following holiday preferences for all repayment schedules. The preferences defined here will be defaulted to commitment level and also overwrites the holiday preferences defined at product level.

Ignore Holidays

Check this box to freeze the schedule dates without considering the holidays into account.

If this option is not selected and the schedule date falls on a holiday, the automatic processing of such a schedule is determined by your holiday handling specifications for automatic processes, as defined in the 'Branch Parameters' screen.

Holiday Check

Select the type of holiday check to be maintained from the drop-down list. The list displays the following values:

- Local - To consider the local holiday to adjust the overlapping holiday schedule.
- Currency - To consider the currency holiday to adjust the overlapping holiday schedule.
- Both - To consider both currency as well as local holiday to adjust the overlapping holiday schedule.

Move Across Month

Check this box to allow the schedule date to be moved to the next or previous month when the schedule due date is either on first or last working day of the month and is a holiday.

Cascade Schedules

Check this box to cascade the current schedule change across all the remaining schedules. If not checked, then only the current schedule is changed.

Schedule Movement

If you have opted to move the schedule date across months by selecting the 'Move Across Month' check box, then select the type of movement. The options are as follows:

- Move Forward - if the schedule date is to be moved to first working day of next month.
- Move Backward - if the schedule date is to be moved to last working day of previous month.

Rounding Method

Select the rounding method for commitment fee from the drop down list. The list displays the following values.

- Up - Select this option to round up the interest amount to a decimal value as indicated by the rounding units.
- Down - Select this option to round down the interest amount to a decimal value as indicated by the rounding units.
- Integer Up - Select this option to round up the interest amount to the next higher integer or units (including decimal points).
- Integer Down - Select this option to consider the interest amount if it is equal to or greater than the minimum amount. The remainder due to round down or the decimal part is truncated. You can round down to the minimum amount of digits or units specified.
- Integer Near - Select this option to round up or down. The rounding units can be for following values.
 - – 1
 - – 10
 - – 100
 - – 1000

Note

- If the digit under consideration for rounding is between 0 and 4 (including both), then the value is rounded down.
 - If the digit under consideration for rounding is between 5 and 9 (including both), then the value is rounded up.
-

Rounding Units

Select the rounding units for commitment fee from the drop down list. The list displays the following values:


- 1
- 2
- 3
- 10
- 100
- 1000

Note

- Rounding Units 1, 2 and 3 are applicable for Rounding Method 'Up' and 'Down'. The remaining are applicable for Rounding Methods 'Integer Up', 'Integer Down' and 'Integer Near'.
 - During save, if you do not select the 'Rounding Method' and 'Rounding Units' values, the system displays an error message stating, 'The Rounding Units should be entered'.
 - If you do not maintain rounding parameters at Facility level, the system uses the parameters maintained at commitment product level, if any.
-

2.14.6 Maintaining Collateral Pool Linkages

For collateral Contribution in Total Effective line amount, the pool code maintained for that particular Liability id has to be linked, which can be achieved using this sub screen. From the Facilities Maintenance screen, click on the 'Pool Links' button.



Pool Code

Select the pool code from the adjoining list. The list displays all the pool codes associated for that liability Id.

Pool Description

System displays the pool description based on the selected pool code.

Pool Currency

System displays the pool currency based on the selected pool code.

Pool Amount

System displays the pool amount based on the selected pool code.

Facility Branch

Select the branch code from the adjoining list.

Pool Percentage,

System displays the pool %.

Facility Amount In Pool CCY

System displays the facility amount In Pool currency.

Facility Currency

System displays the facility currency

Facility Amount

System displays the facility amount

Type

System displays the type.

Percentage Of Contract

System displays the percentage of contract.

Pool Linkages multi entry block does two functions:

Firstly, on clicking 'Plus' button you can link one row of the available pool amount (i.e. Pool amount – Pool Utilized) to that Line code for which the collateral contribution is required. Secondly, it displays at any point in time the pool amount (in percentage terms) utilized by various Line Codes and Contracts.

2.14.7 Maintaining Restrictions for a Line

By default, all customers, branches and products maintained in your bank can utilize the limit defined for a credit line. You can also define the limit for a line in any currency. However, you can opt to restrict the limit available under a credit line to specific customers, branches, products and currencies.

You can define these restrictions in the Limits Restrictions screen. To invoke this screen, click 'Limit Restrictions' button from the Facilities Maintenance screen.

Restriction Maintenance

Restriction Type Allowed
 Disallowed

Currency Restrictions Allowed
 Disallowed

Customer Restrictions

1 Of 1 | Go | + | - | [List Icon]

Customer No *	Short Name

Currency Restrictions

1 Of 1 | Go | + | - | [List Icon]

Currency *	Currency Name

Branch Restrictions Allowed
 Disallowed

Restriction Type Allowed
 Disallowed

Branch Restrictions

1 Of 1 | Go | + | - | [List Icon]

Branch Code *	Branch Name

Product Restrictions

1 Of 1 | Go | + | - | [List Icon]

Source Code	Product Code *	Product De

OK Exit

Restriction Type

Select the restriction type for each restrictions defined for the facility from the following options:

- Allowed
- Disallowed
- Customer Restrictions

Customer Number

Specify the customer number for the Customer Restriction

Short Name

System displays the short name for the customer, as maintained in the 'Customer Maintenance' screen based on the selected 'Customer Number' .

Currency Restrictions

Currency Code

Specify the currency code for the Currency Restriction.

Currency Name

System displays the currency name for the currency, as maintained in the 'Currency Definition' screen based on the selected 'Currency Code'.

Branch Restrictions

Branch Code

Specify the branch code for the Branch Restriction.

Branch Name

System displays the branch name for the branch, as maintained in the 'Branch Parameters Maintenance' screen based on the selected 'Branch Code'.

Ext System Restrictions

External System

Specify the external system for the External System Restriction.

Description

System displays the description for the external system, as maintained in the 'External System Maintenance' screen based on the selected 'External System' chosen

Exposure Restrictions

Exposure Name

Specify the exposure name for the Exposure Restriction.

Exposure Description

System displays the description for the exposure, as maintained in the 'Track Exposure Maintenance' screen based on the selected 'Exposure Name'.

Product Restrictions

Product Code

Specify the product code for the Product Restriction.

Product Description

System displays the description for the product based on the selected 'Product Code'

2.14.7.1 Maintaining Customer Restrictions for a Line

To recall, you can assign a limit to a Line - Liability combination. A liability code can have several customers linked to it. By default, the line that you define is available to all customers linked to the liability code.

You can restrict the limit available under this line-liability combination to specific customers. If you choose the restriction type as 'Allowed', click on the 'Plus' button and select the customer code from the list to indicate that they are allowed to use the line. If you choose the restriction type as 'Disallowed', click on the 'Plus' button and select the customer code from

the list to indicate that they are not allowed to use the line. Once you choose restriction type as 'Allowed', you can restrict a customer(s), from using the credit under a line by highlighting the code that identifies the customer and clicking on the 'Minus' button". You can remove the restrictions earlier imposed on a customer i.e., (allow a restricted customer usage of the limit under a line). To allow a restricted customer usage of a line, select the customer code from the list and click on the 'Plus' button.

2.14.7.2 Maintaining Branch Restrictions for a Line

You can restrict the usage of a credit line that you have defined to certain branches of your bank. If you choose the restriction type as 'Allowed', click on the 'Plus' button and select the branch code from the list to indicate that those branches of your bank can use the line. If you choose the restriction type as 'Disallowed', click on the 'Plus' button and select the branch code from the list to indicate that those branches of your bank are not allowed to use the line.

Once you choose restriction type as 'Allowed', you can disallow a branch(s) from using this line by selecting code that identifies the branch and clicking on the 'Minus' button". You can remove the restrictions earlier imposed on a branch i.e., to allow a restricted branch usage of the limit under this line. To allow a restricted branch usage of a line, select the code that identifies the branch from the option list and click on the 'Plus' button.

2.14.7.3 Maintaining Currency Restrictions for a Line

Just as you can restrict the limit defined for a line to specific customers, branches, and products, you can restrict it to specific currencies. Once you choose the restriction type as 'Allowed', select the currencies to which you would like to restrict application from the available option list. The list of currency codes you choose in this field will be described in the adjacent column.

To remove a currency from the list of allowed currencies, highlight the currency code and click on the 'Minus' button. To add a currency to the list of allowed currencies, click on the 'Plus' button, and choose the currency from the option list available.

2.14.7.4 Maintaining Exposure Restrictions for a Line


You can also define the types of exposures that should be allowed (or disallowed) for a line. Based on the list you maintain, the system will display an error message if a utilization request with a transaction exposure is received where the exposure for the facility is either disallowed or not maintained as part of the allowed exposures.

Indicate if the exposure codes that you are specifying should be allowed or disallowed. From the option list available, select the exposure codes. The system defaults the description of the chosen exposure codes. To remove an exposure code from the list, highlight the code and click on the 'Minus' button. To add to the list, click on the 'Plus' button, and choose the exposure code from the option list available.

While saving the record, if the exposures disallowed here are found to be linked to existing Facility Exposures or Customer Liability Exposures, the system will display an error message and will not save the details.

2.14.7.5 Maintaining Product Restrictions for a Line

You can define the types of products that should be allowed or disallowed for a line. To add a product to the list of allowed products, click on the 'Plus' button and select the Source and Product Code from the adjoining option lists. The system defaults the description of the chosen source and product code.



To remove a product from the list of Allowed Products, select the Product Code and click on the 'Minus' button.


Note

System considers both the source and the product code to validate the restriction.

2.14.8 Defining Tenor based Restrictions

You can define Limits based on the tenor of the contracts that utilize the limit.

Click 'Tenor Restrictions' button from the Facilities Maintenance screen to maintain Tenor restrictions for the limit you have specified for the Line-Liability combination.



Tenor

Specify the name of the tenor.

Days

Specify the number of days

Limit

Specify the limit for the tenor in days.

Utilization

System displays the utilization amount for the specific tenor in days, based on the utilization of the facility in 'Schedules' sub screen

Limit Date

Specify the limit date on which the limit amount is updated in the 'Limit Amount' field

Limit Amount

Specify the limit amount for the specific limit date

You need to enter details in this screen only for transactions that involve a Tenor (e.g. Loans, Money market transactions etc). Through this screen you can specify a list of Tenors and the associated limit that tenor based transactions can utilize under this line.

2.14.8.1 Maintaining Tenor Restrictions for a Main Line

For a main line, you can:

- Specify the list of tenor restrictions for which you would like to limit your exposure.
- Assign limits for the Tenor restrictions.

2.14.8.2 Maintaining Tenor Restrictions for a Sub-Line

You can define a sub-line tenor list and also define limits for each of them. To recall, a sub-line falls under the umbrella of the Main Line to which it is linked. Therefore, the maximum tenor that you define for a sub-line should not exceed the maximum tenor defined for the main line to which it is linked. The limit amount that you define for each sub-line tenor cannot be higher than the tenor limit defined for the main line to which it is linked.

Tenors and limits can be placed at both the sub-line and main line levels. But the maximum tenor of a sub-line cannot exceed the maximum tenor defined for the main line to which it is linked.

Example

You define a Line LOANS and link it to the Liability Code CREATIVITY INC. (the Liability and the Customer Code in this case are the same). The limit set for this line - LOANS is \$ 1million.

Main Line Code
LOANS

You define a credit limit of \$ 1 million for Creativity Inc. under this Credit Line. You also specify the tenor Restrictions for the line to be the following 30D, 60D, and 90D.

Main Line Tenor List	Limit
30D	0.5M
60D	0.3M
90D	0.25M

The loans that this customer can avail can be further classified into Short, Medium and Long Term Loans.

For our example we shall make Short Term, Medium Term and Long Term loans as sub-lines under the Main Line Loans. It is only when you link these credit lines to the Credit Line Loans that it becomes a Main line.

Sub-line Code
STLOANS
MTLOANS
LTLOANS

You can define a tenor list and have tenor based limits for both the *Main Line* and *Sub-lines*. So we shall also maintain tenor based limits for the sub-line STLOANS (as shown in the table below):

Sub-line Tenor List	Limit
30D	0.3M
60D	0.2M
90D	0.1M

You can add to the list of tenors maintained for a Main Line by specifying the Tenor restriction under the head Tenor and clicking on the 'Plus' button. If you want to remove a tenor restriction from the list of tenor restrictions highlight it and click on the 'Minus' button.

2.14.9 Maintaining Source Restrictions

You can specify which sources are allowed or restricted to access the facility in 'Source Restrictions' screen. Click on 'Source Restrictions' button in 'Facilities Maintenance' screen to invoke this screen.

The screenshot shows a software window titled "Source Details". At the top, there is a "Category restriction" section with two radio buttons: "Allowed" and "Disallowed". The "Disallowed" option is selected. Below this is a table with two columns: "Source" and "Description". The table is currently empty. At the bottom right of the window are "Ok" and "Exit" buttons.

Category Restriction

To maintain an allowed list of liability restrictions choose the 'Allowed', option. To maintain a disallowed list of liability restrictions, choose the 'Disallowed' option.

Default value of this field will be 'Disallowed'. If you select restriction type as 'allowed', then you will have to input at least one record.

Source

Specify the source from the adjoining option list.

Description

Give a brief description about the System restriction here.

2.14.10 Maintaining Mandate Details

You can maintain mandate information for specific line codes using 'Mandate' screen. Click 'Mandate' button on 'Facility Maintenance' screen.

The screenshot shows a web-based application window titled "Mandate Details". At the top, there are two input fields labeled "Line Code" and "Serial No". Below these is a section titled "Mandate Details" which contains a table with two columns: "Type" and "Min% Available". The table is currently empty. At the bottom right of the window, there are "OK" and "Exit" buttons.

You can specify the following details here:

Line Code

Specify the line code for which the mandate has to be maintained. The system displays the line code from the main screen of facility.

Serial Number

The system displays the line serial number of the line code maintained.

Mandate

Collateral Type

Specify the collateral type required for validating mandate for the utilization transaction. The option list displays all valid collateral types maintained in the system. Choose the appropriate one.

You can add more rows to the list using add button.

Min % Available

Specify the minimum percentage of the specific collateral type to be collected while processing the utilization transaction against the line code specified. The system verifies whether the mandate percentage of the line utilization amount is greater than the collateral limit contribution. If the mandate percentage is higher, the system displays an override message. You may choose to continue or cancel the maintenance.

2.14.11 Including Netting Amount in Facility's Netting Contribution

You can set the available amount under a Facility to include the Netting Amount too. To enable this feature you must check the 'Netting Required' check box in the following levels:

- Customer Account- Limits tab
- Liability level
- Facility level

Once the netting option is enabled in the above levels the Netting amount maintained as a part of Account Netting screen will be added to the available amount of the facility in facility currency. The netting amount field in the facility screen will be displayed in the Netting Contribution field for the facility in facility currency.

Customer Account- Limits Tab

When an Account Netting Record is closed and authorised, the system will automatically subtract the netting amount from Available Amount and the Netting Amount for the corresponding facility.

When an Account Netting Record is re-opened and authorised, the system should automatically add the netting amount to Available Amount and the Netting Amount for the corresponding facility.

Facility


When the Netting option is un-checked and the modification is authorised, the system will automatically set the netting amount to zero and recalculate the available amount. Likewise, when the netting option is enabled, the system will update the netting amount based on all the Account Nettings which have Netting option enabled for the facility.

Liability

When the Netting option is un-checked and the modification is authorised, the system will automatically set the netting amount of all its facilities to zero and recalculate the available amount. Similarly when the netting option is enabled the system will update the netting amount based on all the Facilities and Account Nettings records, which have Netting option enabled for the liability.

2.14.12 Viewing Previous Credit Limit Changes

You can view previous changes made to the credit limit using the 'Facilities Summary' screen. You can invoke this screen by typing 'GESQYFAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query on records based on all or any of the following criteria:

- Authorization Status
- Mod No
- Serial No
- Line Currency
-
- Record Status
- Line Code
- Liability No
-

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Mod No
- Line Code
- Serial No
- Liability No
- Line Currency
- Eff. Line Amount Basis
- Limit Amount

- Eff, Line Amount
- Utilisation
- Available Amount
- Avl Flg
- Start Date
- Expiry Date
- ID

To view any previous changes made to the credit limit, double-click the corresponding record. A detailed screen appears containing changes made.

The screenshot displays the 'Facilities Maintenance' application window. The interface is organized into several sections:


- Header:** Includes 'New' and 'Enter Query' buttons.
- Liability Details:** Fields for Branch Code, Liability No*, Liability Name, Line Code*, Serial No*, Description, Main Line Code, Main Line Currency, Main Line Exchange Rate, Line Currency*, and Category.
- User Defined Status:** Fields for User Defined Status, Status Changed On, and a set of checkboxes: Revolving Line, Netting Required, UnAdvised, Fund, Shadow Limit, and Bulk Payment Required.
- Internal Remarks:** A text area for notes.
- Amounts:** Fields for Limit Amount, Collateral Amount, Transfer Amount, Effective Line Amount, Effective Line Amount Basis (dropdown menu), Uncollected Amount, Block Amount, Approved Limit Amount, Day Light OD Limit, and Day Light Limit.
- Utilization:** Fields for Available Amount, Date Of First OD, Date Of Last OD, Netting Contribution, Net Amount Utilized Today, Utilized Amount, Tanked Utilization, and Last New Utilization Date.
- Availability:** Fields for Line Start Date, Line Expiry Date, Expiry Allowance Date, and checkboxes for Available and Renewal. Includes an Amendment Date field.
- Exception:** Fields for Exception Transaction Amount and Exception Breach Percentage.
- Interest Fee Required:** A checkbox for Interest Fee Required and a Fee Calculation Account field.
- Footer:** A navigation bar with links: Limit Restrictions | Tenor Restrictions | Source Restrictions | Schedules | Value Date | Charges | Covenants | Pool Links | Exposures | UDE Details | User Defined Status Log | Mandate Details | Fields | and an 'Exit' button.

Note

This is a view-only screen hence you cannot make any modifications in this screen.

2.14.13 Specifying Power Pocket Limit

The power pocket facility is configured for a loan account. When there are payments exceeding the principal demand for a loan, and within a threshold range, an OD facility is created on the CASA account. You can view power pocket limit information for specific line codes using the 'Power Pocket Limit' screen. To view this screen, click 'Power Pocket Limits' button on the 'Facility Maintenance' screen.



Loan Account Number

The system displays the loan account number for which the prepayment records are being inserted.

Limit Amount

The system displays the prepayment amount of the loan account.

Limit Date

The system displays the transaction date of the loan prepayment.

A pre-payment may result in the creation of a new facility or an update of limits to an existing facility. When a new facility is being created, the start date of the facility would be the value date of the prepayment of the loan account. The end date would be the maturity date of the loan account with other values as 'Available', type as 'Revolving' and basis amount as 'Limit'. If an account already has an OD limit line linked to it, then the 'Power Pocket Limit' is updated with the entries of the loan account's prepayment values. The limit amount is updated to the existing limit amount which includes the limit from the 'power pocket limit' screen, if power pocket preference at the loan account is selected.

On every prepayment at the loan account level, a record is inserted in this screen. Whenever the power pocket facility to the account is revoked, then the system reverses the power pocket limit against the linked facility. If there is any prepayment (including the first prepayment which has created the line) reversal at the loan account, then the limit amount is reversed by the system. This in turn will reduce the overall limit amount of the line.

If there is any utilized amount due to the power pocket limit and the supporting power pocket limit is lesser than the utilized amount, it will be treated as 'over line utilization' and separate interest and/or charges will be charged according to the interest rate and/or charge maintenance.

An SDE 'POWER_POCKET_LIMIT' is used to apply different interest rate for 'Power Pocket Limit' and normal OD which can be achieved through IC rule/formula. *For more information on setting up an SDE refer to section "Maintaining System Data Elements" in the Interest and Charges User Manual.*

The interest conditions/criteria are maintained in the 'Interest and Charges Product Maintenance (ICDPRMNT)'. If a debit settlement account of the loan account which has power pocket limit is being modified at the loan account level, then the user needs to delink the power pocket preferences at the loan account level with the old debit settlement account and attach a new debit settlement account with another action of loan amendment.

When a CASA linked to the loan account has multiple lines associated with it and a power pocket facility is chosen for that loan account, then the system displays an error message. Similarly, if a loan account has a power pocket facility extended to a CASA, while CASA has only one line linked to it and a new line is associated with that CASA, then an error message is yet again displayed.

2.15 Track Exposure Maintenance

Maintenances for exposure tracking can be done via the 'Track Exposure Maintenance' screen. This screen not only allows tracking, but also allows you to define a limit for a particular exposure. This means that when the utilization exceeds the limit, you will have to provide a confirmation for process to proceed.

You can invoke the 'Track Exposure Maintenance' screen by typing 'GEDTREXP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Track Exposure Maintenance' application window. The title bar includes a diamond icon, the text 'Track Exposure Maintenance', and standard window controls. Below the title bar is a toolbar with 'New' and 'Enter Query' buttons. The main area contains a form with the following fields and controls:

- Exposure Code * (text input)
- Description (text input)
- Exposure Currency (text input)
- Exposure Amount (text input)
- Block Amount (text input)
- Utilization (text input)
- Exposure Effective Date (date input)
- Exposure Renewal Date (date input)
- Exposure Expiry Date (date input)
- Freeze (checkbox)
- Exposure Rating (text input)
- Remarks (text input)
- Available Amount (text input)
- Exposure Type (text input)
- Utilisation type (radio buttons for Customer, Transaction, Revolving)

At the bottom of the window, there is a table with the following columns: Value Date Exposure | Fields. The table has four rows of data:

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

An 'Exit' button is located in the bottom right corner of the window.

Exposure Code

Specify the Exposure Code. The code maintained in this screen can be linked in the 'Customer to liability link Maintenance' screen if the 'Utilization type' is 'Customer' and it can be linked in the 'Facilities Maintenance' screen if the 'Utilization type' is 'Transaction' to make exposure tracking possible. It is possible to track a customer in multiple exposures. For this multiple exposure code should be linked to the 'Customer to liability link Maintenance' screen.

Description

Provide a brief description of the exposure here.

Exposure Type

Specify what kind of exposure it is. The exposure types will be as maintained in the Static Maintenance screen 'Exposure Maintenance' having function id CODEXPTY.

Utilization Type

Indicate whether exposure is linked with customer or transaction.

As part of utilization, a maximum of five exposures can be linked to customer and another five exposures can be linked to a facility.

Revolving

Check this box if the exposure is a revolving exposure. This implies that each time a repayment is made (revolving amount) against the exposure, the available limit for the exposure is increased by the amount of repayment. In case of non-revolving exposure, the available limit is the amount of exposure reduced by the loans already availed by the customer (if any); repayment does not increase the limit.

This can be denoted in terms of utilized amounts as follows:

For revolving exposure: $\text{New Exposure utilization} = \text{Exposure utilization} - \text{Revolving amount}$

For non-revolving exposure: $\text{New Exposure utilization} = \text{Exposure utilization}$

Exposure Currency

Specify the currency in which the Tracking of Exposure has to be maintained. Once authorized, this field will be non-amendable.

Exposure Amount

Specify the exposure limit amount which is to be maintained for each exposure tracking maintenance. A confirmation will be sought during utilization when the utilization amount crosses the exposure amount.

Block Amount

The value of the 'Block Amount' field in the 'Global Exposure Block Maintenance' screen is displayed here.

Utilization

System displays utilization for the exposure here.

Exposure Effective Date

Specify the effective date after which the maintained exposure becomes valid or applicable.

Exposure Renewal Date

Specify the exposure Renewal date. This is only for information purposes.

Exposure Expiry Date

Specify the expiry date after which the maintained exposure is not applicable for tracking.

Freeze

Select this check box to indicate that the exposure will be frozen and during utilization. Exposure tracking will not be allowed for such an exposure (i.e. Utilization under such exposures will not be allowed).

Exposure Rating

Specify the rating of the exposure (e.g. Sovereign rating). This is only for information purposes.

Remarks

Add remarks about the track exposure maintenance, if any.


Available Amount

This is the limit amount that is considered when processing utilization requests for an exposure. It is the amount available after taking into account previous utilizations and amount block (earmark) in force for an exposure. It is calculated as shown below:

Exposure Available Amount = Exposure Limit Amount – Utilization – Exposure block amount

2.15.1 Maintaining Value Date Exposure Details

Value dated exposure can be specified using the Value Date Exposure screen. Click 'Value Date Exposure' to invoke this screen.



The screenshot shows a software window titled "Value Date Exposure". At the top, there is a navigation bar with "1 Of 1" and a "Go" button. Below this is a table with two columns: "Value Date" and "Exposure Amount". The table is currently empty. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

For each record added here you must specify the following:

- Exposure Amount - The value dated Exposure amount
- Value Date - The value date post which the mentioned amount is valid

2.16 Ear Marking Maintenance

You can use the 'Ear Marking Maintenance' screen for blocking of funds for a Facility.

You can invoke the 'Ear Marking Maintenance' screen by typing 'GEDBLOCK' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'EAR Marking Maintenance' application window. The window title is 'EAR Marking Maintenance'. The interface includes a toolbar with 'New' and 'Enter Query' buttons. The main area contains several input fields: 'Amount Block Number *', 'Branch * 400', 'Liability No', 'Customer No *', 'Line Code *', 'Serial No', 'Block Currency *', 'Block Amount *', 'Effective Date', 'Expiry Date', an 'Auto Block' checkbox, and a 'Remarks' text area. At the bottom, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Amount Block Number

Specify the unique number which is to be assigned for every block that has been created.

Branch

Specify the branch in which the block has been created.

Liability No

Specify the liability code for which the amount block is to be done.

Customer No

Specify the customer for whom the amount block is to be done.

Line Code

Specify the Line code for which the amount block is to be done.

Serial No

System displays the serial number for the line chosen in the field 'Line Code'.

Block Currency

Specify the currency based on which the Block amount for the facility has to be considered. Once authorized, this entry will be non-amendable.

Block Amount

Specify the amount to be blocked for ear marking.

Effective Date

Specify the date from when this block amount for that facility becomes effective.

Expiry Date

Specify the date till when this block amount for that facility is applicable.

Auto Block

Check this box to indicate that the system should automatically create block for the specified amount for the specified facility. This check box will be unchecked by default indicating that the block on the facility will be manual.

Remarks

Add remarks about the ear marking maintenance, if any.

2.17 Global Block Exposure Maintenance

You can block (earmark) a certain amount of an exposure limit using the 'Global Block Exposure Maintenance' screen.

You can invoke the 'Global Exposure Block Maintenance' screen by typing 'GEDEXPBL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Global Exposure Block Maintenance

New Enter Query

Block No *
Branch * 400
Exposure Code *
Exposure Description
Block Currency *
Block Amount *
Effective Date
Expiry Date
 Auto Block

Additional Information

Customer No
Liability No
Remarks
Line Code
Serial No

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	Exit

Block No

Specify a unique number for the block you are creating. The system will not allow you to modify it after authorization of the maintenance.

Branch

Specify the branch from which the block is being maintained. You cannot change the branch after authorization of the maintenance.

Exposure Code

Specify the exposure code for which the amount block is to be done. The adjoining option list contains all the relevant codes. Select the appropriate one.

Exposure Description

The system defaults the exposure description here.

Block Currency

Specify the currency in which the amount block is to be applied. You cannot modify this once the maintenance has been authorized.

Block Amount

Specify the amount to be earmarked. This amount is deducted from the existing utilization of an exposure before additional utilization requests are processed.

Note

It is also updated as the 'Block Amount' in the 'Track Exposure Maintenance' screen.

Effective Date

Specify the date from which the amount block should be applied for the exposure.

Expiry Date

This is the date till which the amount block for the exposure is enforced.

Auto Block

The system automatically checks this option on the date the block on the exposure comes into force i.e. the 'Effective Date'.

2.17.1 Additional Information

As part of additional information for the exposure, you can capture the following details:

Customer No

Specify the customer number for the global exposure block maintenance.

Liability No

Specify the liability number for the global exposure block maintenance.

Remarks

Add remarks about the global block exposure maintenance, if any.

Line Code

Specify the line code for the global exposure block maintenance.

Line Serial

System displays the serial number for the line chosen in the field 'Line Code'.

2.18 Exception Queue Maintenance

You can maintain exception queue records with their respective user roles allowed for authorization in the 'Exception Queue Maintenance' screen.

You can invoke the 'Exception Queue Maintenance' screen by typing 'GEDQUEMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Exception Queue Maintenance' application window. At the top, there is a title bar with the text 'Exception Queue Maintenance'. Below the title bar, there are two buttons: 'New' and 'Enter Query'. Underneath these buttons are two text input fields: 'Queue Name *' and 'Description'. Below the input fields is a section titled 'Queue Details'. This section contains a table with two columns: 'Role Name' and 'Description'. The table currently shows '1 Of 1' records. At the bottom of the window, there are several fields: 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. There is also an 'Exit' button in the bottom right corner.

Queue Name

Specify the Queue Name.

Description

Give a brief description of the queue here.

Queue Detail

Here you can specify multiple user roles for a Queue name. For each record you must specify the Role Name i.e. the user role allowed for authorization. System then defaults the description for the role

2.19 Exception Queue Slab Maintenance

As a part of BEPL process for Credit Exception management, the Transaction authorizer details and breached authorizer details can be entered in the 'Transaction Authorize Maintenance' screen.

You can invoke the 'Exception Queue Slab Maintenance' screen by typing 'GEDTAUTH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Exception Queue Slab Maintenance' application window. The window title is 'Exception Queue Slab Maintenance'. The interface includes a top toolbar with 'New' and 'Enter Query' buttons. Below the toolbar are three input fields: 'Branch *', 'Description', and 'Category'. The main area is divided into two sections: 'Transaction Details' and 'Breached Details'. Each section contains a table with columns for 'Queue Name', 'From Amount', and 'To Amount'. The 'Transaction Details' table is currently empty. The 'Breached Details' table also appears to be empty. At the bottom, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

The transaction authorizer queue first checks for authorizers maintained for that particular branch and category during a utilization transaction for that branch. If no authorizers are maintained for that branch then a default authorizer will be assigned to all branches.

The Default Authorizer details will be used for processing Credit Exception management.

Branch

Specify the branch for which the maintenance is being done.

Description

The description for the branch chosen in the field 'Branch' is displayed here.

Remarks

Specify the remarks about the Transaction Authorize Maintenance

Category

Specify the category for which the transactions authorize maintenance is being done. Having specified the category for the liability and the facility, the transaction authorize maintenance can be done for the same category. When the Exception Txn Amount or Exception Breach Percentage gets breached for a line belonging to the same category as defined in the transaction authorize maintenance, the transaction will be available in the queue defined in the transaction authorize maintenance for the specific category

Transaction Details

Here for each record you can specify the following:

- Queue Name – Specifying this will in turn fetch all the user roles attached to the queue name. During utilization transaction users having these roles will have to perform the authorization for the corresponding amount range.
- From Amount and To Amount – For specifying the amount range

Breached Details

Here for each record you can specify the following:

- Queue Name – Specifying this will in turn fetch all the user roles attached to the queue name. During utilization transaction users having these roles will have to perform the authorization on Breached Transaction amount blocks.
- From Amount and To Amount – For specifying the amount range to define the block of amount

2.20 Limits & Collaterals Parameter Details

You can specify certain parameters relating to the End Of Day operations in the 'Limits & Collaterals Parameter Details' screen.

You can invoke the 'Global Exposure Parameter Detail' screen by typing 'GEDPARAM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Global Exposure Parameter Detail' window. It features a top toolbar with 'New' and 'Enter Query' buttons. The main area contains several input fields and radio button options:

- Maximum No of Processes * 1
- Rate Type STANDARD
- Currency System
- CRM System
- Maximum Retry Lock Transaction * 5
- System Maker ID *
- System Checker ID *
- Auto CNR
- Exposure Tracking
- Generate Customer Number
- CIF Mask 1
- Bank Capital
- Limit Currency JPY
- Central Bank Lending Percent
- Internal Lending Percent
- Reevaluate Currency Online Batch Online
- Reevaluate Market Online Batch Online
- Rate Range Mid Rate Buy Rate Sell Rate
- Holiday Treatment System Date Next Working Day - 1
- UPD Utils Batch Online
- Block Facility On Status Yes No

At the bottom, there is a 'Fields' section with columns for 'Maker Checker', 'Date Time:', 'Mod No', and 'Record Status Authorization Status'. An 'Exit' button is located in the bottom right corner.

The following details are maintained here.

System Maker ID and System Checker ID

During the processing of user entries, if the maker ID and checker ID is not mentioned, then IDs specified here will be recorded.

Maximum Retry Lock Transaction

Specify the number of times authorization can be tried before the transaction is locked.

Maximum Number of Processes

Multi threading feature in Oracle FLEXCUBE ELCM can be controlled by specifying the max number of processes here. In case of load balancer during End Of Day batch operations the maximum process for load sharing can be specified using this field.

Rate Type

Specify the rate type that has to be considered for all amount conversions in Oracle FLEXCUBE ELCM.

Currency System

Specify the external currency system if the Bank is using a external currency system other than the one provided in Oracle FLEXCUBE ELCM.

CRM System

Specify the external CRM system if the Bank is using an external CRM system other than the one provided in Oracle FLEXCUBE ELCM.

Generate Customer Number

Check this box to generate the customer number automatically at the time of customer creation and customer replication from the Oracle FLEXCUBE as per the specified customer mask.

Auto CNR (Auto Closure of Non Revolving Line)

Check this box to close the non-revolving line automatically on expiry date.

Exposure Tracking

Check this check box if exposure tracking is to be enabled in the system.

Customer Mask

If you have selected 'Generate Customer Number' option, you need to specify the customer mask.

The customer mask will be maximum nine characters length, out of which it is mandatory to use three characters from the branch code of the customer number and the rest six can be numbers. E.g. bbbnnnnnn. If branch code is not part of customer mask, then maximum characters of number digit will be nine else it would be six characters and minimum characters of number digit would be four. E.g. nnnnnnnnn.

If the customer number is less than nine digits, then the system will left pad it with '0' i.e zero.

Note

Character 'b' indicates the branch code and character 'n' indicates number digits.

Bank Capital

Specify the amount to calculate internal lending equivalent amount

Limit Currency

The System defaults the local currency of the bank.

Central Bank Lending Limit %

Specify the percentage of central bank lending limit. Central Bank Lending Limit percentage of the bank capital is considered as limit amount allowed by the central bank. The central bank lending limit percentage should be between 0 and 100.

Internal lending Limit %

Specify the percentage of internal lending limit. The internal lending limit percentage should be between 0 and 100.

Note

If Bank Capital is specified then Central Bank Lending Limit % and Internal Lending Limit % fields are mandatory.

Revalue Currency Online

Indicate whether the currency revaluation should be an online or a Batch (EOD) process. Revaluation of the line amount takes place online if the parameter is set to online.

Revalue Market Online

Indicate whether Market price revaluation should be Online or Batch. Market price based security Revaluation takes place online if the parameter is set to online.

UPD Utils

Specify whether Value date utilization updating can be Online or Batch. Value date updating takes place online if the parameter is set to online.

Block Facility on Status

Indicate whether, depending on the worst status of a liability, the EOD process should block the facility or not.

Rate Range

Specify the rate - Mid Rate, Buy rate, Sell rate - which has to be considered during all Conversion Amount calculations in Oracle FLEXCUBE ELCM.

Batch Process

Indicate whether the EOD Batch Process should be set up as part of the Database Server or the Application Server. Application server is the recommended choice.

Holiday Treatment

The revaluation process for the securities, collaterals and covenants may fall on a bank holiday. You can specify which of the following actions must be taken in such cases:

- System Date – Choose this to indicate that only collaterals with a Reval Date prior to or same as the system date will be considered for revaluation.
- Next Working Date -1 – Choose this to indicate that all the collaterals with the Reval Date prior to or same as the day before the next working date will be considered.

The EOD process closes all the active non-revolving lines automatically when the check box 'Auto CNR' is checked. Example

Limits:

Facility	Expiry Date	Revolvin g
FACILI- TY1	15-Jul-2009	N
FACILI- TY2	16-Jul-2009	Y

FACILI- TY3	16-Jul-2009	N
FACILI- TY4	15-Aug- 2009	N

System Date - 15-Jul-2009

Next Working Day - 17-Jul-2009

On 15-Jul-2009 EOD, the system closes FACILITY1 and FACILITY3.

Note

This process does not close the following lines:

- If there are any underlying active transactions on that line
 - If there are any active sub lines reporting to this main line
-

If line is not closed due to the above exceptions then the system logs the same into an exception table 'GETB_EXCEPTION_LOG'. If particular line is not closed on expiry date due to the above exception then same line is taken up for auto closure process on next EOD.

2.21 Facilities Amount Transfer Maintenance

Transfer of full or partial limit amounts from one facility to other within or across liabilities for certain periods is possible. It is also possible to close/cancel this transfer operation before a specified End Date.

Upon manual closure/cancellation or on automatic expiry, the system will transfer the transferred amount back to the original line.

For the above functionality you must do the following maintenances.

Limit transfer details can be defined through the 'Facilities Amount Transfer Maintenance' screen. You can invoke the 'Facilities Amount Transfer Maintenance' screen by typing

'GEDTRANS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

From Liability Number and To Liability Number

Specify the 'From Liability No' i.e. for whom the limit amount is to be transferred

Specify the 'To Liability No' i.e. to whom the liability amount is allocated.

From Liability Name and To Liability Name

System will default the names of the 'From Liability' and 'To Liability' when the 'From Liability Number' and 'To Liability Number' are chosen respectively.

From Line and To Line

Specify the 'From Line' i.e. the Line from which the line amount is transferred.

Specify the 'To Line' i.e. the Line to which the line amount is transferred to for a specified period.

From and To Facility Currencies

System will default the names of the from facility currency and to facility currency when the 'From Line' & 'To Line' are chosen respectively. For effective line transfer from one line to another, the currency of both the lines has to be the same.

From Facility Start Date and End Date

System will default the from facility start date and from facility end date when the 'From Line' is chosen. To Facility Start Date and End Date

System will default the 'To Facility Start Date' and 'To Facility End Date' when the 'To Line' is chosen.

From Facility Available Amount and To Facility Available Amount

System will default the 'From Facility Available Amount' and 'To Facility Available Amount' when the 'From Line' & 'To Line' are chosen respectively.

Effective From Date and Effective To Date

Specify the Effective From Date of transfer i.e. the date from when the transfer of limits will be effective.

Specify the Effective To Date of transfer i.e. the date till when the transfer of limits will be effective. This date must be greater than the Effective From Date


Transfer Amount

Specify the transfer amount to be transferred, from the 'From Line' to the 'To Line', from the 'Effective From Date' onwards.

2.22 Force Collateral Revaluation

You can run the Ad-hoc revaluation process for market based collaterals using the 'Ad Hoc Revaluation' screen. For such collateral values to be revised, an input file containing the latest security prices must be given to the system before using this facility.

You can invoke the 'Ad-hoc Revaluation' screen by typing 'GEDADREV' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Security Id

Specify the security id for which Ad-hoc Revaluation is to be done.

Market Price Code

System displays the price code as maintained in the 'Securities' screen.

Click the 'Process' button to process the Ad-hoc Revaluation.

2.23 Multi Authorization Maintenance

Multi authorisation maintenance can be done via the 'Multi Authorisation Maintenance' screen.

You can invoke the 'Multi Authorization Maintenance' screen by typing 'GEDDAUTH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Whenever Utilization Transactions has been breached then the utilization transaction would require multiple authorizations. Transactions which are breached could be either authorized using BPEL process flow Credit Exception management or using UI multi Auth screen.

Note

During implementation either the BPEL process needs to be used or the screen here needs to be used. Both can't be used at the same time

Whenever utilization transaction has been breached this screen has to be used by the authorizer to either Accept or Reject the breached transaction. The following fields mentioned below indicate all the values that will associated with the transaction. The fields are all display fields and cannot be edited for a transaction using this screen. Only Accept or Reject for authorization of the breached transaction is allowed.

Serial Number

Indicates the Oracle FLEXCUBE ELCM generated unique identifier for the transaction.

Utilization Reference Number

Specifies the Oracle FLEXCUBE ELCM utilization reference number.

Customer No

Specifies the Customer Number of the utilization transaction. Customer Number entered should be valid Customer Number in Oracle FLEXCUBE ELCM system.

Transaction Date

Indicates the date and time when the transaction was entered in the external system.

Utilization Amount

Indicates the Utilization Amount.

Utilization Currency

Indicates the currency of the utilization transaction. Currency code entered should be a valid currency code in Oracle FLEXCUBE ELCM system.

Liability No

Specifies the liability number of the utilization transaction. Liability Number entered should be valid Liability Number in Oracle FLEXCUBE ELCM system.

Line Code

Specifies the facility code of the utilization transaction. Facility Code entered should be valid Facility Code in Oracle FLEXCUBE ELCM system.

Serial No

Specifies the facility serial number of the utilization transaction.

Facility Currency

Specifies the facility currency.

Limit Util

Indicates the facility utilization amount.

Utilization Branch

Indicates the transaction branch.

Utilization Product

Indicates external product code of the utilization transaction. This is only if the utilization has been done from an external product

Value Date

Specifies the value date of the transaction. If value is not passed then system will default to Oracle FLEXCUBE ELCM present branch date.

Source Code

Indicates the product processor name from where the transaction has been originated. This field will be as part of Header section (Source Code). This is only if the utilization has been done from an external product

Utilization status

Indicates the utilization status, possible values are A-Active, R-Reverse, L- Liquated

Delete Status

Indicates whether the transaction is deleted or not. If the check box is selected then it is deleted.

Liability Currency

Specifies the liability currency.

Liability utilization

Indicates the liability utilization amount.

Exception Queue

Specifies the exception queue in which transaction has been parked.

Error Code

Specifies the error code of the transaction.

Error parameter

Specifies the error parameters associated to the transaction.

Remarks

You can enter your remarks associated with the transaction.

2.24 Dual Authorization of Utilization Transaction

During Utilization Transaction process if the utilization amount crosses the breach amount specified, then the transaction requires dual authorization. Transactions which are breached could be either authorized using BPEL process flow Credit Exception management or using UI multi Auth screen. During implementation either the BPEL process needs to be used or the screen here needs to be used. Both can't be used at the same time. You can specify the facility maintenance breach amount and breach percentage in ELCM.

When the transaction amount inputted is more than breach amount or percentage, during utilization process ELCM would flag dual authorized indicator and updates the dual authorization error code as part of response. If response from the ELCM contains dual authorization error code, then Oracle FLEXCUBE logs the transaction details in dual authorization tables and processes it completely.

The authorization for the breached (dual auth) transactions will be authorized using function ID 'GEDDAUTH' of ELCM.

However till the dual authorization happens Oracle FLEXCUBE does not allow you to authorize the main transaction. You can also perform dual authorization using Oracle FLEXCUBE screen, but system performs certain validations to ensure that Oracle FLEXCUBE does not authorize the ELCM breach transactions.

Example

Assume that for liability 'TATA' line 'TATABILL' is created with below details.

Limit amount - 10,000.00

Collateral amount - 0.00

Breach percentage - 110 (which is equal to 11,000)

Brach amount - 15,000

The system calculated values:

Available amount - 10,000.00

Utilized amount - 0

Assume that as part of BC, a contact line 'TATABILL' is linked. As part of the contact data input, when you link the line 'TATABILL' and press 'Save' button during transaction processing in ELCM, if the transaction requires dual authorization then the system displays this information to the user.

Till the dual authorization error code (breached transaction) is authorized in ELCM, Oracle FLEXCUBE does not allow the contact to be authorized. In case, if the breached transaction is rejected, then you have to delete the contact Information irrespective of whether the error code has been authorized or not. Contracts requiring multilevel authorization can be viewed using Oracle FLEXCUBE function 'OVDAUDET'.

If you delete the dual authorization contract in Oracle FLEXCUBE, then the system deletes the contract details in Oracle FLEXCUBE and ELCM will delete the utilization ELCM.

Note

ELCM deletes the utilization transaction if any dual authorization error is not authorized and the system updates the status as 'Ignored' so that this information is not shown to the user. However if the error code is authorized, then this information is ignored.

2.25 Merging Liabilities

You can merge any two liabilities existing in the system into one single liability. Oracle FLEXCUBE ELCM allows you to merge one liability into another. Upon merger, both liabilities will assume the same liability code. The structure of the liabilities will not change.

The merging of liabilities is done in the following two steps:

- Step 1 – Liability Merger Maintenance
- Step 2 – Liability Merger Process

The above steps are described in the sections below.

2.25.1 Liability Merger Maintenance

You must first maintain the details of liabilities to be merged using the 'Liability Merger Maintenance' screen. You can invoke the 'Liability Merger Maintenance' screen by typing 'GEDMERGE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Liability Merger Maintenance' application window. The window title is 'Liability Merger Maintenance'. The interface includes a toolbar with 'New' and 'Enter Query' buttons. The main area contains several input fields: 'Branch Code' (value: 654), 'From Liability Code *', 'To Liability Code *', 'Effective Date', and 'Remarks'. Below the input fields is a horizontal menu with options: 'Customer Link Merger Log', 'Collateral Merger Log', 'Collateral Pool Merger Log', 'Netting Merger Log', 'Facility Merger Log', 'Transfer Merger Log', 'EarMarking Merger Log', and 'Utilization Merger Log'. At the bottom, there is a status bar with fields for 'Maker', 'Date Time:', 'Mod No', 'Record Status', 'Checker', 'Date Time:', 'Authorization Status', and an 'Exit' button.

In the above screen you must maintain the following details for merger of two liabilities.

From Liability Code

Specify using the adjoining list of options the code of the liability which is to be merged into another liability.

To Liability Code

Specify using the adjoining list of options the code of the liability into which the liability specified under 'From Liability Code' must be merged into.

Branch Code

System defaults the branch code as the branch from which the 'Liability Merger Maintenance' screen is launched and 'New' button is clicked.

Effective Date

Specify the date from which the merger of liabilities must take effect.

Remarks

Specify the remarks about the Liability Merger Maintenance.

Once you have maintained the above merger details, you must initiate the Merger Batch Process using an Intra Day Process so as to complete the merger. During this batch process all liability IDs for all the related maintenances will be modified. These include the following maintenances:

- Liability Customer
- Collateral
- Collateral Pool
- Facility
- Netting
- Facility Transfer
- Ear Marking

Upon merger, all the Utilizations will point at the new liability. The liability utilization will then be moved from the old liability to the new liability and the old liability will be closed.

You may view the following merger logs from the above screen:

- Customer Link Merger Log
- Collateral Merger Log
- Collateral Pool Merger Log
- Netting Merger Log
- Facility Merger Log
- Transfer Merger Log
- EarMarking Merger Log
- Utilization Merger Log

2.25.2 Liability Merger Process

Once you maintained the details of liabilities to be merged, you can initiate the process of merger using the 'Liability Merger Process' screen.

You can invoke the 'Liability Merger Process' screen by typing 'GEDMRGTR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Liability Merger Process". At the top left, there is a search icon and the text "Enter Query". Below this, there are seven input fields, each with a label to its left: "Branch Code", "From Liability Code", "To Liability Code", "Status", "Source Code", "User Reference", and "Effective Date". In the bottom right corner of the window, there is a blue button labeled "Exit".

From Liability Code

Specify using the adjoining list of options the code of the liability which is to be merged into another liability.

To Liability Code

Specify using the adjoining list of options the code of the liability into which the liability specified under 'From Liability Code' must be merged into.

Branch Code

System defaults the branch code as the branch from which the 'Liability Merger Process' screen is launched.

Status

System defaults the status.

Source Code

System defaults the Source code

User Reference

System defaults the User Reference.

Effective Date

Note System displays the date from which the merger of liabilities will take effect.

Merger between Liabilities that form part of a hierarchy is not allowed.

2.26 Maintaining Future Dated Amendment or Renewal of Facility

Oracle FLEXCUBE allows you to amend a facility with a future dated effective date. The amendment will take effect only on the date specified. You can amend a facility with a future dated effective date in 'Future Dated Amendment or Renewal of Facility' screen. To invoke

this screen type 'GEDFACAM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

In this screen, you can capture the amendment date and update the following fields during amendment.

Amendment Date

Specify the date of amendment from the adjoining calendar.

Expiry Date

Specify the expiry date from the adjoining calendar. You can extend the date and cannot decrease if a line is linked to any contract.

Expiry Allowance Date

Specifies the final expiry date of the facility.

Note

If you maintain Expiry Allowance Date, system does not close the Facility till this date is reached. When the 'Expiry Allowance Date' is maintained at the Facility level, system validates the loan maturity date with respect to the Expiry Allowance Date. If the loan maturity date is beyond this date, system does not allow the transaction to proceed. System displays error that 'Loan Maturity Date is Beyond the Facility Expiry Allowance Date'

During transaction input, system performs the following validations:

- System compares the loan account maturity date with the Expiry Allowance Date of the linked limit. If the maturity date is less than the Expiry Allowance Date of all the linked limits, transaction becomes successful. However if it is more than the Expiry Allowance

Date of any of the linked limits, then transaction fails. If Expiry Allowance Date is not present, system shall continue to validate the loan maturity date against the Line Expiry Date and show the existing override if the maturity date is beyond the line expiry date.

- You cannot link an expired limit to a new loan.
- If Expiry Allowance Date is less than Line Expiry Date, system displays an error stating Expiry Allowance Date cannot be less than the Expiry Date.
- If there are active loans linked to a facility and if the Facility Expiry Date is modified to be less than the maturity date of the linked loans, system displays an error stating 'Active Loans Exist with Maturity Date Greater than the Expiry Allowance Date'.

Limit Amount

Specify the limit amount. You can only increase the limit amount and cannot decrease it beyond the amount already utilized.

Availment Date

Specify the availment date from the adjoining calendar. You can change the availment date beyond the last utilisation date.

Available

Check this box to indicate whether the line is available along with the change in Availment Date.

Main Line Currency

System displays the main line currency

Main Line Exchange Rate

System displays the main line exchange rate. *For more information on field level explanation, refer to the section 'Facilities Maintenance' in 'Limits & Collaterals' chapter of this User Manual.*

You can also update Commitment, Restrictions and UDF related data. As part of the 'GEBFACLT' Facility batch, you can process the amendment on the Amendment Date. The system will trigger it in the BOD process. During Facility Amendment, the system automatically fires VAMI for the linked commitment contract with the effective date of the VAMI as Amendment Date of Facility.

The amendment of Line End date results in increase in maturity date of attached commitment contract. If there is a change in Limit Amount, it will result in increase or decrease of the attached commitment contract. The amendment of facility fails if amended limit amount is reduced beyond the amount already utilized.

You cannot create new amendments on the facility until a future dated amendment is processed. However, you can modify a future dated amendment.

Note

- The system does not allow facility utilization if future dated amendment. The system displays an error message stating 'Facility cannot be Modified as Future Dated Amendment is Pending'.
 - The system does not allow modification of facility if there are future dated amendment. The system displays an error message stating 'Facility cannot be Modified as Future Dated Amendment is Pending'.
-

You can also close a record when future-dated amendment is yet to be effected, where the amendment is invalidated and will not come into effect. The system defaults the UDFs from the Facility Maintenance, which can be amended.

3. ELCM Data Replication

3.1 Introduction

As a part of ELCM centralized set up, ELCM will be installed as a standalone system. The information related to Oracle FLEXCUBE will be maintained in Oracle FLEXCUBE database, and the information related to ELCM system will be maintained in ELCM database. SMS setup of both Oracle FLEXCUBE and ELCM system will be different.

When a user is created in ELCM stand alone system, basic user details are replicated to Oracle FLEXCUBE instances. ELCM user Id details will not be stored in Oracle FLEXCUBE. So, a user can't login to Oracle FLEXCUBE using ELCM user Id. If an Oracle FLEXCUBE user wants to access ELCM maintenance screen, then SMS rights with ELCM user Id needs to be given. This should be operationally controlled. If the user has rights on ELCM function Ids, when user inputs the transaction in ELCM screen, function will be updated in ELCM stand alone system as well.

A user can input the following function IDs from Oracle FLEXCUBE instance:

Function ID	Replication Details
GEDMLIAB	Liability Input
GEDCULIK	Customer Liability Linkages
GEDCOLLT	Collateral Input
GEDMPOOL	Collateral Pool Input
GEDFACT	Facility Input
GEDBLOCK	Facility Earmarking
GEDTRANS	Facility Transfer
EIDPEDPG	View Pending Unauthorized Transaction
GEDDAUTH	Dual Authorization

Note

All other ELCM Function IDs should be operated from ELCM stand alone system.

Both ELCM and FLEXCUBE needs common data and common data need to be replicated between both the systems. Using ELCM replication framework, data would be replicated online between ELCM to Oracle FLEXCUBE instances and vice-versa.

3.2 Online Data Replication

When the transaction is authorized in the system, replication component applies replication filter to check whether the data needs t be replicated or not.

3.2.1 Replicating Data from Oracle FLEXCUBE to ELCM

As part of replication process following data would be replicated from Oracle FLEXCUBE to ELCM.

Replication Data	Replication Details
Branch	All the Branches with 'ELCM Replication' option selected will be replicated to ELCM.
Branch Holiday	Branch Holidays with 'ELCM Replication' branch option selected will be replicated to ELCM.
Rates	Rates will be replicated to ELCM only if, <ul style="list-style-type: none">• The branch option 'ELCM replication' associated to rates is selected.• The rate types maintained as a part of ELCM parameter.
Product	All product and account class basic details required will be replicated to ELCM.
Customer	If 'ELCM Customer' option at customer maintenance is selected then customer data will be replicated to ELCM.
Account /TD	If the customer of account/TD/CD transaction is ELCM customer then data will be replicated to ELCM
Commitment Reference Number	As part of commitment interface, commitment contract will be created in Oracle FLEXCUBE and commitment contract reference number will be replicated to ELCM.

3.2.2 Processing ELCM Data Replication

You can define the replication mechanism in 'Replication Mode Maintenance' screen. You can invoke this screen by typing 'CODELREP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Source

Specify the Oracle FLEXCUBE instance from the adjoining option list for which the data need to be replicated.

Note

Source Code for Oracle FLEXCUBE instances are:

- FCUBS1 – FCUBS Instance 1
 - FCUBS2 – FCUBS Instance 2
 - FCUBS3 – FCUBS Instance 3
-

Replication Type

Select Synchronous or Asynchronous from the drop-down as a replication type.

Replication URL

If the replication type is 'Synchronous', then specify the servlet URL for replication.

Replication Queue

If the replication type is 'Asynchronous', then specify the JMS queue name for replication.

Remarks

Mention the additional details (if any).

3.2.3 Replicating Data from ELCM to Oracle FLEXCUBE

As part of replication process following data will be replicated from ELCM to Oracle FLEXCUBE.

Replication Data	Replication Details
-------------------------	----------------------------

Liability	Liability details will not be replicated to all the instances of Oracle FLEXCUBE, it will replicate only to customers sources associated to the liability.
Customer liability link	Customer liability link details will not be replicated to all the instances of Oracle FLEXCUBE, it will replicate only to customers sources that are linked to the liability.
Collateral	Collateral details will be replicated to sources maintained as part of collateral maintenance and customers sources associated to the liability.
Collateral Pool	Collateral pool details will not be replicated to all the sources (instances) of Oracle FLEXCUBE, it will replicate all customer sources which are linked to that liability.
Facility details	Facility details will be replicated to only sources maintained as part of collateral maintenance and customers sources associated to the liability.
Credit Approval (Dual authorization)	Credit Approval data will be replicated to specific Oracle FLEXCUBE instance which has initiated the transaction.
User	All ELCM users would be replicated to Oracle FLEXCUBE.
ELCM parameter details	ELCM parameters would be replicated to all the instances of Oracle FLEXCUBE
ELCM customer no	ELCM customer number will be replicated to all the sources associated to the customer.
Commitment Interface	Utilization details related to commitment contract will be replicated to specific Oracle FLEXCUBE instance.

3.2.4 Processing Oracle FLEXCUBE Data Replication

You can define the replication mechanism in 'Replication Mode Maintenance' screen. You can invoke this screen by typing 'CODELREP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Source

Specify the ELCM source from the adjoining option list for which the data need to be replicated.

Note

Source code of ELCM instance is 'SELCM'.

Replication Type

Select 'Synchronous' or 'Asynchronous' from the drop down as a replication type

Replication URL

If the replication type is 'Synchronous', then specify the servlet URL for replication.

Replication Queue

If the replication type is 'Asynchronous', then specify the JMS queue name for replication.

Remarks

Mention the additional details (if any).

3.3 Data Replication Process

Replication process applies function ID filter and data filter to check whether the data needs to replicated or not in Oracle FLEXCUBE/ELCM system. If the data needs to be replicated, then the source, along with the source code key attributes of transaction will be log into the replication table.

As per the replication mechanism, data would be replicated either using two way authentications servlet or JMS queue. In servlet mechanism, URL maintained in replication maintenance would be used to replicate data. In JMS, request queue will be used for replication based on the status received from the other sources.

Note

Replication status will be updated in replication table.

Data replication process takes place automatically or manually. In case of automatic data replication process, system would select the unprocessed data for replication. In case of manual data replication process, system will select only specific records for replication.

3.3.1 **Automatic Data Replication**

Automatic replication takes place using Oracle FLEXCUBE scheduler process. ELCM replication process is configured as part of scheduler maintenance. ELCM scheduler searches in the replication table for the unprocessed records after certain interval. System picks up the unprocessed records, sorts the data according to function ids, and forms a request XML. The request XML is sent to the instance using replication mechanism. In the instance, the data are persisted into the table and response XML is created with status of each replication data. You can view the updated status of data replication in the 'Replication Log' screen.

If data needs be replicated from Oracle FLEXCUBE to ELCM, then system uses scheduler job code 'ELREPLICATION' as a part of Oracle FLEXCUBE scheduler maintenance. If data needs be replicated from ELCM to Oracle FLEXCUBE, then system uses scheduler job code 'ELREPLICATION' as a part of ELCM scheduler maintenance.

3.3.2 **Viewing Successfully Replicated Records**

You can query successfully replicated records in the 'Replication Log Summary' screen. You can invoke the this screen by typing 'COSRELOG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Replication Log Summary

Search Advanced Search Reset

Case Sensitive

Source Code [] Function []
Branch [] Status []

Records per page 15 First Previous 1 Of 1 Next Last Go Lock Columns 0

Source Code	Function	Branch	Primary Key	Mod Number	Status	Data	Data In Time	Replication Start Time	Replication End Time	Priority	Error Code	Rem
-------------	----------	--------	-------------	------------	--------	------	--------------	------------------------	----------------------	----------	------------	-----

Exit

Base your queries on any or all of the following parameters and fetch records:

- Source Code: Oracle FLEXCUBE or ELCM instance for which the data will get replicated.
- Branch: branch code of the transaction

- Function: for which the maintenance is done
- Status: replication status
- Primary Key: Primary key of the data
- Mod Number: modification number of the data to be uploaded

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Source Code
- Branch
- Function
- Status
- Primary Key
- Mod Number

3.4 Batch Replication

As a part of the batch replication data will be replicated in the following way:

- **Complete refresh:** Complete data would be replicated.
- **Incremental refresh:** Transaction inputted on the logic day would be replicated.
- **Error records refresh:** Replicates all the error records associated to online replication.

3.4.1 Replicating Data from Oracle FLEXCUBE to ELCM

Following data will be replicated from Oracle FLEXCUBE to ELCM using GI module of Oracle FLEXCUBE.

Replication Data	Interface ID for Complete Refresh	Interface ID for Incremental Refresh	Interface ID Error Record Refresh
Branch	IFFCCBRN	IFFCIBRN	IFFCEBRN
Branch Holiday	IFFCCBRNH	IFFCIBRNH	IFFCEBRNH
Rates	IFFCCRT	IFFCIRT	IFFCERT
Product	IFFCCPRD	IFFCIPRD	IFFCEPRD
Customer	IFFCCCIF	IFFCICIF	IFFCECIF
Account /TD	IFFCCAC	IFFCIAC	IFFCEAC
Commitment Reference Number	IFFCCCOM	IFFCICOM	IFFCECOM

3.4.2 Replicating Data from ELCM to Oracle FLEXCUBE

As part of replication process following data will be replicated from ELCM to FCUBS.

Replication Data	Interface ID for Complete Refresh	Interface ID for Incremental Refresh	Interface ID Error Record Refresh
------------------	-----------------------------------	--------------------------------------	-----------------------------------

Liability	IFELCLIAB	IFELILIAB	IFELELIAB
Customer liability link	IFELCCIFL	IFELICIFL	IFELECIFL
Collateral	IFELCCOL	IFELICOL	IFELECOL
Collateral Pool	IFELCCOLP	IFELICOLP	IFELECOLP
Facility details	IFELCFACT	IFELIFACT	IFELEFACT
User	IFELCUSER	IFELIUSER	IFELEUSER
ELCM customer no	IFELCCIFN	IFELICIFN	IFELECIFN
Commitment Inter- face	IFELCCOM	IFELICOM	IFELECOM

Note

Data generated from the above interfaces will be a part of ELCM batch file formats and the file name can be changed.

4.1 Introduction

The Queries module under the Menu Browser provides query functions for the following:


- Liabilities
- Liability History
- Facilities
- Utilizations
- Utilization Transactions
- Utilization Log
- Collateral Covenants
- Facility Covenants

4.2 Liabilities Query


The 'Liability Query' screen allows you to query for records based on the following parameters:

- Authorization Status
- Liability Number
- Liability Branch
- Record Status
- Liability Currency


You can invoke the 'Liability Query' screen by typing 'GESQLIAB' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can use this screen to query the Facilities and the Utilizations Details for a Liability. To do this, choose the liability for which you wish to view details by checking the box at the beginning of each row and clicking the 'Facility Detail' button. The 'Facility Query' screen with details of the facilities is displayed:




In the 'Facility Query' screen, choose the facility for which you wish to view the utilization details by checking the box at the beginning of the row and clicking on the 'Utilization Details' button. The system displays the 'Utilization Query' screen containing details of the utilization, as shown below:



4.3 Liability History

- The 'Liability History Query' screen allows you to query for records based on the following parameters:
- Liability No
- Liability Branch
- Liability Name

You can invoke the 'Liability History Query' screen by typing 'GESQHIA' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.




4.4 Utilization Transaction Query

The 'Utilization Transaction Query' screen allows you to query for records based on the following parameters:

- Liability No
- Line Code
- Utilization Branch
- Customer No
- Liability Branch
- Utilization Currency
- Authorization status
- Record Status

The total number of exposure for the customer can be viewed. It also shows the Sum of Amount Utilization in local currency/ branch currency.

You can invoke the 'Utilization Transaction Query' screen by typing 'GESQSLIA' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.




4.5 Covenants Queries

You can perform the following queries for covenants in the system:

The 'Facility Covenants Query' allows you to query the covenants associated with a particular facility. Details including the line code, liability number, last revision date, notice days and so on for the covenant can be viewed.

You can invoke the 'Facility Covenants Query' screen by typing 'GESQFCNV' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The 'Collateral Covenants Query' allows you to query the covenants associated with a particular collateral. Details including the collateral code, liability number, last revision date, notice days for the covenant can be viewed.

You can invoke the 'Collateral Covenants Query' screen by typing 'GESQCCNV' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Collateral Covenants Query

Search Advanced Search Reset Clear All

Case Sensitive

Liability No	<input type="text"/>	Collateral Code	<input type="text"/>
Covenant Reference Number	<input type="text"/>	Due Date On	<input type="text"/>
Covenant Name	<input type="text"/>	Description	<input type="text"/>
Mandatory	<input type="text"/>	Grace Days	<input type="text"/>
Revision Date	<input type="text"/>	Notice Days	<input type="text"/>
Frequency	<input type="text"/>	Start Month	<input type="text"/>

Records per page 15 1 Of 1 Go Lock Columns 0

<input type="checkbox"/>	Liability No	Collateral Code	Covenant Reference Number	Transaction Type	Due Date On	Start Date	Covenant Name	Description	Mandatory	Grace
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										

Exit

5. Reports

5.1 Introduction

This manual lists the details of various reports that you can generate for ELCM module of Oracle FLEXCUBE.

During the day, or at the end of the day, you may want to retrieve information on any of the several operations that were performed during the day in your bank. You can generate this information in the form of reports in Oracle FLEXCUBE.

For every module you can generate reports, which give you data about the various events in the life of a specific contract, or across contracts, at a specific point in time. You can have analysis reports, daily reports, exception reports (reports on events that ought to have taken place on the contract but have not, due to various reasons), history reports and so on. A set of report formats is pre-defined for every module.

5.2 Generating Reports

From the Application Browser, select the Reports option. A list of all the modules to which you have access rights are displayed in the screen. When you click on a module, all the reports for which you have access rights under the selected module are displayed. Click on the report you want to generate. You will be given a selection Criteria based on which the report would be generated.

Click 'OK' button when you have specified your preferences. The 'Print Options' screen gets displayed, where you can specify the preferences for printing the report.

5.3 Generating Covenant History Reports

You can invoke the 'Covenant History Reports' screen by typing 'ELRPCONH' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software dialog box titled "Covenant History" with a subtitle "Covenant History Report-Options". The dialog contains several input fields and controls: a "Covenant Name" dropdown menu, a "Liability" section with two radio buttons labeled "All" (which is selected) and "Single", a table with a header "Type" and an empty body, a "Report Format" dropdown menu set to "PDF", a "Report Output" dropdown menu set to "Print", a "Printer At" dropdown menu set to "Client", and a "Printer" text field. At the bottom right corner, there are "Ok" and "Cancel" buttons.

Covenant Name

Select the covenant name from the adjoining option list.

Liability Number

Select the liability number for which you want to retrieve the covenant data.

5.3.1 Contents of the Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch and branch date, user id, the date and time, the page number and module of the report.

Body of the Report

This report contains details of:

Covenant Name	This is the name of the covenant.
Transaction Type	This is the facility or collateral type of transaction.
Mandatory	This is to specify whether the Covenant is mandatory or not.
Frequency	This is to specify the frequency of the Covenant submission.
Start Date	This is the start date of the covenant.
End date	This is the end date of the covenant.
Grace days	This is the grace days of the Covenant.
Notice days	This is the notice days of the Covenant.
Remarks	This is the additional comments associated with the covenant.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.4 Collateral Review Report

You can invoke the 'Collateral Review Reports' screen by typing 'CORCOLRW' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



The screenshot shows a window titled "Collateral Review Report" with a blue header and footer. The main area is white and contains four dropdown menus: "Report Format" (PDF), "Report Output" (Print), "Printer At" (Client), and "Printer" (empty). The "Ok" and "Exit" buttons are located in the bottom right corner of the window.

5.4.1 Contents of the Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch and branch date, user id, the date and time, the page number and module of the report.

Body of the Report

This report contains details of:

Liability ID	Indicates the liability ID
Customer Name	Indicates the name of the customer
Collateral ID	Indicates the ID of the collateral
Expiry Date	Indicates the date of expiry
Pool Code	Indicates the pool code
Pool CCY	Indicates the currency of the pool
Pool Amount	Indicates the pool amount
Balance	Indicates the balance
Line CCY	Indicates the line currency

Line Amount	Indicates the line amount
-------------	---------------------------

5.5 Ear Mark Transaction Inner Limit Report

You can invoke the 'Ear Mark Transaction Inner Limit' screen by typing 'COREARMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Branch Code

Select the branch code from the option list. The system generates the report for the selected branch code.

5.5.1 Contents of the Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch and branch date, user id, the date and time, the page number and module of the report.


Body of the Report

This report contains details of:

ARM Name	ARM Name
CIF Number	The customer identification number
Customer Name	The name of the customer
Source Ac	The account from which the amount is earmarked
Destination Ac	The account to which the amount is earmarked
Earmarked Amount	The total earmarked amount
Expiry Date	The expiry date

5.6 Expired Limits Report

You can invoke the 'Expired Limit Report' screen by typing 'COREXPLM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



Branch Code

Select the branch code from the option list. The system generates the report for the selected branch code.

5.6.1 Contents of the Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch and branch date, user id, the date and time, the page number and module of the report.

Body of the Report

This report contains details of:

Customer CIF	The customer identification number
Related Liability ID	The related liability identification of the customer
Customer Name	The name of the customer
Line ID	The line identification of the customer
Line CCY	The line currency of the customer
Limit Amount	The limit amount of the customer
Balance Outstanding	The outstanding balance of the line
Expiry Date	The expiry date of the line
Customer MIS Code	The MIS code of the customer

5.7 Foreign Exchange Clean Risk Report

This report gives details of the foreign exchange clean risk.

You can invoke this screen by typing 'ELRFXCL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software dialog box titled "Foreign Exchange Clean Risk Report - Options". It contains several controls for configuring the report: "Customer No" with radio buttons for "All" (selected) and "Single"; a "Customer List" table with a search bar and navigation icons; "Report Format" set to "PDF"; "Report Output" set to "Print"; "Printer At" set to "Client"; and a "Printer" field. "Ok" and "Cancel" buttons are located at the bottom right.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all customers.

Single

Select the option 'Single' if you want to generate reports for single customer.

If you have selected the option 'Single' select the customer number for which the foreign exchange clean risk report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the foreign exchange clean risk. report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Customer Id	Indicates the customer id
Customer Name	Indicates the customer name
Settlement	Indicates the settlement
Currency	Indicates the currency
Amount	Indicates the amount
Total	Indicates the total amount
Limit	Indicates the days to limit
Overdraft	Indicates the overdraft

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.8 Bank wide Clean Risk Tracking Report

This report gives details of the bank wide clean risk tracking.

You can invoke this screen by typing 'ELRPCLBK' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all dates.

Single

Select the option 'Single' if you want to generate reports for single date.

If you have selected the option 'Single' select the date for which the bank wide clean risk tracking report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the bank wide clean risk tracking report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Settle Date	Indicates the settle date
Eurtype lcy	Indicates the eurtype lcy
Eurtype CCY	Indicates the eurtype ccy

CCY	Indicates the currency
Risk Amount	Indicates the risk amount
CF LCY Risk Amount	Indicates the CF LCY risk amount

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.9 Country Exposure Report

This report gives details of the country exposure.

You can invoke this screen by typing 'ELRPCNEX' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all countries.

Single

Select the option 'Single' if you want to generate the report for single country.

If you have selected the option 'Single' select the country code for which the country exposure report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the country exposure report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Country Code	Indicates the country code
Description	Indicates the description
Liability	Indicates the liability
Currency	Indicates the currency

Exposure Amount	Indicates the exposure amount
------------------------	-------------------------------

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.10 Collaterals Details

This report gives details of the collateral details.

You can invoke this screen by typing 'ELRPCOLT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all collaterals.

Single

Select the option 'Single' if you want to generate the report for single collateral.

If you have selected the option 'Single' select the Collateral Value for which collateral details report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the collateral details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Collateral Code	Indicates the Collateral Code
Description	Indicates the Description
Currency	Indicates the Currency

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.11 Collateral Utilization of Collateral Party Report

This report gives details of the collateral utilization of collateral party.

You can invoke this screen by typing 'ELRPCOUL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Collateral utilization of collateral party report". The window contains a section for "Collateral utilization of collateral party report-options" with two radio button options: "All" (selected) and "Single". Below this is a table with a single header row labeled "Issuer List" and an empty data area. At the bottom of the window, there are several control elements: "Report Format" set to "PDF", "Report Output" set to "Print", "Printer At" set to "Client", and a "Printer" field. "Ok" and "Cancel" buttons are located in the bottom right corner.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all issuers.

Single

Select the option 'Single' if you want to generate the report for single issuer.

If you have selected the option 'Single' select the Issuer number for which the collateral utilization of collateral party report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the collateral utilization of collateral party report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Issue No	Indicates the issue number
Overall Limit Ccy	Indicates the overall limit currency
Overall Limit	Indicates the overall limit
Utilization	Indicates the utilization
Collateral Type	Indicates the collateral type
Liab Id	Indicates the Liab Id
Ccy	Indicates the currency
Collateral Value	Indicates the collateral value
Collateral Value In Limit Ccy	Indicates the collateral value in limit Ccy

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.12 Collateral Utilization of Credit Lines Report

This report gives details of the collateral utilization of credit lines.

You can invoke this screen by typing 'ELRPCOUT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Collateral Utilization of credit lines". At the top left, there is a "Credit" label. Below it, the "Pool Code" section has two radio buttons: "All" (which is selected) and "Single". In the center, there is a table with a header "Pool List *" and an empty body. At the bottom, there are several controls: "Report Format" set to "PDF", "Report Output" set to "Print", "Printer At" set to "Client", and a "Printer" field. "Ok" and "Cancel" buttons are located at the bottom right of the window.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all pool codes.

Single

Select the option 'Single' if you want to generate reports for single pool code.

If you have selected the option 'Single' select the pool code for which the collateral utilization of credit lines Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the collateral utilization of credit lines report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability No	Indicates the Liability No
Liability Name	Indicates the Liability Name
Line Code	Indicates the Line Code
Line Serial	Indicates the Line Serial
Line Currency	Indicates the Line Currency
Pool CCy	Indicates the Pool CCy
Facility Amt Pool Ccy	Indicates the Facility Amt Pool Ccy
CfLm Ccy Amt	Indicates the CfLm Ccy Amt
Line Ccy Type	Indicates the Line Ccy Type

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.

- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.13 Credit Movements Report

This report gives details of the credit movements.

You can invoke this screen by typing 'ELRPCRMO' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software dialog box titled "Credit movements report". It contains several configuration options for generating a report. Under the heading "Credit Movements Report --Options", there are radio buttons for "Liability", with "All" selected and "Single" unselected. Below this is a table with a header "Type *" and a scrollable area. At the bottom of the dialog, there are dropdown menus for "Report Format" (set to PDF), "Report Output" (set to Print), "Printer At" (set to Client), and "Printer". "Ok" and "Cancel" buttons are located at the bottom right of the dialog.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability number for which the credit movements report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the credit movements report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability Id	Indicates the liability Id
Liab Name	Indicates the liab name
Line Code	Indicates the line code
Line Serial	Indicates the line serial
Line Currency	Indicates the line currency
Line Amount	Indicates the Line Amount
Collateral Contribution	Indicates the Collateral Contribution
Uncollected Amount	Indicates the Uncollected Amount
Uncollected Funds Limit	Indicates the Uncollected Funds Limit
Revolving Line	Indicates the Revolving Line
Available Amount	Indicates the Available Amount
Amount Reinstated today	Indicates the Amount Reinstated today
Amount Utilised Today	Indicates the Amount Utilised Today
Opening Available	Indicates the Opening Available
Cf Limit	Indicates the Cf Limit

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.14 Exposure Details

This report gives details of the Exposure details.

You can invoke this screen by typing 'ELRPEXP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a window titled 'Exposure Details' with a blue header bar. Below the header, the text 'Exposure Details Report-Options' is displayed. There are two radio buttons for 'Exposure Code': 'All' (selected) and 'Single'. Below this is a table with one header row 'List of Exposures *' and an empty body. At the bottom of the window, there are four controls: 'Report Format' set to 'PDF', 'Report Output' set to 'Print', 'Printer At' set to 'Client', and a 'Printer' field with a dropdown arrow. The window has 'Ok' and 'Cancel' buttons at the bottom right.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all exposures.

Single

Select the option 'Single' if you want to generate the report for single exposure

If you have selected the option 'Single' select the Nom De exposition for which the exposure details report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the exposure details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Exposure Name	Indicates the exposure name
Exposure Currency	Indicates the exposure currency
Exposure Amount	Indicates the exposure amount
Exposure Type	Indicates the exposure type
Revolving	Indicates the revolving
Available Amount	Indicates the available amount
Revolving Amt	Indicates the revolving amount
Block Amt	Indicates the block amount

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.

- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.15 Issuer Exposure Report by Collateral Type

This report gives details of the issuer exposure by collateral type.

You can invoke this screen by typing 'ELRPISEX' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all issuers.

Single

Select the option 'Single' if you want to generate the report for single issuer.

If you have selected the option 'Single' select the Issuer code for which the issuer exposure report by collateral type has to be generated from the adjoining option list.

Contents of the Report

The report options that you selected while generating the report are printed at the beginning of the report.

The contents of the report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, the date and time of report generation, the user-ID of the user generating the report, and the page number.

Body of the report

Issuer ID	The code you assigned to the issuer in the Issuer Maintenance screen.
Overall Limit Currency	Indicates the overall limit currency.
Overall Limit	Indicates the overall limit.
Collateral Type	Indicates the collateral type..
Limit Currency	Indicates the limit currency.
Limit Amount	Indicates the limit amount.
Collateral Currency	Indicates the collateral currency.
Exposure Amount	Indicates the exposure amount.
Limit Currency	Indicates the limit currency.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.16 Issuer Details Report

This report gives details of the issuer.

You can invoke this screen by typing 'ELRPISUR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Issuer Details Report". The window has a blue header bar with a diamond icon on the left and standard window controls (minimize, maximize, close) on the right. Below the header is a white area with the text "Issuer Details Report- Options". Underneath, there are two radio buttons: "All" (which is selected) and "Single". Below the radio buttons is a navigation bar with "1 Of 1" and a "Go" button. The main area of the window is a large, empty white space with a vertical scrollbar on the right side. At the bottom of the window, there are several controls: "Report Format" set to "PDF", "Report Output" set to "Print", "Printer At" set to "Client", and a "Printer" field with a dropdown arrow. At the very bottom right, there are "Ok" and "Cancel" buttons.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all issuers.

Single

Select the option 'Single' if you want to generate the report for single issuer.

If you have selected the option 'Single' select the issuer code for which the issuer details report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the issuer details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Issuer Code	Indicates the issuer code.
Issuer Details	Indicates the issuer details
Issuer CIF No	Indicates the issuer CIF number
Overall Limit Currency	Indicates the overall limit currency
Overall Limit	Indicates the overall limit.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.17 Liability Summary Report

This report gives details of the liability summary.

You can invoke this screen by typing 'ELRPLB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Liability summary report -options

Liability All
 Single

Type *	

Report Format PDF
Report Output Print

Printer At Client
Printer

Ok Cancel

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability number for which the Liability Summary Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the liability summary report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Auth	Indicates the author
Liability	Indicates the liability
Liability Name	Indicates the liability name
Currency	Indicates the currency
Limit Amount	Indicates the limit amount
Utilisation Amount	Indicates the utilisation amount
Overdraft	Indicates the overdraft

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.18 Limit Details Report

This report gives details of the limit details.

You can invoke this screen by typing 'ELRPLIMIT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all lines.

Single

Select the option 'Single' if you want to generate reports for single line.

If you have selected the option 'Single' select the line code for which the Limit Details Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the limit details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Line Code	Indicates the line code
Serial Number	Indicates the serial number
Currency	Indicates the currency

Start Date	Indicates the start date
Expiry Date	Indicates the expiry date
Limit Amount	Indicates the limit amount
Available Amount	Indicates the available amount

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.19 Line Details Report

This report gives details of the line.

You can invoke this screen by typing 'ELRPLN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability name for which the Line Details Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the line details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability ID	Indicates the liability ID
Limit	Indicates the limit of the liability
Utilisation	Indicates the utilisation for liability
Overdraft	Indicates the overdraft for liability

Main Line	Indicates the main line
Line ID	Indicates the line ID
Currency	Indicates the currency
Limit	Indicates the limit for line
Utilisation	Indicates the utilisation for line
Overdraft	Indicates the overdraft
Status	Indicates the status

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.20 Line Summary Report

This report gives details of the line summary.

You can invoke this screen by typing 'ELRPML' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all lines.

Single

Select the option 'Single' if you want to generate reports for single line.

If you have selected the option 'Single' select the line code for which the Line Summary Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the line summary report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liab Name	Indicates the liability name
Limit	Indicates the limit
Util	Indicates the Util
O/D	Indicates the O/D

Line ID	Indicates the line ID
Currency	Indicates the currency
Limit	Indicates the limit
Utilization	Indicates the utilization
Overdraft	Indicates the overdraft
Status	Indicates the status

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.21 Movements to Non-Revolving Lines

This report gives details of the movements to non-revolving lines.

You can invoke this screen by typing 'ELRPNRLN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all lines.

Single

Select the option 'Single' if you want to generate reports for single line.

If you have selected the option 'Single' select the line code for which the Movements of Non-Revolving Lines Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the movements to non-revolving lines report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Line Code	Indicates the line code
Line Currency	Indicates the line currency

Util ID	Indicates the utilization ID
Limit Amount	Indicates the limit amount
Available Amount	Indicates the available amount

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.22 Pool Linkage Report

This report gives details of the pool linkage.

You can invoke this screen by typing 'ELRPOLNK' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all pool codes.

Single

Select the option 'Single' if you want to generate reports for single pool code.

If you have selected the option 'Single' select the pool code for which the Pool Linkage Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the pool linkage report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Pool Code	Indicates the pool code
------------------	-------------------------

Description	Indicates the description
Collateral Code	Indicates the collateral code
Collateral Currency	Indicates the collateral currency
Collateral Amount	Indicates the collateral amount
Linked Amount	Indicates the linked amount
Linked Amt Pool Currency	Indicates the linked amount pool currency

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.23 Pool Utilization Report

This report gives details of the pool utilization.

You can invoke this screen by typing 'ELRPOLUT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all pool codes.

Single

Select the option 'Single' if you want to generate reports for single pool code.

If you have selected the option 'Single' select the pool code for which the Pool Utilization Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the pool utilization report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability Name	Indicates the liability name
Pool Code	Indicates the pool code
Pool Currency	Indicates the pool currency

Pool Currency Type	Indicates the pool currency type
Pool Amount	Indicates the pool amount
Pool Utilization	Indicates the pool utilization
Collateral Currency	Indicates the collateral currency
Linked Amount	Indicates the linked amount
Utilization	Indicates the utilization

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.24 Overdrawn Lines

This report gives details of the overdrawn lines.

You can invoke this screen by typing 'ELRPOVLN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all lines.

Single

Select the option 'Single' if you want to generate reports for single line.

If you have selected the option 'Single' select the line code for which the Overdrawn Lines Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the overdrawn lines report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability	Indicates the liability
Name	Indicates the name

Line	Indicates the line
Serial	Indicates the serial number
Ccy	Indicates the currency name
Main Line	Indicates the main line
Overdrawn Amount	Indicates the overdrawn amount

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.25 Product Exposure Report

This report gives details of the product exposure.

You can invoke this screen by typing 'ELRPPREX' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all products.

Single

Select the option 'Single' if you want to generate reports for single product.

If you have selected the option 'Single' select the product type for which the Product Exposure Report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the product exposure report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Product	Indicates the product
Bank LCY	Indicates the bank currency name

Product Description	Indicates the product description
CS PROD AMT	Indicates the CS product amount
CF F PROD AMT	Indicates the CF F product amount
CCY	Indicates the currency
CS CCY AMT	Indicates the CS currency amount
CF CCY AMT IN LCY	Indicates the CF currency amount in LCY
CF F CCY AMT	Indicates the CF F currency amount
AMT	Indicates the amount
Branch	Indicates the branch code

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.26 Securities Details Report

This report gives details of security.

You can invoke this screen by typing 'ELRPSECM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Securities Details". Inside, there's a section "Securities Details Report - Options". Under "Security Code", the "All" radio button is selected. Below that is a search bar showing "1 Of 1". A table titled "List of Securities *" is empty. At the bottom, there are settings for "Report Format" (PDF), "Report Output" (Print), "Printer At" (Client), and a "Printer" field. "Ok" and "Cancel" buttons are at the bottom right.

You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all securities.

Single

Select the option 'Single' if you want to generate reports for single security.

If you have selected the option 'Single' select the security code for which the Securities Details report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the security details report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Security Code	Indicates the security code
Description	Indicates the description
Face Value	Indicates the face value
Currency	Indicates the currency

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.27 Limits – Tenor wise Details Report

This report gives details of the limits tenor wise.

You can invoke this screen by typing 'ELRPTN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability name for which the Limits – Tenor wise Details report has to be generated from the adjoining option list.

5.27.1 Contents of the Report

The report has distinct sections for each Liability Code. The utilization of tenor based limits is printed for both Main Lines and Sub-Lines.

The report options that you selected while generating the report are printed at the beginning of the report.

The contents of the report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, the date and time of report generation, the user-ID of the user generating the report, and the page number.

Body of the report

Liability	The Liability code of the customer.
Limit	The credit limit assigned to the Liability code and the currency in which it is defined.
Utilization	The utilization of the limit under the Liability Code.
Overdraft	This is the amount by which the customer has exceeded the limit set for the Liability Code.

For each Liability Code the following details are printed for the Main Line or sub-line as the case may be.

Main Line	This is the code of the Main Line to which the customer s Liability number has been linked.
Limit	The Limit set for the Main line and the currency in which the limit under the Main Line or Sub-Line is defined.
Utilization	The utilization of the limit under this line is displayed here.
Overdraft	This is the overdrawn amount of the Line or sub-line.

After the details of the Line are displayed the following details are printed in tabular columns:

Tenor	This is the tenor code.
Limit	The limit assigned to the tenor.
Utilization	The utilization of the limit under the tenor code.
Overdraft	This is the overdrawn amount.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.28 Utilization Report

This report gives details of the utilization.

You can invoke this screen by typing 'ELRPUA' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability name for which the Utilization report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the utilization report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability	Indicates Liability
Limit	Indicates limit
Main Line	Indicates main line
Line Id	Indicates line id
Reference No	Indicates reference number
Tenor	Indicates tenor
Amount Tag	Indicates amount tag
Amount	Indicates amount
Line Currency Equivalent	Indicates line currency
Utilisation	Indicates the utilisation
Overdraft	Indicates the overdraft

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.29 Issuer Exposure by Security Report

This report gives details of the issue exposure by security.

You can invoke this screen by typing 'ELRPUSEX' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all issuers.

Single

Select the option 'Single' if you want to generate the report for single issuer.

If you have selected the option 'Single' select the Issuer ID for which the issuer exposure report by security has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the issue exposure by security report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Issure Id	Indicates the issure id
Overall Limit	Indicates the overall limit
Util	Indicates the util
Security Id	Indicates the security id
Ccy	Indicates the currency
Limit	Indicates the limit
Utilization	Indicates the utilization
Price Code	Indicates the price code
Market Price	Indicates the market price

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.30 Limit Tenor Restriction Details Report

This report gives details of the limit tenor restriction.

You can invoke this screen by typing 'ELRPUT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability name for which the limit tenor restriction has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the limit tenor restriction report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Utilisation	Indicates the utilisation
Overdraft	Indicates the overdraft
Main Line	Indicates the main line
Limit	Indicates the limit
Overdraft	Indicates the overdraft
Line ID	Indicates the line ID
Reference No	Indicates the reference number
Tenor	Indicates the tenor
Amount Tag	Indicates the amount tag
Amount	Indicates the amount
Line Currency Equivalent	Indicates the line currency equivalent

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.31 Date Wise Utilisations Report

This report gives details of the date wise utilization.

You can invoke this screen by typing 'ELRPUTLD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability name for which the date wise utilization report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the Date wise utilization report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability	Indicates the liability
Line Code	Indicates the line code
Serial	Indicates the serial number
Datewise	Indicates the date
Utilisation	Indicates the utilisation

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location


Printer

Select printer using which you wish to print the report from the adjoining option list.

5.32 Credit Lines by Maturity Dates

This report gives details of credit lines sorted on the basis of their maturity dates. The maturity date of a line indicates the expiry date of the line. The report also prints the number of days to maturity.

You can invoke this screen by typing 'ELRPCLMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can indicate the following preferences for generating the report:

All

Select the option 'All' if you want to generate the report for all liabilities.

Single

Select the option 'Single' if you want to generate reports for single liability.

If you have selected the option 'Single' select the liability number for which the credit lines by maturity date report has to be generated from the adjoining option list.

Contents of the report

The options that you specified while generating the report are printed at the beginning of the report.

The contents of the credit lines by maturity dates report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the report

Liability Id	Indicates the liability code to which the customer is linked
---------------------	--

Customer Name	Indicates the name of the customer linked to this credit line.
Line Id	Indicates the Credit Line to which the customer's Liability number has been linked.
Serial Number	Indicates the running serial number for the Liability-Line Combination
Start Date	Indicates the start date
Expiry Date	Indicates the date on which the Credit Line Matures. Maturity of a Credit Line indicates that the Line expires after this date.
Days to Maturity	Indicates the number of days left, before the Line matures

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.33 Country Utilization Report

You can invoke the 'Country Utilization Report' screen by typing 'ELRPCUT!' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Country Utilization Report". The window contains a section for "Country Utilization Report- Options". Under "Exposure Name", the "All" radio button is selected, and the "Single" radio button is unselected. Below this is a "List of Exposures" table, which is currently empty. At the bottom of the window, there are several controls: "Report Format" is set to "PDF", "Report Output" is set to "Print", "Printer At" is set to "Client", and there is a "Printer" field. "Ok" and "Cancel" buttons are located at the bottom right of the window.

Exposure Name

Select All Exposures or Single Exposure.

Note

Exposure should not be selected from the list of exposures list, if All Exposures are selected, else an error message is displayed. The country can be selected only if single exposure is selected.

5.33.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the Report

Exposure Name	Displays the exposure name..
Description	Displays the description of the exposure.
Currency	Displays the currency of the exposure.
Amount	Displays the exposure amount.
Utilization Amount	Displays the utilization amount.
Effective Date	Displays the effective date.
Renewal Date	Displays the date of renewal
Expiry Date	Displays the expiry date.
Freeze	Displays the freeze status.
Type	Displays the type.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

5.34 Credit Rating Report

You can invoke the 'Credit Rating Report' screen by typing 'ELRPLIAB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Credit Ratings Report". Inside the window, there is a section titled "Credit Rating Report --Options". Under this section, there are two radio buttons labeled "Liability": "All" (which is selected) and "Single". Below the radio buttons is a table with one column header "Type *". At the bottom of the window, there are several controls: "Report Format" is set to "PDF", "Report Output" is set to "Print", "Printer At" is set to "Client", and there is a "Printer" field. At the bottom right corner, there are "Ok" and "Cancel" buttons.

Liability No.

Select the liability from the adjoining option list, if single liability is selected.

Note

The list of liability names is enabled only if Single Liability is selected. This field is disabled if 'All Liabilities' are selected.

5.34.1 Contents of the Report

The options that you specified while generating the report are printed at the beginning of the report. The contents of the credit rating report are discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, branch date, the date and time of report generation, the user-ID of the user generating the report, module and the page number.

Body of the Report

Liability	Displays the liability number
Name	Displays the name of the customer linked to the credit line
Credit Rating	Displays the credit rating of the customer.
Revision Date	Displays the revision date of the customer.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

6. Annexure 1 - Utilization Transactions

6.1 Introduction

Utilization is a change in the Facility Available Amount. Whenever a contract is booked using a particular Line Code, then the respective line/main line's Available Amount should be altered in Oracle FLEXCUBE ELCM.

All utilization transactions maybe captured in their own external systems or through the 'Utilization Transaction' screen. The utilization details for each transaction taken place in the external product processor have to be sent to Oracle FLEXCUBE ELCM via Gateway online Inbound or Gateway Batch Inbound process.

Following utilizations transactions allowed by Oracle FLEXCUBE ELCM:

- New Utilization
- Increase Utilization
- Decrease Utilization
- Alter Utilization
- Reverse Utilization
- Mature
- Set balance
- Query Utilization

Each of the above utilization transactions (apart from Query transaction) has the following sub transactions:

- Input Utilization
- Authorize Utilization
- Delete Utilization
- Technical undo (Special delete)

6.2 New Utilization

The process wherein a facility is given to a customer and is utilized by the customer is called a Utilization Process. Utilization Process is termed as a New Utilization when the customer utilizes his facility in a new transaction.

A New Utilization Transaction can arise from any kind of transaction like Loan input, Letter of credit input, Bill/Collection input, foreign exchange deal input etc.

New utilization involves the following actions:

- Input Utilization
- Authorize Utilization
- Delete Utilization
- Technical undo (Special delete)

6.2.1 Input Utilization

New Utilization process increases the Utilization Amount and decreases the Available Amount for the associated Liability, Facility, or Exposure. If the Liability Facility, Sector

Facility Or Country Facility has an associated Main Line then the utilization will reflect at all the parent levels.

Following data are input for a New Utilization transaction.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Source	AlphaNumeric(35)	Indicates the product processor name from where the transaction has been originated. This field will be as part of Header section (Source Code)	Yes
2	TxnID	AlphaNumeric(50)	Indicates the Transaction Id of the message. Transaction Id should be unique across the system. This information is captured as part of header.	Yes
3	Action	Alphabet (10)	Indicates the transaction type. This field will be as part of Header section (operation Code)	Yes
4	Utilization Branch	AlphaNumeric (3)	Indicates the transaction branch. This field will be as part of Header section (Branch code).	Yes
5	External Reference Number	AlphaNumeric(50)	Specifies the product processor reference number	Yes
6	Customer Number	AlphaNumeric(11)	Specifies the Customer Number of the utilization transaction. Customer Number entered should be valid Customer Number in Oracle FLEXCUBE ELCM system.	Yes
7	Liability Number	AlphaNumeric(11)	Specifies the Liability Number of the utilization transaction. Liability Number entered should be valid Liability Number in Oracle FLEXCUBE ELCM system.	Yes
8	Facility Code	AlphaNumeric(9)	Specifies the Facility Code of the utilization transaction. Facility Code entered should be valid Facility Code in Oracle FLEX-CUBE ELCM system.	No

9	Facility Serial Number	Numeric (2)	Specifies the Facility Serial number of the utilization transaction	No
10	Utilization Amount	Numeric	Indicates the Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEX-CUBE ELCM system.	Yes
12	Utilization Product	Alphabet (10)	Indicates External product code of the utilization transaction	No
13	Tenor Basis	Alphabet (1)	Indicates the tenor bases of the transaction	No
14	Tenor	Numeric	Indicates the tenor of the transaction	No
15	Maturity Date	Date	Specifies the maturity date of the transaction	No
16	Matured Amount	Numeric	Specifies the maturity amount of the transaction	No
17	Matured	Alphabet (1)	Indicates whether transaction is matured or Not.	No
18	Uncollected Amount	Numeric	Specifies the uncollected amount of the transaction	No
19	Amount Tag	Alphabet (20)	Indicates the type of the component of the transaction.	No
20	Module	Alphabet (10)	Indicates the module of the transaction	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes
22	Value Date	Date	Specifies the Value date of the transaction. If value is not passed then system will default to Oracle FLEXCUBE ELCM present branch date.	No

23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No
24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not force authorized). Default value is "N"	No
25	User ID	AlphaNumeric(11)	Specifies valid Oracle FLEXCUBE ELCM user id, who is performing the operation. This field will be as part of Header section (User ID)	Yes
26	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No
27	Block Reference Number	Alphanumeric(50)	Specifies a valid block number for a facility. If liability and facility details for new utilization and the facility match, the earmarked amount corresponding to the block maintained for the facility is made available for the new utilization.	No

6.2.2 Validations for a New Utilization Process

Apart from the mandatory checks, system performs the following validations:

- Transaction ID should be unique
- Action code should be a valid Oracle FLEXCUBE ELCM action code
- Source and User should be valid in Oracle FLEXCUBE ELCM system and should have the rights to perform the action
- Utilization Branch - Branch code should be valid branch code
- Customer number should be a valid customer number
- Currency Code should be a valid currency code
- Liability Number should be a valid
- Facility code and Facility serial number should be valid

6.2.2.1 Overrides for New Utilization process

System raises overrides for the following actions

- Customer/Liability/Facility is unadvised
- Utilization Amount is greater than the available amount in both liability and facility levels
- Breach of Day Light Limit
- Breach Sector limit - This override will be raised only if Online Update option in Oracle FLEXCUBE ELCM parameters is enabled.

6.2.2.2 Credit Exception Management (Multi Authorization)

As part of the Utilization Transaction process, Oracle FLEXCUBE ELCM provides the Credit Exception Management feature. This process will be executed in the following case.

Inputted Transaction Amount Crosses Specified Limit

At facility maintenance level, you can specify what would be the Maximum Transaction amount, which can be processed without any RISK department approval. If the transaction amount is greater than the specified amount then system passes this transaction to Multi Authorization stage.

Example

Assume that facility has been maintained with following details

Liability No : TATA

Facility Name: PERLOAN

Facility SI No: 1

Facility currency : INR

Limit amount : 1,00,000.00

Utilized amount: 0

Available amount: 1,00,000.00

Max transaction amount : 10,000.00

Max breach amount: 1,20,000.00

If the utilization amount is greater than 10,000.00 (INR) then the system passes these transactions to Multi authorization stage.

For more details, refer the section Credit Exception Management in the Process Flows document.

Inputted Transaction Amount Crosses the Breached Limit

At Facility Maintenance, you can specify a Maximum Breach Amount above which necessary approval is required from RISK department. If the transaction has been breached, i.e. the utilized and the breached amount are greater than the specified breached amount, then the system passes this transaction to Multi authorization stage.

In the above example, if the utilized amount is greater than 1,20,000.00 then the system passes these transactions to Multi Authorization stage. If the utilized amount is between 1,00,000 and 1,20,000 then the system throws an override.

Note: If transaction is Force Authorized then the system will upload the transaction as authorized and the system will send the information to RISK department. RISK department can't reject this transaction.

For more details, refer the section Credit Exception Management in the Process Flows document.

6.2.3 Authorize Utilization

A New Utilization transaction can be entered as Authorized Online or Unauthorized. If the transaction is not authorized online, then Oracle FLEXCUBE ELCM provides the facility to authorize the inputted transaction.

Apart from the Gate Way header information, Authorization process will require following the information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be authorized.	No

6.2.4 Delete Utilization

A New Utilization Transaction can be inputted as Authorized Online or Unauthorized. If transaction is not authorized online, then Oracle FLEXCUBE ELCM provides the facility to delete the inputted transaction.

Apart from the Gate Way header information, delete process would require the following information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
-------	------------	------------------	---------	-----------

1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be deleted.	No

6.2.5 Technical Undo (Special Delete)

This feature of gateway will allow the external system to rollback previous inputted transaction in Oracle FLEXCUBE ELCM. This feature will be supported in Gateway Inbound (online), information required as part of Technical undo is also Transaction Id of the previous transaction.

Note: As part of technical undo transaction information related to header needs to be passed and in body only previous Transaction ID needs to be passed.

Refer the Gateway Maintenance user manual for more details.

6.3 Increase/Decrease Utilization

Increase/Decrease utilization transaction would be used to modify the utilization amount of the transaction. This transaction will be used when customer is making payment for the loan or when the loan amount is modified.

Apart from the GW header information, system requires following information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes

3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be modified.	No
10	Modified Utilization Amount	Numeric	Indicates the Increase/ Decrease Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEX-CUBE ELCM system.	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes
22	Value Date	Date	Specifies the Value date of the transaction.	No
23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No
24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not force authorized). Default value is "N"	No
25	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No

6.3.1 Validations for Modify Utilization Process

Apart from the mandatory checks, system performs the following validations

- Utilization Reference Number: If this value is passed, then the system will check whether it is a valid utilization reference number and the system would modify this reference number.

- External Reference Number: If Oracle FLEXCUBE ELCM Utilization Reference Number is not passed, then the system has to pass an External Reference Number. Based on this number the system would retrieve the Oracle FLEXCUBE ELCM utilization reference number.

Other processing would be same as New Utilization Process.

6.4 Alter Utilization

Alter Utilization is used to modify the entire utilization transaction details. As part of Alter Utilization the external system should give the entire latest utilization details. Oracle FLEXCUBE ELCM will internally reverse previous transaction and upload alter utilization as the new utilization.

Example

Assume that loan has been created in the external system. As a part of loan creation, new utilization has been uploaded in Oracle FLEXCUBE ELCM. When loan parameters like product code, tenor of loan, customer etc. has to be changed then the loan transaction will be modified and subsequently Alter Utilization needs to be passed to the Oracle FLEXCUBE ELCM system.

Increase/decrease utilization would only modify only the utilization amount.

6.4.1 Input Alter Utilization

Oracle FLEXCUBE ELCM will internally reverse the previous transaction and upload Alter Utilization as a new utilization. New Utilization process will increase the utilization amount and decrease the available amount for the associated liability, liability facility, sector facility and country facility.

If the liability facility, sector facility or country facility has an associated Main Line then the utilization will be recored at all the parent levels.

Following data will be captured for a Alter Utilization transaction.

SI No	Field Name	Data Type	Remarks	Mandatory
1	Source	AlphaNumeric(35)	Indicates the product processor name from where the transaction has been originated. This field will be as part of Header section (Source Code)	Yes
2	TxnID	AlphaNumeric(50)	Indicates the Transaction Id of the message. Transaction Id should be unique across the system. This information is captured as part of header.	Yes
3	Action	Alphabet (10)	Indicates the transaction type. This field will be as part of Header section (operation Code)	Yes

4	Utilization Branch	AlphaNumeric (3)	Indicates the transaction branch. This field will be as part of Header section (Branch code).	Yes
5	External Reference Number	AlphaNumeric(50)	Specifies the product processor reference number	Yes
6	Customer Number	AlphaNumeric(11)	Specifies the Customer Number of the utilization transaction. Customer Number entered should be valid Customer Number in Oracle FLEXCUBE ELCM system.	Yes
7	Liability Number	AlphaNumeric(11)	Specifies the Liability Number of the utilization transaction. Liability Number entered should be valid Liability Number in Oracle FLEXCUBE ELCM system.	Yes
8	Facility Code	AlphaNumeric(9)	Specifies the Facility Code of the utilization transaction. Facility Code entered should be valid Facility Code in Oracle FLEXCUBE ELCM system.	Yes
9	Facility Serial Number	Numeric (2)	Specifies the Facility Serial number of the utilization transaction	Yes
10	Utilization Amount	Numeric	Indicates the Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEXCUBE ELCM system.	Yes
12	Utilization Product	Alphabet (10)	Indicates External product code of the utilization transaction	No
13	Tenor Basis	Alphabet (1)	Indicates the tenor bases of the transaction	No
14	Tenor	Numeric	Indicates the tenor of the transaction	No
15	Maturity Date	Date	Specifies the maturity date of the transaction	No

16	Matured Amount	Numeric	Specifies the maturity amount of the transaction	No
17	Matured	Alphabet (1)	Indicates whether transaction is matured or Not.	No
18	Uncollected Amount	Numeric	Specifies the uncollected amount of the transaction	No
19	Amount Tag	Alphabet (20)	Indicates the type of the component of the transaction.	No
20	Module	Alphabet (10)	Indicates the module of the transaction	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes
22	Value Date	Date	Specifies the Value date of the transaction. If value is not passed then system will default to Oracle FLEXCUBE ELCM present branch date.	No
23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No
24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not fore authorized). Default value is "N"	No
25	User ID	AlphaNumeric(11)	Specifies valid Oracle FLEXCUBE ELCM user id, who is performing the operation. This field will be as part of Header section (User ID)	Yes
26	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No

6.5 Reverse Utilization

Reverse Utilization transaction is used to reverse an authorized utilization transaction. This is used when user/customer wants to close the transaction.

6.5.1 Input Reverse Utilization

Apart from the Gate Way header information, the system requires following information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be modified.	No
10	Modified Utilization Amount	Numeric	Indicates the Increase/ Decrease Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEXCUBE ELCM system.	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes
22	Value Date	Date	Specifies the Value date of the transaction.	No
23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No

24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not fore authorized). Default value is "N"	No
25	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No

6.5.1.1 Validations for Modify Utilization process

Apart from the mandatory checks, system performs the following validations:

- Utilization Reference Number - If this value is passed, then the system will be check whether it is a valid utilization reference number. If so the system will reverse this reference number.
- External Reference Number - If Oracle FLEXCUBE ELCM utilization reference number is not passed then system has to pass an External Reference Number. Based on this number system will retrieve the Oracle FLEXCUBE ELCM utilization reference number and do the process.

Other processing will be same as New Utilization Process.

6.6 Set Balance of Utilization Transaction

Set Balance Transaction will be used when an external system processes the Utilization Transactions and then during EOD or some point of time the final balance of the utilization transaction is given to the Oracle FLEXCUBE ELCM system.

Oracle FLEXCUBE ELCM system will update the balance of the utilization transaction and subsequent difference in the utilization amount will be updated at liability, facility, sector and country levels. If there facility, sector and country has a main line associated with it, then the system will update the utilization details in all the main lines.

Apart from the Gate Way header information, system requires following information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEXCUBE ELCM utilization reference number.	No

2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be modified.	No
10	Modified Utilization Amount	Numeric	Indicates the Increase/Decrease Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEXCUBE ELCM system.	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes
22	Value Date	Date	Specifies the Value date of the transaction.	No
23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No
24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not fore authorized). Default value is "N"	No

25	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No
----	----------	-------------	--	----

6.6.0.1 Validations for Modify Utilization process

Apart from the mandatory checks, system performs the following validations:

- Utilization Reference Number - If this value is passed, then the system will be check whether it is a valid utilization reference number. If so the system will reverse this reference number.
- External Reference Number - If Oracle FLEXCUBE ELCM utilization reference number is not passed then system has to pass an External Reference Number. Based on this number system will retrieve the Oracle FLEXCUBE ELCM utilization reference number and do the process.

Other processing will be same as New Utilization Process.

6.7 Query Utilization

A Query Utilization transaction can be performed on all the Contracts. Here on query only the consolidated information about the contract will be provided.

Apart from the Gate Way header information, Query process will require following the information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be authorized.	No

4	Simulate	Alphabet(1)	Indicates if the transaction should be used only for simulation. Possible Values 'Y' (simulate) and 'N' (actual transaction). Default value is 'N'	No
---	----------	-------------	--	----

6.8 Mature Utilization Transaction

Mature Transaction will be used to set the mature amount for that the specified contract Utilization Transactions and then the amount specified will be treated as the matured amount for that contract.

Oracle FLEXCUBE ELCM system will update the mature amount of the utilization transaction. Apart from the Gate Way header information, system requires following information.

SI No	Field Name	Data Type (size)	Remarks	Mandatory
1	Utilization Reference Number	AlphaNumeric (16)	Specifies Oracle FLEX-CUBE ELCM utilization reference number.	No
2	External Reference Number	AlphaNumeric(50)	If the product processor does not have Oracle FLEXCUBE ELCM utilization reference number then it should pass the product processor reference number.	Yes
3	AmountTag	AlphaNumeric(20)	Amount tag would be required when there are multiple utilization for the same reference number. This tag would indicate which component needs to be modified.	No
10	Modified Utilization Amount	Numeric	Indicates the Increase/ Decrease Utilization Amount	Yes
11	Utilization Currency	AlphaNumeric (3)	Indicated the currency of the utilization transaction. Currency code entered should be valid currency code in Oracle FLEXCUBE ELCM system.	No
21	Transaction Initiated Date	Date	Indicates the date and time when the transaction was entered in product processor.	Yes

22	Value Date	Date	Specifies the Value date of the transaction.	No
23	Authorization Status	Alphabet (1)	Indicates whether transaction should be authorized online or not. Possible values are "A" (Authorize online) and "U" (upload transaction as unauthorized). Default value is U	No
24	Force Authorization	Alphabet (1)	Indicates whether transaction should ignore the overrides occurred in the process or not. Possible values "Y" (force authorize) and "N" (not fore authorized). Default value is "N"	No

6.9 Utilization Transaction Screen

All utilization requests explained above can also be raised through the 'Limit Utilization' screen.

You can invoke the 'Limit Utilization' screen by typing 'GEDUTILS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Utilization' application window. The top bar includes 'New' and 'Enter Query' buttons. The main area is divided into several sections:

- Utilization Details:** Utilization Id, Utilization Branch *, User Reference *, Limit Type (dropdown menu).
- Transaction Details:** Customer Number *, Utilization Currency, Utilization Product, Uncollected Amount, Tenor Basis (checkbox), Tenor, Maturity Date, Matured Amount, Amount Tag *, Remarks, Value Date, Liability Number, Facility Block No, Linkage Reference, Utilization Amount.
- Liability Details:** Liability Currency, Branch, Liability Utilization.
- Limit Utilization Details:** Limit Currency, Limit Utilizations.
- Global Settings:** Module (AC), Source (ELCM), Transaction Date, Simulate (checkbox).
- Exposures:** Input By (Date Time), Authorized By (Date Time), Contract Status (Authorized checkbox), and an Exit button.

Note

The limit utilization feature explained in this section will be available only if the Enterprise Limits and Collateral Management module has been set up in standalone mode. In case of embedded or hybrid setups, you will not be able to invoke this screen.

Utilisation Branch

Specify the branch where the utilization request should be processed. The adjoining option list contains all the branches maintained in the system. Select the appropriate one.

User Reference Number

Specify a unique reference number for the transaction.

Transaction Module

Specify the module for the transaction. The adjoining option list contains all the modules in the system. Select the appropriate one.

Transaction Date

Specify the date for the transaction.

Simulate

Check this box to indicate that the details for the transaction being entered should be used only for simulation and not stored permanently within the system. After a simulated transaction has been successfully put through, the system will display the utilized amount for the facility and the for the liability.

Customer Number

Specify a valid customer number for the transaction. The adjoining option list contains all the customers maintained in the system. Select the appropriate one.

Utilisation Amount

Specify the amount for the utilization transaction.

Utilisation Currency

Specify the currency for the amount entered. The adjoining option list contains all the currencies maintained in the system. Select the appropriate one.

Utilisation Product

Specify the product for the transaction. The adjoining option list contains all the relevant products. Select the appropriate one.

Uncollected Amount

Specify the amount that has not yet been collected from the customer.

Tenor Basis

Check this box to indicate that the utilization should be tracked tenor wise for the facility. You can specify the basis on which it is to be tracked in the 'Tenor' field.

Tenor

Enter the basis on which tenor tracking should be done for the utilization. You need to have checked the 'Tenor Basis' option before you can specify the basis here.

Maturity Date

Specify the date on which the transaction matures.

Amount Tags

Specify the component type for the transaction. The adjoining option list contains all the relevant tags. Select the appropriate one.

Remarks

Enter any additional remarks that you wish to maintain for this transaction. You can enter up to 255 characters.

Value Date

Specify the value date for the transaction.

Line Code

Specify the line code to be used for the transaction. The adjoining option list contains all the line codes allowed. Select the appropriate one.

Facility Block Reference Number

During a new utilization, you can specify a valid block reference number to increase the amount in a facility. On the basis of the block reference number, the system validates if the liability and facility details of the new utilization and the existing facility for which the block has been maintained match. If there is a match, it increases the amount available under the facility by unblocking the corresponding amount block for the facility and making it available for use by the new utilization.

Click the 'Exposures' button. In the screen that is displayed, you can specify the transaction exposures that the system should track while processing utilization requests. The system defaults the customer exposures.

Transaction Exposures		Customer Exposures	
Exposure Code 1	<input type="text"/>	Exposure Code 1	<input type="text"/>
Exposure Code 2	<input type="text"/>	Exposure Code 2	<input type="text"/>
Exposure Code 3	<input type="text"/>	Exposure Code 3	<input type="text"/>
Exposure Code 4	<input type="text"/>	Exposure Code 4	<input type="text"/>
Exposure Code 5	<input type="text"/>	Exposure Code 5	<input type="text"/>

6.10 Reconciliation of Utilization Transactions

The Oracle FLEXCUBE Enterprise Limits and Collateral Management (hereafter referred to as Oracle FLEXCUBE ELCM) system receives Utilization Transactions (or contracts) from different external product processing systems. These external systems include Loans systems, Treasury systems, Trade and Finance systems and others. The bulk of the contract details will remain with these external systems and the only the details required for processing will be sent to Oracle FLEXCUBE ELCM.

During such Utilization Transactions, mismatch of details between the external product processor and Oracle FLEXCUBE ELCM may occur. To handle such mismatches, the Oracle FLEXCUBE ELCM system features an EOD Reconciliation Process to bring both system in sync by the end of the day.

EOD Reconciliation Process

As part of the EOD Reconciliation Process, an inbound transaction process happens wherein each product processor generates a batch file containing details pertaining to all the utilization requests for the day. The Oracle FLEXCUBE ELCM system will process these batch files as part of EOD batch operation and perform the reconciliation process.

The “Manual/System” parameter will specify whether the mismatched transaction should be handled manually by the user or the system should perform the reconciliation process

The system will read all the batch files for reconciliation and perform a comparison of all the transaction that has been performed in the product process with the utilization transactions performed in Oracle FLEXCUBE ELCM.

The following table shows the possible types of the mismatch.

Transaction Status in Product Processor/ Oracle FLEXCUBE	Corresponding Utilization status in Oracle FLEXCUBE ELCM	Resulting Oracle FLEXCUBE ELCM Action
Not Saved	Saved	Reversal
Saved	Not saved	Upload

The above mentioned Oracle FLEXCUBE ELCM action is performed only if the system parameter has been set to 'System'.

Viewing Mismatch Summary

You can view in the mismatch Summary screen all the counter transactions that has been performed by Oracle FLEXCUBE ELCM for handling the mismatches. The summary also indicates whether the counter transactions have succeeded or failed.

For failed transactions, the reason for failure will be shown. You will have to take manual action in case of failed transactions.

6.11 Increasing/Decreasing Utilizations

You can modify the utilization amount of the transaction through the 'Utilization Increase And Decrease' screen. This transaction can be used when customer is making payment for the loan or when the loan amount is modified.

You can invoke the 'Utilization Increase and Decrease' screen by typing 'GEDUTNID' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Note

The feature explained in this section will be available only if the Enterprise Limits and Collateral Management module has been set up in standalone mode. In case of embedded or hybrid setups, you will not be able to invoke this screen.

Utilization Reference No

Specify the reference number for the utilization that you wish to modify. The adjoining option list contains all the utilizations in the system. Select the appropriate one. The system displays the user reference number, the utilization currency and the amount tag.

Utilization Amount

Enter the amount by which you wish to modify the utilization.

Action

Indicate the operation for the utilization – whether you would like to increase or decrease the utilization amount

Transaction Date

Specify the transaction date from the adjoining calendar.

Value Date

Specify the value date (the date on which the transaction comes into effect) for the transaction from the adjoining calendar. It can be the system date or a future date.

The 'Limit Utilization' screen will be displayed when you click on the 'Details' button where you can view the details of the original utilization request.


6.12 Linking an Utilization Transaction to a Facility

If you link an Oracle FLEXCUBE transaction to a facility, then based on the event of transaction corresponding, you need to process limits related data in Enterprise Limits and Collateral Management (ELCM) systems.

During processing if any error or override occurs in ELCM, then ELCM sends an error or override information to Oracle FLEXCUBE. Later Oracle FLEXCUBE will display the details to you. The Interface between Oracle FLEXCUBE and ELCM is online real time using HTTP and all transaction posted into ELCM is auto authorized. If delete or reversal action is triggered, the system will reverse the transaction in ELCM.

If a contact needs to be tracked under facility, then you have to link the contact to the facility and during transaction processing, Oracle FLXCUBE sends the utilization details to ELCM for processing.

The below diagram briefs the Utilization Transaction Integration Approach flow between Oracle FLEXCUBE and ELCM:



The table below explains the actions you can perform for which Oracle FLEXCUBE hands-off utilization transaction to ELCM:

SI. No	Oracle FLEXCUBE Transaction Action	Utilization Transaction Action
1	New	New
2	Modify	Modify/ Increase/Decrease
3	Delete	Delete
4	Reverse	Reverse
5	Liquate	Liquate
6	Rollover	Rollover
7	Payment	Decrease

As part of the contract or transaction process, if a line code is linked to a contract then it is required to track the limits of the linked line. The system exposes limits process as subsystem and any module would interact with Limits subsystem.

The system allows you to trap all the utilization transaction. The system would interface with ELCM Gateway HTTP to upload the utilization transactions in ELCM. Based on the utilization event, the system creates utilization request in ELCM format. It also logs transaction data and status of each utilization transaction.

6.12.1 Collateral Pool Utilization Transaction Process

You are allowed to link collateral pool as part of contract and upload all collateral pool utilization transactions in ELCM. You can process the following events as part collateral pool utilization:

- New
- Modify
- Delete

The system allows you to plug the pool utilization data from Oracle FLEXCUBE and passes to ELCM using ELCM Gateway HTTP/WS communication channel.

6.12.2 Utilization Transaction Status

The following are the possible transaction status for utilization upload:

- Success
- Failure
- Override
- Dual Auth

6.12.2.1 Transaction Status Success

Oracle FLEXCUBE sends the utilization transaction to ELCM and while processing this transaction, if ELCM processes it completely, then this transaction would be considered as success. Oracle FLEXCUBE would continue to process remaining contract process.

During transaction process, if transaction is uploaded successfully in ELCM and if any error or overrides (overrides not accepted) occurs in Oracle FLEXCUBE then uploaded transaction is reverted back using technical undo feature of ELCM.

6.12.2.2 Transaction Status Failure

Oracle FLEXCUBE sends the utilization transaction to ELCM and while processing this transaction, if any error occurs, ELCM will send failure status with error details to Oracle FLEXCUBE.

ELCM plug-in updates the transaction error objects which ELCM error code, as part of transaction process. Later Oracle FLEXCUBE checks the error object and subsequently raises error as part of contract process.

As part of the transaction process, if ELCM process is failed then ELCM error details are displayed to the user.

Note

- All error code of ELCM are available as part of the Oracle FLEXCUBE

- All ELCM error codes starts with 'EL'
-

6.12.2.3 Transaction Status Override

Oracle FLEXCUBE sends the utilization transaction to ELCM and while processing this transaction, if any override occurs, in such cases ELCM would generate override reference number (Multitrip ID) and log override details along with Multitrip ID for further reference. It marks the final transaction status as override and override details only with Multitrip ID is passed to Oracle FLEXCUBE for further processing.

ELCM plug-in would updates override details in Oracle FLEXCUBE error object it also logs the status and Multitrip ID as part of log table, later as part of transaction process Oracle FLEXCUBE checks the error object and subsequently raises transaction status as override.

Note

If overrides occur as part of transaction process, then the system displays the override details to the user. You have an option to accept or reject the overrides.

If the override occurs as part of the request, XML Multitrip ID is also passed and this Multitrip ID is passed to ELCM as part of utilization transaction. As part of the utilization process in ELCM if same (previous transaction) overrides occurs, then it is accepted and the transaction will be saved.

6.12.2.4 Transaction Status Dual Auth

Oracle FLEXCUBE sends the utilization transaction to ELCM and while processing this transaction, if any of the validation requires authorization, then ELCM processes the transaction completely and sends dual auth details and marks the transaction status as Dual auth required.

ELCM plug-in updates dual auth details in error object, later as part of transaction process it updates dual auth details in Oracle FLEXCUBE tables. It updates the Auth status for the dual auth error code as 'U' – Unauthorized, if you try to authorize the contract, Oracle FLEXCUBE will check whether contract has any unauthorized dual-auth error code. If yes, the system does not allow contract to be authorized, till all dual-auth error codes are authorized.

In ELCM if any error code requires dual authorization, the system triggers credit exception management process flow. You are allowed to accept or reject the validation (dual-auth) error code. On accept or reject of the validation code, ELCM handoffs these details to JMS queue and ELCM out adapter is used to invoke Oracle FLEXCUBE WS for updating status of dual-auth error code.

6.12.2.5 Authorization of utilization transaction

All utilization transactions which are uploaded from Oracle FLEXCUBE are auto authorized and if contract or transaction is deleted in Oracle FLEXCUBE then ELCM would trigger the reversal transaction.

Example

Assume the following:

Liability 'COCACOLA' is created in ELCM with below details:

Liability Code - COCACOLA

Liability Currency - USD

Overall Limit - 100,000,000

Amount Utilized - 0

Customer 'C00001' is created in Oracle FLEXCUBE and Customer 'C00001' is linked in ELCM using liability 'COCACOLA' using customer liability linkage maintenance. Facility 'COCALOAN01' is created in ELCM with below details:

Liability Code - COCACOLA

Facility Code - COCALOAN01

Facility currency - USD

Limit Amount - 0

Amount Utilized - Yes

Revolving Flag - 1,000,000

Loan (CL module) has been inputted for customer 'C00001' created in Oracle FLEXCUBE with below details:

Customer No - C00001

Loan currency - USD

Loan Amount - 500,000

Value Date - 01-Mar-2008

Maturity Date - 01-Sept-2008

Facility Code - COCALOAN01

As part of loan processing, Oracle FLEXCUBE sends new utilization transaction to ELCM for the loan. As part of the utilization process ELCM updates utilized amount at facility level and liability level. The Liability details after loan transaction would be as below:

Liability Code - COCACOLA

Liability Currency - USD

Overall Limit - 100,000,000

Amount Utilized - 500,000

The Facility details after loan transaction is as below:

Liability Code - COCACOLA

Facility Code - COCALOAN01

Limit Amount - USD

Facility currency - 1,000,000

Amount Utilized - 500,000

Revolving Flag - Yes

Assume that you have paid the first installment of amount 100,000 (principal) using CL payment screen in Oracle FLEXCUBE and after processing the transaction, the liability and facility details would be as below:

Liability Code - COCACOLA

Liability Currency - USD

Amount Utilized - 100,000,000

Overall Limit - 400,000

Note

Since line linked to loan is revolving, as part payment transaction ELCM would reduce amount utilized.

The facility details after processing the loan transaction is as below:

Liability Code - COCACOLA

Facility Code - COCALOAN01

Facility currency - USD

Limit Amount - 1,000,000

Amount Utilized - 400,000

Revolving Flag - Yes

7. Annexure 2 - Value Dated Facility

7.1 Introduction

Oracle FLEXCUBE ELCM provides a feature to maintain Facility details based on a particular value date. This is called the Value Dated Facility. This facilitates the changes in the Limits Amount, Main Line Linkage etc. to take effect from the particular date.

Oracle FLEXCUBE ELCM also tracks all the Utilizations of the Facility based on the value date of the transaction. The utilizations will take effect from the value date of the transaction onwards.

Note

- Tenor wise limits will continue to be based on booking date
 - Booking dated limit revaluation only will be done
 - Booking dated based overrides only will be provided
 - No validations based on the value dated balances will be done
 - Auto limits transfer / limits transfer will be based on booking date
-

7.2 Value Date Based Facility Maintenance

Oracle FLEXCUBE ELCM facilitates maintaining Facility details based on a particular value date. The changes in the Limits amount, Main line linkage etc. would take effect from the particular date.

The following parameters will be taken from the Facility Maintenance screen:

- Value date - Any valid date in the past can be maintained. No future valued records can be maintained and the value date cannot be before the conversion date.
- Main Line Code - It is the main line that the Line reports to. It will be validated that the main line in the Facilities maintenance (booking dated) is same as the main line in the latest record (value dated) in the maintenance.
- Limit Amount - The limit amount for the facility. It will be validated that the limit amount in the Facilities maintenance (booking dated) is same as the limit amount in the latest record (value dated) in the maintenance.

Whenever a new Limit Line is created, a new record will be automatically created by the system with the value date as the Limit Start Date. The Main Line and the Limit Amount will be same as the booking dated limit maintenance.

Whenever the Mainline or the Limit amount is changed in the facility, a new record will be created in the maintenance with value date as the application date. The mainline and limit amount values will be same as in the booking dated Limits maintenance. You can manually change the value to an older value date by clicking 'Value Date' button.

The 'Conversion Date' contains the date when facility was migrated from the external system to Oracle FLEXCUBE ELCM. In the Facility screen this date will be displayed.

Back Valued Static Maintenance Changes

The value dated utilization details will be rebuilt from the value date of the change whenever the following static maintenances are done:

- Limit Amount Change
- Mainline Sub Line Linkage

If the facility has been migrated then back valued static maintenance cannot be prior to the conversion date.

7.3 Value Date Based Utilization Processing

Oracle FLEXCUBE ELCM also tracks all the utilizations of the facility based on the value date of the transaction. The utilizations will take effect from the value date of the transaction onwards.

The following transactions are supported for Value dated processing:

- New utilization
- Increase utilization
- Decrease utilization
- Alter utilization

As part of the above utilization transactions, the Value Date will be the value date of the transaction. Updating of value dated utilization can be set to be online or to be a part of EOD process. This parameter is maintained in Oracle FLEXCUBE ELCM Parameter Maintenance.

- If the parameter is set to update Value Date online, then during the transaction process the Value Date utilization details will be updated online. Otherwise it will be updated during EOD process.
- In the case of main lines, the system will identify all the sub lines linked and track the utilization. This utilization will be tracked in addition to the contracts that are directly linked to the main line.

Refer Annexure – 1 for more details on Utilization Transactions.

7.3.1 Back Valued Transactions

The following back valued operations will cause a rebuild of value dated utilization details:

- New utilization
- Increase utilization
- Decrease utilization
- Alter utilization

If the utilization currency is not same as the line amount currency, then the system will convert the utilization into line amount currency and update the utilization. The exchange rate will be that of the value date of the utilization. So for back valued utilization the exchange rate on the value date of the back valued transaction will be used.

In case the Value Date is less than the conversion date, then the rebuild of balances will be from the conversion date only.

7.3.2 EOD Processing

If the value date update is not online, but as part of Facility EOD process, it would be updated as shown in the following examples.

Example,

Let us consider a Loan of 1 Million USD. Value date 10-Jan-2005 Revolving Line

Step 1: Initiation - Utilization Log

S.n o	Value date	Line code	Utilizatio n	Componen t	Increase/ decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase

Line Utilization

S.n o	Value date	Line code	Utilizatio n
1	10-Jan-05	LINE1	1000000

Step 2: Payment of 0.1M Principal value date 10-Feb-2005 - Utilization Log

S.n o	Value date	Line code	Utilizatio n	Componen t	Increase/ decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase
2	10-Feb-05	LINE1	100000	PRINCIPAL	Decrease

Line Utilization

S.n o	Line code	Value date	Utilizatio n
1	LINE1	10-Jan-05	1000000
2	LINE1	10-Feb-05	900000

Step 3: Value dated amendment of 0.5M Principal increase value date 15-Feb-2005 - Utilization Log

S.n o	Value date	Line code	Utilizatio n	Componen t	Increase/ decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase
2	10-Feb-05	LINE1	100000	PRINCIPAL	Decrease
3	15-Feb-05	LINE1	500000	PRINCIPAL	Increase

Line Utilization

S.n o	Line code	Value date	Utilizatio n
1	LINE1	10-Jan-05	1000000
2	LINE1	10-Feb-05	900000
3	LINE1	15-Feb-05	1400000

Step 4: Payment of 0.2M value date 10-mar-2005 - Utilization Log

S.no	Value date	Line code	Utilization	Component	Increase/Decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase
2	10-Feb-05	LINE1	100000	PRINCIPAL	Decrease
3	15-Feb-05	LINE1	500000	PRINCIPAL	Increase
4	10-Mar-05	LINE1	200000	PRINCIPAL	Decrease

Line Utilization

S.no	Line code	Value date	Utilization
1	LINE1	10-Jan-05	1000000
2	LINE1	10-Feb-05	900000
3	LINE1	15-Feb-05	1400000
4	LINE1	10-Mar-05	1200000

Step 5: Reversal of Payment of 0.2M value date 10-mar-2005 on 15-mar-2005 - Utilization Log

S.no	Value date	Line code	Utilization	Component	Increase/decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase
2	10-Feb-05	LINE1	100000	PRINCIPAL	Decrease
3	15-Feb-05	LINE1	500000	PRINCIPAL	Increase
4	10-Mar-05	LINE1	200000	PRINCIPAL	Decrease
5	10-Mar-05	LINE1	200000	PRINCIPAL	Increase

Line Utilization - Step 6 Liquidation of Contract Value date 10-apr-2005 - Utilization Log

S.no	Value date	Line code	Utilization	Component	Increase/decrease
1	10-Jan-05	LINE1	1000000	PRINCIPAL	Increase
2	10-Feb-05	LINE1	100000	PRINCIPAL	Decrease
3	15-Feb-05	LINE1	500000	PRINCIPAL	Increase
4	10-Mar-05	LINE1	200000	PRINCIPAL	Decrease
5	10-Mar-05	LINE1	200000	PRINCIPAL	Increase
6	10-Apr-05	LINE1	1400000	PRINCIPAL	Decrease

Line Utilization

S.n o	Line code	Value date	Utilizatio n
1	LINE1	10-Jan-05	1000000
2	LINE1	10-Feb-05	900000
3	LINE1	15-Feb-05	1400000
4	LINE1	10-Mar-05	1400000
5	LINE1	10-Apr-05	0

8. Annexure 3 – Revaluation

8.1 Introduction

Oracle FLEXCUBE ELCM caters to different types of currencies and collaterals backed by marketable securities. Exchange rates and the value of marketable securities are driven by market forces and hence tend to fluctuate over a period of time. Revaluation is essential to keep set limits realistic and to reflect the current market trends.

Revaluation can be of two types:

- Currency Revaluation - The changes in the exchange rates of currencies involved in the active contracts and collateral linked to the Facility affects the Credit Limit under the facility.
- Collateral Revaluation - A change in the market price of a marketable security backing collateral causes a revaluation of the collateral amount.

8.2 Currency Revaluation

Currency revaluation is triggered off as a result of the cases explained in the sections explained below.

8.2.1 Facility Currency and Utilization Currency

Consider that a change takes place in the exchange rate between the line currency and the currency of a contract utilizing the limit under the line. Due to this change in exchange rate revaluation takes place in two in the following two stages:

Stage 1 – Currency Revaluation occurs between utilized contract and the credit line of the facility

In the Currency Rates Screen of the Core services module, you can maintain exchange rates for currency pairs that your bank deals with. Along with this, you can also specify the Mid Rate and the Buy or Sell Spread for various currency pairs. After you update and authorize the new exchange rates, they become effective.

While defining a credit line for a facility, you have the option of maintaining currency restrictions for the line. If you do not specify currency restrictions for a facility, then contracts having currencies other than the facility currency, can utilize the limit under the credit line. The revaluation process is applicable for such a line.

If the above conditions hold good, then a change in the exchange rate will trigger of the revaluation process. The system calculates the Facility currency equivalent of all the contracts linked to the facility (using the new exchange rates) and updates the utilization and available amount under the line.

Example

You have defined a line for Loans, and linked the Liability Code Symphony Group to it. The credit limit assigned to the credit line is USD 100,000, the facility currency is USD. No currency restrictions have been maintained for the facility.

Liability Code	Line Code	Facility Limit	Facility Currency
----------------	-----------	----------------	-------------------

Symphony Group	Loans	100,000	USD
----------------	-------	---------	-----

On 01 January 2008 the following Loan contracts has been sent to Oracle FLEXCUBE ELCM system for utilization, which are linked to this Credit Line. At the time of saving these utilization details, the line utilization will be computed based on the exchange rates as of the transaction date (i.e. 01 January 2008) of these contracts. The following table contains the details.

Loan Amount	Exchange Rate	Facility Currency Equivalent (USD)	Utilization	Availability
AUD 15,000	1.50	22500.00	22500.00	27500.00
DEM 2,000	1.20	2400.00	2400.00	25100.00
GBP10,000	0.5	20000.00	20000.00	5100.00
INR 72,000	36.00	2,000.00	2,000.00	3100.00
Total			\$46900.00	\$3100.00

On 01 February 2008 the exchange rates have changed (now 1USD=1.6 AUD). After the exchange rate revision has been changed and authorized, the revaluation process (online process) scans the contracts linked to the line, converts the contract currency to the Facility currency (using the new exchange rates) and updates the line's utilization and available amount.

The following table indicates these details:

Loan Amount	Exchange Rate	Facility Currency Equivalent (USD)	Utilization	Availability
AUD 15,000	1.60	24000.00	24000.00	26000.00
DEM 2,000	1.20	2400.00	2400.00	23600.00
GBP10,000	0.5	20000.00	20000.00	3600.00
INR 72,000	36.00	2,000.00	2,000.00	1600.00
Total			\$48400.00	\$1600.00

Stage 2: Revaluation occurs between the facility and the liability which is linked to that facility.

Due to the currency revaluation between utilized contract and the credit line of the facility (as per **Stage 1**) there will be a revaluation on credit limit utilized by the liability.

Considering the same example as in Stage 1

You have defined a line for Loans, and linked the Liability Code Symphony Group to it. The credit limit assigned to the credit line is USD 100000. This liability is linked only to one Facility (or line code) Loans.

Initially before the change in the exchange rate the utilization of the liability is as shown in the table:

Liability Code	Line Code	Liability Limit	Liability Currency	Liability Utilization	Availability
Symphony Group	Loans	100,000	USD	\$46900.00	\$53100.00

After the change in the exchange rate between the line currency and the currency of a contract utilizing the limit under the line, due to this the utilization at the facility level is will changed. Due to this change the utilization at the Liability level also gets changed as shown in the table below:

Liability Code	Line Code	Liability Limit	Liability Currency	Liability Utilization	Availability
Symphony Group	Loans	100,000	USD	\$48400.00	\$51600.00

8.2.2 Facility Currency and Collateral Currency

Change in exchange rates between the Credit Line currency and the currency of the collateral.

When you update and authorize the exchange rates in the currency table, the system scans all the collateral linked to a line (bearing different currencies). The collateral contribution is then converted the into the line currency (using the latest exchange rates). After the conversion, the collateral contribution to the line is updated.

The calculated limit contribution of the collateral has to be linked to the pool. This pool containing the pool amount will be linked to the Facility. Hence any revaluation at collateral level will affect the pool amount.

Example

You have defined a line for Loans on 01 January 2008, and linked the Liability Code Symphony Group to it. The credit limit assigned to the credit line is USD 100,000, the facility currency is USD. No currency restrictions have been maintained for the facility. Let us say that the Loans line has been backed by Collateral "ABC" and its maximum contribution amount that can be linked to the limit is GBP 10,000.

(1 GBP= 2 USD)

Collateral Code	Max. Collateral Contribution amount	Collateral Currency	POOL code	Pool Currency	Collateral Pool % linkage	Pool amount
ABC	10,000	GBP	Pool1	USD	100%	20,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution	Line Avl. amount
Pool1	USD	Loans	USD	100%	\$20,000	\$120,000

On 01 February 2008 the exchange rates have changed. After the exchange rate revision has been changed and authorized, the revaluation process (online process) scans all the pools where this collateral has been linked and having the above exchange pair will be revaluated.

(1 GBP= 1.5 USD)

Collateral Code	Line Code	Max. Collateral Contribution amount	Collateral Currency	Pool code	Pool Currency	Collateral Pool % linkage	Pool amount
ABC	Loans	10,000	GBP	Pool 1	USD	100%	15,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount
Pool1	USD	Loans	USD	100%	\$15,000	\$115,000

The revaluation in both cases is triggered off automatically whenever there is a change in the exchange rates (i.e. online process).

The process explained above is an online process wherein the change in the currency exchange rate immediately revaluates all the contracts and the collaterals having this exchange pair with the facility currency. If at the Oracle FLEXCUBE ELCM Global Parameter maintenance, the option for Revaluate Currency during Offline (batch) has been selected then the currency revaluation as explained above will be taken up as part of revaluation batch process.

8.3 Collateral Revaluation

Collateral Revaluation will be of two types. These types are explained in the sections below.

8.3.1 Collateral Revaluation of Market Based Securities

The assets that are offered as collateral generally back the credit facilities that the bank grants a customer. Your customers can offer 'marketable securities' as collateral. As Marketable Securities are by nature given to fluctuations based on the forces of short-term demand and supply, their value also tends to fluctuate.

A rise or fall in the market value of a security, affects its collateral value. Therefore, the value of a collateral should reflect the changes in the value of the securities backing it.

Revaluation of a Collateral is caused only if the value of the marketable security that backs the collateral, fluctuates beyond the price sensitivity you prescribed for the security in the Securities Maintenance screen and the Revalue collateral check box has been checked for that collateral in the collateral maintenance. Based on these changes, the collateral contribution to the overall credit limit of the customer will increase or decrease. Hence the availability under the line will also change.

After you authorize the price change:

- The price change is compared with the last price stored in the Collateral Maintenance screen.
- If the price change (in percentage) of the security is greater than the Price-Increase-Sensitivity defined for the collateral or less than the Price-Decrease-Sensitivity defined for the collateral, the revaluation process will be triggered off. Otherwise the price change will not affect the existing collateral value.

If the revaluation causes the collateral value to raise, this new value is compared with the Cap Amount that you specified for the collateral in the Collateral Maintenance screen.

- If the computed value is less than the cap amount then the collateral contribution will be increased to that effect on account of the revaluation. The available amount under the credit line increases.
- If it exceeds the Cap amount then the cap amount will be taken as the collateral contribution.

Similarly, if the market price of the security decreases, the collateral contribution to the overall limit of the customer also decreases and as a result, the available amount under the credit line reduces.

Example

Your customer XYZ has 1000 units of Debentures'08 that have been issued by Reliance as part of her portfolio, which you consider as Collateral. The Market value of the Debentures'08 is \$ 50 per unit. You have defined the Price Increase and Decrease Sensitivity for this security to be 8% and 5% respectively. Let the customer have credit limit of USD 1 million for the facility of line code "Loans".

You have specified that this collateral's contribution to the overall Limit of the customer should be \$ 50,000.

The maximum amount that it can contribute to the overall limit of the customer as \$ 60,000 (Cap Amount).

Liability Code	Line Code	Liability Limit	

Symphony Group	Loans	\$1million	
Collateral Code			Pool amount Collateral POOL code Cap Amount Collateral Contribution amount Pool % linkage
ABB			\$50,000 100% Pool1 \$60,000 \$50,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount(credit limit + Pool contribution)
Pool1	USD	Loans	USD	100%	\$50,000	\$1.05million

A Rise in Value

The market value of Debentures2008 has increased to \$55, which is a 10% increase over the old market price of \$50.

At the time you update the Market price of Debentures 2008 in the Securities Maintenance screen, the revaluation process is triggered off, as the increase (10%) is higher than the Increase sensitivity (8%) defined for Debentures 2008. The value of this collateral now stands at \$ 55,000. As this amount is less than the Cap Amount you specified for the collateral the Credit Limit available to the XYZ has increased by \$ 5,000, as a result of the revaluation.

Collateral Code	Collateral Contribution amount	Cap Amount	POOL code	Collateral Pool % linkage	Pool amount
ABB	\$55,000	\$60,000	Pool1	100%	\$55,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount
-----------	---------------	-----------	---------------	---------------------	----------------------------------	-----------------------

Pool1	USD	Loans	USD	100%	\$55,000	\$1.055 million
-------	-----	-------	-----	------	----------	-----------------

A Rise in Value beyond the Cap Amount

The market value of Debentures2008 has increased to \$65 which is a 30% increase over the old market price of \$50.

At the time you update the Market price of Debentures2008 in the Securities Maintenance screen, the revaluation process is triggered off, as the increase (30%) is higher than the Increase Sensitivity (8%) defined for Debentures 1999. The value of this collateral now stands at \$ 65,000. As this amount is more than the Cap Amount of \$60,000 that you specified for the collateral, the Credit Limit available to the XYZ will be increased. However, the increase will not exceed the Cap Amount.

XYZ's maximum amount that is contributed to the overall limit will now stand at \$ 60,000 (cap Amount) and not at \$65,000 (market value) as a result of the revaluation.

Collateral Code	Collateral Contribution amount	Cap Amount	POOL code	Collateral Pool % linkage	Pool amount
ABB	\$60,000	\$60,000	Pool1	100%	\$60,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount
Pool1	USD	Loans	USD	100%	\$60,000	\$1.06 million

A fall in value

The market value of Debentures2008 has decreased to \$45, which is a 10% decrease from the old market price of \$50. At the time you update the Market price of Debentures2008 in the Securities Maintenance screen, the revaluation process is triggered off, as the decrease (11.11%) is higher than the decrease sensitivity (5%) defined for Debentures 1999.

The market value of this collateral now stands at \$ 45,000. XYZ's credit limit will stand decreased by \$ 5,000 as a result of the revaluation.

Collateral Code	Collateral Contribution amount	Cap Amount	POOL code	Collateral Pool % linkage	Pool amount
ABB	\$45,000	\$60,000	Pool1	100%	\$45,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount
Pool1	USD	Loans	USD	100%	\$45,000	\$1.045 million

This process explained above is online process where in the change in the Security Price immediately revaluates all the collateral linked to these securities. If at the Oracle FLEXCUBE ELCM Global Parameter maintenance, the option for 'Revaluate Market Online' has been selected, as batch, then the collateral revaluation as explained above will be taken up as part of revaluation batch process.

Adhoc Revaluation of Market Based Collaterals

In the 'Adhoc Revaluation' screen, specific market based collaterals can be chosen to forcefully run the revaluation process. If such collateral values have to be revised then an input file containing the latest security price has to be sent to system prior running the Collateral Force Revalue.

8.3.2 Collateral Revaluation of Non-Market Based Securities

Collateral revaluation of non-market based securities is not subjected to market fluctuation. Hence if such collateral values have to be revised then an input file containing the collateral code of all such collaterals and the latest revised collateral value must be sent to the system.

The revaluation process takes place online when ever there is a change in the collateral value.

Example

Non market Based collateral Fixed Deposit (having 100% lendable margin) has been linked to a facility on 1st January 2008 owned by a XYZ customer having the liability Symphony Group.

Liability Code	Line Code	Liability Limit
Symphony Group	Loans	\$1million

Collateral Code	Collateral Value	Collateral Contribution amount	Pool code	Collateral Pool % linkage	Pool Amount
Fixed Deposit	\$50,000	\$50,000	Pool1	100%	\$50,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount
Pool1	USD	Loans	USD	100%	\$50,000	\$1.05million

After one Year on 1st January 2009 the Fixed Deposit amount has increased due to interest earned. Now having a revised value as \$55,000. Now the latest value has to be sent to the Oracle FLEXCUBE ELCM system via input file and then the "Collateral Force Revalue" for this collateral has to be triggered manually.

The revaluation increases the overall limit amount as shown below.

Liability Code	Line Code	Liability Limit	
Symphony Group	Loans	\$1million	
Collateral Code			Pool amount Collateral Pool code Collateral Contribution amount Collateral Value Pool % linkage
Fixed Deposit			\$55,000 100% Pool1 \$55,000 \$55,000

Pool contribution to the line

Pool Code	Pool Currency	Line Code	Line Currency	Pool Line linkage %	Pool contribution amount to line	Line available amount(credit limit + Pool contribution)
Pool1	USD	Loans	USD	100%	\$55,000	\$1.055million

9. Annexure 4 - Gateway Processes & Interfaces

9.1 Introduction

The Oracle FLEXCUBE Enterprise Limits and Collateral Management (hereafter referred to as Oracle FLEXCUBE ELCM) system's Gateway processes allow seamless communication and integration with variety of other specialized applications. These other systems maybe deployed on different platforms and may use different infrastructure. The Gateway bridges the external system and the Oracle FLEXCUBE ELCM system.

Oracle FLEXCUBE Enterprise Limits and Collateral Management Gateway provides two main kinds of processes:

- Gateway Online process
- Gateway Batch process

9.2 Gateway Online Process

Gateway Online process provides following process:

- Online Inbound process
- Online Outbound process
- Embedded process

Following are the transactions supported by Gateway process:

- Maintenance transactions
- Utilization transactions
- Batch process

9.2.1 Maintenance Transactions

Below table specifies the maintenance transactions supported by Gateway Online Process

Transaction	Creation & Modification	Delete	Auth	Close & Reopen	Query	Notify	Tech. undo
Customer	Yes	Yes	Yes	Yes	Yes	No	No
Liability	Yes	Yes	Yes	Yes	Yes	No	Yes
Facility	Yes	Yes	Yes	Yes	Yes	No	Yes
Collateral	Yes	Yes	Yes	Yes	Yes	No	Yes
Collateral Pool	Yes	Yes	Yes	Yes	Yes	No	No
Issuers	Yes	Yes	Yes	Yes	Yes	No	No
Securities	Yes	Yes	Yes	Yes	Yes	No	No

Limits Transfer	Yes	Yes	Yes	Yes	Yes	No	No
Account Service	Yes	Yes	Yes	Yes	Yes	No	No

9.2.2 Utilization Transactions

Below table specifies the Utilization transactions supported by Gateway Online Process

Utilization Transactions	Input	Authorization	Deletion	Technical undo
New Utilization	Yes	Yes	Yes	Yes
Increase Utilization	Yes	Yes	Yes	Yes
Decrease Utilization	Yes	Yes	Yes	Yes
Alter Utilization	Yes	Yes	Yes	Yes
Reverse	Yes	Yes	Yes	Yes
Set Balance	Yes	Yes	Yes	Yes
Query Utilization				

9.2.3 Batch Process

The Batch processes which can be triggered using Gateway Online Process:

- EOD Process
- Input File Process
- Output File Process

9.2.4 Reprocessing Locked Online Transactions

During the processing of Gate Way online transactions some of the transactions processing may be fail because of a lock in the database. Oracle FLEXCUBE ELCM provides a feature to process the locked records.

9.2.5 Technical undo (Functional Rollback)

This feature of Gateway will allow the external system to rollback previously entered transactions in Oracle FLEXCUBE ELCM. This feature will be supported in Gateway Inbound (online), information required as part of Technical undo is also Transaction Id of the previous transaction. Technical undo is not supported for Query and Notification transactions.

9.3 Gateway Batch Process

Gateway Online processes are mainly used to process single transaction. Gateway Batch process will be used when high volume of data needs to be transferred from external system to Oracle FLEXCUBE ELCM system or vice versa. Communication format for the Gateway Batch process would be through ASCII file and data within the file is delimited with a Delimiter Character. All interface transaction file formats are predefined in the Oracle FLEXCUBE ELCM system.

Gateway Batch Process provides two kinds of process

- Batch Inbound Process
- Batch Outbound Process

9.3.1 **Batch Inbound Process**

Oracle FLEXCUBE ELCM Batch Inbound process is used to upload large records. As a batch operation the necessary input files will be fetched from the mentioned location path.

The Batch Inbound process can also be initiated from the following screen:

Batch Operations→In Bound Batch→detailed

The following operations (via input files) will be supported as an Input Files Batch Operations:

- Customer upload
- Utilization Upload
- Liability upload
- Facility upload
- Collateral upload
- Securities upload
- Rates upload

Utilization Upload

All the utilizations as part of Oracle FLEXCUBE ELCM Transaction functions are provided for as a part of Batch Inbound operations. Utilization upload allows more than one utilization record to be uploaded in a single upload process.

Liability Upload

Liability creation as a part of batch upload is provided for. Liability upload allows more than one Liability record to be uploaded in a single upload process.

Facility Upload

Facility creation as part of batch upload is provided for. Facility upload allows more than one Facility record to be uploaded in a single upload process.

Collateral Upload

Collateral creation as part of batch upload is provided for. Collateral upload allows more than one Collateral record to be uploaded in a single upload process.

Securities Upload

Securities creation as part of batch upload is provided for. Securities upload allows more than one Securities record to be uploaded in a single upload process.

Customer Upload

Customer creation as part of batch upload is provided for. Customer upload allows more than one Customer record to be uploaded in a single upload process.

Rates Upload

Rates creation as part of batch upload is provided for. Rates upload allows more than one Customer record to be uploaded in a single upload process.

9.3.2 **Batch Outbound Process**

Oracle FLEXCUBE ELCM Batch Outbound process is used to upload large records. As a batch operation the necessary output files will be generated into the mentioned work path.

You can initiate the Batch Outbound Process using the following screen.

Batch Operations→Out Bond Batch→Detailed

The following operations will be supported as an Input Files Batch Operations.

- Utilization
- Liability
- Facility
- Collateral

Utilization Handoff (For the Current Day)

All the utilizations which have occurred during the day can be grouped into a file. This file is a part of batch handoff operation. This file will contain only the current day's utilization records.

Liability Handoff (Zero Based)

All the Liabilities created in Oracle FLEXCUBE ELCM can be grouped in to file via the Batch Facility Handoff. This handoff will contain all the details of the records.

Facility Handoff (Zero Based)

All the facilities created in Oracle FLEXCUBE ELCM can be grouped into file via the Batch Facility Handoff. This handoff will contain all the details of the records.

Collateral Handoff (Zero Based)

All the Collateral created in Oracle FLEXCUBE ELCM can be grouped into file via the Batch Facility Handoff. This handoff will contain all the details of the records.

9.4 **Interfaces**

The following interfaces are available as part of the Oracle FLEXCUBE ELCM system.

Module	Interface Name	Interface Type
Currency	Rates Interface	Online incoming
Core	Product Interface	Batch Incoming
Branch Holiday	Holiday Interface	Batch Incoming
SMS	User Interface	Batch Incoming
Account	Account Interface	Online Incoming
TD	TD Interface	Online/Batch Incoming
TD	TD block/unblock Interface	Online/Batch Outgoing
Core	Liability Link Interface	Online/Batch Outgoing
Limits	Facility Interface	Batch Outgoing

Limits	Utilization interface	Batch Outgoing
Limits	Dual Authorization	Online Outgoing

For more details on maintaining External Systems and Interfaces refer the chapter titled 'Gateway Maintenance'.

10. Function ID Glossary

E

ELRFXCL	5-6
ELRPCLBK	5-7
ELRPCLMT	5-54
ELRPCNEX	5-9
ELRPCOLT	5-11
ELRPCOUL	5-13
ELRPCOUT	5-15
ELRPCRMO	5-17
ELRPCUTI	5-57
ELRPEXP	5-19
ELRPISEX	5-21
ELRPISUR	5-23
ELRPLB	5-25
ELRPLIAB	5-59
ELRPLIMT	5-26

ELRPLN	5-28
ELRPML	5-30
ELRPNRLN	5-32
ELRPOLNK	5-34
ELRPOLUT	5-36
ELRPOVLN	5-38
ELRPPREX	5-40
ELRPSECM	5-43
ELRPTN	5-44
ELRPUA	5-47
ELRPUSEX	5-49
ELRPUT	5-51
ELRPUTLD	5-53

G

GEDFACAM	2-93
GESCULIK	2-10