

# Oracle® Database

## Database Installation Guide



19c for IBM AIX on POWER Systems (64-bit)  
E96437-09  
December 2024

ORACLE®

Contributors: David Austin, Jean-Francois VERRIER, Neha Avasthy, Prasad Bagal, Subhranshu Banerjee, Gia-Khanh Nguyen, Richard Roddy, Tammy Bednar, David Ruiz, Gavin Bowe, Robert Chang, Darcy Christensen, Kiran Chamala, Jonathan Creighton, Benoit Dageville, Logeshwaran Rajan, Rajesh Dasari, Angad Gokakkar, Anu Natarajan, Girdhari Ghantiyala, Chandrasekharan Iyer, David Jimenez, Vishal Saxena, Vasu Venkatasubramanian, Suman Palavalli, Sameer Joshi, Malai Stalin, Markus Michalewicz, Subrahmanyam Kodavaluru, David Price, Sudip Datta, Jim Erickson, Marcus Fallen, Joseph Francis, Allan Graves, Barbara Glover, Asad Hasan, Thirumaleshwara Hasandka, Clara Jaeckel, Michael Coulter, Aneesh Khandelwal, Joel Kallman, Eugene Karichkin, Jai Krishnani, Sangeeth Kumar, Ranjith Kundapur, Kevin Jernigan, Christopher Jones, Simon Law, Bryn Llewellyn, Saar Maoz, Sreejith Minnanghat, Gopal Mulagund, Annie Chen, Rich Long, Barb Lundhild, Rolly Lv, Rudregowda Mallegowda, Padmanabhan Manavazhi, Mughees Minhas, Krishna Mohan, Matthew McKerley, John McHugh, Gurudas Pai, Satish Panchumarthy, Rajesh Prasad, Rajendra Pingte, Robert Achacoso, Srinivas Poovala, Hanlin Qian, Prasad Kuruvadi Nagaraj, Hema Ramamurthy, Sunil Ravindrachar, Mark Richwine, Dipak Saggi, Trivikrama Samudrala, David Schreiner, Ara Shakian, Ramesh Chakravarthula, Mohit Singhal, Dharma Sirnappalli, Akshay Shah, James Spiller, Roy Swonger, Binoy Sukumaran, Ravi Thammaiah, Shekhar Vaggu, Peter Wahl, Sergiusz Wolicki, Sivakumar Yarlagadda

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

## Preface

---

Audience	xi
Documentation Accessibility	xi
Set Up Java Access Bridge to Implement Java Accessibility	xi
Command Syntax	xii
Related Documentation	xiii
Conventions	xiii

## Changes in this Release for Oracle Database

---

New Features	xiv
Deprecated Features	xiv

## 1 Oracle Database Installation Checklist

---

Server Hardware Checklist for Oracle Database Installation	1-1
Operating System Checklist for Oracle Database on IBM AIX on POWER Systems (64-Bit)	1-2
Server Configuration Checklist for Oracle Database Installation	1-2
Oracle User Environment Configuration Checklist for Oracle Database Installation	1-4
Storage Checklist for Oracle Database Installation	1-5
Installer Planning Checklist for Oracle Database	1-6

## 2 Checking and Configuring the Server for Oracle Database

---

Logging In to a Remote System Using X Window System	2-1
Checking Server Hardware and Memory Configuration	2-2

## 3 Configuring Operating Systems for Oracle Database on IBM AIX on POWER Systems (64-Bit)

---

Guidelines for IBM AIX on POWER Systems (64-Bit) Operating System Installation	3-2
Reviewing Operating System and Software Upgrade Best Practices	3-2
General Upgrade Best Practices	3-2
New Server Operating System Upgrade Option	3-3

Oracle ASM Upgrade Notifications	3-3
Reviewing Operating System Security Common Practices	3-4
About Installation Fixup Scripts	3-4
About Operating System Requirements	3-5
Operating System Requirements for IBM AIX on POWER Systems (64-Bit)	3-5
Supported IBM AIX 7.1 Versions	3-6
Supported IBM AIX 7.2 Versions	3-6
Supported IBM AIX 7.3 Versions	3-7
Additional Drivers and Software Packages for IBM AIX on POWER Systems (64-Bit)	3-8
Installing Oracle Messaging Gateway	3-9
Installation Requirements for ODBC and LDAP	3-9
About ODBC Drivers and Oracle Database	3-10
Installing ODBC Drivers for IBM AIX	3-10
About LDAP and Oracle Plug-ins	3-10
Installing the LDAP Package	3-10
Installation Requirements for Programming Environments for IBM AIX	3-10
Installation Requirements for Web Browsers	3-11
Checking the Software Requirements	3-12
Confirming Host Name Resolution	3-12
Enabling I/O Completion Ports	3-13
Using Automatic SSH Configuration During Installation	3-13

## 4 Configuring Users, Groups and Environments for Oracle Grid Infrastructure and Oracle Database

---

Required Operating System Groups and Users	4-1
Determining If an Oracle Inventory and Oracle Inventory Group Exist	4-2
Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist	4-3
About Oracle Installation Owner Accounts	4-3
Identifying an Oracle Software Owner User Account	4-3
Oracle Installations with Standard and Job Role Separation Groups and Users	4-4
About Oracle Installations with Job Role Separation	4-5
Standard Oracle Database Groups for Database Administrators	4-6
Extended Oracle Database Groups for Job Role Separation	4-6
Creating an ASMSNMP User	4-7
Oracle Automatic Storage Management Groups for Job Role Separation	4-7
Creating Operating System Privileges Groups	4-8
Creating the OSDBA for ASM Group	4-9
Creating the OSOPER for ASM Group	4-9
Creating the OSDBA Group for Database Installations	4-9
Creating an OSOPER Group for Database Installations	4-10
Creating the OSBACKUPDBA Group for Database Installations	4-10

Creating the OSDGDBA Group for Database Installations	4-10
Creating the OSKMDBA Group for Database Installations	4-11
Creating the OSRACDBA Group for Database Installations	4-11
Creating Operating System Oracle Installation User Accounts	4-11
Creating an Oracle Software Owner User	4-12
Environment Requirements for Oracle Software Owners	4-13
Procedure for Configuring Oracle Software Owner Environments	4-13
Modifying Oracle Owner User Groups	4-16
Setting Remote Display and X11 Forwarding Configuration	4-16
Preventing Installation Errors Caused by Terminal Output Commands	4-17
Creating Oracle Database Vault User Accounts	4-18
Unsetting Oracle Installation Owner Environment Variables	4-18
Running the rootpre.sh Script	4-19

## 5 Configuring Networks for Oracle Database

---

About Oracle Database Network Configuration Options	5-1
About Assigning Global Database Names During Installation	5-2
Network Configuration for Computers Completed After Installation	5-3
Network Configuration for Multihome Computers	5-3
Setting the ORACLE_HOSTNAME Environment Variable	5-4
Network Configuration for Computers with Multiple Aliases	5-4

## 6 Supported Storage Options for Oracle Database and Oracle Grid Infrastructure

---

Supported Storage Options for Oracle Database	6-1
About Oracle Grid Infrastructure for a Standalone Server	6-2
Oracle ACFS and Oracle ADVM	6-3
Oracle ACFS and Oracle ADVM Support on IBM AIX	6-4
Restrictions and Guidelines for Oracle ACFS	6-4
File System Options for Oracle Database	6-5
Guidelines for Placing Oracle Database Files On a File System or Logical Volume	6-6
About NFS Storage for Data Files	6-7
About Direct NFS Client Mounts to NFS Storage Devices	6-7

## 7 Configuring File System Storage for Oracle Database

---

Configuring NFS Buffer Size Parameters for Oracle Database	7-1
Checking TCP Network Protocol Buffer for Direct NFS Client	7-2
Creating an oranfstab File for Direct NFS Client	7-2
Enabling and Disabling Direct NFS Client Control of NFS	7-5

## 8 Configuring Storage for Oracle Grid Infrastructure for a Standalone Server

---

Configuring Storage for Oracle Automatic Storage Management	8-2
Identifying Storage Requirements for Oracle Automatic Storage Management	8-2
Oracle ASM Disk Space Requirements	8-5
ASM Disk Group Options for Installation	8-6
Using an Existing Oracle ASM Disk Group	8-6
Configuring Disk Devices for Oracle ASM on IBM AIX	8-7
Creating DAS or SAN Disk Partitions for Oracle Automatic Storage Management	8-8
Creating Directories for Oracle Database Files	8-8
Creating Files on a NAS Device for Use with Oracle Automatic Storage Management	8-9

## 9 Installing and Configuring Oracle Grid Infrastructure for a Standalone Server

---

About Image-Based Oracle Grid Infrastructure Installation	9-2
Setup Wizard Installation Options for Creating Images	9-2
Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation	9-3
Installing Oracle Grid Infrastructure for a Standalone Server for an Existing Database	9-5
Installing Oracle Grid Infrastructure for a Standalone Server Using a Software-Only Installation	9-6
About Oracle Grid Infrastructure Software-Only Installations	9-6
Installing Software Binaries for Oracle Grid Infrastructure for a Standalone Server	9-6
Configuring Software Binaries for Oracle Grid Infrastructure for a Standalone Server	9-8
Testing the Oracle Automatic Storage Management Installation	9-9
Relinking Oracle Restart and Oracle ASM Binaries	9-10
Configuring Oracle ASM Disk Groups Manually using Oracle ASMCA	9-10
Enabling Oracle ACFS on Oracle Restart Configurations	9-11
Applying Patches During an Oracle Grid Infrastructure Installation or Upgrade	9-11

## 10 Installing Oracle Database

---

About Image-Based Oracle Database Installation	10-2
About Deploying Oracle Database Using Oracle Fleet Patching and Provisioning	10-2
Downloading Oracle Software	10-3
Downloading the Installation Archive Files from Oracle Website	10-3
Downloading the Software from Oracle Software Delivery Cloud Portal	10-4
About Character Set Selection During Installation	10-4
About Automatic Memory Management Installation Options	10-5

Running the Installer in a Different Language	10-6
Installing the Oracle Database Software	10-6
Setup Wizard Installation Options for Creating Images	10-7
Applying Patches During an Oracle Database Installation or Upgrade	10-7
Running Oracle Database Setup Wizard to Install Oracle Database	10-8
Installing Standard Edition High Availability	10-9
About Standard Edition High Availability	10-10
Requirements for Installing Standard Edition High Availability	10-10
Deploying Standard Edition High Availability	10-11
Installing Standard Edition High Availability Database Software on Local File System	10-12
Installing Standard Edition High Availability Database Software on Oracle ACFS	10-14

## 11 Oracle Database Postinstallation Tasks

---

Required Postinstallation Tasks	11-1
Downloading Release Update Patches	11-2
Unlocking and Resetting Oracle Database User Passwords	11-2
Requirements for Database Passwords	11-3
Oracle Database System Privileges Accounts and Passwords	11-3
Guidelines for Changing System Privileges Account Passwords	11-6
Locking and Unlocking User Accounts	11-7
Using SQL*Plus to Unlock Accounts and Reset Passwords	11-7
Recommended Postinstallation Tasks	11-8
Creating a Backup of the root.sh Script	11-8
Setting Language and Locale Preferences for Client Connections	11-8
Recompile Invalid Objects in the Database	11-9
About Installing Oracle Autonomous Health Framework	11-11
About Changes in Default SGA Permissions for Oracle Database	11-11
Checking Installed Oracle Database Contents and Directory Location	11-12
Enabling and Disabling Oracle Database Options After Installation	11-12
Chopt Tool	11-13
Starting Oracle Enterprise Manager Database Express	11-14
Creating a Fast Recovery Area	11-14
About the Fast Recovery Area and the Fast Recovery Area Disk Group	11-14
Creating the Fast Recovery Area Disk Group	11-15
Cloning an Oracle Database Home	11-16

## 12 Removing Oracle Database Software

---

About Oracle Deinstallation Options	12-1
Oracle Deinstallation (Deinstall)	12-3
Deinstallation Examples for Oracle Database	12-5

Downgrading Oracle Restart	12-5
Removing an RPM-based Oracle Database Installation	12-7
Deinstalling Previous Release Grid Home	12-8

## A Completing Preinstallation Tasks Manually

---

Configuring Shell Limits and System Configuration Parameters for IBM AIX	A-1
Configuring Shell Limits on IBM AIX	A-2
Configuring System Configuration Parameters for IBM AIX	A-3
Checking Asynchronous Input Output Processes	A-4
Setting UDP and TCP Kernel Parameters Manually	A-4

## B Response Files

---

How Response Files Work	B-1
Reasons for Using Silent Mode or Response File Mode	B-2
Using Response Files	B-2
Preparing Response Files	B-3
Editing a Response File Template	B-3
Recording Response Files	B-4
Running Oracle Universal Installer Using a Response File	B-5
Running Configuration Assistants Using Response Files	B-7
Running Net Configuration Assistant Using Response Files	B-7
Running Oracle DBCA Using Response Files	B-8
Postinstallation Configuration Using Response File Created During Installation	B-9
Using the Installation Response File for Postinstallation Configuration	B-9
Running Postinstallation Configuration Using Response File	B-11
Postinstallation Configuration Using the ConfigToolAllCommands Script	B-12
About the Postinstallation Configuration File	B-12
Creating a Password Response File	B-13
Running Postinstallation Configuration Using a Password Response File	B-14

## C Optimal Flexible Architecture

---

About the Optimal Flexible Architecture Standard	C-1
About Multiple Oracle Homes Support	C-2
About the Oracle Inventory Directory and Installation	C-2
Oracle Base Directory Naming Convention	C-4
Oracle Home Directory Naming Convention	C-4
Optimal Flexible Architecture File Path Examples	C-5



## D Configuring Read-Only Oracle Homes

---

Evolution of Oracle Homes	D-1
About Read-Only Oracle Homes	D-2
About Oracle Base Homes	D-2
About Oracle Base Config	D-3
About orabasetab	D-3
Location of Networking Files in a Read-Only Oracle Home	D-4
Enabling a Read-Only Oracle Home	D-5
Copying demo Directories to Oracle Base Home	D-6
Determining if an Oracle Home is Read-Only	D-9
File Path and Directory Changes in Read-Only Oracle Homes	D-9

## E Managing Oracle Database Port Numbers

---

About Managing Ports	E-1
Oracle Database Component Port Numbers and Protocols	E-1

## Index

---

## List of Tables

---

1-1	Server Hardware Checklist for Oracle Database Installation	1-1
1-2	Operating System General Checklist for Oracle Database on IBM AIX on POWER Systems (64-Bit)	1-2
1-3	Server Configuration Checklist for Oracle Database	1-2
1-4	User Environment Configuration for Oracle Database	1-5
1-5	Storage Checklist for Oracle Database	1-6
1-6	Oracle Universal Installer Planning Checklist for Oracle Database Installation	1-7
3-1	IBM AIX 7.1 on POWER Systems (64-Bit) Minimum Operating System Requirements	3-6
3-2	IBM AIX 7.2 on POWER Systems (64-Bit) Minimum Operating System Requirements	3-6
3-3	IBM AIX 7.3 on POWER Systems (64-Bit) Minimum Operating System Requirements	3-8
3-4	Requirements for Programming Environments for IBM AIX on POWER Systems (64-Bit)	3-11
6-1	Supported Storage Options for Oracle Database	6-2
8-1	Oracle ASM Disk Number and Minimum Space Requirements for an Oracle database (non-CDB)	8-5
8-2	Oracle ASM Disk Number and Minimum Space Requirements for a multitenant container database (CDB) with one pluggable database (PDB)	8-5
9-1	Image-Creation Options for Setup Wizard	9-3
10-1	Image-Creation Options for Setup Wizard	10-7
11-1	Partial List of Oracle Database System Privileges Accounts Locked After Installation	11-4
A-1	Recommended Shell Limit Values	A-2
A-2	Minimum System Configuration Parameter Values	A-3
B-1	Response Files for Oracle Database and Oracle Grid Infrastructure	B-3
C-1	Examples of OFA-Compliant Oracle Base Directory Names	C-4
C-2	Optimal Flexible Architecture Hierarchical File Path Examples	C-6
D-1	read/write and Read-Only Oracle Home File Path Examples	D-10
E-1	Protocols and Default Port Numbers for Oracle Database Components	E-2

# Preface

This guide explains how to install and configure single-instance Oracle Database.

This guide also provides information about Optimal Flexible Architecture, cloning an Oracle home, and how to remove the database software.

- [Audience](#)  
This guide is intended for anyone responsible for installing Oracle Database 19c.
- [Documentation Accessibility](#)
- [Set Up Java Access Bridge to Implement Java Accessibility](#)  
Install Java Access Bridge so that assistive technologies on Microsoft Windows systems can use the Java Accessibility API.
- [Command Syntax](#)  
Refer to these command syntax conventions to understand command examples in this guide.
- [Related Documentation](#)  
The related documentation for Oracle Database products includes the following manuals:
- [Conventions](#)

## Audience

This guide is intended for anyone responsible for installing Oracle Database 19c.

Additional installation guides for Oracle Database, Oracle Real Application Clusters, Oracle Clusterware, Oracle Database Examples, and Oracle Enterprise Manager Cloud Control are available at the following URL:

<http://docs.oracle.com>

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

### Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

## Set Up Java Access Bridge to Implement Java Accessibility

Install Java Access Bridge so that assistive technologies on Microsoft Windows systems can use the Java Accessibility API.

Java Access Bridge is a technology that enables Java applications and applets that implement the Java Accessibility API to be visible to assistive technologies on Microsoft Windows systems.

Refer to *Java Platform, Standard Edition Accessibility Guide* for information about the minimum supported versions of assistive technologies required to use Java Access Bridge. Also refer to this guide to obtain installation and testing instructions, and instructions for how to use Java Access Bridge.

### Related Topics

- *Java Platform, Standard Edition Java Accessibility Guide*

## Command Syntax

Refer to these command syntax conventions to understand command examples in this guide.

Convention	Description
\$	Bourne or BASH shell prompt in a command example. Do not enter the prompt as part of the command.
%	C Shell prompt in a command example. Do not enter the prompt as part of the command.
#	Superuser (root) prompt in a command example. Do not enter the prompt as part of the command.
monospace	UNIX command syntax
backslash \	A backslash is the UNIX and Linux command continuation character. It is used in command examples that are too long to fit on a single line. Enter the command as displayed (with a backslash) or enter it on a single line without a backslash:  <pre>dd if=/dev/rdisk/c0t1d0s6 of=/dev/rst0 bs=10b \ count=10000</pre>
braces { }	Braces indicate required items:  <pre>.DEFINE {macro1}</pre>
brackets [ ]	Brackets indicate optional items:  <pre>cvtcrt termname [outfile]</pre>
ellipses ...	Ellipses indicate an arbitrary number of similar items:  <pre>CHKVAL fieldname value1 value2 ... valueN</pre>
<i>italic</i>	Italic type indicates a variable. Substitute a value for the variable:  <pre><i>library_name</i></pre>
vertical line	A vertical line indicates a choice within braces or brackets:  <pre>FILE filesize [K M]</pre>

## Related Documentation

The related documentation for Oracle Database products includes the following manuals:

### Related Topics

- *Oracle Database Concepts*
- *Oracle Database New Features Guide*
- *Oracle Database Licensing Information User Manual*
- *Oracle Database Release Notes*
- *Oracle Grid Infrastructure Installation and Upgrade Guide*
- *Oracle Database Client Installation Guide for IBM AIX on POWER Systems (64-Bit)*
- *Oracle Database Examples Installation Guide*
- *Oracle Real Application Clusters Installation Guide for Linux and UNIX*
- *Oracle Database Administrator's Reference for Linux and UNIX-Based Operating Systems*
- *Oracle Automatic Storage Management Administrator's Guide*
- *Oracle Database Upgrade Guide*
- *Oracle Database 2 Day DBA*
- *Oracle Application Express Installation Guide*

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

# Changes in this Release for Oracle Database

Learn about the new features and changes in Oracle Database Installation Guide for Oracle Database 19c.

- [New Features](#)  
Review new features available with Oracle Database installation in Oracle Database 19c.
- [Deprecated Features](#)  
Review features that are deprecated starting with Oracle Database 19c.

## Related Topics

- *Oracle Database New Features Guide*

## New Features

Review new features available with Oracle Database installation in Oracle Database 19c.

- [Root Scripts Automation Support for Oracle Database Installation](#)
- [Simplified Image-Based Oracle Database Client Installation](#)

## Root Scripts Automation Support for Oracle Database Installation

Starting with Oracle Database 19c, the database installer, or setup wizard, provides options to set up permissions to run the root configuration scripts automatically, as required, during a database installation. You continue to have the option to run the root configuration scripts manually.

Setting up permissions for root configuration scripts to run without user intervention can simplify database installation and help avoid inadvertent permission errors.

## Simplified Image-Based Oracle Database Client Installation

Starting with Oracle Database 19c, the Oracle Database client software is available as an image file for download and installation. You must extract the image software into a directory where you want your Oracle home to be located, and then run the `runInstaller` script to start the Oracle Database client installation. Oracle Database client installation binaries continue to be available in the traditional format as non-image zip files.

As with Oracle Database and Oracle Grid Infrastructure image file installations, Oracle Database client image installations simplify Oracle Database client installations and ensure best practice deployments.

## Deprecated Features

Review features that are deprecated starting with Oracle Database 19c.

The following feature is deprecated in this release, and may be desupported in another release. For more information about deprecated and desupported features, parameters and views, refer to *Oracle Database Upgrade Guide*.

- Deprecation of clone.pl

The `clone.pl` script is deprecated in Oracle Database 19c. The functionality of performing a software-only installation, using the gold image, is available in the installer wizard.

The `clone.pl` script can be removed in a future release. Instead of using the `clone.pl` script, Oracle recommends that you install the extracted gold image as a home, using the installer wizard.

- Deprecation of the SERVICE\_NAMES parameter

The use of the `SERVICE_NAMES` parameter is no longer actively supported. It must not be used for high availability (HA) deployments. It is not supported to use service names parameter for any HA operations. This restriction includes FAN, load balancing, `FAILOVER_TYPE`, `FAILOVER_RESTORE`, `SESSION_STATE_CONSISTENCY`, and any other uses.

- Deprecation of Oracle ACFS on IBM AIX

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

To align the support for the IBM AIX platform, Oracle Automatic Storage Management Cluster File System (ACFS) on IBM AIX (called Oracle Advanced Cluster File System starting with Oracle Database 21c) is deprecated in Oracle Database 19c. For data or files currently stored on an ACFS file system that cannot be stored in the Oracle database, the IBM General Parallel File System (GPFS) can be used.

### Related Topics

- *Oracle Database Upgrade Guide*

# 1

## Oracle Database Installation Checklist

Use checklists to review system requirements, and to plan and carry out Oracle Database installation.

Oracle recommends that you use checklists as part of your installation planning process. Using checklists can help you to confirm that your server hardware and configuration meet minimum requirements for this release, and can help you to ensure you carry out a successful installation.

- [Server Hardware Checklist for Oracle Database Installation](#)  
Use this checklist to check hardware requirements for Oracle Database.
- [Operating System Checklist for Oracle Database on IBM AIX on POWER Systems \(64-Bit\)](#)  
Use this checklist to check minimum operating system requirements for Oracle Database.
- [Server Configuration Checklist for Oracle Database Installation](#)  
Use this checklist to check minimum server configuration requirements for Oracle Database installations.
- [Oracle User Environment Configuration Checklist for Oracle Database Installation](#)  
Use this checklist to plan operating system users, groups, and environments for Oracle Database management.
- [Storage Checklist for Oracle Database Installation](#)  
Use this checklist to review storage minimum requirements and assist with configuration planning.
- [Installer Planning Checklist for Oracle Database](#)  
Use this checklist to assist you to be prepared before starting Oracle Universal Installer.

### Server Hardware Checklist for Oracle Database Installation

Use this checklist to check hardware requirements for Oracle Database.

**Table 1-1 Server Hardware Checklist for Oracle Database Installation**

Check	Task
Runlevel	2
Server Display Cards	At least 1024 x 768 display resolution, which Oracle Universal Installer requires.
Minimum network connectivity	Server is connected to a network
Minimum RAM	<ul style="list-style-type: none"><li>• At least 1 GB RAM for Oracle Database installations. 2 GB RAM recommended.</li><li>• At least 8 GB RAM for Oracle Grid Infrastructure installations.</li></ul>



# Operating System Checklist for Oracle Database on IBM AIX on POWER Systems (64-Bit)

Use this checklist to check minimum operating system requirements for Oracle Database.

**Table 1-2 Operating System General Checklist for Oracle Database on IBM AIX on POWER Systems (64-Bit)**

Item	Task
Operating system general requirements	The following IBM AIX on POWER Systems (64-bit) versions are supported: AIX 7.1 Technology Level 5 Service Pack 1 (7100-05-01-1731) or later, 64-bit kernel AIX 7.2 Technology Level 2 Service Pack 1 (7200-02-01-1731) or later, 64-bit kernel AIX 7.3 Technology Level 0 Service Pack 1 (7300-00-01-2148) or later, 64-bit kernel  Review the system requirements section for a list of operating system filesets and APARs.

## Related Topics

- [Operating System Requirements for IBM AIX on POWER Systems \(64-Bit\)](#)  
The versions, filesets, and Authorized Problem Analysis Reports (APARs) listed in this section are supported for this release on IBM AIX on POWER Systems (64-Bit).

# Server Configuration Checklist for Oracle Database Installation

Use this checklist to check minimum server configuration requirements for Oracle Database installations.

**Table 1-3 Server Configuration Checklist for Oracle Database**

Check	Task
Disk space allocated to the <code>/tmp</code> directory	At least 5 GB of space in the temporary disk space ( <code>/tmp</code> ) directory

**Table 1-3 (Cont.) Server Configuration Checklist for Oracle Database**

Check	Task
Swap space allocation relative to RAM (Oracle Database)	<p>Between 1 GB and 2 GB: 1.5 times the size of the RAM                      Between 2 GB and 16 GB: Equal to the size of the RAM                      More than 16 GB: 16 GB</p> <p><b>Note:</b>                      Contact your operating system vendor for swap space allocation guidance for your server. The vendor guidelines supersede the swap space requirements listed in this guide. On IBM AIX systems with 1 GB or more of memory, Oracle recommends that you set the paging space to an initial setting of half the size of RAM plus 4 GB, with an upper limit of 32 GB. During installation, to optimize paging, monitor the paging space use in a separate window. Use the command <code>chps</code> to increase or decrease the paging space size. The output of <code>chps</code> should indicate paging space use of less than 25 percent on a healthy system.</p>
Swap space allocation relative to RAM (Oracle Restart)	<p>Between 8 GB and 16 GB: Equal to the size of the RAM                      More than 16 GB: 16 GB</p>
Oracle Inventory (oraInventory) and OINSTALL Group Requirements	<ul style="list-style-type: none"> <li>For upgrades, Oracle Universal Installer (OUI) detects an existing oraInventory directory from the <code>/etc/oraInst.loc</code> file, and uses the existing oraInventory.</li> <li>For new installs, if you have not configured an oraInventory directory, then the installer creates an Oracle inventory that is one directory level up from the Oracle base for the Oracle Grid Infrastructure install, and designates the installation owner's primary group as the Oracle Inventory group.</li> </ul> <p>The Oracle Inventory directory is the central inventory of Oracle software installed on your system. Users who have the Oracle Inventory group as their primary group are granted the OINSTALL privilege to write to the central inventory.</p> <p>The OINSTALL group must be the primary group of all Oracle software installation owners on the server. It should be writable by any Oracle installation owner.</p>
Groups and users	<p>Oracle recommends that you create groups and user accounts required for your security plans before starting installation. Installation owners have resource limits settings and other requirements. Group and user names must use only ASCII characters.</p>
Mount point paths for the software binaries	<p>Oracle recommends that you create an Optimal Flexible Architecture configuration as described in the appendix "Optimal Flexible Architecture" in <i>Oracle Database Installation Guide</i> for your platform.</p>
Ensure that the Oracle home (the Oracle home path you select for Oracle Database) uses only ASCII characters	<p>The ASCII character restriction includes installation owner user names, which are used as a default for some home paths, as well as other directory names you may select for paths.</p>

**Table 1-3 (Cont.) Server Configuration Checklist for Oracle Database**

Check	Task
Unset Oracle software environment variables	<p>If you have an existing Oracle software installation, and you are using the same user to install this installation, then unset the following environment variables: \$ORACLE_HOME; \$ORA_NLS10; \$TNS_ADMIN.</p> <p>If you have set \$ORA_CRS_HOME as an environment variable, then unset it before starting an installation or upgrade. Do not use \$ORA_CRS_HOME as a user environment variable, except as directed by Oracle Support.</p>
Set locale (if needed)	<p>Specify the language and the territory, or locale, in which you want to use Oracle components. A locale is a linguistic and cultural environment in which a system or program is running. NLS (National Language Support) parameters determine the locale-specific behavior on both servers and clients. The locale setting of a component determines the language of the user interface of the component, and the globalization behavior, such as date and number formatting.</p>

**Related Topics**

- [Configuring Users, Groups and Environments for Oracle Grid Infrastructure and Oracle Database](#)  
Before installation, create operating system groups and users, and configure user environments.
- [Checking and Configuring the Server for Oracle Database](#)  
Verify that servers where you install Oracle Database meet the minimum requirements for installation.
- *Oracle Database Globalization Support Guide*

## Oracle User Environment Configuration Checklist for Oracle Database Installation

Use this checklist to plan operating system users, groups, and environments for Oracle Database management.

**Table 1-4 User Environment Configuration for Oracle Database**

Check	Task
Review Oracle Inventory (oralnventory) and OINSTALL Group Requirements	<p>The physical group you designate as the Oracle Inventory directory is the central inventory of Oracle software installed on your system. It should be the primary group for all Oracle software installation owners. Users who have the Oracle Inventory group as their primary group are granted the OINSTALL privilege to read and write to the central inventory.</p> <ul style="list-style-type: none"> <li>If you have an existing installation, then OUI detects the existing oralnventory directory from the <code>/etc/oraInst.loc</code> file, and uses this location.</li> <li>If you are installing Oracle software for the first time, then you can specify the Oracle inventory directory and the Oracle base directory during the Oracle software installation, and Oracle Universal Installer will set up the software directories for you. Ensure that the directory paths that you specify are in compliance with the Oracle Optimal Flexible Architecture recommendations.</li> </ul> <p>Ensure that the group designated as the OINSTALL group is available as the primary group for all planned Oracle software installation owners.</p>
Create operating system groups and users for standard or role-allocated system privileges	<p>The Preinstallation RPM automatically creates the <code>oracle</code> user and the <code>oralnventory</code> (<code>oinstall</code>) and <code>OSDBA</code> (<code>dba</code>) groups for you.</p> <p>Create additional operating system groups and users depending on your security requirements as described in this installation guide.</p> <p>Set resource limits settings and other requirements for Oracle software installation owners.</p> <p>Group and user names must use only ASCII characters.</p>
Unset Oracle Software Environment Variables	<p>If you have had an existing installation on your system, and you are using the same user account for this installation, then unset the <code>ORACLE_HOME</code>, <code>ORACLE_BASE</code>, <code>ORACLE_SID</code>, <code>TNS_ADMIN</code> environment variables and any other environment variable set for the Oracle installation user that is connected with Oracle software homes.</p>
Configure the Oracle Software Owner Environment	<p>Configure the environment of the <code>oracle</code> or <code>grid</code> user by performing the following tasks:</p> <ul style="list-style-type: none"> <li>Set the default file mode creation mask (<code>umask</code>) to <code>022</code> in the shell startup file.</li> <li>Set the <code>DISPLAY</code> environment variable.</li> </ul>


**Related Topics**

- [Configuring Users, Groups and Environments for Oracle Grid Infrastructure and Oracle Database](#)  
Before installation, create operating system groups and users, and configure user environments.

## Storage Checklist for Oracle Database Installation

Use this checklist to review storage minimum requirements and assist with configuration planning.

**Table 1-5 Storage Checklist for Oracle Database**

Check	Task
Minimum local disk storage space for Oracle software	<p>At least 11.5 GB for an Oracle Grid Infrastructure for a standalone server installation</p> <p>At least 10.2 GB for Oracle Database Enterprise Edition</p> <p>At least 10.2 GB for Oracle Database Standard Edition 2</p>
	<div style="border: 1px solid #0070C0; padding: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>Oracle recommends that you allocate approximately 100 GB to allow additional space for applying any future patches on top of the existing Oracle home. For specific patch-related disk space requirements, please refer to your patch documentation.</p> </div>
Select Database File Storage Option	<p>Ensure that you have one of the following storage options available:</p> <ul style="list-style-type: none"> <li>• File system mounted on the server. Oracle recommends that the file system you select is separate from the file system used by the operating system or the Oracle software. Options include the following:             <ul style="list-style-type: none"> <li>– A file system on a logical volume manager (LVM) volume or a RAID device</li> <li>– A network file system (NFS) mounted on a certified network-attached storage (NAS) device</li> </ul> </li> <li>• Oracle Automatic Storage Management (Oracle ASM).                Oracle ASM is installed as part of an Oracle Grid Infrastructure installation. If you plan to use Oracle ASM for storage, then you should install Oracle Grid Infrastructure before you install and create the database.</li> </ul>
Determine your recovery plan	<p>If you want to enable recovery during installation, then be prepared to select one of the following options:</p> <ul style="list-style-type: none"> <li>• <b>File system:</b> Configure a fast recovery area on a file system during installation</li> <li>• <b>Oracle Automatic Storage Management:</b> Configure a fast recovery area disk group using Oracle ASMCA.</li> </ul> <p>Review the storage configuration sections of this document for more information about configuring recovery.</p>

**Related Topics**

- [Configuring File System Storage for Oracle Database](#)  
 Complete these procedures to use file system storage for Oracle Database.

# Installer Planning Checklist for Oracle Database

Use this checklist to assist you to be prepared before starting Oracle Universal Installer.

**Table 1-6 Oracle Universal Installer Planning Checklist for Oracle Database Installation**

Check	Task
Read the Release Notes	Review release notes for your platform, which are available for your release at the following URL: <a href="http://docs.oracle.com/en/database/database.html">http://docs.oracle.com/en/database/database.html</a>
Review Oracle Support Certification Matrix	New platforms and operating system software versions may be certified after this guide is published, review the certification matrix on the My Oracle Support website for the most up-to-date list of certified hardware platforms and operating system versions: <a href="https://support.oracle.com/">https://support.oracle.com/</a>  You must register online before using My Oracle Support. After logging in, from the menu options, select the <b>Certifications</b> tab. On the Certifications page, use the <b>Certification Search</b> options to search by Product, Release, and Platform. You can also search using the <b>Certification Quick Link</b> options such as Product Delivery, and Lifetime Support.
Review the Licensing Information	You are permitted to use only those components in the Oracle Database media pack for which you have purchased licenses. For more information about licenses, refer to the following URL: <i>Oracle Database Licensing Information</i>
Run OUI with CVU and use fixup scripts	Oracle Universal Installer is fully integrated with Cluster Verification Utility (CVU), automating many CVU prerequisite checks. Oracle Universal Installer runs all prerequisite checks and creates fixup scripts when you run the installer. You can run OUI up to the Summary screen without starting the installation.  You can also run CVU commands manually to check system readiness. For more information, see: <i>Oracle Clusterware Administration and Deployment Guide</i>
Update and run Oracle ORAchk for runtime and upgrade checks, or runtime health checks	Oracle recommends that you update to the latest version of Oracle ORAchk by installing the latest version of Autonomous Health Framework (AHF).  The Oracle ORAchk utility provides system checks that can help to prevent issues before and after installation. These checks include kernel requirements, operating system resource allocations, and other system requirements.  Use the Oracle ORAchk Upgrade Readiness Assessment to obtain an automated upgrade-specific system health check for upgrades to 19c. For example: <ul style="list-style-type: none"><li>• Before you perform a fresh database installation: <pre>./orachk -profile preinstall</pre></li><li>• To upgrade your existing database to a higher version or release: <pre>./orachk -pregupgrade -targetversion 19.0.0.0.0</pre></li></ul> The Oracle ORAchk Upgrade Readiness Assessment automates many of the manual pre- and post-upgrade checks described in Oracle upgrade documentation. Check My Oracle Support Note 2550798.1 for more information about Oracle ORAchk support. <a href="https://support.oracle.com/epmos/faces/DocContentDisplay?id=2550798.1&amp;parent=DOCUMENTATION&amp;sourceId=USERGUIDE">https://support.oracle.com/epmos/faces/DocContentDisplay?id=2550798.1&amp;parent=DOCUMENTATION&amp;sourceId=USERGUIDE</a>

**Table 1-6 (Cont.) Oracle Universal Installer Planning Checklist for Oracle Database Installation**

Check	Task
Verify if Oracle Grid Infrastructure is installed	<p>If you want to use Oracle ASM or Oracle Restart, then install Oracle Grid Infrastructure for a standalone server before you install and create the database. Otherwise, to use Oracle ASM, you must complete an Oracle Grid Infrastructure installation, and then manually register the database with Oracle Restart.</p> <p>For Oracle Real Application Clusters (Oracle RAC) installations, ensure that you have installed and configured Oracle Grid Infrastructure for a cluster.</p>
Check running Oracle processes, and shut down if necessary	<ul style="list-style-type: none"> <li>• On a standalone database not using Oracle ASM: You do not need to shut down the database while you install Oracle Grid Infrastructure.</li> <li>• On a standalone database using Oracle ASM: The Oracle ASM instances are restarted during installation.</li> <li>• On an Oracle RAC Database node: This installation requires an upgrade of Oracle Clusterware, as Oracle Clusterware is required to run Oracle RAC. As part of the upgrade, you must shut down the database one node at a time as the rolling upgrade proceeds from node to node.</li> </ul>
Ensure <code>cron</code> jobs do not run during installation	<p>If the installer is running when daily <code>cron</code> jobs start, then you may encounter unexplained installation problems if your <code>cron</code> job is performing cleanup, and temporary files are deleted before the installation is finished. Oracle recommends that you complete installation before daily <code>cron</code> jobs are run, or disable daily</p> <p><code>cron</code></p> <p>jobs that perform cleanup until after the installation is completed.</p>
Obtain your My Oracle Support account information.	<p>During installation, you may require a My Oracle Support user name and password to configure updates, download software updates, and other installation tasks. You can register for My Oracle Support at the following URL:</p> <p><a href="https://support.oracle.com/">https://support.oracle.com/</a></p>
Decide Oracle Database management tool	<p>By default, Oracle Database is managed by Oracle Enterprise Manager Database Express.</p> <p>If you have an existing Oracle Management Agent, and decide to use Oracle Enterprise Manager Cloud Control to centrally manage your database, then obtain the following information to enter during the database installation:</p> <ul style="list-style-type: none"> <li>• OMS host</li> <li>• OMS port</li> <li>• EM admin username</li> <li>• EM admin password</li> <li>• Specify password of ASMSNMP user</li> </ul> <p>For more information, see:</p> <ul style="list-style-type: none"> <li>• <i>Oracle Database 2 Day DBA</i></li> <li>• <i>Oracle Enterprise Manager Cloud Control Administrator's Guide</i></li> </ul>

**Table 1-6 (Cont.) Oracle Universal Installer Planning Checklist for Oracle Database Installation**

Check	Task
Review memory allocation and Automatic Memory Management feature	<p>You can enable automatic memory management either during, or after Oracle Database installation. If you enable automatic memory management after installation, then you must shut down and restart the database.</p> <p>If the total physical memory of your database instance is greater than 4 GB, then you cannot select the Oracle Automatic Memory Management option during database installation and creation. Instead, use automatic shared memory management. Automatic shared memory management automatically distributes the available memory among the various components as required, allowing the system to maximize the use of all available SGA memory.</p> <p>For more information, see:  <i>Oracle Database Administrator's Guide</i></p>
Determine superuser (root) privilege delegation option for installation	<p>During a database or grid infrastructure installation, you are asked to run configuration scripts as the <code>root</code> user.</p> <p>You can either run these scripts manually as <code>root</code> when prompted, or you can provide configuration information and passwords using a root privilege delegation option.</p> <p>To run <code>root</code> scripts automatically, select <b>Automatically run configuration scripts</b> during installation.</p> <ul style="list-style-type: none"> <li>• <b>Use root user credentials</b>            Provide the superuser password for cluster member node servers.</li> <li>• <b>Use Sudo</b>            Sudo is a UNIX and Linux utility that allows members of the sudoers list privileges to run individual commands as <code>root</code>. Provide the username and password of an operating system user that is a member of sudoers, and is authorized to run Sudo on each cluster member node.             To enable Sudo, have a system administrator with the appropriate privileges configure a user that is a member of the sudoers list, and provide the username and password when prompted during installation.</li> </ul>
Oracle Database Client and Oracle Database interoperability	<p>For information about interoperability between Oracle Database Client and Oracle Database releases, see My Oracle Support Note 207303.1:  <a href="https://support.oracle.com/rs?type=doc&amp;id=207303.1">https://support.oracle.com/rs?type=doc&amp;id=207303.1</a></p>

**Related Topics**

- [Installing and Configuring Oracle Grid Infrastructure for a Standalone Server](#)  
 Oracle Grid Infrastructure for a standalone server includes Oracle Restart and Oracle Automatic Storage Management.
- [Installing Oracle Database](#)  
 Oracle Database and Oracle Grid Infrastructure installation software is available as image-based zip files and can be installed using several options.



# 2

## Checking and Configuring the Server for Oracle Database

Verify that servers where you install Oracle Database meet the minimum requirements for installation.

This section provides minimum server requirements to complete installation of Oracle Database. It does not provide system resource guidelines, or other tuning guidelines for particular workloads.

- [Logging In to a Remote System Using X Window System](#)  
Use this procedure to run Oracle Universal Installer (OUI) by logging on to a remote system where the runtime setting prohibits logging in directly to a graphical user interface (GUI).
- [Checking Server Hardware and Memory Configuration](#)  
Use this procedure to gather information about your server configuration.

### Logging In to a Remote System Using X Window System

Use this procedure to run Oracle Universal Installer (OUI) by logging on to a remote system where the runtime setting prohibits logging in directly to a graphical user interface (GUI).

OUI is a graphical user interface (GUI) application. On servers where the runtime settings prevent GUI applications from running, you can redirect the GUI display to a client system connecting to the server.



#### Note:

If you log in as another user (for example, `oracle` or `grid`), then repeat this procedure for that user as well.

1. Start an X Window System session. If you are using an X Window System terminal emulator from a PC or similar system, then you may need to configure security settings to permit remote hosts to display X applications on your local system.
2. Enter a command using the following syntax to enable remote hosts to display X applications on the local X server:

```
# xhost + RemoteHost
```

*RemoteHost* is the fully qualified remote host name. For example:

```
# xhost + somehost.example.com  
somehost.example.com being added to the access control list
```

3. If you are not installing the software on the local system, then use the `ssh` command to connect to the system where you want to install the software:

```
# ssh -Y RemoteHost
```

*RemoteHost* is the fully qualified remote host name. The `-Y` flag ("yes") enables remote clients to have full access to the original server display. For example:

```
# ssh -Y somehost.example.com
```

4. If you are not logged in as the `root` user, and you are performing configuration steps that require `root` user privileges, then switch the user to `root`.

 **Note:**

For more information about remote login using X Window System, refer to your X server documentation, or contact your X server vendor or system administrator. Depending on the X server software that you are using, you may have to complete the tasks in a different order.

## Checking Server Hardware and Memory Configuration

Use this procedure to gather information about your server configuration.

1. To determine physical RAM size on the server:

```
# /usr/sbin/lssattr -E -l sys0 -a realmem
```

2. To determine the available RAM and swap space:

```
# /usr/sbin/lssps -s
```

Oracle recommends that you take multiple values for the available RAM and swap space before finalizing a value. This is because the available RAM and swap space keep changing depending on the user interactions with the computer.

3. To determine the size of the configured swap space:

```
# /usr/sbin/lssps -a
```

If necessary, see your operating system documentation for information about how to configure additional swap space.

4. Determine the amount of space available in the `/tmp` directory:

```
# df -m /tmp
```

If the free space available in the `/tmp` directory is less than what is required, then complete one of the following steps:

- Delete unnecessary files from the `/tmp` directory to meet the disk space requirement.

- When you set the Oracle user's environment, also set the TMP and TMPDIR environment variables to the directory you want to use instead of /tmp.
  - Extend the file system that contains the /tmp directory.
5. Determine the amount of free disk space on the system:

```
# df -g  
# df -m
```

6. Determine if the system architecture can run the software:

```
# /usr/bin/getconf HARDWARE_BITMODE
```

The expected output of this command is 64. If you do not see the expected output, then you cannot install the software on this system.

To determine if the system is started in 64-bit mode:

```
# /usr/sbin/bootinfo -K
```

The result of this command must be 64, indicating that the 64-bit kernel is enabled.

Verify that the processor architecture matches the Oracle software release to install. If you do not see the expected output, then you cannot install the software on this system.

 **Note:**

For AIX Based Systems, Oracle Database supports 64-bit kernel and does not provide support for 32-bit kernel applications.

7. To determine the run level:

```
/usr/bin/who -r
```

### Related Topics

- [Server Hardware Checklist for Oracle Database Installation](#)  
Use this checklist to check hardware requirements for Oracle Database.

# 3

## Configuring Operating Systems for Oracle Database on IBM AIX on POWER Systems (64-Bit)

Complete operating system configuration requirements and checks for IBM AIX on POWER Systems (64-Bit) before you start installation.

You must meet the minimum versions, filesets, Authorized Problem Analysis Reports (APARs), and other software requirements for this release before you start an Oracle Database or Oracle Grid Infrastructure installation.

- [Guidelines for IBM AIX on POWER Systems \(64-Bit\) Operating System Installation](#)  
Operating system guidelines to be aware of before proceeding with an Oracle installation.
- [Reviewing Operating System and Software Upgrade Best Practices](#)  
These topics provide general planning guidelines and platform-specific information about upgrades and migration.
- [Reviewing Operating System Security Common Practices](#)  
Secure operating systems are an important basis for general system security.
- [About Installation Fixup Scripts](#)  
Oracle Universal Installer detects when the minimum requirements for an installation are not met, and creates shell scripts, called fixup scripts, to finish incomplete system configuration steps.
- [About Operating System Requirements](#)  
Depending on the products that you intend to install, verify that you have the required operating system kernel and packages installed.
- [Operating System Requirements for IBM AIX on POWER Systems \(64-Bit\)](#)  
The versions, filesets, and Authorized Problem Analysis Reports (APARs) listed in this section are supported for this release on IBM AIX on POWER Systems (64-Bit).
- [Additional Drivers and Software Packages for IBM AIX on POWER Systems \(64-Bit\)](#)  
Information about optional drivers and software packages.
- [Checking the Software Requirements](#)  
Check your software to see if they meet the minimum version, filesets, and Authorized Problem Analysis Reports (APARs) requirements for installation:
- [Confirming Host Name Resolution](#)  
Check to ensure that the host name for your server is resolvable.
- [Enabling I/O Completion Ports](#)  
To ensure successful database, client, and grid infrastructure installation, set IOCP to `Available` using this procedure.
- [Using Automatic SSH Configuration During Installation](#)  
To install Oracle software, configure secure shell (SSH) connectivity between all cluster member nodes.

# Guidelines for IBM AIX on POWER Systems (64-Bit) Operating System Installation

Operating system guidelines to be aware of before proceeding with an Oracle installation.

For IBM AIX on POWER Systems (64-Bit), Oracle Database supports 64-bit kernel and does not provide support for 32-bit kernel applications. Refer to your IBM AIX on POWER Systems (64-Bit) documentation to obtain information about installing IBM AIX on POWER Systems (64-Bit) on your servers.

## Reviewing Operating System and Software Upgrade Best Practices

These topics provide general planning guidelines and platform-specific information about upgrades and migration.

- [General Upgrade Best Practices](#)  
Be aware of these guidelines as a best practice before you perform an upgrade.
- [New Server Operating System Upgrade Option](#)  
You can upgrade your operating system by installing a new operating system on a server, and then migrating your database either manually, or by using Export/Import method.
- [Oracle ASM Upgrade Notifications](#)  
Understand Oracle ASM upgrade options and restrictions.

## General Upgrade Best Practices

Be aware of these guidelines as a best practice before you perform an upgrade.

If you have an existing Oracle Database installation, then do the following:

- Record the version numbers, patches, and other configuration information
- Review upgrade procedures for your existing installation
- Review Oracle Database upgrade documentation before proceeding with installation, to decide how you want to proceed

### **Caution:**

Always create a backup of existing databases before starting any configuration change.

Refer to *Oracle Database Upgrade Guide* for more information about required software updates, pre-upgrade tasks, post-upgrade tasks, compatibility, and interoperability between different releases.

### **Related Topics**

- *Oracle Database Upgrade Guide*

## New Server Operating System Upgrade Option

You can upgrade your operating system by installing a new operating system on a server, and then migrating your database either manually, or by using Export/Import method.

### Note:

Confirm that the server operating system is supported, and that kernel and package requirements for the operating system meet or exceed the minimum requirements for the Oracle Database release to which you want to migrate.

### Manual, Command-Line Copy for Migrating Data and Upgrading Oracle Database

You can copy files to the new server and upgrade it manually. If you use this procedure, then you cannot use Oracle Database Upgrade Assistant. However, you can revert to your existing database if you encounter upgrade issues.

1. Copy the database files from the computer running the previous operating system to the one running the new operating system.
2. Re-create the control files on the computer running the new operating system.
3. Manually upgrade the database using command-line scripts and utilities.

### See Also:

*Oracle Database Upgrade Guide* to review the procedure for upgrading the database manually, and to evaluate the risks and benefits of this option

### Export/Import Method for Migrating Data and Upgrading Oracle Database

You can install the operating system on the new server, install the new Oracle Database release on the new server, and then use Oracle Data Pump Export and Import utilities to migrate a copy of data from your current database to a new database in the new release. Data Pump Export and Import are recommended for higher performance and to ensure support for new data types.

### See Also:

*Oracle Database Upgrade Guide* to review the Export/Import method for migrating data and upgrading Oracle Database

## Oracle ASM Upgrade Notifications

Understand Oracle ASM upgrade options and restrictions.

- You can upgrade Oracle Automatic Storage Management (Oracle ASM) 11g release 2 (11.2) and later without shutting down an Oracle RAC database by performing a rolling

upgrade either of individual nodes, or of a set of nodes in the cluster. However, if you have a standalone database on a cluster that uses Oracle ASM, then you must shut down the standalone database before upgrading.

- The location of the Oracle ASM home changed in Oracle Grid Infrastructure 11g release 2 (11.2) so that Oracle ASM is installed with Oracle Clusterware in the Oracle Grid Infrastructure home (Grid home).
- Two nodes of different releases cannot run in the cluster. When upgrading from Oracle Grid Infrastructure 11g release 2 (11.2) or Oracle Grid Infrastructure 12c release 1 (12.1) to a later release, if there is an outage during the rolling upgrade, then when you restart the upgrade, ensure that you start the earlier release of Oracle Grid Infrastructure and bring the Oracle ASM cluster back in the rolling migration mode.

## Reviewing Operating System Security Common Practices

Secure operating systems are an important basis for general system security.

Ensure that your operating system deployment is in compliance with common security practices as described in your operating system vendor security guide.

## About Installation Fixup Scripts

Oracle Universal Installer detects when the minimum requirements for an installation are not met, and creates shell scripts, called fixup scripts, to finish incomplete system configuration steps.

If Oracle Universal Installer detects an incomplete task, then it generates fixup scripts (`runfixup.sh`). You can run the fixup script and click **Fix and Check Again**. The fixup script modifies both persistent parameter settings and parameters in memory, so you do not have to restart the system.

The Fixup script does the following tasks:

- Sets kernel parameters, if necessary, to values required for successful installation, including:
  - Shared memory parameters.
  - Open file descriptor and UDP send/receive parameters.
- Creates and sets permissions on the Oracle Inventory (central inventory) directory.
- Creates or reconfigures primary and secondary group memberships for the installation owner, if necessary, for the Oracle Inventory directory and the operating system privileges groups.
- Sets shell limits, if necessary, to required values.

### Note:

Using fixup scripts does not ensure that all the prerequisites for installing Oracle Database are met. You must still verify that all the preinstallation requirements are met to ensure a successful installation.

Oracle Universal Installer is fully integrated with Cluster Verification Utility (CVU) automating many prerequisite checks for your Oracle Grid Infrastructure or Oracle Real Application

Clusters (Oracle RAC) installation. You can also manually perform various CVU verifications by running the `cluvfy` command.

#### Related Topics

- [Completing Preinstallation Tasks Manually](#)  
You can complete the preinstallation configuration tasks manually.
- *Oracle Clusterware Administration and Deployment Guide*

## About Operating System Requirements

Depending on the products that you intend to install, verify that you have the required operating system kernel and packages installed.

Requirements listed in this document are current as of the date listed on the title page.

Oracle Universal Installer performs checks on your system to verify that it meets the listed operating system package requirements. To ensure that these checks complete successfully, verify the requirements before you start OUI.



#### Note:

Oracle does not support running different operating system versions on cluster members, unless an operating system is being upgraded. You cannot run different operating system version binaries on members of the same cluster, even if each operating system is supported.

## Operating System Requirements for IBM AIX on POWER Systems (64-Bit)

The versions, filesets, and Authorized Problem Analysis Reports (APARs) listed in this section are supported for this release on IBM AIX on POWER Systems (64-Bit).

The platform-specific hardware and software requirements included in this guide were current when this guide was published. However, because new platforms and operating system software versions might be certified after this guide is published, review the certification matrix on the My Oracle Support website for the most up-to-date list of certified hardware platforms and operating system versions:

<https://support.oracle.com/>

Identify the requirements for your IBM AIX on POWER Systems (64-Bit) version, and ensure that you have a supported kernel, filesets and APARs installed before starting installation.

- [Supported IBM AIX 7.1 Versions](#)  
Use the following information to check the minimum supported IBM AIX 7.1 on POWER Systems (64-bit) versions:
- [Supported IBM AIX 7.2 Versions](#)  
Use the following information to check the minimum supported IBM AIX 7.2 on POWER Systems (64-bit) versions:



- [Supported IBM AIX 7.3 Versions](#)  
 Use the following information to check the minimum supported IBM AIX 7.3 on POWER Systems (64-bit) versions:

## Supported IBM AIX 7.1 Versions

Use the following information to check the minimum supported IBM AIX 7.1 on POWER Systems (64-bit) versions:

**Table 3-1 IBM AIX 7.1 on POWER Systems (64-Bit) Minimum Operating System Requirements**

Item	Minimum Requirements
SSH Requirement	OpenSSH_7.5p1 or later
AIX 7.1 Operating System	AIX 7.1 Technology Level 5 Service Pack 1 (7100-05-01-1731) or later, 64-bit kernel
AIX 7.1 Operating System Filesets	<p>The following operating system filesets are required:</p> <ul style="list-style-type: none"> <li>• bos.adt.base</li> <li>• bos.adt.lib</li> <li>• bos.adt.libm</li> <li>• bos.perf.libperfstat</li> <li>• bos.perf.perfstat</li> <li>• bos.perf.proctools</li> <li>• security.pkcs11.7.1.3.15 or later</li> <li>• xlC.aix61.rte:13.1.0.1 or later</li> <li>• xlC.rte:13.1.0.1 or later</li> <li>• xlfрте.aix61-15.1.0.9 or later</li> </ul> <p>The following filesets are required for Oracle Real Application Clusters (Oracle RAC) Installations only:</p> <ul style="list-style-type: none"> <li>• rsct.basic.rte</li> <li>• rsct.compat.clients.rte</li> </ul>
AIX 7.1 APARs and Other Operating System Fixes	<p>If you are using the minimum operating system TL level for AIX 7.1 listed above, then install the following AIX APAR fix:</p> <ul style="list-style-type: none"> <li>• AIX7.1 TL05 : IJ04311 – GETSOCKNAME returns invalid path name for AF_UNIX sockets</li> </ul> <p>AIX APAR numbers are tied to AIX versions and technology levels. Download and install the APAR that matches your AIX versions and Technology Levels from the IBM fix central website at the following URL:  <a href="https://www.ibm.com/">https://www.ibm.com/</a></p>

## Supported IBM AIX 7.2 Versions

Use the following information to check the minimum supported IBM AIX 7.2 on POWER Systems (64-bit) versions:

**Table 3-2 IBM AIX 7.2 on POWER Systems (64-Bit) Minimum Operating System Requirements**

Item	Minimum Requirements
SSH Requirement	OpenSSH_7.5p1 or later

**Table 3-2 (Cont.) IBM AIX 7.2 on POWER Systems (64-Bit) Minimum Operating System Requirements**

Item	Minimum Requirements
AIX 7.2 Operating System	AIX 7.2 Technology Level 2 Service Pack 1 (7200-02-01-1731) or later, 64-bit kernel
AIX 7.2 Operating System Filesets	<p>The following operating system filesets are required:</p> <ul style="list-style-type: none"> <li>• bos.adt.base</li> <li>• bos.adt.lib</li> <li>• bos.adt.libm</li> <li>• bos.perf.libperfstat</li> <li>• bos.perf.perfstat</li> <li>• bos.perf.proctools</li> <li>• xlc.aix61.rte:13.1.0.1 or later</li> <li>• xlc.rte:13.1.0.1 or later</li> <li>• xlfrte.aix61-15.1.0.9 or later</li> </ul> <p>The following filesets are required for Oracle Real Application Clusters (Oracle RAC) Installations only:</p> <ul style="list-style-type: none"> <li>• rsct.basic.rte</li> <li>• rsct.compat.clients.rte</li> </ul>
AIX 7.2 APARs and Other Operating System Fixes	<p>If you are using the minimum operating system TL level for AIX 7.2 listed above, then install the following AIX APAR fix:</p> <ul style="list-style-type: none"> <li>• AIX7.2 TL02 : IJ06143 – GETSOCKNAME returns invalid path name for AF_UNIX sockets</li> </ul>

 **Note:**

- If you are using a later TL level than the minimum level listed for this release, then contact IBM to determine if the required APARs listed in this section are included in the TL level that you have on your system. If they are included, then you do not have to install them. If they are not included, then you must install the equivalent APAR for the appropriate TL level.
- AIX APAR numbers are tied to AIX versions and technology levels. Download and install the APAR that matches your AIX versions and Technology Levels from the IBM fix central website at the following URL:  
<https://www.ibm.com/>

## Supported IBM AIX 7.3 Versions

Use the following information to check the minimum supported IBM AIX 7.3 on POWER Systems (64-bit) versions:

**Table 3-3 IBM AIX 7.3 on POWER Systems (64-Bit) Minimum Operating System Requirements**

Item	Minimum Requirements
SSH Requirement	OpenSSH_7.5p1 or later
AIX 7.3 Operating System	AIX 7.3 Technology Level 0 Service Pack 1 (7300-00-01-2148) or later, 64-bit kernel
AIX 7.3 Operating System Filesets	<p>The following operating system filesets are required:</p> <ul style="list-style-type: none"> <li>• bos.adt.base</li> <li>• bos.adt.lib</li> <li>• bos.adt.libm</li> <li>• bos.perf.libperfstat</li> <li>• bos.perf.perfstat</li> <li>• bos.perf.proctools</li> <li>• xlC.aix61.rte.13.1.2.0 or later</li> <li>• xlC.rte.13.1.2.0 or later</li> <li>• xlfрте</li> </ul> <p>The following filesets are required for Oracle Real Application Clusters (Oracle RAC) Installations only:</p> <ul style="list-style-type: none"> <li>• rsct.basic.rte</li> <li>• rsct.compat.clients.rte</li> </ul>
AIX 7.3 APARs and Other Operating System Fixes	<p>If you are using the minimum operating system TL level for AIX 7.3 listed above, then install the following AIX APAR fix:</p> <ul style="list-style-type: none"> <li>• APAR IJ38518</li> </ul>

 **Note:**

- If you are using a later TL level than the minimum level listed for this release, then contact IBM to determine if the required APARs listed in this section are included in the TL level that you have on your system. If they are included, then you do not have to install them. If they are not included, then you must install the equivalent APAR for the appropriate TL level.
- AIX APAR numbers are tied to AIX versions and technology levels. Download and install the APAR that matches your AIX versions and Technology Levels from the IBM fix central website at the following URL:  
<https://www.ibm.com/>

## Additional Drivers and Software Packages for IBM AIX on POWER Systems (64-Bit)

Information about optional drivers and software packages.

You are not required to install additional drivers and packages, but you may choose to install or configure these drivers and packages.

- [Installing Oracle Messaging Gateway](#)  
Oracle Messaging Gateway is installed with Enterprise Edition of Oracle Database. However, you may require a CSD or Fix Packs.
- [Installation Requirements for ODBC and LDAP](#)  
Review these topics to install Open Database Connectivity (ODBC) and Lightweight Directory Access Protocol (LDAP).
- [Installation Requirements for Programming Environments for IBM AIX](#)  
Ensure that your system meets the requirements for the programming environment you want to configure:
- [Installation Requirements for Web Browsers](#)  
Web browsers are required only if you intend to use Oracle Enterprise Manager Database Express and Oracle Enterprise Manager Cloud Control. Web browsers must support JavaScript, and the HTML 4.0 and CSS 1.0 standards.

## Installing Oracle Messaging Gateway

Oracle Messaging Gateway is installed with Enterprise Edition of Oracle Database. However, you may require a CSD or Fix Packs.

For AIX 7.1, check My Oracle Support Certification for current Oracle Messaging Gateway requirements:

<https://support.oracle.com/>

If you require a CSD or Fix Packs for IBM WebSphere MQ, then see the following website for more information:

<http://www.ibm.com>

### Related Topics

- *Oracle Database Advanced Queuing User's Guide*

## Installation Requirements for ODBC and LDAP

Review these topics to install Open Database Connectivity (ODBC) and Lightweight Directory Access Protocol (LDAP).

- [About ODBC Drivers and Oracle Database](#)  
Open Database Connectivity (ODBC) is a set of database access APIs that connect to the database, prepare, and then run SQL statements on the database.
- [Installing ODBC Drivers for IBM AIX](#)  
If you intend to use ODBC, then install the most recent ODBC Driver Manager for IBM AIX on POWER Systems (64-Bit).
- [About LDAP and Oracle Plug-ins](#)  
Lightweight Directory Access Protocol (LDAP) is an application protocol for accessing and maintaining distributed directory information services over IP networks.
- [Installing the LDAP Package](#)  
LDAP is included in a default operating system installation.

## About ODBC Drivers and Oracle Database

Open Database Connectivity (ODBC) is a set of database access APIs that connect to the database, prepare, and then run SQL statements on the database.

An application that uses an ODBC driver can access non-uniform data sources, such as spreadsheets and comma-delimited files.

## Installing ODBC Drivers for IBM AIX

If you intend to use ODBC, then install the most recent ODBC Driver Manager for IBM AIX on POWER Systems (64-Bit).

Download and install the ODBC Driver Manager from the following website:

<http://www.unixodbc.org>

Oracle ODBC driver on IBM AIX is certified with ODBC Driver Manager 2.3.4. To use ODBC with Oracle Database, you must also install the following package:

`gcc 4.2.1 or later`

## About LDAP and Oracle Plug-ins

Lightweight Directory Access Protocol (LDAP) is an application protocol for accessing and maintaining distributed directory information services over IP networks.

You require the LDAP package if you want to use features requiring LDAP, including the Oracle Database scripts `odisrvreg` and `oidca` for Oracle Internet Directory, or `schemasync` for third-party LDAP directories.

## Installing the LDAP Package


LDAP is included in a default operating system installation.

If you did not perform a default operating system installation, and you intend to use Oracle scripts requiring LDAP, then use a package management system for your distribution to install a supported LDAP package for your distribution, and install any other required packages for that LDAP package.

## Installation Requirements for Programming Environments for IBM AIX

Ensure that your system meets the requirements for the programming environment you want to configure:

**Table 3-4 Requirements for Programming Environments for IBM AIX on POWER Systems (64-Bit)**

Programming Environments	Support Requirements
Java Database Connectivity (JDBC) / Oracle Call Interface (OCI)	JDK 8 (64-bit 8.0.0.0 or later) with the JNDI extension with Oracle Java Database Connectivity and Oracle Call Interface drivers.
<div style="border: 1px solid #0070C0; padding: 10px; background-color: #E6F2FF;">  <b>Note:</b> These are not mandatory requirements for database installation.                 </div>	
Oracle C++ Oracle C++ Call Interface Pro*C/C++ Oracle XML Developer's Kit (XDK)	IBM XL C/C++ Runtime for AIX, v13.1.3.3 Fix Pack (June 2017) IBM XL C/C++ for AIX Fix Pack 11 (November 2018 PTF) for 13.1 Download this software from the following URLs: <a href="http://www-01.ibm.com/support/docview.wss?uid=swg24043829">http://www-01.ibm.com/support/docview.wss?uid=swg24043829</a>
Pro*COBOL	IBM COBOL for AIX version 4.1.1, Fix Pack 12, (October 2014 PTF) Micro Focus Server Express 5.1 Micro Focus Visual COBOL for Eclipse 2.3 - Update 2 Micro Focus Visual COBOL v6.0
Pro*FORTRAN	IBM XL Fortran Runtime for AIX, Version 15.1, September 2014 PTF IBM XL Fortran for AIX, Version 15.1, September 2014 PTF
ADA	OC Systems PowerAda 5.5 For more information about OC Systems and PowerAda, go to: <a href="http://www.ocsystems.com/w/index.php/OCS:PowerAda">http://www.ocsystems.com/w/index.php/OCS:PowerAda</a>
Network	Communications Server for AIX V6.4.0.2 PTF VIO Server 2.2.1.1 FP25 (28 Nov 2011)
Oracle Clusterware	HACMP 7.1 RSCT 3.1.0.3 or higher GPFS 4.1 cluster.license-7.1
Unzip utility	Unzip 6.0 or later. Unzip is required to extract the image files for Oracle Database and Oracle Grid Infrastructure installations.

## Installation Requirements for Web Browsers

Web browsers are required only if you intend to use Oracle Enterprise Manager Database Express and Oracle Enterprise Manager Cloud Control. Web browsers must support JavaScript, and the HTML 4.0 and CSS 1.0 standards.

<https://support.oracle.com>

**Related Topics**

- *Oracle Enterprise Manager Cloud Control Basic Installation Guide*

## Checking the Software Requirements

Check your software to see if they meet the minimum version, filesets, and Authorized Problem Analysis Reports (APARs) requirements for installation:

1. To determine the distribution and version of IBM AIX installed:

```
# oslevel -s
```

If the operating system version is lower than what is required, then upgrade your operating system accordingly to the currently supported or later version and level.

IBM AIX maintenance packages are available from the following website:

<https://www.ibm.com>

2. To determine if the required filesets are installed and committed enter a command similar to the following:

```
# lslpp -l bos.adt.base bos.adt.lib bos.adt.libm bos.perf.perfstat \  
bos.perf.libperfstat bos.perf.proctools
```

3. To determine the supported kernel mode:

```
# getconf KERNEL_BITMODE
```

- The expected output of this command is 64. If you do not see the expected output, then you cannot install the software on this system.
- Oracle Database supports 64-bit kernel and does not provide support for 32-bit kernel applications.

4. To determine if an APAR is installed:

```
# /usr/sbin/instfix -i -k "IV16716 IV20880 IV21128 IV28319"
```

If an APAR is not installed, then download it from the following website and install it:

<https://www.ibm.com>

5. If you require a CSD for WebSphere MQ, then refer to the following website for download and installation information:

<https://www.ibm.com>

## Confirming Host Name Resolution

Check to ensure that the host name for your server is resolvable.

Typically, the computer on which you want to install Oracle Database is connected to a network. Ensure that the computer host name is resolvable, either through a Domain Name System (DNS), a network information service (NIS), or a centrally-maintained TCP/IP host file,

such as `/etc/hosts`. Use the `ping` command to ensure that your computer host name is resolvable. For example:

```
ping myhostname
pinging myhostname.example.com [192.0.2.2] with 32 bytes of data:
Reply from 192.0.2.2: bytes=32 time=138ms TTL=56
```

### Related Topics

- [Configuring Networks for Oracle Database](#)  
If you install Oracle Databases on servers with multiple Oracle homes, multiple aliases, or without a static IP address, then review these network configuration topics.

## Enabling I/O Completion Ports

To ensure successful database, client, and grid infrastructure installation, set IOCP to `Available` using this procedure.

On IBM AIX on POWER Systems (64-Bit), enable I/O completion ports (IOCP) to ensure successful database and grid infrastructure installation.

To check if the IOCP module is enabled, run the `lsdev` command:

```
$ lsdev | grep iocp
```

The following sample output shows the IOCP status is set to `Defined` and hence not enabled:

```
iocp0      Defined      I/O Completion Ports
```

By default, IOCP is set to `Defined`. To enable IOCP, set IOCP to `Available` using the following procedure:

1. Log in as `root` and run the following command:  

```
# smitty iocp
```
2. Select **Change / Show Characteristics of I/O Completion Ports**.
3. Change configured state at system restart from `Defined` to `Available`.
4. Run the `lsdev` command to confirm the IOCP status is set to `Available`:

```
$ lsdev | grep iocp
iocp0      Available      I/O Completion Ports
```

Restart the system to make the changes permanent.

## Using Automatic SSH Configuration During Installation

To install Oracle software, configure secure shell (SSH) connectivity between all cluster member nodes.

Oracle Universal Installer (OUI) uses the `ssh` and `scp` commands during installation to run remote commands on and copy files to the other cluster nodes. You must configure SSH so that these commands do not prompt for a password.



 **Note:**

Oracle configuration assistants use SSH for configuration operations from local to remote nodes. Oracle Enterprise Manager also uses SSH. RSH is no longer supported.

You can configure SSH from the OUI interface during installation for the user account running the installation. The automatic configuration creates passwordless SSH connectivity between all cluster member nodes. Oracle recommends that you use the automatic procedure if possible.

To enable the script to run, you must remove `stty` commands from the profiles of any existing Oracle software installation owners you want to use, and remove other security measures that are triggered during a login, and that generate messages to the terminal. These messages, mail checks, and other displays prevent Oracle software installation owners from using the SSH configuration script that is built into OUI. If they are not disabled, then SSH must be configured manually before an installation can be run.

In rare cases, Oracle Clusterware installation can fail during the "AttachHome" operation when the remote node closes the SSH connection. To avoid this problem, set the timeout wait to unlimited by setting the following parameter in the SSH daemon configuration file `/etc/ssh/sshd_config` on all cluster nodes:

```
LoginGraceTime 0
```

**Related Topics**

- [Preventing Installation Errors Caused by Terminal Output Commands](#)  
During an Oracle Grid Infrastructure installation, OUI uses SSH to run commands and copy files to the other nodes. During the installation, hidden files on the system (for example, `.bashrc` or `.cshrc`) can cause `makefile` and other installation errors if they contain terminal output commands.

# 4

## Configuring Users, Groups and Environments for Oracle Grid Infrastructure and Oracle Database

Before installation, create operating system groups and users, and configure user environments.

- [Required Operating System Groups and Users](#)  
Oracle software installations require an installation owner, an Oracle Inventory group, which is the primary group of all Oracle installation owners, and at least one group designated as a system privileges group.
- [Oracle Installations with Standard and Job Role Separation Groups and Users](#)  
A job role separation configuration of Oracle Database and Oracle ASM is a configuration with groups and users to provide separate groups for operating system authentication.
- [Creating Operating System Privileges Groups](#)  
The following sections describe how to create operating system groups for Oracle Grid Infrastructure and Oracle Database:
- [Creating Operating System Oracle Installation User Accounts](#)  
Before starting installation, create Oracle software owner user accounts, and configure their environments.
- [Creating Oracle Database Vault User Accounts](#)  
If you intend to use Oracle Database Vault by default, then you must create an Oracle Database Vault user account, and configure that user.
- [Unsetting Oracle Installation Owner Environment Variables](#)  
Unset Oracle installation owner environment variables before starting installation
- [Running the rootpre.sh Script](#)  
Run the `rootpre.sh` script only the first time you install Oracle Database on IBM AIX on POWER Systems (64-Bit).

### Required Operating System Groups and Users

Oracle software installations require an installation owner, an Oracle Inventory group, which is the primary group of all Oracle installation owners, and at least one group designated as a system privileges group.

Review group and user options with your system administrator. If you have system administration privileges, then review the topics in this section and configure operating system groups and users as needed.

- [Determining If an Oracle Inventory and Oracle Inventory Group Exist](#)  
Determine if you have an existing Oracle central inventory, and ensure that you use the same Oracle Inventory for all Oracle software installations. Also, ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

- [Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist](#)  
Create an Oracle Inventory group manually as part of a planned installation, particularly where more than one Oracle software product is installed on servers.
- [About Oracle Installation Owner Accounts](#)  
Select or create an Oracle installation owner for your installation, depending on the group and user management plan you want to use for your installations.
- [Identifying an Oracle Software Owner User Account](#)  
You must create at least one software owner user account the first time you install Oracle software on the system. Either use an existing Oracle software user account, or create an Oracle software owner user account for your installation.

## Determining If an Oracle Inventory and Oracle Inventory Group Exist

Determine if you have an existing Oracle central inventory, and ensure that you use the same Oracle Inventory for all Oracle software installations. Also, ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

When you install Oracle software on the system for the first time, OUI creates the `oraInst.loc` file. This file identifies the name of the Oracle Inventory group (by default, `oinstall`), and the path of the Oracle central inventory directory. If you have an existing Oracle central inventory, then ensure that you use the same Oracle Inventory for all Oracle software installations, and ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

```
oraInst.loccentral_inventory_locationgroup
```

```
inventory_loc=central_inventory_location  
inst_group=group
```

Use the `more` command to determine if you have an Oracle central inventory on your system. For example:

```
# more /etc/oraInst.loc  
  
inventory_loc=/u01/app/oraInventory  
inst_group=oinstall
```

Use the command `grep groupname /etc/group` to confirm that the group specified as the Oracle Inventory group still exists on the system. For example:

```
$ grep oinstall /etc/group  
oinstall:x:54321:grid,oracle
```

### Note:

Do not put the `oraInventory` directory under the Oracle base directory for a new installation, because that can result in user permission errors for other installations.

## Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist

Create an Oracle Inventory group manually as part of a planned installation, particularly where more than one Oracle software product is installed on servers.

By default, if an `oraInventory` group does not exist, then the installer uses the primary group of the installation owner for the Oracle software being installed as the `oraInventory` group. Ensure that this group is available as a primary group for all planned Oracle software installation owners. If the `oraInst.loc` file does not exist, then create the Oracle Inventory group using the following procedure:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the Oracle Inventory (`oinstall`) group.
3. Press **F10** to exit.

## About Oracle Installation Owner Accounts

Select or create an Oracle installation owner for your installation, depending on the group and user management plan you want to use for your installations.

You must create a software owner for your installation in the following circumstances:

- If an Oracle software owner user does not exist; for example, if this is the first installation of Oracle software on the system.
- If an Oracle software owner user exists, but you want to use a different operating system user, with different group membership, to separate Oracle Grid Infrastructure administrative privileges from Oracle Database administrative privileges.

In Oracle documentation, a user created to own only Oracle Grid Infrastructure software installations is called the Grid user (`grid`). This user owns both the Oracle Clusterware and Oracle Automatic Storage Management binaries. A user created to own either all Oracle installations, or one or more Oracle database installations, is called the Oracle user (`oracle`). You can have only one Oracle Grid Infrastructure installation owner, but you can have different Oracle users to own different installations.

Oracle software owners must have the Oracle Inventory group as their primary group, so that each Oracle software installation owner can write to the central inventory (`oraInventory`), and so that OCR and Oracle Clusterware resource permissions are set correctly. The database software owner must also have the OSDBA group and (if you create them) the OSOPER, OSBACKUPDBA, OSDGDBA, OSRACDBA, and OSKMDBA groups as secondary groups.

## Identifying an Oracle Software Owner User Account

You must create at least one software owner user account the first time you install Oracle software on the system. Either use an existing Oracle software user account, or create an Oracle software owner user account for your installation.

To use an existing user account, obtain the name of an existing Oracle installation owner from your system administrator. Confirm that the existing owner is a member of the Oracle Inventory group.

For example, if you know that the name of the Oracle Inventory group is `oinstall`, then an Oracle software owner should be listed as a member of `oinstall`:

```
$ grep "oinstall" /etc/group
oinstall:x:54321:grid,oracle
```

You can then use the `ID` command to verify that the Oracle installation owners you intend to use have the Oracle Inventory group as their primary group. For example:

```
$ id oracle
uid=54321(oracle) gid=54321(oinstall) groups=54321(oinstall),54322(dba),
54323(oper),54324(backupdba),54325(dgdba),54326(kmdba),54327(asmdba),54330(rac
dba)
```

```
$ id grid
uid=54331(grid) gid=54321(oinstall) groups=54321(oinstall),54322(dba),
54327(asmdba),54328(asmoper),54329(asmadmin),54330(racdba)
```

For Oracle Restart installations, to successfully install Oracle Database, ensure that the `grid` user is a member of the `racdba` group.

After you create operating system groups, create or modify Oracle user accounts in accordance with your operating system authentication planning.

### Related Topics

- [Modifying Oracle Owner User Groups](#)  
If you have created an Oracle software installation owner account, but it is not a member of the groups you want to designate as the OSDBA, OSOPER, OSDBA for ASM, ASMAADMIN, or other system privileges group, then modify the group settings for that user before installation.
- [Creating an Oracle Software Owner User](#)  
If the Oracle software owner user (`oracle` or `grid`) does not exist, or if you require a new Oracle software owner user, then create it as described in this section.

## Oracle Installations with Standard and Job Role Separation Groups and Users

A job role separation configuration of Oracle Database and Oracle ASM is a configuration with groups and users to provide separate groups for operating system authentication.

Review the following sections to understand more about a Job Role Separation deployment:

- [About Oracle Installations with Job Role Separation](#)  
Job role separation requires that you create different operating system groups for each set of system privileges that you grant through operating system authorization.
- [Standard Oracle Database Groups for Database Administrators](#)  
Oracle Database has two standard administration groups: OSDBA, which is required, and OSOPER, which is optional.
- [Extended Oracle Database Groups for Job Role Separation](#)  
Oracle Database provides an extended set of database groups to grant task-specific system privileges for database administration.

- [Creating an ASMSNMP User](#)  
The `ASMSNMP` user is an Oracle ASM user with privileges to monitor Oracle ASM instances. You are prompted to provide a password for this user during installation.
- [Oracle Automatic Storage Management Groups for Job Role Separation](#)  
Oracle Grid Infrastructure operating system groups provide their members task-specific system privileges to access and to administer Oracle Automatic Storage Management.

## About Oracle Installations with Job Role Separation

Job role separation requires that you create different operating system groups for each set of system privileges that you grant through operating system authorization.

With Oracle Grid Infrastructure job role separation, Oracle ASM has separate operating system groups that provide operating system authorization for Oracle ASM system privileges for storage tier administration. This operating system authorization is separated from Oracle Database operating system authorization. In addition, the Oracle Grid Infrastructure installation owner provides operating system user authorization for modifications to Oracle Grid Infrastructure binaries.

With Oracle Database job role separation, each Oracle Database installation has separate operating system groups to provide authorization for system privileges on that Oracle Database. Multiple databases can, therefore, be installed on the cluster without sharing operating system authorization for system privileges. In addition, each Oracle software installation is owned by a separate installation owner, to provide operating system user authorization for modifications to Oracle Database binaries. Note that any Oracle software owner can start and stop all databases and shared Oracle Grid Infrastructure resources such as Oracle ASM or Virtual IP (VIP). Job role separation configuration enables database security, and does not restrict user roles in starting and stopping various Oracle Clusterware resources.

You can choose to create one administrative user and one group for operating system authentication for all system privileges on the storage and database tiers. For example, you can designate the `oracle` user to be the installation owner for all Oracle software, and designate `oinstall` to be the group whose members are granted all system privileges for Oracle Clusterware; all system privileges for Oracle ASM; all system privileges for all Oracle Databases on the servers; and all `OINSTALL` system privileges for installation owners. This group must also be the Oracle Inventory group.

If you do not want to use role allocation groups, then Oracle strongly recommends that you use at least two groups:

- A system privileges group whose members are granted administrative system privileges, including `OSDBA`, `OSASM`, and other system privileges groups.
- An installation owner group (the `oraInventory` group) whose members are granted Oracle installation owner system privileges (the `OINSTALL` system privilege).

### Note:

To configure users for installation that are on a network directory service such as Network Information Services (NIS), refer to your directory service documentation.

### Related Topics

- [Oracle Database Administrator's Guide](#)
- [Oracle Automatic Storage Management Administrator's Guide](#)

## Standard Oracle Database Groups for Database Administrators

Oracle Database has two standard administration groups: OSDBA, which is required, and OSOPER, which is optional.

- The OSDBA group (typically, `dba`)

You must create this group the first time you install Oracle Database software on the system. This group identifies operating system user accounts that have database administrative privileges (the `SYSDBA` privilege).

If you do not create separate OSDBA, OSOPER, and OSASM groups for the Oracle ASM instance, then operating system user accounts that have the `SYSOPER` and `SYSASM` privileges must be members of this group. The name used for this group in Oracle code examples is `dba`. If you do not designate a separate group as the OSASM group, then the OSDBA group you define is also by default the OSASM group.

- The OSOPER group for Oracle Database (typically, `oper`)

OSOPER grants the OPERATOR privilege to start up and shut down the database (the `SYSOPER` privilege). By default, members of the OSDBA group have all privileges granted by the `SYSOPER` privilege.

## Extended Oracle Database Groups for Job Role Separation

Oracle Database provides an extended set of database groups to grant task-specific system privileges for database administration.

The extended set of Oracle Database system privileges groups are task-specific and less privileged than the OSDBA/SYSDBA system privileges. They are designed to provide privileges to carry out everyday database operations. Users granted these system privileges are also authorized through operating system group membership.

You do not have to create these specific group names, but during interactive and silent installation, you must assign operating system groups whose members are granted access to these system privileges. You can assign the same group to provide authorization for these privileges, but Oracle recommends that you provide a unique group to designate each privilege.

The subset of OSDBA job role separation privileges and groups consist of the following:

- OSBACKUPDBA group for Oracle Database (typically, `backupdba`)

Create this group if you want a separate group of operating system users to have a limited set of database backup and recovery related administrative privileges (the `SYSBACKUP` privilege).

- OSDGDBA group for Oracle Data Guard (typically, `dgdba`)

Create this group if you want a separate group of operating system users to have a limited set of privileges to administer and monitor Oracle Data Guard (the `SYSDBG` privilege). To use this privilege, add the Oracle Database installation owners as members of this group.

- The OSKMDBA group for encryption key management (typically, `kmdba`)

Create this group if you want a separate group of operating system users to have a limited set of privileges for encryption key management such as Oracle Wallet Manager management (the `SYSKM` privilege). To use this privilege, add the Oracle Database installation owners as members of this group.



- The OSRACDBA group for Oracle Real Application Clusters Administration (typically, `racdba`)

Create this group if you want a separate group of operating system users to have a limited set of Oracle Real Application Clusters (RAC) administrative privileges (the SYSRAC privilege). To use this privilege:

- Add the Oracle Database installation owners as members of this group.
- For Oracle Restart configurations, if you have a separate Oracle Grid Infrastructure installation owner user (`grid`), then you must also add the `grid` user as a member of the OSRACDBA group of the database to enable Oracle Grid Infrastructure components to connect to the database.

#### Related Topics

- *Oracle Database Administrator's Guide*
- *Oracle Database Security Guide*

## Creating an ASMSNMP User

The `ASMSNMP` user is an Oracle ASM user with privileges to monitor Oracle ASM instances. You are prompted to provide a password for this user during installation.

In addition to the OSASM group, whose members are granted the SYSASM system privilege to administer Oracle ASM, Oracle recommends that you create a less privileged user, `ASMSNMP`, and grant that user SYSDBA privileges to monitor the Oracle ASM instance. Oracle Enterprise Manager uses the `ASMSNMP` user to monitor Oracle ASM status.

During installation, you are prompted to provide a password for the `ASMSNMP` user. You can create an operating system authenticated user, or you can create an Oracle Database user called `asmsnmp`. In either case, grant the user SYSDBA privileges.

## Oracle Automatic Storage Management Groups for Job Role Separation

Oracle Grid Infrastructure operating system groups provide their members task-specific system privileges to access and to administer Oracle Automatic Storage Management.

- The OSASM group for Oracle ASM Administration (typically, `asmadmin`)

Create this group as a separate group to separate administration privileges groups for Oracle ASM and Oracle Database administrators. Members of this group are granted the SYSASM system privileges to administer Oracle ASM. In Oracle documentation, the operating system group whose members are granted privileges is called the OSASM group, and in code examples, where there is a group specifically created to grant this privilege, it is referred to as `asmadmin`.

Oracle ASM can support multiple databases. If you have multiple databases on your system, and use multiple OSDBA groups so that you can provide separate SYSDBA privileges for each database, then you should create a group whose members are granted the OSASM/SYSASM administrative privileges, and create a grid infrastructure user (`grid`) that does not own a database installation, so that you separate Oracle Grid Infrastructure SYSASM administrative privileges from a database administrative privileges group.

Members of the OSASM group can use SQL to connect to an Oracle ASM instance as SYSASM using operating system authentication. The SYSASM privileges permit mounting and dismounting disk groups, and other storage administration tasks. SYSASM privileges provide no access privileges on an RDBMS instance.



If you do not designate a separate group as the OSASM group, but you do define an OSDBA group for database administration, then by default the OSDBA group you define is also defined as the OSASM group.

- The OSOPER group for Oracle ASM (typically, `asmoper`)

This is an optional group. Create this group if you want a separate group of operating system users to have a limited set of Oracle instance administrative privileges (the SYSOPER for ASM privilege), including starting up and stopping the Oracle ASM instance. By default, members of the OSASM group also have all privileges granted by the SYSOPER for ASM privilege.

## Creating Operating System Privileges Groups

The following sections describe how to create operating system groups for Oracle Grid Infrastructure and Oracle Database:

- [Creating the OSDBA for ASM Group](#)  
You must designate a group as the OSDBA for ASM (`asmdba`) group during installation. Members of this group are granted access privileges to Oracle Automatic Storage Management.
- [Creating the OSOPER for ASM Group](#)  
You can choose to designate a group as the OSOPER for ASM group (`asmoper`) during installation. Members of this group are granted startup and shutdown privileges to Oracle Automatic Storage Management.
- [Creating the OSDBA Group for Database Installations](#)  
Each Oracle Database requires an operating system group to be designated as the OSDBA group. Members of this group are granted the SYSDBA system privileges to administer the database.
- [Creating an OSOPER Group for Database Installations](#)  
Create an OSOPER group only if you want to identify a group of operating system users with a limited set of database administrative privileges (SYSOPER operator privileges).
- [Creating the OSBACKUPDBA Group for Database Installations](#)  
You must designate a group as the OSBACKUPDBA group during installation. Members of this group are granted the SYSBACKUP privileges to perform backup and recovery operations using RMAN or SQL Plus.
- [Creating the OSDGDBA Group for Database Installations](#)  
You must designate a group as the OSDGDBA group during installation. Members of this group are granted the SYSDG privileges to perform Data Guard operations.
- [Creating the OSKMDBA Group for Database Installations](#)  
You must designate a group as the OSKMDBA group during installation. Members of this group are granted the SYSKM privileges to perform Transparent Data Encryption keystore operations.
- [Creating the OSRACDBA Group for Database Installations](#)  
You must designate a group as the OSRACDBA group during installation. Members of this group are granted the SYSRAC privileges to perform day to day administration of Oracle databases on a RAC cluster.

## Creating the OSDBA for ASM Group

You must designate a group as the OSDBA for ASM (`asmdba`) group during installation. Members of this group are granted access privileges to Oracle Automatic Storage Management.

Create an OSDBA for ASM group using the group name `asmdba` unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `asmadmin` group.
3. Press **F10** to exit.

## Creating the OSOPER for ASM Group

You can choose to designate a group as the OSOPER for ASM group (`asmoper`) during installation. Members of this group are granted startup and shutdown privileges to Oracle Automatic Storage Management.

If you want to create an OSOPER for ASM group, use the group name `asmoper` unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `asmoper` group.
3. Press **F10** to exit.

## Creating the OSDBA Group for Database Installations

Each Oracle Database requires an operating system group to be designated as the OSDBA group. Members of this group are granted the SYSDBA system privileges to administer the database.

You must create an OSDBA group in the following circumstances:

- An OSDBA group does not exist, for example, if this is the first installation of Oracle Database software on the system
- An OSDBA group exists, but you want to give a different group of operating system users database administrative privileges for a new Oracle Database installation

Create the OSDBA group using the group name `dba`, unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `dba` group.
3. Press **F10** to exit.

## Creating an OSOPER Group for Database Installations

Create an OSOPER group only if you want to identify a group of operating system users with a limited set of database administrative privileges (SYSOPER operator privileges).

For most installations, it is sufficient to create only the OSDBA group. To use an OSOPER group, then you must create it in the following circumstances:

- If an OSOPER group does not exist; for example, if this is the first installation of Oracle Database software on the system
- If an OSOPER group exists, but you want to give a different group of operating system users database operator privileges in a new Oracle installation

If the OSOPER group does not exist, or if you require a new OSOPER group, then create it. Use the group name `oper` unless a group with that name already exists. For example:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `oper` group.
3. Press **F10** to exit.

## Creating the OSBACKUPDBA Group for Database Installations

You must designate a group as the OSBACKUPDBA group during installation. Members of this group are granted the SYSBACKUP privileges to perform backup and recovery operations using RMAN or SQL Plus.

Create the OSBACKUPDBA group using the group name `backupdba`, unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `backupdba` group.
3. Press **F10** to exit.

### Note:

On IBM AIX on POWER Systems (64-bit), the user and group name length limit parameter default value is 9 characters. Refer your operating system documentation, to increase the user and group name length limit.

## Creating the OSDGDBA Group for Database Installations

You must designate a group as the OSDGDBA group during installation. Members of this group are granted the SYSDG privileges to perform Data Guard operations.

Create the OSDGDBA group using the group name `dgdba`, unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `dgdba` group.
3. Press **F10** to exit.

## Creating the OSKMDBA Group for Database Installations

You must designate a group as the OSKMDBA group during installation. Members of this group are granted the SYSKM privileges to perform Transparent Data Encryption keystore operations.

Create the OSKMDBA group using the groups name `kmdba` unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `kmdba` group.
3. Press **F10** to exit.

## Creating the OSRACDBA Group for Database Installations

You must designate a group as the OSRACDBA group during installation. Members of this group are granted the SYSRAC privileges to perform day to day administration of Oracle databases on a RAC cluster.

Create the OSRACDBA group using the groups name `racdba` unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `racdba` group.
3. Press **F10** to exit.

## Creating Operating System Oracle Installation User Accounts

Before starting installation, create Oracle software owner user accounts, and configure their environments.

Oracle software owner user accounts require resource settings and other environment configuration. To protect against accidents, Oracle recommends that you create one software installation owner account for each Oracle software program you install.

- [Creating an Oracle Software Owner User](#)  
If the Oracle software owner user (`oracle` or `grid`) does not exist, or if you require a new Oracle software owner user, then create it as described in this section.
- [Environment Requirements for Oracle Software Owners](#)  
You must make the following changes to configure Oracle software owner environments:

- [Procedure for Configuring Oracle Software Owner Environments](#)  
Configure each Oracle installation owner user account environment.
- [Modifying Oracle Owner User Groups](#)  
If you have created an Oracle software installation owner account, but it is not a member of the groups you want to designate as the OSDBA, OSOPER, OSDBA for ASM, ASMAADMIN, or other system privileges group, then modify the group settings for that user before installation.
- [Setting Remote Display and X11 Forwarding Configuration](#)  
If you are on a remote terminal, and the local system has only one visual (which is typical), then use the following syntax to set your user account `DISPLAY` environment variable:
- [Preventing Installation Errors Caused by Terminal Output Commands](#)  
During an Oracle Grid Infrastructure installation, OUI uses SSH to run commands and copy files to the other nodes. During the installation, hidden files on the system (for example, `.bashrc` or `.cshrc`) can cause `makefile` and other installation errors if they contain terminal output commands.

## Creating an Oracle Software Owner User

If the Oracle software owner user (`oracle` or `grid`) does not exist, or if you require a new Oracle software owner user, then create it as described in this section.

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `oracle` user, specifying the following information:
  - In the **Primary GROUP** field, specify the Oracle Inventory group, for example `oinstall`.
  - In the **Group SET** field, specify the OSDBA group and if required, the OSOPER group. For example `dba, asmdba, or oper`.

 **Note:**

The UID for the `oracle` user must be less than 65536.

3. Press **F10** to exit.
4. Set the password of the `oracle` user:

```
# passwd oracle
```
5. Ensure that the Oracle software owner user (`oracle` or `grid`) has the capabilities `CAP_NUMA_ATTACH`, `CAP_BYPASS_RAC_VMM`, and `CAP_PROPAGATE`.
  - a. To check existing capabilities, enter the following command as `root`; in this example, the Oracle Database installation user account is `oracle`:

```
# /usr/bin/lsuser -a capabilities oracle
```

- b. To add capabilities, enter a command similar to the following:

```
# /usr/bin/chuser  
capabilities=CAP_NUMA_ATTACH,CAP_BYPASS_RAC_VMM,CAP_PROPAGATE oracle
```

You must note the user ID number for installation users, because you need it during preinstallation.

 **Note:**

On IBM AIX on POWER Systems (64-bit), Oracle Database software installations using an Active Directory (AD) account is not supported.

## Environment Requirements for Oracle Software Owners

You must make the following changes to configure Oracle software owner environments:

- Set the installation software owner user (`grid`, `oracle`) default file mode creation mask (`umask`) to 022 in the shell startup file. Setting the mask to 022 ensures that the user performing the software installation creates files with 644 permissions.
- Set `ulimit` settings for file descriptors and processes for the installation software owner (`grid`, `oracle`).
- Set the `DISPLAY` environment variable in preparation for running an Oracle Universal Installer (OUI) installation.
- Unset `EXTSHM`.

 **Caution:**

If you have existing Oracle installations that you installed with the user ID that is your Oracle Grid Infrastructure software owner, then unset all Oracle environment variable settings for that user.

### Related Topics

- [Configuring Shell Limits on IBM AIX](#)  
For IBM AIX on POWER Systems (64-Bit), it is the `ulimit` settings that determine process memory related resource limits. Use these instructions to display and change the shell limit values if they are different from the recommended value.

## Procedure for Configuring Oracle Software Owner Environments

Configure each Oracle installation owner user account environment.

1. Start an X terminal session (`xterm`) on the server where you are running the installation.
2. Enter the following command to ensure that X Window applications can display on this system, where `hostname` is the fully qualified name of the local host from which you are accessing the server:

```
$ xhost + hostname
```

3. If you are not logged in as the software owner user, then switch to the software owner user you are configuring. For example, with the user `grid`:

```
$ su - grid
```

On systems where you cannot run `su` commands, use `sudo` instead:

```
$ sudo -u grid -s
```

4. To determine the default shell for the user, enter the following command:

```
$ echo $SHELL
```

5. Open the user's shell startup file in any text editor:

- Bash shell (`bash`):

```
$ vi .bash_profile
```

- Bourne shell (`sh`) or Korn shell (`ksh`):

```
$ vi .profile
```

- C shell (`csh` or `tcsh`):

```
% vi .login
```

6. Enter or edit the following line, specifying a value of `022` for the default file mode creation mask:

```
umask 022
```

7. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variables are set in the file, then remove these lines from the file.

8. Save the file, and exit from the text editor.

9. To run the shell startup script, enter one of the following commands:

- Bash shell:

```
$ . ./bash_profile
```

- Bourne, Bash, or Korn shell:

```
$ . ./profile
```

- C shell:

```
% source ./login
```

10. Use the following command to check the `PATH` environment variable:

```
$ echo $PATH
```

Remove any Oracle environment variables.

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ export DISPLAY=local_host:0.0
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, `local_host` is the host name or IP address of the system (your workstation, or another client) on which you want to display the installer.

12. If the `/tmp` directory has less than 5 GB of free space, then identify a file system with at least 5 GB of free space and set the `TMP` and `TMPDIR` environment variables to specify a temporary directory on this file system:

 **Note:**

You cannot use a shared file system as the location of the temporary file directory (typically `/tmp`) for Oracle RAC installations. If you place `/tmp` on a shared file system, then the installation fails.

- a. Use the `df -h` command to identify a suitable file system with sufficient free space.
- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ sudo - s
# mkdir /mount_point/tmp
# chmod 775 /mount_point/tmp
# exit
```

- c. Enter commands similar to the following to set the `TMP` and `TMPDIR` environment variables:

Bourne, Bash, or Korn shell:

```
$ TMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TMP TMPDIR
```

C shell:

```
% setenv TMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```



13. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the `umask` command displays a value of `22`, `022`, or `0022` and that the environment variables you set in this section have the correct values.

## Modifying Oracle Owner User Groups

If you have created an Oracle software installation owner account, but or it is not a member of the groups you want to designate as the OSDBA, OSOPER, OSDBA for ASM, ASMADMIN, or other system privileges group, then modify the group settings for that user before installation.

### Warning:

Each Oracle software owner must be a member of the same central inventory group. Do not modify the primary group of an existing Oracle software owner account, or designate different groups as the OINSTALL group. If Oracle software owner accounts have different groups as their primary group, then you can corrupt the central inventory.

During installation, the user that is installing the software should have the OINSTALL group as its primary group, and it must be a member of the operating system groups appropriate for your installation. For example:

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to modify the Oracle installation owner user group.
3. In the **Primary GROUP** field, specify the Oracle Inventory group. For example: `oinstall`.
4. In the **Group SET** field, specify the required secondary groups. For example: `dba, asmdba, backupdba, dgdba, kmdba, and racdba`.
5. Press **F10** to exit.

## Setting Remote Display and X11 Forwarding Configuration

If you are on a remote terminal, and the local system has only one visual (which is typical), then use the following syntax to set your user account `DISPLAY` environment variable:

### Remote Display

Bourne, Korn, and Bash shells

```
$ export DISPLAY=hostname:0
```

```
C shell
```

```
% setenv DISPLAY hostname:0
```

For example, if you are using the Bash shell and if your host name is `local_host`, then enter the following command:

```
$ export DISPLAY=nodel:0
```

### X11 Forwarding

To ensure that X11 forwarding does not cause the installation to fail, use the following procedure to create a user-level SSH client configuration file for Oracle installation owner user accounts:

1. Using any text editor, edit or create the software installation owner's `~/.ssh/config` file.
2. Ensure that the `ForwardX11` attribute in the `~/.ssh/config` file is set to `no`. For example:

```
Host *
    ForwardX11 no
```

3. Ensure that the permissions on `~/.ssh` are secured to the Oracle installation owner user account. For example:

```
$ ls -al .ssh
total 28
drwx----- 2 grid oinstall 4096 Jun 21 2020
drwx----- 19 grid oinstall 4096 Jun 21 2020
-rw-r--r--  1 grid oinstall 1202 Jun 21 2020 authorized_keys
-rwx-----  1 grid oinstall  668 Jun 21 2020 id_dsa
-rwx-----  1 grid oinstall  601 Jun 21 2020 id_dsa.pub
-rwx-----  1 grid oinstall 1610 Jun 21 2020 known_hosts
```

## Preventing Installation Errors Caused by Terminal Output Commands

During an Oracle Grid Infrastructure installation, OUI uses SSH to run commands and copy files to the other nodes. During the installation, hidden files on the system (for example, `.bashrc` or `.cshrc`) can cause `makefile` and other installation errors if they contain terminal output commands.

To avoid this problem, you must modify hidden files in each Oracle installation owner user home directory to suppress all output on `STDOUT` or `STDERR` (for example, `stty`, `xtitle`, and other such commands) as in the following examples:

Bourne, Bash, or Korn shell:

```
if [ -t 0 ]; then
    stty intr ^C
fi
```

C shell:

```
test -t 0
if ($status == 0) then
    stty intr ^C
endif
```

**Note:**

If the remote shell can load hidden files that contain `stty` commands, then OUI indicates an error and stops the installation.

## Creating Oracle Database Vault User Accounts

If you intend to use Oracle Database Vault by default, then you must create an Oracle Database Vault user account, and configure that user.

You must create the Database Vault Owner account before you can use Oracle Database Vault. You can also create a Database Vault Account Manager administrative account.

Oracle Database Vault installs a baseline database auditing policy. This policy covers the access control configuration information stored in Oracle Database Vault database tables, information stored in Oracle Catalog (rollback segments, tablespaces, and so on), the use of system privileges, and Oracle Label Security configuration. When you install Oracle Database Vault, the security specific database initialization parameters are initialized with default values.

**Related Topics**

- *Oracle Database Vault Administrator's Guide*

## Unsetting Oracle Installation Owner Environment Variables

Unset Oracle installation owner environment variables before starting installation

The environment variables you have set for the Oracle installation owner account you use to run the installation can cause issues if they are set to values that conflict with the values needed for installation.

If you have set `ORA_CRS_HOME` as an environment variable, following instructions from Oracle Support, then unset it before starting an installation or upgrade. You should never use `ORA_CRS_HOME` as an environment variable except under explicit direction from Oracle Support.

If you have had an existing installation on your system, and you are using the same user account to install this installation, then unset the following environment variables: `ORA_CRS_HOME`; `ORACLE_HOME`; `ORA_NLS10`; `TNS_ADMIN`; and any other environment variable set for the Oracle installation user that is connected with Oracle software homes.

Also, ensure that the `$ORACLE_HOME/bin` path is removed from your `PATH` environment variable.

Unset the environment variable `EXTSHM`.

## Running the rootpre.sh Script

Run the `rootpre.sh` script only the first time you install Oracle Database on IBM AIX on POWER Systems (64-Bit).



### Note:

You do not have to run the `rootpre.sh` script on an IBM AIX on POWER Systems (64-Bit) server that has an Oracle Database software already installed.

Use the following procedure to run the `rootpre.sh` script:

1. Download the Oracle Database installation image files (`db_home.zip`) and extract the files into a new Oracle home directory. For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/dbhome_1
$ chgrp oinstall /u01/app/oracle/product/19.0.0/dbhome_1
$ cd /u01/app/oracle/product/19.0.0/dbhome_1
$ unzip -q /tmp/db_home.zip
```

2. Switch the user to `root`:

```
$ su - root
password:
#
```

3. Run the `rootpre.sh` script using the following command:

```
# $ORACLE_HOME/clone/rootpre.sh
```

4. Exit from the `root` account:

```
# exit
```

# 5

## Configuring Networks for Oracle Database

If you install Oracle Databases on servers with multiple Oracle homes, multiple aliases, or without a static IP address, then review these network configuration topics.

If you are installing Oracle Database on a server with a static host name and IP address and at least one network interface, then no special network configuration is required.

- [About Oracle Database Network Configuration Options](#)  
You can enable database clients to connect to servers associated with multiple IP addresses, and you can install Oracle Database on servers with no network connections, and set up database services after installation.
- [About Assigning Global Database Names During Installation](#)  
The database name input field is used to set the `DB_NAME`, `DB_UNIQUE_NAME`, and `DB_DOMAIN` Oracle initialization parameter values.
- [Network Configuration for Computers Completed After Installation](#)  
You must confirm that a non-networked computer can connect to itself to ensure that you can configure client network resolution after installation. A non-networked computer is a computer that does not have a fixed network address, such as a computer using DHCP.
- [Network Configuration for Multihomed Computers](#)  
You must set the `ORACLE_HOSTNAME` environment variable to install Oracle Database on a multihomed computer. A multihomed computer is associated with multiple IP addresses.
- [Setting the ORACLE\\_HOSTNAME Environment Variable](#)  
Run the commands shown in this example as the Oracle user account to set the `ORACLE_HOSTNAME` environment variable.
- [Network Configuration for Computers with Multiple Aliases](#)  
You must set the `ORACLE_HOSTNAME` environment variable to install Oracle Database on a multialias computer. A multialias computer is one to which multiple aliases resolve.

### About Oracle Database Network Configuration Options

You can enable database clients to connect to servers associated with multiple IP addresses, and you can install Oracle Database on servers with no network connections, and set up database services after installation.

Typically, the computer on which you want to install Oracle Database is a server running a single database instance, with a single host name that is resolvable on a network. Oracle Universal Installer uses the host name and Oracle Database instance information to set up network services automatically. The database provides database services to clients using a connect descriptor that resolves to the host name where the database instance is running.

However, you can configure Oracle Database on servers with the following nonstandard configurations:

- **Multihomed Computers:** Servers with multiple Oracle Database installations
- **Multiple Alias Computers:** Servers with multiple aliases, so that more than one host name resolves to the computer

- **Non-Networked computers:** Servers that do not have network connectivity at the time of installation

## About Assigning Global Database Names During Installation

The database name input field is used to set the `DB_NAME`, `DB_UNIQUE_NAME`, and `DB_DOMAIN` Oracle initialization parameter values.

The Oracle Database software identifies a database by its global database name. A global database name consists of the database name and database domain. Usually, the database domain is the same as the network domain, but it need not be. The global database name uniquely distinguishes a database from any other database in the same network. You specify the global database name when you create a database during the installation or using the Oracle Database Configuration Assistant.

```
sales.us.example.com
```

Here:

- `sales.us` is the name of the database. The database name, `DB_UNIQUE_NAME`, portion is a string of no more than 30 characters that can contain alphanumeric characters, underscore (`_`), dollar sign (`$`), and pound sign (`#`) but must begin with an alphabetic character. No other special characters are permitted in a database name.
- `sales.us` is also the `DB_NAME`. The `DB_NAME` initialization parameter specifies a database identifier of up to eight characters.
- `example.com` is the database domain in which the database is located. In this example, the database domain equals the network domain. Together, the database name and the database domain make the global database name unique. The domain portion is a string of no more than 128 characters that can contain alphanumeric characters, underscore (`_`), and pound sign (`#`). The `DB_DOMAIN` initialization parameter specifies the database domain name.

However, the `DB_NAME` parameter need not necessarily be the first eight characters of `DB_UNIQUE_NAME`.

The `DB_NAME` parameter and the `DB_DOMAIN` parameter combine to create the global database name value.

The system identifier (SID) identifies a specific database instance. The SID uniquely distinguishes the instance from any other instance on the same computer. Each database instance requires a unique SID and database name. In most cases, the SID equals the database name portion of the global database name.

### Related Topics

- *Oracle Database Reference*
- *Oracle Database Administrator's Guide*

## Network Configuration for Computers Completed After Installation

You must confirm that a non-networked computer can connect to itself to ensure that you can configure client network resolution after installation. A non-networked computer is a computer that does not have a fixed network address, such as a computer using DHCP.

You can install Oracle Database on a non-networked computer. If the computer, such as a laptop, is configured for DHCP and you plan to connect the computer to the network after the Oracle Database installation, then use the `ping` command on the computer on which you want to install the database to check if the computer can connect to itself. Perform this step by first using only the host name and then using the fully qualified name, which should be in the `/etc/hosts` file.

If you connect the computer to a network after installation, then the Oracle Database instance on the computer can work with other instances on the network. The computer can use a static IP or DHCP, depending on the network to which you are connected.

When you run the `ping` command on the computer itself, the `ping` command should return the IP address of the computer. If the `ping` command fails, then contact your network administrator.

## Network Configuration for Multihomed Computers

You must set the `ORACLE_HOSTNAME` environment variable to install Oracle Database on a multihomed computer. A multihomed computer is associated with multiple IP addresses.

Typically, a server configured to run multiple Oracle Database Oracle homes is configured with multiple network interface cards. A host name resolves to an IP address configured for one network card for each Oracle Database. You can also set up aliases for host names. By default, during installation, Oracle Universal Installer uses the value set for the environment variable `ORACLE_HOSTNAME` set for the Oracle installation user account running the installation to find the host name. If the user environment variable `ORACLE_HOSTNAME` is not set for the Oracle user, and you are installing on a computer that has multiple network cards, then Oracle Universal Installer determines the host name from the `/etc/hosts` file and the information you provide during the installation session.

Oracle Database clients connecting to the database must be able to access the computer by using either the alias for the host name, or by using the host name associated with that instance. To verify that the client can resolve to the database using both alias and host name, use the `ping` command to check connectivity to the host name both for the database on the server (host name only), and for the fully qualified domain name (host name and domain name).

### Note:

Clients must be able to obtain a response using the `ping` command both for the host name and for the fully qualified domain name. If either test fails, then contact your network administrator to resolve the issue.

## Setting the ORACLE\_HOSTNAME Environment Variable

Run the commands shown in this example as the Oracle user account to set the ORACLE\_HOSTNAME environment variable.

The following example shows the commands to run on the Oracle user account to set the ORACLE\_HOSTNAME environment variable. In this example, the fully qualified host name is somehost.example.com.

### Bourne, Bash or Korn Shell

```
$ ORACLE_HOSTNAME=somehost.example.com  
$ export ORACLE_HOSTNAME
```

### C Shell

```
% setenv ORACLE_HOSTNAME somehost.example.com
```

## Network Configuration for Computers with Multiple Aliases

You must set the ORACLE\_HOSTNAME environment variable to install Oracle Database on a multialias computer. A multialias computer is one to which multiple aliases resolve.

A computer with multiple aliases is a computer that is registered with the naming service under a single IP address, but which resolves multiple aliases to that address. The naming service resolves any of those aliases to the same computer. Before installing Oracle Database on such a computer, set the Oracle installation owner environment variable ORACLE\_HOSTNAME to the computer whose host name you want to use.



# 6

## Supported Storage Options for Oracle Database and Oracle Grid Infrastructure

Review supported storage options as part of your installation planning process.

- [Supported Storage Options for Oracle Database](#)  
The following table shows the storage options supported for Oracle Database binaries and files:
- [About Oracle Grid Infrastructure for a Standalone Server](#)  
If you plan to use Oracle Automatic Storage Management (Oracle ASM), then you must install Oracle Restart before installing your database.
- [Oracle ACFS and Oracle ADVM](#)  
Oracle Automatic Storage Management Cluster File System (Oracle ACFS) extends Oracle ASM technology to support of all of your application data in both single instance and cluster configurations.
- [File System Options for Oracle Database](#)  
If you install Oracle Database files on a file system, then Oracle Database Configuration Assistant creates the database files in a directory on a file system mounted on the computer.
- [Guidelines for Placing Oracle Database Files On a File System or Logical Volume](#)  
If you choose to place the Oracle Database files on a file system, then use the following guidelines when deciding where to place them:
- [About NFS Storage for Data Files](#)  
Review this section for NFS storage configuration guidelines.
- [About Direct NFS Client Mounts to NFS Storage Devices](#)  
Direct NFS Client integrates the NFS client functionality directly in the Oracle software to optimize the I/O path between Oracle and the NFS server. This integration can provide significant performance improvements.

### Supported Storage Options for Oracle Database

The following table shows the storage options supported for Oracle Database binaries and files:



**Note:**

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

**Table 6-1 Supported Storage Options for Oracle Database**

Storage Option	Oracle Database Binaries	Oracle Database Data Files	Oracle Database Recovery Files
Oracle Automatic Storage Management (Oracle ASM) <b>Note:</b> Loopback devices are not supported for use with Oracle ASM	No	Yes	Yes
Oracle Automatic Storage Management Cluster File System (Oracle ACFS)	Yes	Yes (Oracle Database 12c Release 1 (12.1) and later)	Yes (Oracle Database 12c Release 1 (12.1) and later)
Local file system	Yes	Yes, but not recommended	Yes, but not recommended
Network file system (NFS) on a certified network-attached storage (NAS) filer	Yes	Yes	Yes
Oracle Memory Speed	No	Yes	Yes

### Guidelines for Storage Options

Use the following guidelines when choosing storage options:

- Oracle strongly recommends that you use a dedicated set of disks for Oracle ASM.
- You can choose any combination of the supported storage options for each file type provided that you satisfy all requirements listed for the chosen storage options.
- You can use Oracle ASM to store Oracle Clusterware files.
- Direct use of raw or block devices is not supported. You can only use raw or block devices under Oracle ASM.

### Related Topics

- *Oracle Database Upgrade Guide*

## About Oracle Grid Infrastructure for a Standalone Server

If you plan to use Oracle Automatic Storage Management (Oracle ASM), then you must install Oracle Restart before installing your database.

Oracle Grid Infrastructure for a standalone server is a version of Oracle Grid Infrastructure that supports single instance databases. This support includes volume management, file system, and automatic restart capabilities. Oracle Grid Infrastructure for a standalone server includes Oracle Restart and Oracle Automatic Storage Management. Oracle combined the two infrastructure products into a single set of binaries that is installed into an Oracle Restart home.

Oracle Restart is a feature provided as part of Oracle Grid Infrastructure. Oracle Restart monitors and can restart Oracle Database instances, Oracle Net Listeners, and Oracle ASM instances. Oracle Restart is currently restricted to manage single instance Oracle Databases and Oracle ASM instances only.

Oracle Automatic Storage Management is a volume manager and a file system for Oracle Database files that supports single-instance Oracle Database and Oracle Real Application Clusters (Oracle RAC) configurations. Oracle Automatic Storage Management also supports a general purpose file system for your application needs, including Oracle Database binaries. Oracle Automatic Storage Management is Oracle's recommended storage management solution that provides an alternative to conventional volume managers, and file systems.

Oracle Restart improves the availability of your Oracle database by providing the following services:

- When there is a hardware or a software failure, Oracle Restart automatically starts all Oracle components, including the Oracle database instance, Oracle Net Listener, database services, and Oracle ASM.
- Oracle Restart starts components in the proper order when the database host is restarted.
- Oracle Restart runs periodic checks to monitor the status of Oracle components. If a check operation fails for a component, then the component is shut down and restarted.

Note the following restrictions for using Oracle Restart:

- You can neither install Oracle Restart on an Oracle Grid Infrastructure cluster member node, nor add an Oracle Restart server to an Oracle Grid Infrastructure cluster member node. Oracle Restart supports single-instance databases on one server, while Oracle Grid Infrastructure for a Cluster supports single-instance or Oracle RAC databases on a cluster.
- If you want to use Oracle ASM or Oracle Restart, then you should install Oracle Grid Infrastructure for a standalone server before you install and create the database. Otherwise, you must install Oracle Restart, and then manually register the database with Oracle Restart.
- You can use the Oracle Restart implementation of Oracle Grid Infrastructure only in single-instance (nonclustered) environments. Use Oracle Grid Infrastructure with Oracle Clusterware for clustered environments.

## Oracle ACFS and Oracle ADVM

Oracle Automatic Storage Management Cluster File System (Oracle ACFS) extends Oracle ASM technology to support of all of your application data in both single instance and cluster configurations.

### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

To align the support for the IBM AIX platform, Oracle Automatic Storage Management Cluster File System (ACFS) on IBM AIX (called Oracle Advanced Cluster File System starting with Oracle Database 21c) is deprecated in Oracle Database 19c. For data or files currently stored on an ACFS file system that cannot be stored in the Oracle database, the IBM General Parallel File System (GPFS) can be used.

Oracle Automatic Storage Management Dynamic Volume Manager (Oracle ADVM) provides volume management services and a standard disk device driver interface to clients. Oracle ACFS communicates with Oracle ASM through the Oracle ADVM interface.

- [Oracle ACFS and Oracle ADVM Support on IBM AIX](#)  
Oracle ACFS and Oracle ADVM are supported on IBM AIX on POWER Systems (64-Bit).

- [Restrictions and Guidelines for Oracle ACFS](#)  
Review these topics as part of your storage plan for using Oracle ACFS for single instance and cluster configurations.

#### Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*

## Oracle ACFS and Oracle ADVM Support on IBM AIX

Oracle ACFS and Oracle ADVM are supported on IBM AIX on POWER Systems (64-Bit).

#### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

Oracle ACFS and Oracle ADVM are supported on:

- IBM AIX 7.1 and later updates to IBM AIX 7.1
- IBM AIX 7.2 and later updates to IBM AIX 7.2

Oracle ACFS and Oracle ADVM are not supported on IBM AIX Workload Partitions (WPARs).

#### See Also:

- My Oracle Support Note 1369107.1 for more information about platforms and releases that support Oracle ACFS and Oracle ADVM:  
<https://support.oracle.com/CSP/main/article?cmd=show&type=NOT&id=1369107.1>
- Patch Set Updates for Oracle Products (My Oracle Support Note 854428.1) for current release and support information:  
<https://support.oracle.com/CSP/main/article?cmd=show&type=NOT&id=854428.1>

## Restrictions and Guidelines for Oracle ACFS

Review these topics as part of your storage plan for using Oracle ACFS for single instance and cluster configurations.

#### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

- Oracle Automatic Storage Management Cluster File System (Oracle ACFS) provides a general purpose file system.
- You can only use Oracle ACFS when Oracle ASM is configured.

- Note the following general guidelines and restrictions for placing Oracle Database and Oracle Grid Infrastructure files on Oracle ACFS:
  - You can place Oracle Database binaries, data files, and administrative files (for example, trace files) on Oracle ACFS.
  - Oracle ACFS does not support encryption or replication with Oracle Database data files, tablespace files, control files, redo logs, archive logs, RMAN backups, Data Pump dumpsets, and flashback files.
  - You can place Oracle Database homes on Oracle ACFS only if the database release is Oracle Database 11g Release 2, or more recent releases. You cannot install earlier releases of Oracle Database on Oracle ACFS.
  - For installations on Oracle Clusterware, you cannot place Oracle Clusterware files on Oracle ACFS.
- Oracle Restart does not support root-based Oracle Clusterware resources. For this reason, the following restrictions apply if you run Oracle ACFS on an Oracle Restart Configuration:
  - Starting with Oracle Database 18c, configuration assistants do not allow the creation of Oracle Database homes on Oracle ACFS in an Oracle Restart configuration.
  - Oracle Restart does not support Oracle ACFS resources on all platforms.
  - Starting with Oracle Database 12c, Oracle Restart configurations do not support the Oracle ACFS registry.
  - On Linux, Oracle ACFS provides an automated mechanism to load and unload drivers and mount and unmount Oracle ACFS file systems on system restart and shutdown. However, Oracle ACFS does not provide automated recovery of mounted file systems when the system is running. Other than Linux, Oracle ACFS does not provide this automated mechanism on other operating systems.
  - Creating Oracle data files on an Oracle ACFS file system is not supported in Oracle Restart configurations. Creating Oracle data files on an Oracle ACFS file system is supported on Oracle Grid Infrastructure for a cluster configurations.
- Oracle ACFS and Oracle ADVM are not supported on IBM AIX Workload Partitions (WPARs).

#### Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*

## File System Options for Oracle Database

If you install Oracle Database files on a file system, then Oracle Database Configuration Assistant creates the database files in a directory on a file system mounted on the computer.

Oracle recommends that the file system be separate from the file systems used by the operating system or the Oracle Database software.

The file system can be any of the following:

#### Standard Oracle Database Creation Options

- A file system on a disk that is physically attached to the system.  
If you are creating a database on basic disks that are not logical volumes or RAID devices, then Oracle recommends that you follow the Optimal Flexible Architecture (OFA) recommendations and distribute the database files over many disks.
- A file system on a logical volume manager (LVM) volume or a RAID device.

If you are using multiple disks in an LVM or RAID configuration, then Oracle recommends that you use the Stripe and Mirror Everything (S.A.M.E) methodology to increase performance and reliability. Using this methodology, you do not have to specify multiple file system mount points for the database storage.

- A network file system (NFS) mounted from a certified network-attached storage (NAS) device. You also have the option to use Direct NFS Client, which simplifies the administration of NFS configurations and also improves performance.

#### Advanced Oracle Database Creation Options

- The three file system options available to standard Oracle Database installations.
- With Oracle Managed Files, you specify file system directories in which the database automatically creates, names, and manages files at the database object level.

If you use the Oracle Managed Files feature, then you must specify only the database object name instead of file names when creating or deleting database files.

#### Related Topics

- [Oracle RAC Technologies Matrix for Linux Platforms](#)
- *Oracle Database Administrator's Guide*

## Guidelines for Placing Oracle Database Files On a File System or Logical Volume

If you choose to place the Oracle Database files on a file system, then use the following guidelines when deciding where to place them:

- The default path suggested by Oracle Universal Installer for the database file directory is a subdirectory of the Oracle base directory.
- You can choose either a single file system or more than one file system to store the database files:

- If you want to use a single file system, then choose a file system on a physical device that is dedicated to the database.

For best performance and reliability, choose a RAID device or a logical volume on more than one physical device, and implement a stripe-and-mirror-everything (SAME) storage policy.

- If you want to use more than one file system, then choose file systems on separate physical devices that are dedicated to the database.

This method enables you to distribute physical input-output operations and create separate control files on different devices for increased reliability. It also enables you to fully implement Oracle Optimal Flexible Architecture (OFA) guidelines. Choose the *Advanced* database creation option to implement this method.

- If you intend to create a preconfigured database during the installation, then the file system (or file systems) that you choose must have at least 2 GB of free disk space.

For production databases, you must estimate the disk space requirement depending on the use of the database.

- For optimum performance, the file systems that you choose must be on physical devices that are used only by the database.

- The Oracle user running the Oracle Database installation must have write permissions to create the files in the path that you specify.

## About NFS Storage for Data Files

Review this section for NFS storage configuration guidelines.

### Network-Attached Storage and NFS Protocol

Network-attached storage (NAS) systems use the network file system (NFS) protocol to access files over a network, which enables client servers to access files over networks as easily as to storage devices attached directly to the servers. You can store data files on supported NFS systems. NFS is a shared file system protocol, so NFS can support both single instance and Oracle Real Application Clusters databases.

#### Note:

The performance of Oracle software and databases stored on NAS devices depends on the performance of the network connection between the servers and the network-attached storage devices. For better performance, Oracle recommends that you connect servers to NAS devices using private dedicated network connections. NFS network connections should use Gigabit Ethernet or better.

Refer to your vendor documentation to complete NFS configuration and mounting.

### Requirements for Using NFS Storage

Before you start installation, NFS file systems must be mounted and available to servers.

## About Direct NFS Client Mounts to NFS Storage Devices

Direct NFS Client integrates the NFS client functionality directly in the Oracle software to optimize the I/O path between Oracle and the NFS server. This integration can provide significant performance improvements.

Direct NFS Client supports NFSv3, NFSv4, NFSv4.1, and pNFS protocols to access the NFS server. Direct NFS Client also simplifies, and in many cases automates, the performance optimization of the NFS client configuration for database workloads.

Starting with Oracle Database 12c Release 2, when you enable Direct NFS, you can also enable the Direct NFS dispatcher. The Direct NFS dispatcher consolidates the number of TCP connections that are created from a database instance to the NFS server. In large database deployments, using Direct NFS dispatcher improves scalability and network performance. Parallel NFS deployments also require a large number of connections. Hence, the Direct NFS dispatcher is recommended with Parallel NFS deployments too.

Direct NFS Client can obtain NFS mount points either from the operating system mount entries, or from the `oranfstab` file.

### Direct NFS Client Requirements

- NFS servers must have write size values (`wtmax`) of 32768 or greater to work with Direct NFS Client.

- NFS mount points must be mounted both by the operating system kernel NFS client and Direct NFS Client, even though you configure Direct NFS Client to provide file service.  
If Oracle Database cannot connect to an NFS server using Direct NFS Client, then Oracle Database connects to the NFS server using the operating system kernel NFS client. When Oracle Database fails to connect to NAS storage through Direct NFS Client, it logs an informational message about the Direct NFS Client connect error in the Oracle alert and trace files.
- Follow standard guidelines for maintaining integrity of Oracle Database files mounted by both operating system NFS and by Direct NFS Client.

### Direct NFS Mount Point Search Order

Direct NFS Client searches for mount entries in the following order:

1. `$ORACLE_HOME/dbs/oranfstab`
2. `/etc/oranfstab`
3. `/etc/mtab`

Direct NFS Client uses the first matching entry as the mount point.

#### Note:

You can have only one active NFS Client implementation for each instance. Enabling Direct NFS Client on an instance prevents you from using another NFS Client implementation, such as kernel NFS Client.

### Related Topics

- [Configuring NFS Buffer Size Parameters for Oracle Database](#)  
Set the values for the NFS buffer size parameters `rsize` and `wsize` to 32768.
- [Creating an oranfstab File for Direct NFS Client](#)  
Direct NFS uses a configuration file, `oranfstab`, to determine the available mount points.

#### See Also:

- *Oracle Database Reference* for information about setting the `enable_dnfs_dispatcher` parameter in the initialization parameter file to enable Direct NFS dispatcher
- *Oracle Database Performance Tuning Guide* for performance benefits of enabling Parallel NFS and Direct NFS dispatcher
- *Oracle Automatic Storage Management Administrator's Guide* for guidelines about managing Oracle Database data files created with Direct NFS Client or kernel NFS



# 7

## Configuring File System Storage for Oracle Database

Complete these procedures to use file system storage for Oracle Database.

For optimal database organization and performance, Oracle recommends that you install data files and the Oracle Database software in different disks.

- [Configuring NFS Buffer Size Parameters for Oracle Database](#)  
Set the values for the NFS buffer size parameters `rsize` and `wsize` to 32768.
- [Checking TCP Network Protocol Buffer for Direct NFS Client](#)  
Check your TCP network buffer size to ensure that it is adequate for the speed of your servers.
- [Creating an `orantstab` File for Direct NFS Client](#)  
Direct NFS uses a configuration file, `orantstab`, to determine the available mount points.
- [Enabling and Disabling Direct NFS Client Control of NFS](#)  
By default, Direct NFS Client is installed in a disabled state with single-instance Oracle Database installations. Before enabling Direct NFS, you must configure an `orantstab` file.
- [Enabling HCC on Direct NFS Client](#)  
Perform these steps to enable Hybrid Columnar Compression (HCC) on Direct NFS Client:

## Configuring NFS Buffer Size Parameters for Oracle Database

Set the values for the NFS buffer size parameters `rsize` and `wsize` to 32768.

For example, to use `rsize` and `wsize` buffer settings with the value 32768 for an Oracle Database data files mount point, set mount point parameters to values similar to the following:

```
/NFS_mount:  
dev = "/NFS_mount"  
vfs = nfs  
nodename = NFS_server  
mount = true  
options = bg,soft,intr,rsize=32768,wsize=32768  
account = false
```

Direct NFS Client issues writes at `wtmax` granularity to the NFS server.

### Related Topics

- [My Oracle Support note 359515.1](#)

## Checking TCP Network Protocol Buffer for Direct NFS Client

Check your TCP network buffer size to ensure that it is adequate for the speed of your servers.

By default, the network buffer size is set to 1 MB for TCP, and 2 MB for UDP. The TCP buffer size can set a limit on file transfers, which can negatively affect performance for Direct NFS Client users.

To check the current TCP buffer size:

```
# /usr/sbin/no -o sb_max
```

Oracle recommends that you set the value based on the link speed of your servers. For example:

```
# /usr/sbin/no -p -o sb_max=524288
```

## Creating an oranfstab File for Direct NFS Client

Direct NFS uses a configuration file, `oranfstab`, to determine the available mount points.

Create an `oranfstab` file with the following attributes for each NFS server that you want to access using Direct NFS Client:

- `server`

The NFS server name.

For NFS setup with Kerberos authentication, the `server` attribute name must be the fully-qualified name of the NFS server. This `server` attribute name is used to create service principal for Ticket Granting Service (TGS) request from the Kerberos server. If you are configuring external storage snapshot cloning, then the NFS `server` name should be a valid host name. For all other scenarios, the NFS `server` name can be any unique name.

- `local`

Up to four paths on the database host, specified by IP address or by name, as displayed using the `ifconfig` command run on the database host.

- `path`

Up to four network paths to the NFS server, specified either by IP address, or by name, as displayed using the `ifconfig` command on the NFS server.

- `export`

The exported path from the NFS server.

- `mount`

The corresponding local mount point for the exported volume.

- `mnt_timeout`

Specifies (in seconds) the time Direct NFS Client should wait for a successful mount before timing out. This parameter is optional. The default timeout is 10 minutes (600).

- `nfs_version`

Specifies the NFS protocol version used by Direct NFS Client. Possible values are NFSv3, NFSv4, NFSv4.1, and pNFS. The default version is NFSv3. If you select NFSv4.x, then you must configure the value in `orafstab` for `nfs_version`.

Specify `nfs_version` as `pNFS`, if you want to use Direct NFS with Parallel NFS. Direct NFS supports only the default `sys` security authentication with Parallel NFS. Direct NFS does not support Parallel NFS when combined with any of the Kerberos authentication parameters.

- `security_default`

Specifies the default security mode applicable for all the exported NFS server paths for a server entry. This parameter is optional. `sys` is the default value. See the description of the `security` parameter for the supported security levels for the `security_default` parameter.

- `security`

Specifies the security level, to enable security using Kerberos authentication protocol with Direct NFS Client. This optional parameter can be specified per export-mount pair. The supported security levels for the `security_default` and `security` parameters are:

`sys`: UNIX level security AUTH\_UNIX authentication based on user identifier (UID) and group identifier (GID) values. This is the default value for security parameters.

`krb5`: Direct NFS runs with plain Kerberos authentication. Server is authenticated as the real server which it claims to be.

`krb5i`: Direct NFS runs with Kerberos authentication and NFS integrity. Server is authenticated and each of the message transfers is checked for integrity.

`krb5p`: Direct NFS runs with Kerberos authentication and NFS privacy. Server is authenticated, and all data is completely encrypted.

The `security` parameter, if specified, takes precedence over the `security_default` parameter. If neither of these parameters are specified, then `sys` is the default authentication.

For NFS server Kerberos security setup, review the relevant NFS server documentation. For Kerberos client setup, review the relevant operating system documentation.

- `dontroute`

Specifies that outgoing messages should not be routed by the operating system, but instead sent using the IP address to which they are bound.

 **Note:**

The `dontroute` option is a POSIX option, which sometimes does not work on Linux systems with multiple paths in the same subnet.

- `management`

Enables Direct NFS Client to use the management interface for SNMP queries. You can use this parameter if SNMP is running on separate management interfaces on the NFS server. The default value is the server parameter value.

- `community`

Specifies the community string for use in SNMP queries. Default value is `public`.

The following examples show three possible NFS server entries in `orafstab`. A single `orafstab` can have multiple NFS server entries.

**Example 7-1 Using Local and Path NFS Server Entries**

The following example uses both local and path. Because they are in different subnets, you do not have to specify `dontroute`.

```
server: MyDataServer1
local: 192.0.2.0
path: 192.0.2.1
local: 192.0.100.0
path: 192.0.100.1
export: /vol/oradata1 mount: /mnt/oradata1
```

**Example 7-2 Using Local and Path in the Same Subnet, with dontroute**

Local and path in the same subnet, where `dontroute` is specified:

```
server: MyDataServer2
local: 192.0.2.0
path: 192.0.2.128
local: 192.0.2.1
path: 192.0.2.129
dontroute
export: /vol/oradata2 mount: /mnt/oradata2
```

**Example 7-3 Using Names in Place of IP Addresses, with Multiple Exports, management and community**

```
server: MyDataServer3
local: LocalPath1
path: NfsPath1
local: LocalPath2
path: NfsPath2
local: LocalPath3
path: NfsPath3
local: LocalPath4
path: NfsPath4
dontroute
export: /vol/oradata3 mount: /mnt/oradata3
export: /vol/oradata4 mount: /mnt/oradata4
export: /vol/oradata5 mount: /mnt/oradata5
export: /vol/oradata6 mount: /mnt/oradata6
management: MgmtPath1
community: private
```

**Example 7-4 Using Kerberos Authentication with Direct NFS Export**

The `security` parameter overrides `security_default`:

```
server: nfsserver
local: 192.0.2.0
path: 192.0.2.2
local: 192.0.2.3
path: 192.0.2.4
export: /private/oracle1/logs mount: /logs security: krb5
export: /private/oracle1/data mount: /data security: krb5p
```

```
export: /private/oracle1/archive mount: /archive security: sys
export: /private/oracle1/data1 mount: /data1
security_default: krb5i
```

## Enabling and Disabling Direct NFS Client Control of NFS

By default, Direct NFS Client is installed in a disabled state with single-instance Oracle Database installations. Before enabling Direct NFS, you must configure an `oranfstab` file.

Use these procedures to enable or disable Direct NFS Client Oracle Disk Manager Control of NFS

### Enabling Direct NFS Client Control of NFS

1. Change the directory to `$ORACLE_HOME/rdbms/lib`.
2. Enter the following command:

```
make -f ins_rdbms.mk dnfs_on
```

### Disabling Direct NFS Client Control of NFS

1. Log in as the Oracle software installation owner, and disable Direct NFS Client using the following commands:

```
cd $ORACLE_HOME/rdbms/lib
make -f ins_rdbms.mk dnfs_off
```

2. Remove the `oranfstab` file.



#### Note:

If you remove an NFS path that an Oracle Database is using, then you must restart the database for the change to take effect.

## Enabling HCC on Direct NFS Client

Perform these steps to enable Hybrid Columnar Compression (HCC) on Direct NFS Client:

1. Ensure that SNMP is enabled on the ZFS storage server. For example:

```
# snmpinfo -m get -c public -v -h server_name 1.3.6.1.4.1.42.2.225.1.4.2.0
enterprises.42.2.225.1.4.2.0 =
53:75:6e:20:53:74:6f:72:61:67:65:20:37:34:31:30
```

The above sequence of bytes `53:75:6e: . . . :31:30` is an ascii character representation for Sun Storage 7410.

2. If SNMP is enabled on an interface other than the NFS server, then configure `oranfstab` using the `management` parameter.

3. If SNMP is configured using a community string other than `public`, then configure `orantstab` file using the `community` parameter.
4. Ensure that `libnetsnmp.so` is installed. If `libnetsnmp.so` is not installed, download and install it from the following URL:  
<https://oss.oracle.com/netsnmp/>



**Note:**

On IBM AIX on POWER Systems (64-Bit), HCC is not supported for block based devices.

# 8

## Configuring Storage for Oracle Grid Infrastructure for a Standalone Server

Complete these procedures to use Oracle Grid Infrastructure for a standalone server, which includes Oracle Automatic Storage Management (Oracle ASM).

### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

To align the support for the IBM AIX platform, Oracle Automatic Storage Management Cluster File System (ACFS) on IBM AIX (called Oracle Advanced Cluster File System starting with Oracle Database 21c) is deprecated in Oracle Database 19c. For data or files currently stored on an ACFS file system that cannot be stored in the Oracle database, the IBM General Parallel File System (GPFS) can be used.

Oracle Grid Infrastructure for a standalone server, also known as Oracle Restart, provides system support for a single-instance Oracle Database. Oracle ASM is a volume manager and a file system for Oracle database files that supports single-instance Oracle Database and Oracle Real Application Clusters (Oracle RAC) configurations. Oracle Automatic Storage Management also supports a general purpose file system for your application needs, including Oracle Database binaries. Oracle Automatic Storage Management is Oracle's recommended storage management solution. It provides an alternative to conventional volume managers and file systems.

### Note:

- If you want to use Oracle ASM or Oracle Restart, then you must install Oracle Grid Infrastructure for a standalone server before you install and create the database. Otherwise, you must manually register the database with Oracle Restart.
- You can neither install Oracle Restart on an Oracle Grid Infrastructure cluster member node, nor add an Oracle Restart server to an Oracle Grid Infrastructure cluster member node. Oracle Restart supports single-instance databases on one server, while Oracle Grid Infrastructure for a Cluster supports single-instance or Oracle RAC databases on a cluster.

- [Configuring Storage for Oracle Automatic Storage Management](#)  
Identify storage requirements and Oracle ASM disk group options.
- [Configuring Disk Devices for Oracle ASM on IBM AIX](#)  
Complete these tasks to configure disk devices for use with Oracle Automatic Storage Management (Oracle ASM).

- [Creating DAS or SAN Disk Partitions for Oracle Automatic Storage Management](#)  
You can use direct-attached storage (DAS) and storage area network (SAN) disks with Oracle ASM.
- [Creating Directories for Oracle Database Files](#)  
You can store Oracle Database and recovery files on a separate file system from the configuration files.
- [Creating Files on a NAS Device for Use with Oracle Automatic Storage Management](#)  
If you have a certified NAS storage device, then you can create zero-padded files in an NFS mounted directory and use those files as disk devices in an Oracle ASM disk group.

## Configuring Storage for Oracle Automatic Storage Management

Identify storage requirements and Oracle ASM disk group options.

- [Identifying Storage Requirements for Oracle Automatic Storage Management](#)  
To identify the storage requirements for using Oracle ASM, you must determine the number of devices and the amount of free disk space that you require.
- [Oracle ASM Disk Space Requirements](#)  
Determine the total amount of Oracle Automatic Storage Management (Oracle ASM) disk space that you require for the database files and recovery files.
- [ASM Disk Group Options for Installation](#)  
Plan how you want to configure Oracle ASM disk groups for deployment.
- [Using an Existing Oracle ASM Disk Group](#)  
Use Oracle Enterprise Manager Cloud Control or the Oracle ASM command line tool (`asmcmd`) to identify existing disk groups, and to determine if sufficient space is available in the disk group.

### Related Topics

- [Oracle Automatic Storage Management Administrator's Guide](#)

## Identifying Storage Requirements for Oracle Automatic Storage Management

To identify the storage requirements for using Oracle ASM, you must determine the number of devices and the amount of free disk space that you require.

To complete this task, perform the following steps:

1. Determine whether you want to use Oracle ASM for Oracle Database files, recovery files, or both. Oracle Database files include data files, control files, redo log files, the server parameter file, and the password file.

During the database installation, you have the option to select either a file system or Oracle ASM as the storage mechanism for Oracle Database files. Similarly, you also have the option to select either a file system or Oracle ASM as the storage mechanism for your recovery files.



 **Note:**

You do not have to use the same storage mechanism for both Oracle Database files and recovery files. You can use a file system for one file type and Oracle ASM for the other.

If you select Oracle ASM as your storage option for Oracle Database files, then depending on your choice in the Specify Recovery Options screen, you have the following recovery options:

- If you select the Oracle ASM option for your recovery files, then Oracle Universal Installer provides you with only the option to use the same disk group for both Oracle Database files and recovery files.
  - If you decide not to enable recovery during the database installation, then, after the database installation, you can modify the `DB_RECOVERY_FILE_DEST` parameter to enable the fast recovery area.
2. Choose the Oracle ASM redundancy level to use for each Oracle ASM disk group that you create.

The redundancy level that you choose for the Oracle ASM disk group determines how Oracle ASM mirrors files in the disk group and determines the number of disks and amount of disk space that you require, as follows:

- **External redundancy**

This option does not allow Oracle ASM to mirror the contents of the disk group. Oracle recommends that you select this redundancy level either when the disk group contains devices, such as RAID devices, that provide their own data protection or when the database does not require uninterrupted access to data.

- **Normal redundancy**

To optimize performance and reliability in a normal redundancy disk group, Oracle ASM uses two-way mirroring for data files and three-way mirroring for control files, by default. In addition, you can choose the mirroring characteristics for individual files in a disk group.

A normal redundancy disk group requires a minimum of two failure groups (or two disk devices) if you are using two-way mirroring. The effective disk space in a normal redundancy disk group is half the sum of the disk space of all of its devices.

For most installations, Oracle recommends that you use normal redundancy disk groups. On Oracle Exadata, Oracle recommends that you use high redundancy disk groups for added protection against failure.

- **High redundancy**

The contents of the disk group are three-way mirrored by default. To create a disk group with high redundancy, you must specify at least three failure groups (a minimum of three devices).

Although high-redundancy disk groups provide a high level of data protection, you must consider the higher cost of additional storage devices before deciding to use this redundancy level.

- **Flex redundancy**

A flex redundancy disk group is a new disk group type with features such as flexible file redundancy, mirror splitting, and redundancy change. A flex disk group can

consolidate files with different redundancy requirements into a single disk group. It also provides the capability for databases to change the redundancy of its files.

For database data, you can choose no mirroring (unprotected), two-way mirroring (mirrored), or three-way mirroring (high). A flex redundancy disk group requires a minimum of three disk devices (or three failure groups).

- **Extended redundancy**

Extended redundancy disk group has features similar to the flex redundancy disk group. Extended redundancy is available when you configure an Oracle Extended Cluster. Extended redundancy extends Oracle ASM data protection to cover failure of sites by placing enough copies of data in different failure groups of each site.

3. Determine the total amount of disk space that you require for the database files and recovery files.

If an Oracle ASM instance is running on the system, then you can use an existing disk group to meet these storage requirements. If necessary, you can add disks to an existing disk group during the database installation.

See, "Oracle ASM Disk Space Requirements" in *Oracle Database Installation Guide* for the Oracle ASM disk space requirements.

 **Note:**

- The disk devices must be owned by the user performing the grid installation. Check with your system administrator to determine if the disks used by Oracle ASM are mirrored at the storage level. If so, select External for the redundancy. If the disks are not mirrored at the storage level, then select Normal for the redundancy.
- Every Oracle ASM disk is divided into allocation units (AU). An allocation unit is the fundamental unit of allocation within a disk group. You can select the AU Size value from 1, 2, 4, 8, 16, 32 or 64 MB, depending on the specific disk group compatibility level. The default value is 4 MB for flex disk group and 1 MB for all other disk group types. On engineered systems, the default value is 4 MB.

4. Optionally, identify failure groups for the Oracle ASM disk group devices.

If you intend to use a normal, high or flex redundancy disk group, then you can further protect your database against hardware failure by associating a set of disk devices in a custom failure group. By default, each device comprises its own failure group. However, if two disk devices in a normal redundancy disk group are attached to the same Host Bus Adapter (HBA), then the disk group becomes unavailable if the controller fails. The controller in this example is a single point of failure.

To protect against failures of this type, use two HBAs, each with two disks, and define a failure group for the disks attached to each controller. This configuration enables the disk group to tolerate the failure of one HBA.

Consider the following guidelines while defining custom failure groups:

- You can specify custom failure groups in the **Create ASM Disk Group** screen during an Oracle Grid Infrastructure installation.
- You can also define custom failure groups after installation, using the GUI tool ASMCA, the command line tool `asmcmd`, or SQL commands.

- If you define custom failure groups, then for failure groups containing database files only, you must specify a minimum of two failure groups for normal redundancy disk groups and three failure groups for high redundancy disk groups.
5. If you are sure that a suitable disk group does not exist on the system, then install or identify appropriate disk devices to add to a new disk group.

Use the following guidelines when identifying appropriate disk devices:

- The disk devices must be owned by the user performing the Oracle Grid Infrastructure installation.
- All the devices in an Oracle ASM disk group must be the same size and have the same performance characteristics.
- Do not specify multiple partitions on a single physical disk as a disk group device. Oracle ASM expects each disk group device to be on a separate physical disk.
- Although you can specify a logical volume as a device in an Oracle ASM disk group, Oracle does not recommend their use because it adds a layer of complexity that is unnecessary with Oracle ASM. Oracle recommends that if you choose to use a logical volume manager, then use the logical volume manager to represent a single logical unit number (LUN) without striping or mirroring, so that you can minimize the effect on storage performance of the additional storage layer.

#### Related Topics

- [Oracle ASM Disk Space Requirements](#)  
Determine the total amount of Oracle Automatic Storage Management (Oracle ASM) disk space that you require for the database files and recovery files.
- *Oracle Automatic Storage Management Administrator's Guide*

## Oracle ASM Disk Space Requirements

Determine the total amount of Oracle Automatic Storage Management (Oracle ASM) disk space that you require for the database files and recovery files.

**Table 8-1 Oracle ASM Disk Number and Minimum Space Requirements for an Oracle database (non-CDB)**

Redundancy Level	Minimum Number of Disks	Data Files	Recovery Files	Both File Types
External	1	2.5 GB	7.5 GB	10 GB
Normal or Flex with two-way mirroring	2	5.2 GB	15.6 GB	20.8 GB
High or Flex with three-way mirroring	3	7.6 GB	22.8 GB	30.4 GB

**Table 8-2 Oracle ASM Disk Number and Minimum Space Requirements for a multitenant container database (CDB) with one pluggable database (PDB)**

Redundancy Level	Minimum Number of Disks	Data Files	Recovery Files	Both File Types
External	1	4 GB	12 GB	16 GB
Normal or Flex with two-way mirroring	2	8 GB	24 GB	32 GB

**Table 8-2 (Cont.) Oracle ASM Disk Number and Minimum Space Requirements for a multitenant container database (CDB) with one pluggable database (PDB)**

Redundancy Level	Minimum Number of Disks	Data Files	Recovery Files	Both File Types
High or Flex with three-way mirroring	3	12 GB	36 GB	48 GB

 **Note:**

- If an Oracle ASM instance is running on the system, then you can use an existing disk group to meet these storage requirements. If necessary, you can add disks to an existing disk group during the database installation.
- The disk devices must be owned by the user performing the grid installation.  
Check with your system administrator to determine if the disks used by Oracle ASM are mirrored at the storage level. If so, select External for the redundancy. If the disks are not mirrored at the storage level, then select Normal for the redundancy.
- Every Oracle ASM disk is divided into allocation units (AU). An allocation unit is the fundamental unit of allocation within a disk group. You can select the AU Size value from 1, 2, 4, 8, 16, 32 or 64 MB, depending on the specific disk group compatibility level. The default value is 4 MB for flex disk group and 1 MB for all other disk group types. On engineered systems, the default value is 4 MB.

## ASM Disk Group Options for Installation

Plan how you want to configure Oracle ASM disk groups for deployment.

During Oracle Grid Infrastructure installation, you can create one Oracle ASM disk group. After the Oracle Grid Infrastructure installation, you can create additional disk groups using Oracle Automatic Storage Management Configuration Assistant (Oracle ASMCA), SQL\*Plus, or Automatic Storage Management Command-Line Utility (ASMCMD).

### Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*

## Using an Existing Oracle ASM Disk Group

Use Oracle Enterprise Manager Cloud Control or the Oracle ASM command line tool (`asmcmd`) to identify existing disk groups, and to determine if sufficient space is available in the disk group.

1. Connect to the Oracle ASM instance and start the instance if necessary:

```
$ $ORACLE_HOME/bin/asmcmd
ASMCMD> startup
```

2. Enter one of the following commands to view the existing disk groups, their redundancy level, and the amount of free disk space in each one:

```
ASMCMD> lsdg
```

or

```
$ORACLE_HOME/bin/asmcmd -p lsdg
```

The `lsdg` command lists information about mounted disk groups only.

3. From the output, identify a disk group with the appropriate redundancy level and note the free space that it contains.
4. If necessary, install or identify the additional disk devices required to meet the storage requirements for your installation.

 **Note:**

If you are adding devices to an existing disk group, then Oracle recommends that you use devices that have the same size and performance characteristics as the existing devices in that disk group.

## Configuring Disk Devices for Oracle ASM on IBM AIX

Complete these tasks to configure disk devices for use with Oracle Automatic Storage Management (Oracle ASM).

1. If necessary, install the disks that you intend to use for the disk group and restart the system.
2. To ensure that the disks are available, enter the following command:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdisk0 Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L      SSA Logical Disk Drive
```

3. If a disk is not listed as available, then configure the new disks:

```
# /usr/sbin/cfgmgr
```

4. Enter the following command on any node to identify the device names for the physical disks that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk that is not configured in a volume group:

```
hdisk2      0000078752249812  None
```

In this example, `hdisk2` is the device name of the disk and `0000078752249812` is the physical volume ID (PVID). The disks that you want to use may have a PVID, but they must not belong to a volume group.

5. Enter commands similar to the following to clear the PVID from each disk device that you want to use:

```
# /usr/sbin/chdev -l hdiskn -a pv=clear
```

6. Enter commands similar to the following to change the owner, group, and permissions on the character file for each disk that you want to add to the disk group:

```
# chown -R grid:asmadmin /dev/rhdiskn  
# chmod 660 /dev/rhdiskn
```

 **Note:**

If you are using a multi-pathing disk driver with Automatic Storage Management, then ensure that you set the permissions only on the correct logical device name for the disk.

## Creating DAS or SAN Disk Partitions for Oracle Automatic Storage Management

You can use direct-attached storage (DAS) and storage area network (SAN) disks with Oracle ASM.

To use a DAS or SAN disk in Oracle ASM, Oracle recommends that the disk have a partition table. Oracle recommends creating exactly one partition for each disk.

## Creating Directories for Oracle Database Files

You can store Oracle Database and recovery files on a separate file system from the configuration files.

Perform this procedure to place the Oracle Database or recovery files on a separate file system from the Oracle base directory:

1. Use the following command to determine the free disk space on each mounted file system:

```
# df -h
```

2. Identify the file systems to use, from the display:

Option	Description
Database Files	Select one of the following: <ul style="list-style-type: none"> <li>• A single file system with at least 1.5 GB of free disk space</li> <li>• Two or more file systems with at least 3.5 GB of free disk space in total</li> </ul>
Recovery Files	Choose a file system with at least 2 GB of free disk space

If you are using the same file system for multiple file types, then add the disk space requirements for each type to determine the total disk space requirement.

- Note the names of the mount point directories for the file systems that you identified.
- If the user performing installation has permissions to create directories on the disks where you plan to install Oracle Database, then Oracle DBCA creates the Oracle Database file directory, and the Recovery file directory. If the user performing installation does not have write access, then you must create these directories manually.

For example, given the user `oracle` and Oracle Inventory Group `oinstall`, and using the paths `/u03/oradata/wrk_area` for Oracle Database files, and `/u01/oradata/rcv_area` for the recovery area, these commands create the recommended subdirectories in each of the mount point directories and set the appropriate owner, group, and permissions on them:

- Database file directory:

```
# mkdir -p /u01/oradata/
# chown oracle:oinstall /u01/oradata/
# chmod 775 /u01/oradata
```

The default location for the database file directory is `$ORACLE_BASE/oradata`.

- Recovery file directory (fast recovery area):

```
# mkdir -p /u01/oradata/rcv_area
# chown oracle:oinstall /u01/oradata/rcv_area
# chmod 775 /u01/oradata/rcv_area
```

The default fast recovery area is `$ORACLE_BASE/fast_recovery_area`.

Oracle recommends that you keep the fast recovery area on a separate physical disk than that of the database file directory. This method enables you to use the fast recovery area to retrieve data if the disk containing `oradata` is unusable for any reason.

## Creating Files on a NAS Device for Use with Oracle Automatic Storage Management

If you have a certified NAS storage device, then you can create zero-padded files in an NFS mounted directory and use those files as disk devices in an Oracle ASM disk group.

Ensure that you specify the ASM discovery path for Oracle ASM disks.

During installation of Oracle Grid Infrastructure, Oracle Universal Installer (OUI) can create files in the NFS mounted directory you specify. The following procedure explains how to

manually create files in an NFS mounted directory to use as disk devices in an Oracle ASM disk group:

1. If necessary, create an exported directory for the disk group files on the NAS device.
2. Switch user to `root`.
3. Create a mount point directory on the local system.

For example:

```
# mkdir -p /mnt/oracleasm
```

4. To ensure that the NFS file system is mounted when the system restarts, add an entry for the file system in the mount file `/etc/fstab`.
5. Enter a command similar to the following to mount the NFS on the local system:

```
# mount /mnt/oracleasm
```

6. Choose a name for the disk group to create, and create a directory for the files on the NFS file system, using the disk group name as the directory name.

For example, if you want to set up a disk group for a sales database:

```
# mkdir /mnt/oracleasm/sales1
```

7. Use commands similar to the following to create the required number of zero-padded files in this directory:

```
# dd if=/dev/zero  
of=/mnt/oracleasm/sales1/disk1 bs=1024k  
count=1000
```

This example creates 1 GB files on the NFS file system. You must create one, two, or three files respectively to create an external, normal, or high redundancy disk group.

 **Note:**

Creating multiple zero-padded files on the same NAS device does not guard against NAS failure. Instead, create one file for each NAS device and mirror them using the Oracle ASM technology.

8. Enter commands similar to the following to change the owner, group, and permissions on the directory and files that you created:

```
# chown -R grid:asmadmin /mnt/oracleasm  
# chmod -R 660 /mnt/oracleasm
```

In this example, the installation owner is `grid` and the OSASM group is `asmadmin`.

9. During Oracle Database installations, edit the Oracle ASM disk discovery string to specify a regular expression that matches the file names you created.



For example:

```
/mnt/oracleasm/sales1/
```

#### **Related Topics**

- [My Oracle Support Note 359515.1](#)

# 9

## Installing and Configuring Oracle Grid Infrastructure for a Standalone Server

Oracle Grid Infrastructure for a standalone server includes Oracle Restart and Oracle Automatic Storage Management.

If you install Oracle Grid Infrastructure for a standalone server and then create your database, then the database is automatically added to the Oracle Restart configuration. Oracle Restart automatically restarts the database when required.

If you install Oracle Grid Infrastructure for a standalone server on a host computer on which a database already exists, then you must manually add the database, the listener, the Oracle ASM instance, and other components to the Oracle Restart configuration before you are able to configure automatic database restarts.



### Note:

Oracle Grid Infrastructure for a standalone server can support multiple single-instance databases on a single host computer.

- [About Image-Based Oracle Grid Infrastructure Installation](#)  
Installation and configuration of Oracle Grid Infrastructure software is simplified with image-based installation.
- [Setup Wizard Installation Options for Creating Images](#)  
Before you start the setup wizards for your Oracle Database or Oracle Grid Infrastructure installation, decide if you want to use any of the available image-creation options.
- [Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation](#)  
Complete these steps to Install Oracle Grid Infrastructure for a standalone server and then create a database that is managed by Oracle Restart.
- [Installing Oracle Grid Infrastructure for a Standalone Server for an Existing Database](#)  
Follow the high-level instructions in this section to install Oracle Grid Infrastructure for a standalone server and configure it for an existing Oracle Database.
- [Installing Oracle Grid Infrastructure for a Standalone Server Using a Software-Only Installation](#)  
A software-only installation only installs the Oracle Grid Infrastructure for a standalone server binaries at the specified location. You must complete a few manual configuration steps to enable Oracle Restart after you install the software.
- [Testing the Oracle Automatic Storage Management Installation](#)  
After installing Oracle Grid Infrastructure for a single instance, use the ASMCMD command-line utility to test the Oracle ASM installation.
- [Relinking Oracle Restart and Oracle ASM Binaries](#)  
Relink the Oracle Restart and Oracle ASM binaries every time you apply an operating system patch or after an operating system upgrade.

- [Configuring Oracle ASM Disk Groups Manually using Oracle ASMCA](#)  
After installing Oracle Grid Infrastructure for a standalone server, you can also use Oracle ASMCA to create and configure disk groups, Oracle ADVM, and Oracle ACFS.
- [Enabling Oracle ACFS on Oracle Restart Configurations](#)  
You must enable root access to use Oracle ACFS.
- [Applying Patches During an Oracle Grid Infrastructure Installation or Upgrade](#)  
Starting with Oracle Grid Infrastructure 18c, you can download and apply Release Updates (RUs) and one-off patches during an Oracle Grid Infrastructure installation or upgrade.

## About Image-Based Oracle Grid Infrastructure Installation

Installation and configuration of Oracle Grid Infrastructure software is simplified with image-based installation.

To install Oracle Grid Infrastructure, create the new Grid home with the necessary user group permissions, and then extract the image file into the newly-created Grid home, and run the setup wizard to register the Oracle Grid Infrastructure product.

Using image-based installation, you can do the following:

- Configure Oracle Grid Infrastructure for a new cluster.
- Configure Oracle Grid Infrastructure for a standalone server (Oracle Restart).
- Upgrade Oracle Grid Infrastructure.
- Setup software only.
- Add or remove nodes from your existing cluster, if the Oracle Grid Infrastructure software is already installed or configured.

This installation feature streamlines the installation process and supports automation of large-scale custom deployments. You can also use this installation method for deployment of customized images, after you patch the base-release software with the necessary Release Updates (RUs) or Release Update Revisions (RURs).

### Note:

You must extract the image software into the directory where you want your Grid home to be located, and then run the `ORACLE_HOME\gridSetup.sh` script to start the Oracle Grid Infrastructure Setup Wizard. Ensure that the Grid home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations.

## Setup Wizard Installation Options for Creating Images

Before you start the setup wizards for your Oracle Database or Oracle Grid Infrastructure installation, decide if you want to use any of the available image-creation options.

In image-based installations, you can start your Oracle Database installation or Oracle Grid Infrastructure installations by running the setup wizards `runInstaller` and `gridSetup.sh` respectively. Both these wizards come with the following image-creation options.

**Table 9-1 Image-Creation Options for Setup Wizard**

Option	Description
-createGoldImage	Creates a gold image from the current Oracle home.
-destinationLocation	Specify the complete path, or location, where the gold image will be created.
-exclFiles	Specify the complete paths to the files to be excluded from the newly created gold image.
-help	Displays help for all the available options.

For example:

```
./runInstaller -createGoldImage -destinationLocation /tmp/my_db_images
```

```
./gridSetup.sh -createGoldImage -destinationLocation /tmp/my_grid_images
```

Where:

/tmp/my\_db\_images is a temporary file location where the image zip file is created.

/tmp/my\_grid\_images is a temporary file location where the image zip file is created.

/u01/app/oracle/product/19.0.0/dbhome\_1/relnotes is the file to be excluded in the newly created gold image.

## Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation

Complete these steps to Install Oracle Grid Infrastructure for a standalone server and then create a database that is managed by Oracle Restart.

Install Oracle Grid Infrastructure for a standalone server, which installs Oracle Restart and Oracle ASM, and creates one disk group.

You should have your network information, storage information, and operating system users and groups available to you before you start the installation. You should also be prepared to run root scripts or provide information to automate root scripts.

1. Log in as the Oracle Restart software owner user (oracle).
2. Download the Oracle Grid Infrastructure for a standalone server installation image files, create the Grid home directory, and extract the image files in this Grid home directory.

For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/grid
$ chgrp oinstall /u01/app/oracle/product/19.0.0/grid
$ cd /u01/app/oracle/product/19.0.0/grid
$ unzip -q /tmp/grid.zip
```

 **Note:**

Ensure that the Grid home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations. Also, unzip the installation image files only in this Grid home directory that you created.

3. Run `gridSetup.sh` to start the Oracle Grid Infrastructure setup wizard:

```
$ Grid_home/gridSetup.sh
```

 **Note:**

You can use the `gridSetup.sh` command with the `-applyRU` and `-applyOneOffs` options to install Release Updates (RUs) and one-off patches during an Oracle Grid Infrastructure installation or upgrade.

4. In the Select Configuration Option screen, select the **Configure Oracle Grid Infrastructure for a Standalone Server (Oracle Restart)** option to install and configure Oracle Restart and Oracle ASM. Click **Next**.
5. During installation, disk paths mounted on Oracle ASM with the string `AFD:*` are listed as default database storage candidate disks.
6. Configure Oracle ASM as needed with additional disk groups.
  - The default Disk Group Name is DATA. You can enter a new name for the disk group, or use the default name.
  - Any additional disk devices that you create must be owned by the user performing the grid installation.
7. Respond to the configuration prompts as needed to configure Oracle Grid Infrastructure. Click **Help** for information.
8. Provide information to automate root scripts, or run scripts as `root` when prompted by OUI. If you configure automation for running root scripts, and a root script fails, then you can fix the problem manually, and click **Retry** to run the root script again.
9. Start the Oracle Database installation, and select Oracle ASM disk groups for Oracle Database files storage. For assistance during installation, click **Help** on the Oracle Universal Installer page where you need more information.

**Related Topics**

- [Optimal Flexible Architecture File Path Examples](#)  
Review examples of hierarchical file mappings of an Optimal Flexible Architecture-compliant installation.

## Installing Oracle Grid Infrastructure for a Standalone Server for an Existing Database

Follow the high-level instructions in this section to install Oracle Grid Infrastructure for a standalone server and configure it for an existing Oracle Database.

Oracle Restart can manage resources from the same release and releases up to one version lower than Oracle Restart. For instance, you can install Oracle Grid Infrastructure for a standalone server 19c (Oracle Restart) to provide services for Oracle Database 19c and Oracle Database 18c. Earlier Oracle Database releases can coexist on the same server without being managed by Oracle Restart.

To install Oracle Grid Infrastructure for a standalone server for a database that is already installed:

1. Log in as the Oracle Database software owner user.
2. Set the ORACLE\_HOME and ORACLE\_SID environment variables.

Bourne, Bash or Korn shell:

```
$ ORACLE_SID=orcl
$ export ORACLE_SID
$ ORACLE_HOME=/u01/app/oracle/product/19.0.0/dbhome_1
$ export ORACLE_HOME
```

C shell:

```
% setenv ORACLE_SID orcl
% setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/dbhome_1
```

3. Go to the Oracle home and stop any existing database listeners.

```
$ $ORACLE_HOME/lsnrctl stop listener_name
```

### Note:

If this command throws an error, reload the listener using `lsnrctl reload LISTENER`

4. On the same host computer as the database, install Oracle Grid Infrastructure for a standalone server, and select **Configure Oracle Grid Infrastructure for a Standalone Server (Oracle Restart)** as the installation option. See, “Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation” in *Oracle Database Installation Guide*.

The Oracle Grid Infrastructure for a standalone server components are installed in an Oracle Grid Infrastructure Oracle home (Grid home), which is in a different location from existing Oracle Database homes.

5. If you have an existing Oracle Database, then register it for High Availability with Oracle Restart using the `srvctl` command:

```
$ cd $ORACLE_HOME/bin
$ srvctl add database -db dbname -o oracle_home_path
```

#### Related Topics

- [Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation](#)  
Complete these steps to Install Oracle Grid Infrastructure for a standalone server and then create a database that is managed by Oracle Restart.
- *Oracle Database Administrator's Guide*

## Installing Oracle Grid Infrastructure for a Standalone Server Using a Software-Only Installation

A software-only installation only installs the Oracle Grid Infrastructure for a standalone server binaries at the specified location. You must complete a few manual configuration steps to enable Oracle Restart after you install the software.

- [About Oracle Grid Infrastructure Software-Only Installations](#)  
Manually installing and configuring the software binaries for Oracle Grid Infrastructure.
- [Installing Software Binaries for Oracle Grid Infrastructure for a Standalone Server](#)  
Use this procedure to do a software-only installation of Oracle Grid Infrastructure for a standalone server.
- [Configuring Software Binaries for Oracle Grid Infrastructure for a Standalone Server](#)  
Use these steps to configure and activate a software-only Oracle Grid Infrastructure for a standalone server installation for Oracle Restart.

### About Oracle Grid Infrastructure Software-Only Installations

Manually installing and configuring the software binaries for Oracle Grid Infrastructure.

Oracle recommends that only advanced users perform software-only installations, because this installation method provides no validation of the installation, and this installation option requires manual postinstallation steps to enable the Oracle Grid Infrastructure for a standalone server software.

Performing a software-only installation requires the following steps:

1. Installing the software binaries.
2. Configuring the software binaries.

### Installing Software Binaries for Oracle Grid Infrastructure for a Standalone Server

Use this procedure to do a software-only installation of Oracle Grid Infrastructure for a standalone server.

1. Log in as the Oracle Restart software owner user (`oracle`).

2. Download the Oracle Grid Infrastructure for a standalone server installation image files, create the Grid home directory, and extract the image files in this Grid home directory.

For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/grid
$ chown oracle:oinstall /u01/app/oracle/product/19.0.0/grid
$ cd /u01/app/oracle/product/19.0.0/grid
$ unzip -q /tmp/grid_home.zip
```

 **Note:**

Ensure that the Grid home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations. Also, unzip the installation image files only in this Grid home directory that you created.

3. Ensure that you complete all the storage and server preinstallation requirements. Verify that your server meets the installation requirements using the following command:

```
$ cd /u01/app/oracle/product/19.0.0/grid
$ runcluvfy.sh stage -pre hacfg
```

4. Run `gridSetup.sh` to start the Oracle Grid Infrastructure setup wizard:

```
$ Grid_home/gridSetup.sh
```

Where, *Grid\_home* is the Oracle Grid Infrastructure home directory.

 **Note:**

You must install Oracle Grid Infrastructure for a standalone server from the Oracle Grid Infrastructure media.

5. In the Select Configuration Option screen, select the **Set Up Software Only** option to perform a software-only installation of Oracle Grid Infrastructure for a standalone server. Click **Next**.
6. Respond to the prompts as needed to set up Oracle Grid Infrastructure. Click **Help** for information.
7. The Oracle Grid Infrastructure setup wizard prompts you to run the `root.sh` script and, if required, the `orainstRoot.sh` script.
8. The `root.sh` script output provides information about how to proceed, depending on the configuration you plan to complete in this installation. Note this information.



## Configuring Software Binaries for Oracle Grid Infrastructure for a Standalone Server

Use these steps to configure and activate a software-only Oracle Grid Infrastructure for a standalone server installation for Oracle Restart.

### Configuring With Oracle Automatic Storage Management

1. Install the software binaries. See, “Installing Software Binaries for Oracle Grid Infrastructure for a Standalone Server” in *Oracle Database Installation Guide*.
2. Run `gridSetup.sh` to start the Oracle Grid Infrastructure setup wizard.  
See, “Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation” in *Oracle Database Installation Guide*.

### Configuring Without Oracle Automatic Storage Management

1. Log in as `root` and run the `roothas.sh` script located in the `Grid_home` path, using the following syntax:

```
# cd Grid_home/crs/install
# ./roothas.sh
```

Where, `Grid_home` is the Oracle Grid Infrastructure home directory.

For example:

```
# cd /u01/app/oracle/product/19.0.0/grid/crs/install
# ./roothas.sh
```

2. Change directory to the path `Grid_home/oui/bin`.
3. Log in as the Oracle Restart software owner user and use the following command syntax, where `Grid_home` is the path of the Oracle Grid Infrastructure for a standalone server home.

```
$ ./runInstaller -updateNodeList ORACLE_HOME=Grid_home -defaultHomeName
CLUSTER_NODES= CRS=TRUE
```

For example:

```
$ ./runInstaller -updateNodeList ORACLE_HOME=/u01/app/oracle/product/
19.0.0/grid
-defaultHomeName CLUSTER_NODES= CRS=TRUE
```

4. Use the `SRVCTL` utility along with Oracle Network Configuration Assistant to add the listener to the Oracle Restart configuration.



#### Note:

This procedure does not work for Oracle Restart upgrades from previous releases.

### Related Topics

- [Installing Software Binaries for Oracle Grid Infrastructure for a Standalone Server](#)  
Use this procedure to do a software-only installation of Oracle Grid Infrastructure for a standalone server.
- [Installing Oracle Grid Infrastructure for a Standalone Server with a New Database Installation](#)  
Complete these steps to Install Oracle Grid Infrastructure for a standalone server and then create a database that is managed by Oracle Restart.

## Testing the Oracle Automatic Storage Management Installation

After installing Oracle Grid Infrastructure for a single instance, use the ASMCMD command-line utility to test the Oracle ASM installation.

1. Open a shell window, and temporarily set the ORACLE\_SID and ORACLE\_HOME environment variables to specify the appropriate values for the Oracle ASM instance to use.

For example, if the Oracle ASM SID is named +ASM and the Oracle home is located in the grid subdirectory of the ORACLE\_BASE directory, then enter the following commands to create the required settings:

Bourne, Bash or Korn shell:

```
$ ORACLE_SID=+ASM
$ export ORACLE_SID
$ ORACLE_HOME=/u01/app/oracle/product/19.0.0/grid
$ export ORACLE_HOME
```

C shell:

```
% setenv ORACLE_SID +ASM
% setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/grid
```

2. Use ASMCMD to list the disk groups for the Oracle ASM instance:

```
$ORACLE_HOME/bin/asmcmd lsdg
```

If the Oracle ASM instance is running, then ASMCMD connects by default as the SYS user with SYSASM privileges, and is available.

3. If the Oracle ASM instance is not running, then start the Oracle ASM instance using the following command:

```
$ORACLE_HOME/bin/srvctl start asm
```

### Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*

## Relinking Oracle Restart and Oracle ASM Binaries

Relink the Oracle Restart and Oracle ASM binaries every time you apply an operating system patch or after an operating system upgrade.

### Caution:

Before relinking executables, you must shut down all executables that run in the Oracle home directory that you are relinking. In addition, shut down applications linked with Oracle shared libraries.

1. Log in as `root` and unlock the grid home:

```
# cd Grid_home/crs/install
# roothas.sh -unlock
```

2. Log in as the `grid` user and relink the binaries:

```
$ export ORACLE_HOME=Grid_home
$ Grid_home/bin/relink
```

3. Log in as `root` again and perform the following steps:

```
# cd Grid_home/rdbms/install/
# ./rootadd_rdbms.sh
# cd Grid_home/crs/install
# roothas.sh -lock
```

## Configuring Oracle ASM Disk Groups Manually using Oracle ASMCA

After installing Oracle Grid Infrastructure for a standalone server, you can also use Oracle ASMCA to create and configure disk groups, Oracle ADVM, and Oracle ACFS.

During Oracle Grid Infrastructure for a standalone server installation, Oracle Automatic Storage Management Configuration Assistant (Oracle ASMCA) utility creates a new Oracle Automatic Storage Management instance if there is no Oracle ASM instance currently configured on the computer. After installation, you can create and configure additional disk groups, and you can configure Oracle ADVM and Oracle ACFS.

To create disk groups or manually configure Oracle ASM disks, start Oracle ASMCA, where `Grid_home` is the path to the Oracle Grid Infrastructure home:

```
$ cd Grid_home/bin
$ ./asmca
```

### Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*

## Enabling Oracle ACFS on Oracle Restart Configurations

You must enable root access to use Oracle ACFS.



### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

To enable root access, log in as `root`, navigate to the path `Grid_home/crs/install`, and run the script `roothas.sh -lockacfs`.

Where, `Grid_home` is the Oracle Grid Infrastructure home directory path.

For example:

```
# cd /u01/app/oracle/product/19.0.0/grid/crs/install
# roothas.sh -lockacfs
```



### Note:

Starting with Oracle Database 12c Release 1 (12.1.0.2), the `roothas.sh` script replaces the `roothas.pl` script in the Oracle Grid Infrastructure home.

## Applying Patches During an Oracle Grid Infrastructure Installation or Upgrade

Starting with Oracle Grid Infrastructure 18c, you can download and apply Release Updates (RUs) and one-off patches during an Oracle Grid Infrastructure installation or upgrade.

1. Download the patches you want to apply from My Oracle Support:

<https://support.oracle.com>

2. Select the **Patches and Updates** tab to locate the patch.

Oracle recommends that you select **Recommended Patch Advisor**, and enter the product group, release, and platform for your software.

3. Move the patches to an accessible directory like `/tmp`.
4. Change to the Oracle Grid Infrastructure home directory:

```
$ cd /u01/app/oracle/product/19.0.0/grid
```

5. Apply Release Updates (RUs) and any one-off patches during the installation or upgrade process:

```
$ ./gridSetup.sh -applyRU patch_directory_location -applyOneOffs
comma_seperated_list_of_patch_directory_locations
```

 **Note:**

You can apply RUs and one-off patches separately or together in the same command.

6. Complete the remaining steps in the Oracle Grid Infrastructure configuration wizard to complete the installation or upgrade.

**Related Topics**

- *Oracle Grid Infrastructure Upgrading Oracle Restart for Linux and Unix-Based Operating Systems*

# 10

## Installing Oracle Database

Oracle Database and Oracle Grid Infrastructure installation software is available as image-based zip files and can be installed using several options.

You can download Oracle Database software from the Oracle website or the Oracle Software Delivery Cloud portal. In most cases, you use the graphical user interface (GUI) provided by Oracle Universal Installer to install the software. However, you can also run silent mode installations, without using the GUI. You can also use Oracle Fleet Patching and Provisioning for Oracle Database and Oracle Grid Infrastructure (clusterware) deployments.

Oracle Database software may be available on installation media on-demand.

### Note:

To install Oracle Database files on Oracle Automatic Storage Management (Oracle ASM), you must first complete an Oracle Grid Infrastructure for a standalone server installation. Oracle Grid Infrastructure for a standalone server includes Oracle Restart and Oracle ASM.

To upgrade an existing Oracle ASM installation, upgrade Oracle ASM by running an Oracle Grid Infrastructure upgrade. If you do not have Oracle ASM installed and you want to use Oracle ASM as your storage option, then you must complete an Oracle Grid Infrastructure for a standalone server installation before you start your Oracle Database installation.

You cannot use Oracle Universal Installer from an earlier Oracle release to install components from this release.

- [About Image-Based Oracle Database Installation](#)  
Understand image-based installation to simplify installation and configuration of Oracle Database software.
- [About Deploying Oracle Database Using Oracle Fleet Patching and Provisioning](#)  
You can use Oracle Fleet Patching and Provisioning (Oracle FPP) to provision Oracle Database software.
- [Downloading Oracle Software](#)  
Select the method you want to use to download the software.
- [About Character Set Selection During Installation](#)  
Before you create the database, decide the character set that you want to use.
- [About Automatic Memory Management Installation Options](#)  
Decide if you want to configure Automatic Memory Management during installation.
- [Running the Installer in a Different Language](#)  
Describes how to run the installer in other languages.
- [Installing the Oracle Database Software](#)  
These topics explain how to run Oracle Universal Installer to perform most database installations.

- [Installing Standard Edition High Availability](#)  
Learn how to Install high availability on Oracle Database Standard Edition 2.

## About Image-Based Oracle Database Installation

Understand image-based installation to simplify installation and configuration of Oracle Database software.

To install Oracle Database, create the new Oracle home, extract the image file into the newly-created Oracle home, and run the setup wizard to register the Oracle Database product.

Using image-based installation, you can install and upgrade Oracle Database for single-instance and cluster configurations. If you install or clone an Oracle Database image, then all Oracle Database options such as Oracle OLAP (`olap`) and Oracle Real Application Testing (`rat`) are enabled by default.

This installation feature streamlines the installation process and supports automation of large-scale custom deployments. You can also use this installation method for deployment of customized images, after you patch the base-release software with the necessary Release Updates (Updates) or Monthly Recommended Patches (MRPs).



### Note:

You must extract the image software (`db_home.zip`) into the directory where you want your Oracle Database home to be located, and then run the Oracle Database Setup Wizard to start the Oracle Database installation and configuration. Oracle recommends that the Oracle home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations.

## About Deploying Oracle Database Using Oracle Fleet Patching and Provisioning

You can use Oracle Fleet Patching and Provisioning (Oracle FPP) to provision Oracle Database software.

Starting with Oracle Database 19c, Rapid Home Provisioning is renamed to Oracle Fleet Patching and Provisioning (Oracle FPP).

With Oracle Fleet Patching and Provisioning, you create, store, and manage templates of Oracle homes as images (called gold images) of Oracle software, such as databases, middleware, and applications. You can make a working copy of any gold image and then you can provision that working copy to any node in the data center or cloud computing environment.

You can use Oracle Fleet Patching and Provisioning to provision, patch, and upgrade single-instance databases running on Oracle Restart, on clusters, or on single, standalone nodes. These may be on nodes with or without Oracle Grid Infrastructure installed.



**Note:**

Oracle Fleet Patching and Provisioning is not supported on Microsoft Windows and HP-UX Itanium systems.

**Related Topics**

- *Oracle Fleet Patching and Provisioning Administrator's Guide*

## Downloading Oracle Software

Select the method you want to use to download the software.

You can download Oracle Database software from the Oracle website or the Oracle Software Delivery Cloud portal and extract them to the Oracle home. Ensure that you review and understand the terms of the license.

- [Downloading the Installation Archive Files from Oracle Website](#)  
Download installation archive files from the Oracle website.
- [Downloading the Software from Oracle Software Delivery Cloud Portal](#)  
You can download the software from Oracle Software Delivery Cloud.

## Downloading the Installation Archive Files from Oracle Website

Download installation archive files from the Oracle website.

1. Use any browser to access the software download page on the Oracle website:  
<http://www.oracle.com/technetwork/indexes/downloads/index.html>
2. Go to the download page for the product to install.
3. On the download page, identify the required disk space by adding the file sizes for each required file.  
The file sizes are listed next to the file names.
4. Select a file system with enough free space to store and expand the archive files.  
In most cases, the available disk space must be at least twice the size of all of the archive files.
5. On the file system, create a parent directory for each product (for example, OraDB19c) to hold the installation directories.
6. Download all of the installation archive files to the directory you created for the product.



**Note:**

For Oracle Database Client installations, there are two installation archive files available for download. The first file is the client installation binary and the second file is a client gold image file. Download the appropriate zip file based on the type of installation you want to perform.

7. Verify that the files you downloaded are the same size as the corresponding files on the Oracle website. Also verify the checksums are the same as noted on the Oracle website



using a command similar to the following, where *filename* is the name of the file you downloaded:

```
cksum filename.zip
```

8. Extract the files in each directory that you just created.

## Downloading the Software from Oracle Software Delivery Cloud Portal

You can download the software from Oracle Software Delivery Cloud.

1. Use a browser to access the Oracle Software Delivery Cloud portal:  
<https://edelivery.oracle.com/>
2. Click **Sign In** and enter your Oracle account username and password.
3. Type **Oracle Database** in the search bar. Click the **Add to Cart** button corresponding to the Oracle Database version that you want to download.
4. In the Checkout page, click **Checkout** and deselect any products that you do not want to download.
5. Select the operating system platform on which you want to install the software from the **Platform/Languages** column.
6. Click **Continue**.
7. Review the license agreement.
8. Select the **I reviewed and accept the Oracle License Agreement** checkbox. Click **Continue**.
9. Click **Download** to start downloading the software.
10. After you download the files, click **View Digest** to verify that the checksum matches the value listed on the download page.

## About Character Set Selection During Installation

Before you create the database, decide the character set that you want to use.

After a database is created, changing its character set is usually very expensive in terms of time and resources. Such operations may require converting all character data by exporting the whole database and importing it back. Therefore, it is important that you carefully select the database character set at installation time.

Oracle Database uses character sets for the following:

- Data stored in SQL character data types (CHAR, VARCHAR2, CLOB, and LONG).
- Identifiers such as table names, column names, and PL/SQL variables.
- Stored SQL and PL/SQL source code, including text literals embedded in this code.

Starting with Oracle Database 12c Release 2 (12.2), the default database character set of a database created from the General Purpose/Transaction Processing or the Data Warehousing template is Unicode AL32UTF8.

Unicode is the universal character set that supports most of the currently spoken languages of the world. It also supports many historical scripts (alphabets). Unicode is the native encoding

of many technologies, including Java, XML, XHTML, ECMAScript, and LDAP. Unicode is ideally suited for databases supporting the Internet and the global economy.

Because `AL32UTF8` is a multibyte character set, database operations on character data may be slightly slower when compared to single-byte database character sets, such as `WE8ISO8859P1` or `WE8MSWIN1252`. Storage space requirements for text in most languages that use characters outside of the ASCII repertoire are higher in `AL32UTF8` compared to legacy character sets supporting the language. English data may require more space only if stored in `CLOB` (character large object) columns. Storage for non-character data types, such as `NUMBER` or `DATE`, does not depend on a character set. The universality and flexibility of Unicode usually outweighs these additional costs.

Consider legacy character sets only when the database needs to support a single group of languages and the use of a legacy character set is critical for fulfilling compatibility, storage, or performance requirements. The database character set to be selected in this case is the character set of most clients connecting to this database.

The database character set of a multitenant container database (CDB) determines which databases can be plugged in later. Ensure that the character set you choose for the CDB is compatible with the database character sets of the databases to be plugged into this CDB. If you use Unicode `AL32UTF8` as your CDB character set, then you can plug in a pluggable database (PDB) in any database character set supported by Oracle Database (with the exception of EBCDIC-based character sets).



#### See Also:

*Oracle Database Globalization Support Guide* for more information about choosing a database character set for a multitenant container database (CDB)

## About Automatic Memory Management Installation Options

Decide if you want to configure Automatic Memory Management during installation.

During a **Typical** installation, you create your database with Oracle Database Configuration Assistant (DBCA), and automatic memory management is enabled. If you choose **Advanced** installation, then you can either specify memory allocation manually, or enable automatic memory management.

If the total physical memory of your database instance is greater than 4 GB, then you cannot select the Oracle Automatic Memory Management option during database installation and creation. Instead, use automatic shared memory management. Automatic shared memory management automatically distributes the available memory among the various components as required, allowing the system to maximize the use of all available SGA memory.

With automatic memory management, the Oracle Database instances automatically manage and tune memory for you. With automatic memory management, you choose a memory target, and the instance automatically distributes memory between the system global area (SGA) and the instance program global area (instance PGA). As memory requirements change, the instance dynamically redistributes memory between the SGA and instance PGA.

You can enable automatic memory management either during, or after the database installation. Enabling automatic memory management after installation involves a shutdown and restart of the database.

 **Note:**

By default, automatic memory management is disabled when you perform typical installation on a node that has more than 4 GB of RAM.

**Related Topics**

- *Oracle Database Administrator's Guide*

## Running the Installer in a Different Language

Describes how to run the installer in other languages.

Your operating system locale determines the language in which the database installer runs. You can run the installer in one of these languages:

- Brazilian Portuguese (pt\_BR)
- French (fr)
- German (de)
- Italian (it)
- Japanese (ja)
- Korean (ko)
- Simplified Chinese (zh\_CN)
- Spanish (es)
- Traditional Chinese (zh\_TW)

To run the database installer in a supported language, change the locale in which your operating system session is running before you start the installer.

If the selected language is not one of the supported languages, then the installer runs in English.

## Installing the Oracle Database Software

These topics explain how to run Oracle Universal Installer to perform most database installations.

 **Note:**

- If you plan to use Oracle Restart or Oracle ASM, then you must install Oracle Grid Infrastructure for a standalone server before you install and create the database. Otherwise, you must manually register the database with Oracle Restart.
- You can install Oracle Database by using the silent or response file installation method, without the GUI. This method is useful to perform multiple installations of Oracle Database.

- [Setup Wizard Installation Options for Creating Images](#)
- [Applying Patches During an Oracle Database Installation or Upgrade](#)  
Starting with Oracle Database 18c, you can download and apply Release Updates (RUs) during an Oracle Database installation or upgrade.
- [Running Oracle Database Setup Wizard to Install Oracle Database](#)  
Extract the database image files and use the `runInstaller` command to start the installation.

## Setup Wizard Installation Options for Creating Images

Before you start the setup wizards for your Oracle Database or Oracle Grid Infrastructure installation, decide if you want to use any of the available image-creation options.

In image-based installations, you can start your Oracle Database installation or Oracle Grid Infrastructure installations by running the setup wizards `runInstaller` and `gridSetup.sh` respectively. Both these wizards come with the following image-creation options.

**Table 10-1 Image-Creation Options for Setup Wizard**

Option	Description
<code>-createGoldImage</code>	Creates a gold image from the current Oracle home.
<code>-destinationLocation</code>	Specify the complete path, or location, where the gold image will be created.
<code>-exclFiles</code>	Specify the complete paths to the files to be excluded from the newly created gold image.
<code>-help</code>	Displays help for all the available options.

For example:

```
./runInstaller -createGoldImage -destinationLocation /tmp/my_db_images
```

```
./gridSetup.sh -createGoldImage -destinationLocation /tmp/my_grid_images
```

Where:

`/tmp/my_db_images` is a temporary file location where the image zip file is created.

`/tmp/my_grid_images` is a temporary file location where the image zip file is created.

`/u01/app/oracle/product/19.0.0/dbhome_1/relnotes` is the file to be excluded in the newly created gold image.

## Applying Patches During an Oracle Database Installation or Upgrade

Starting with Oracle Database 18c, you can download and apply Release Updates (RUs) during an Oracle Database installation or upgrade.

1. Download the patches you want to apply from My Oracle Support:  
<https://support.oracle.com>
2. Select the **Patches and Updates** tab to locate the patch.

Oracle recommends that you select **Recommended Patch Advisor**, and enter the product group, release, and platform for your software.

3. Move the patches to an accessible directory like `/tmp`.
4. Change to the Oracle Database home directory:

```
$ cd $ORACLE_HOME
```

5. Apply Release Updates (RUs) during the installation or upgrade process:

```
$ ./runInstaller -applyRU patch_directory_location
```

6. Complete the remaining steps in the Oracle Database configuration wizard to complete the installation or upgrade.

## Running Oracle Database Setup Wizard to Install Oracle Database

Extract the database image files and use the `runInstaller` command to start the installation.

Have all the information you need to provide regarding users groups, and storage paths before you start installation. Oracle recommends that you have your My Oracle Support credentials available during installation. You should also be prepared to run root scripts or provide information to automate root scripts.

1. Log in as the Oracle installation owner user account (`oracle`) that you want to own the software binaries.
2. If this is the first time you are installing Oracle software, then create the Oracle base and the Oracle inventory directories as per the Oracle Optimal Flexible Architecture (OFA) recommendations. Specify the correct owner, group, and permissions for these directories.

```
# mkdir -p /u01/app/oracle
# mkdir -p /u01/app/oraInventory
# chown -R oracle:oinstall /u01/app/oracle
# chown -R oracle:oinstall /u01/app/oraInventory
# chmod -R 775 /u01/app
```

3. Download the Oracle Database installation image files (`db_home.zip`) to a directory of your choice. For example, you can download the image files to the `/tmp` directory.
4. Create an OFA-compliant Oracle home directory and extract the image files that you have downloaded in to this Oracle home directory. For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/dbhome_1
$ cd /u01/app/oracle/product/19.0.0/dbhome_1
$ unzip -q /tmp/db_home.zip
```

 **Note:**

- Ensure that the Oracle home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations. Also, unzip the installation image files only in this Oracle home directory that you created.
- Oracle home or Oracle base cannot be `symlinks`, nor can any of their parent directories, all the way to up to the `root` directory.

5. From the Oracle home directory, run the `runInstaller` command to start the Oracle Database Setup Wizard.

```
$ cd /u01/app/oracle/product/19.0.0/dbhome_1
$ ./runInstaller
```

 **Note:**

- Run the `runInstaller` command from the Oracle home directory only. Do not use the `runInstaller` command that resides at `$ORACLE_HOME/oui/bin/`, or any other location, to install Oracle Database, Oracle Database Client, or Oracle Grid Infrastructure.
- Use the `runInstaller` command with the `-applyRU` option to install Release Updates (RUs) during an Oracle Database installation or upgrade.

6. In the Select Configuration Option screen, select **Create and configure a single instance database**.

7. Select your installation type.

Installation screens vary depending on the installation option you select. Respond to the configuration prompts as needed.

8. Provide information to automate root scripts, or run scripts as root when prompted by the setup wizard.

If you configure automation for running root scripts, and a root script fails, then you can fix the problem manually, and click **Retry** to run the root script again.

 **Note:**

Click **Help** if you have any questions about the information you are asked to submit during installation.

## Installing Standard Edition High Availability

Learn how to Install high availability on Oracle Database Standard Edition 2.

- [About Standard Edition High Availability](#)  
Starting with Oracle Database 19c, you can install Oracle Database Standard Edition 2 in high availability mode.
- [Requirements for Installing Standard Edition High Availability](#)  
Review these requirements before you install and deploy the Standard Edition High Availability feature on IBM AIX on POWER Systems (64-Bit).
- [Deploying Standard Edition High Availability](#)  
Learn the process and options to deploy high availability on Oracle Database Standard Edition 2.

## About Standard Edition High Availability

Starting with Oracle Database 19c, you can install Oracle Database Standard Edition 2 in high availability mode.



### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

Standard Edition High Availability provides cluster-based failover for single-instance Standard Edition Oracle Databases using Oracle Clusterware.

Oracle Standard Edition High Availability benefits from the cluster capabilities and storage solutions that are already part of Oracle Grid Infrastructure, such as Oracle Clusterware, Oracle Automatic Storage Management (Oracle ASM) and Oracle ASM Cluster File System (Oracle ACFS).

Using integrated, shared, and concurrently mounted storage, such as Oracle ASM and Oracle ACFS for database files as well as for unstructured data, enables Oracle Grid Infrastructure to restart an Oracle Database on a failover node much faster than any cluster solution that relies on failing over and remounting volumes and file systems.

Starting with Oracle Database 19c Release Update (19.7), Standard Edition High Availability is supported on Linux x86-64, Oracle Solaris on SPARC (64-bit), and Microsoft Windows.

Starting with Oracle Database 19c Release Update (19.13), Standard Edition High Availability is supported on IBM AIX on POWER Systems (64-bit) and HP-UX Itanium.



### Note:

This section is specific to Standard Edition High Availability, which provides cluster-based database failover for Standard Edition Oracle Databases 19c. For more information about high availability options for Oracle Database, see *Oracle Clusterware Administration and Deployment Guide*.

## Requirements for Installing Standard Edition High Availability

Review these requirements before you install and deploy the Standard Edition High Availability feature on IBM AIX on POWER Systems (64-Bit).

- You must configure Standard Edition High Availability using at least two nodes of a cluster running Oracle Grid Infrastructure 19.13 or later for Standalone Cluster.

- You must configure Standard Edition High Availability using Oracle Database home of version 19.13 or later.

 **Note:**

When updating your Oracle Database home using Release Update (RU) 19.13 or later, ensure that you apply the Oracle Clusterware (OCW) RU of the same version to the Oracle Database home.

- Ensure that all cluster nodes on which you plan to install Oracle Database have the same operating system users, groups, and resource limits for the database software owner.
- You must store the Oracle Database binaries only on local storage or Oracle Automatic Storage Management Cluster File System (Oracle ACFS).

 **Note:**

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

- You must store the Oracle Database data files only on Oracle ASM or Oracle ACFS.
- If you are using Oracle ACFS for storing data files, then you must register Oracle ACFS as a clusterware resource. The Oracle Database software owner user (`oracle`) must be the mount owner of the Oracle ACFS volume. When using an Oracle home on Oracle ACFS, Oracle recommends that you have Oracle base on the local file system.
- If you are using a local file system, then you must have the same single-instance Standard Edition 2 installation and updates on each node. You must also use the same Oracle base and Oracle home directory structure on each node.
- You must perform the same Oracle home operations on all the nodes.
- You must use an SPFILE for the database instance initialization parameters and a database password file stored for the database instance initialization parameters in Oracle ASM or Oracle ACFS. This approach ensures that the parameters are consistent across all nodes and the password file is available after a failover or a relocation.
- You must register the Standard Edition 2 single-instance database with SCAN listeners as remote listener and node listeners as local listener.

## Deploying Standard Edition High Availability

Learn the process and options to deploy high availability on Oracle Database Standard Edition 2.

After installing Oracle Clusterware, as described in *Oracle Grid Infrastructure Installation and Upgrade Guide* for your platform, install single instance Standard Edition 2 Oracle Database software on the cluster nodes on which you want to configure Standard Edition High Availability.

- [Installing Standard Edition High Availability Database Software on Local File System](#)  
You can install Oracle Database software binaries on a local file system to enable the Oracle Database Standard Edition high availability feature on IBM AIX on POWER Systems (64-bit).



- [Installing Standard Edition High Availability Database Software on Oracle ACFS](#)  
You can install Oracle Database software binaries on an Oracle ASM Cluster File System (Oracle ACFS) volume to enable the Oracle Database Standard Edition High Availability feature on IBM AIX on POWER Systems (64-bit).

#### Related Topics

- *Oracle Grid Infrastructure Installation and Upgrade Guide for IBM AIX on POWER Systems (64-Bit)*
- *Oracle Database Administrator's Guide*

## Installing Standard Edition High Availability Database Software on Local File System

You can install Oracle Database software binaries on a local file system to enable the Oracle Database Standard Edition high availability feature on IBM AIX on POWER Systems (64-bit).

Ensure that all the cluster nodes, on which you plan to configure Standard Edition High Availability, have the same operating system configuration, database users, database groups, resource limits, and SSH equivalence for the Oracle Database software owner user (`oracle`).

Before you start the installation, have all the information you need about users, groups, and storage paths. You should also be prepared to run root scripts or provide information to automate root scripts.

1. As the `root` user, log into the first cluster node on which you want to configure Standard Edition High Availability and create the Oracle base directory on the local file system. Follow the Oracle Optimal Flexible Architecture (OFA) recommendations and specify the correct owner, group, and permissions for this directory.

```
# mkdir -p /u01/app/oracle
# chown oracle:oinstall /u01/app/oracle
```

2. Log in to the first cluster node as the Oracle Database software owner user (`oracle`).
3. Download the Oracle Database 19c release 19.3 installation image file (`db_home.zip`) from Oracle Software Delivery Cloud website to a directory of your choice.

<https://edelivery.oracle.com/>

4. Download the Oracle Database Release Update 19.13 or later patch from My Oracle Support to a directory of your choice and unzip it.

<https://support.oracle.com/>

5. Create an OFA-compliant Oracle home directory on the local file system and extract the image files that you have downloaded in to this Oracle home directory. For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/dbhome_1
$ cd /u01/app/oracle/product/19.0.0/dbhome_1
$ unzip -q /tmp/db_home.zip
```

6. From the Oracle home directory, run the `runInstaller` command with the `-applyRU` flag to start the Oracle Database Setup Wizard and apply the Oracle Database Release Update 19.13 or later patch during installation.

```
$ ./runInstaller -applyRU patch_directory_location/patch_ID
```

 **Note:**

Run the `runInstaller` command from the Oracle home directory only. Do not use the `runInstaller` command that resides at `$ORACLE_HOME/oui/bin/`, or any other location, to install Oracle Database.

7. In the Select Configuration Option screen, select **Set Up Software Only**.
8. In the Select Database Installation Option screen, select **Single instance database installation**.
9. In the Select Database Edition screen, select **Standard Edition 2**.
10. Respond to the configuration prompts as needed.
11. Provide information to automate root scripts, or run scripts as root when prompted by the setup wizard.

If you configure automation for running root scripts, and a root script fails, then you can fix the problem manually, and click **Retry** to run the root script again.

 **Note:**

Click **Help** if you have any questions about the information you are asked to submit during installation.

12. Optional: As the `oracle` user, enable read-only Oracle home on the first cluster node.

```
$ $ORACLE_HOME/bin/roohctl -enable
```

13. As the `root` user, create the Oracle base directory on all of the other cluster nodes on which you want to configure Standard Edition High Availability.

```
# mkdir -p /u01/app/oracle
# chown oracle:oinstall /u01/app/oracle
```

14. As the `oracle` user, run the `addnode.sh` script from the first node to perform the following operations on the other nodes on which you want to configure Standard Edition High Availability:

- Copy the Oracle home directory from the first node to the other nodes.
- Setup Oracle base and Oracle inventory directories on the other nodes.

```
$ $ORACLE_HOME/addnode/addnode.sh -silent
CLUSTER_NEW_NODES=comma_separated_list_of_other_nodes
```

15. As the `root` user, run the `root.sh` script on all the other cluster nodes on which you are configuring Standard Edition High Availability.

```
# /u01/app/oracle/product/19.0.0/dbhome_1/root.sh
```

After the Oracle Database software installation is complete, use Oracle Database Configuration Assistant (Oracle DBCA), in either interactive or silent mode, to create a Standard Edition database on the first cluster node on which you installed the Oracle Database software.

For more information about the requirements for creating a database, and the procedure for enabling and configuring Standard Edition High Availability for Oracle Databases, refer to *Oracle Database Administrator's Guide*.

### Related Topics

- [Response Files](#)  
Review the following topics to install and configure Oracle Database, Oracle Grid Infrastructure, and other Oracle products using response files.
- *Oracle Grid Infrastructure Installation and Upgrade Guide for IBM AIX on POWER Systems (64-Bit)*
- *Creating a Database with Oracle DBCA*

## Installing Standard Edition High Availability Database Software on Oracle ACFS

You can install Oracle Database software binaries on an Oracle ASM Cluster File System (Oracle ACFS) volume to enable the Oracle Database Standard Edition High Availability feature on IBM AIX on POWER Systems (64-bit).

### Note:

The ACFS storage option on IBM AIX is deprecated in Oracle Database 19c.

To align the support for the IBM AIX platform, Oracle Automatic Storage Management Cluster File System (ACFS) on IBM AIX (called Oracle Advanced Cluster File System starting with Oracle Database 21c) is deprecated in Oracle Database 19c. For data or files currently stored on an ACFS file system that cannot be stored in the Oracle database, the IBM General Parallel File System (GPFS) can be used.

Ensure that all the cluster nodes, on which you plan to configure Standard Edition High Availability, have the same operating system configuration, database users, database groups, resource limits, and SSH equivalence for the Oracle Database software owner user (`oracle`) between the nodes.

Before you start the installation, have all the information you need about users groups, and storage paths. You should also be prepared to run root scripts or provide information to automate root scripts.

1. As the `root` user, register Oracle ACFS as an Oracle Clusterware resource specifying the Oracle Database software owner user (`oracle`) as the mount owner.

```
# Grid_home/bin/srvctl add filesystem -volume acfs_volume_name -diskgroup  
diskgroup_name -path mount_point -fstype ACFS -autostart ALWAYS -user  
oracle
```

### Note:

Mount Oracle ACFS to a mount point where you plan to create Oracle base and Oracle home directories for this installation. For example, `/u01/app/oracle`.

2. As the `oracle` user, mount the Oracle ACFS file system on all of the cluster nodes on which you want to configure Standard Edition High Availability.

```
$ Grid_home/bin/srvctl start filesystem -volume acfs_volume_name -  
diskgroup diskgroup_name
```

3. As the `root` user, create the Oracle base directory in an Oracle ACFS volume on the first cluster node on which you want to configure Standard Edition High Availability. Follow the Oracle Optimal Flexible Architecture (OFA) recommendations and specify the correct owner, group, and permissions for this directory.

```
# mkdir -p /u01/app/oracle  
# chown oracle:oinstall /u01/app/oracle
```

 **Note:**

If you have configured the Oracle ACFS file system with the `oracle` user as the mount owner and the `/u01/app/oracle` directory as the mount point, then this step is not required.

4. Log in to the first cluster node as the Oracle Database software owner user (`oracle`).
5. Download the Oracle Database 19c release 19.3 installation image file (`db_home.zip`) from Oracle Software Delivery Cloud website to a directory of your choice.

<https://edelivery.oracle.com/>

6. Download the Oracle Database Release Update 19.13 or later patch from My Oracle Support to a directory of your choice and unzip it.

<https://support.oracle.com/>

7. Create an OFA-compliant Oracle home directory in an Oracle ACFS volume and extract the image files that you have downloaded in to this Oracle home directory. For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/dbhome_1  
$ cd /u01/app/oracle/product/19.0.0/dbhome_1  
$ unzip -q /tmp/db_home.zip
```

8. From the Oracle home directory, run the `runInstaller` command with the `-applyRU` flag to start the Oracle Database Setup Wizard and apply the Oracle Database Release Update 19.13 or later patch during installation.

```
$ ./runInstaller -applyRU patch_directory_location/patch_ID
```

 **Note:**

Run the `runInstaller` command from the Oracle home directory only. Do not use the `runInstaller` command that resides at `$ORACLE_HOME/oui/bin/`, or any other location, to install Oracle Database.

9. In the Select Configuration Option screen, select **Set Up Software Only**.

10. In the Select Database Installation Option screen, select **Single instance database installation**.
11. In the Select Database Edition screen, select **Standard Edition 2**.
12. Respond to the configuration prompts as needed.
13. Provide information to automate root scripts, or run scripts as root when prompted by the setup wizard.

If you configure automation for running root scripts, and a root script fails, then you can fix the problem manually, and click **Retry** to run the root script again.

 **Note:**

Click **Help** if you have any questions about the information you are asked to submit during installation.

14. Optional: As the `oracle` user, enable read-only Oracle home on the first cluster node.

```
$ $ORACLE_HOME/bin/roohctl -enable
```

15. Attach the Oracle home on the first node to the other cluster nodes on which you want to configure Standard Edition High Availability.

```
$ $ORACLE_HOME/addnode/addnode.sh -silent  
CLUSTER_NEW_NODES=comma_separated_list_of_other_nodes
```

16. As the `root` user, run the `root.sh` script on all the other cluster nodes on which you are configuring Standard Edition High Availability.

```
# /u01/app/oracle/product/19.0.0/dbhome_1/root.sh
```

After the Oracle Database software installation is complete, use Oracle Database Configuration Assistant (Oracle DBCA), in either interactive or silent mode, to create a Standard Edition database on the first cluster node on which you installed the Oracle Database software.

For more information about the requirements for creating a database, and the procedure for enabling and configuring Standard Edition High Availability for Oracle Databases, refer to *Oracle Database Administrator's Guide*.

#### Related Topics

- *Oracle Grid Infrastructure Installation and Upgrade Guide for IBM AIX on POWER Systems (64-Bit)*
- *Configuring Oracle Automatic Storage Management Cluster File System*
- *Creating a Database with Oracle DBCA*

# Oracle Database Postinstallation Tasks

Complete configuration tasks after you install Oracle Database.

You are required to complete some configuration tasks after Oracle Database is installed. In addition, Oracle recommends that you complete additional tasks immediately after installation. You must also complete product-specific configuration tasks before you use those products.



## Note:

This chapter describes basic configuration only. Refer to product-specific administration and tuning guides for more detailed configuration and tuning information.

- [Required Postinstallation Tasks](#)  
Download and apply required patches for your software release after completing your initial installation.
- [Recommended Postinstallation Tasks](#)  
Oracle recommends that you complete these tasks after installation.
- [About Changes in Default SGA Permissions for Oracle Database](#)  
Starting with Oracle Database 12c Release 2 (12.2.0.1), by default, permissions to read and write to the System Global Area (SGA) are limited to the Oracle software installation owner.
- [Checking Installed Oracle Database Contents and Directory Location](#)  
Use these steps to check the contents and directory location of an Oracle Database installation:
- [Enabling and Disabling Oracle Database Options After Installation](#)  
The `chopt` tool changes your database options after installation.
- [Starting Oracle Enterprise Manager Database Express](#)  
Use these steps to log in to Oracle Enterprise Manager Database Express (EM Express).
- [Creating a Fast Recovery Area](#)  
During an Oracle Restart installation, you can create only one disk group. During an Oracle Clusterware installation, you can create multiple disk groups. If you plan to add an Oracle Database for a standalone server or an Oracle RAC database, then you should create the fast recovery area for database files.
- [Cloning an Oracle Database Home](#)  
Cloning an Oracle home involves creating a copy of the Oracle home and then configuring it for a new environment.

## Required Postinstallation Tasks

Download and apply required patches for your software release after completing your initial installation.

- [Downloading Release Update Patches](#)  
Download and install Release Updates (RU) and Monthly Recommended Patches (MRPs) patches for your Oracle software after you complete installation.
- [Unlocking and Resetting Oracle Database User Passwords](#)  
Passwords for all Oracle system administration accounts except SYS, SYSTEM, and DBSMP are revoked after installation. Before you use a locked account, you must unlock it and reset its password.

## Downloading Release Update Patches

Download and install Release Updates (RU) and Monthly Recommended Patches (MRPs) patches for your Oracle software after you complete installation.

Oracle provides quarterly updates in the form of Release Updates (RU) and Monthly Recommended Patches (MRPs). Oracle no longer releases patch sets. For more information, see My Oracle Support Note 2285040.1.

Check the My Oracle Support website for required updates for your installation.

1. Use a web browser to view the My Oracle Support website:

<https://support.oracle.com>

2. Log in to My Oracle Support website.

### Note:

If you are not a My Oracle Support registered user, then click **Register for My Oracle Support** and register.

3. On the main My Oracle Support page, click **Patches & Updates**.
4. In the **Patch Search** region, select **Product or Family (Advanced)**.
5. On the **Product or Family (Advanced)** display, provide information about the product, release, and platform for which you want to obtain patches, and click **Search**.

The Patch Search pane opens, displaying the results of your search.

6. Select the patch number and click **ReadMe**.

The README page is displayed. It contains information about the patch and how to apply the patches to your installation.

7. Uncompress the Oracle patch updates that you downloaded from My Oracle Support.

### Related Topics

- [My Oracle Support note 888.1](#)
- [Patch Delivery Methods for Oracle Database](#)

## Unlocking and Resetting Oracle Database User Passwords

Passwords for all Oracle system administration accounts except SYS, SYSTEM, and DBSMP are revoked after installation. Before you use a locked account, you must unlock it and reset its password.

If you created a preconfigured database during the installation, but you did not unlock accounts required to use the database, then you must unlock and reset those accounts using these procedures.

- [Requirements for Database Passwords](#)  
To secure your database, use passwords that satisfy the Oracle recommended password requirements, even the passwords for predefined user accounts.
- [Oracle Database System Privileges Accounts and Passwords](#)  
Review these system privileges accounts after installation in preparation for unlocking accounts and changing passwords.
- [Guidelines for Changing System Privileges Account Passwords](#)  
Follow these rules for changing Oracle Database system privileges account passwords.
- [Locking and Unlocking User Accounts](#)
- [Using SQL\\*Plus to Unlock Accounts and Reset Passwords](#)  
Use this SQL\*Plus procedure to unlock and reset user account passwords.

## Requirements for Database Passwords

To secure your database, use passwords that satisfy the Oracle recommended password requirements, even the passwords for predefined user accounts.

Oracle Database provides a set of predefined user accounts. Create passwords in a secure fashion. If you have default passwords, change these passwords to secure passwords.

You can manage the security for Oracle Database users in various ways:

- Enforce restrictions on the way that passwords are created
- Create user profiles
- Use user resource limits to further secure user accounts

### Related Topics

- *Oracle Database Security Guide*

## Oracle Database System Privileges Accounts and Passwords

Review these system privileges accounts after installation in preparation for unlocking accounts and changing passwords.

All databases created by the Database Configuration Assistant (DBCA) include the `SYS`, `SYSTEM`, and `DBSNMP` database accounts. In addition, Oracle Database provides several other administrative accounts. Before using these accounts, you must unlock them and reset their passwords.

Starting with Oracle Database 12c Release 2 (12.2), only the HR sample schema is automatically installed after a database installation. All sample schemas, including HR, are distributed on GitHub:

<https://github.com/oracle/db-sample-schemas>





**Note:**

This list contains some of the important system privileges user accounts, but it is not complete. Use Oracle Enterprise Manager Database Express 12c to view the complete list of database accounts.

**Table 11-1 Partial List of Oracle Database System Privileges Accounts Locked After Installation**

User Name	Description	For More Information
ANONYMOUS	Enables HTTP access to Oracle XML DB.	<i>Oracle XML DB Developer's Guide</i>
APEX_050100	The account that owns the Oracle Application Express schema and metadata.	<i>Oracle Application Express App Builder User's Guide</i>
APEX_PUBLIC_USER	The minimally privileged account used for Oracle Application Express configuration with Oracle Application Express Listener or Oracle HTTP Server and <code>mod_plsql</code> .	<i>Oracle Application Express App Builder User's Guide</i>
APPQOSSYS	Used for storing and managing all data and metadata required by Oracle Quality of Service Management.	None
AUDSYS	The account where the unified audit data trail resides.	<i>Oracle Database Security Guide</i>
CTXSYS	The Oracle Text account.	<i>Oracle Text Application Developer's Guide</i>
DBSFUSER	The account used to run the <code>DBMS_SFW_ACL_ADMIN</code> package.	<i>Oracle Database PL/SQL Packages and Types Reference</i>
DBSNMP	The account used by the Management Agent component of Oracle Enterprise Manager to monitor and manage the database.	<i>Oracle Enterprise Manager Cloud Control Administrator's Guide</i>
DIP	The account used by the Directory Integration Platform (DIP) to synchronize the changes in Oracle Internet Directory with the applications in the database.	None
DVSYS	There are two roles associated with this account. The Database Vault owner role manages the Database Vault roles and configurations. The Database Vault Account Manager is used to manage database user accounts.  <b>Note:</b> Part of Oracle Database Vault user interface text is stored in database tables in the DVSYS schema. By default, only the English language is loaded into these tables. You can use the <code>DVSYS.DBMS_MACADM.ADD-NLS_DATA</code> procedure to add other languages to Oracle Database Vault.	<i>Oracle Database Vault Administrator's Guide</i>
DVF	The account owned by Database Vault that contains public functions to retrieve the Database Vault Factor values.	<i>Oracle Database Vault Administrator's Guide</i>

**Table 11-1 (Cont.) Partial List of Oracle Database System Privileges Accounts Locked After Installation**

User Name	Description	For More Information
FLows_FILES	The account owns the Oracle Application Express uploaded files.	<i>Oracle Application Express App Builder User's Guide</i>
GGSYS	The internal account used by Oracle GoldenGate. It should not be unlocked or used for a database login.	None
GSMADMIN_INTERN AL	The internal account that owns the Global Data Services schema. It should not be unlocked or used for a database login.	<i>Oracle Database Global Data Services Concepts and Administration Guide</i>
GSMCATUSER	The account used by Global Service Manager to connect to the Global Data Services catalog.	<i>Oracle Database Global Data Services Concepts and Administration Guide</i>
GSMUSER	The account used by Global Service Manager to connect to the database.	<i>Oracle Database Global Data Services Concepts and Administration Guide</i>
HR	The account that owns the Human Resources schema included in the Oracle Sample Schemas.	<i>Oracle Database Sample Schemas</i>
LBACSYS	The Oracle Label Security administrator account. Starting with Oracle Database 18c, the LBACSYS user account is created as a schema-only account.	<i>Oracle Label Security Administrator's Guide</i>
MDDATA	The schema used by Oracle Spatial and Graph for storing geocoder and router data.	<i>Oracle Spatial and Graph Developer's Guide</i>
MDSYS	The Oracle Spatial and Graph administrator account.	<i>Oracle Spatial and Graph Developer's Guide</i>
OUTLN	The account that supports plan stability. Plan stability enables you to maintain the same execution plans for the same SQL statements. OUTLN acts as a role to centrally manage metadata associated with stored outlines.	None
ORACLE_OCM	This account contains the instrumentation for configuration collection used by the Oracle Configuration Manager.	None
REMOTE_SCHEDUL ER_AGENT	The account to disable remote jobs on a database. This account is created during the remote scheduler agent configuration. You can disable the capability of a database to run remote jobs by dropping this user.	<i>Oracle Database Administrator's Guide</i>
SYS	The account used to perform database administration tasks.	<i>Oracle Database Administrator's Guide</i>
SYSTEM	Another account used to perform database administration tasks.	<i>Oracle Database Administrator's Guide</i>
SYSBACKUP	The account used to perform backup and recovery tasks.	<i>Oracle Database Administrator's Guide</i>
SYSKM	The account used to perform encryption key management.	<i>Oracle Database Administrator's Guide</i>
SYSDBG	The account used to administer and monitor Oracle Data Guard.	<i>Oracle Database Administrator's Guide</i>

**Table 11-1 (Cont.) Partial List of Oracle Database System Privileges Accounts Locked After Installation**

User Name	Description	For More Information
SYSRAC	The account used to administer Oracle Real Application Clusters (RAC).	<i>Oracle Database Administrator's Guide</i>
SYS\$UMF	The account used to administer Remote Management Framework, including the remote Automatic Workload Repository (AWR).	<i>Oracle Database Performance Tuning Guide</i>
WMSYS	The account used to store the metadata information for Oracle Workspace Manager.	<i>Oracle Database Workspace Manager Developer's Guide</i>
XDB	The account used for storing Oracle XML DB data and metadata.	<i>Oracle XML DB Developer's Guide</i>
XS\$NULL	The internal account that represents the absence of a database schema user in a session, and indicates an application user session is in use. XS\$NULL cannot be authenticated to a database, nor can it own any database schema objects, or possess any database privileges.	<i>Oracle Database Real Application Security Administrator's and Developer's Guide</i>

Except for the accounts provided with the Oracle Sample Schemas, most of these database accounts are locked by default and created without passwords as schema only. This prevents malicious users from logging into these accounts using the default password set during catalog creation. To find the status of an account, query the `AUTHENTICATION_TYPE` column of the `DBA_USERS` data dictionary view. If `AUTHENTICATION_TYPE` is schema only, then the status is `NONE`.

Many of these accounts are automatically created when you run standard scripts such as the various `cat*.sql` scripts. To find user accounts that are created and maintained by Oracle, query the `USERNAME` and `ORACLE_MAINTAINED` columns of the `ALL_USERS` data dictionary view. If the output for `ORACLE_MAINTAINED` is `Y`, then you must not modify the user account except by running the script that was used to create it.

### Related Topics

- *Oracle Database Security Guide*
- *Oracle Database Sample Schemas*

## Guidelines for Changing System Privileges Account Passwords

Follow these rules for changing Oracle Database system privileges account passwords.

Before you use a locked account, you must unlock it and reset its password. Passwords for all Oracle system administration accounts except `SYS`, `SYSTEM`, and `DBSNMP` are revoked after installation. If you created a starter database during the installation, Oracle Database Configuration Assistant displays a screen with your database information and the Password Management button. Use the Password Management button to unlock only the user names you use.

For more information about how to create a secure password, see:

*Oracle Database Security Guide*

## Locking and Unlocking User Accounts

To temporarily deny access to the database for a particular user account, you can lock the user account. If the user then attempts to connect, then the database displays an error message and does not allow the connection. You can unlock the user account when you want to permit database access again for that user. You can use Oracle Enterprise Manager Database Express (EM Express) to lock and unlock user accounts.

### To lock or unlock a user account:

1. In EM Express, go to the Users page.
2. Click the desired user account.
3. From the **Actions** menu, select **Alter Account**.  
The Alter Account page appears.
4. Do one of the following:
  - To lock the account, enable the **Account Locked** option, and then click **OK**.
  - To unlock the account, disable the **Account Locked** option, and then click **OK**.

## Using SQL\*Plus to Unlock Accounts and Reset Passwords

Use this SQL\*Plus procedure to unlock and reset user account passwords.

1. Log in as the Oracle Database software owner user.
2. Set the ORACLE\_HOME and ORACLE\_SID environment variables.

Bourne, Bash or Korn shell:

```
$ ORACLE_SID=orcl
$ export ORACLE_SID
$ ORACLE_HOME=/u01/app/oracle/product/19.0.0/dbhome_1
$ export ORACLE_HOME
```

C shell:

```
% setenv ORACLE_SID orcl
% setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/dbhome_1
```

3. Start SQL\*Plus and log in as the SYS user, connecting as SYSDBA:

```
$ $ORACLE_HOME/bin/sqlplus
SQL> CONNECT SYS as SYSDBA
Enter password: sys_password
```

4. To unlock an account:

```
ALTER USER account ACCOUNT UNLOCK;
```

5. To reset the password:

```
ALTER USER user_name IDENTIFIED BY new_password;
```

 **Note:**

If you unlock an account but do not reset the password, then the password remains expired. The first time someone connects as that user, they must change the user's password.

**Related Topics**

- *Oracle Database Administrator's Guide*

## Recommended Postinstallation Tasks

Oracle recommends that you complete these tasks after installation.

- [Creating a Backup of the root.sh Script](#)  
Oracle recommends that you back up the `root.sh` script after you complete an installation.
- [Setting Language and Locale Preferences for Client Connections](#)  
Configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set.
- [Recompile Invalid Objects in the Database](#)  
After you install, patch, or upgrade a database, recompile invalid objects on the CDB and PDBs with a recompilation driver script.
- [About Installing Oracle Autonomous Health Framework](#)  
Install the latest version of Oracle Autonomous Health Framework to perform proactive health checks and collect diagnostics data for the Oracle software stack.

### Creating a Backup of the root.sh Script

Oracle recommends that you back up the `root.sh` script after you complete an installation.

If you install other products in the same Oracle home directory subsequent to this installation, then Oracle Universal Installer updates the contents of the existing `root.sh` script during the installation. If you require information contained in the original `root.sh` script, then you can recover it from the backed up `root.sh` file.

### Setting Language and Locale Preferences for Client Connections

Configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set.

You must configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set. If your applications do not have their own specific methods to configure locale preferences, then the method you use to configure an Oracle database client connection depends on the access API you use to connect to the database. Check your application documentation, before you configure locale preferences for your applications.

For applications that connect to Oracle Databases using Oracle Call Interface (OCI) use `NLS_LANG` and other client settings with names that start with `NLS_` to set the locale conventions and client character set for Oracle Database sessions. It is important that you set the character set part of the `NLS_LANG` value properly. The character set you set must correspond to the character set used by your I/O devices, which in case of Microsoft Windows

is either the ANSI Code Page (for GUI applications), such as WE8MSWIN1252, or the OEM Code Page (for Console mode applications), such as US8PC437. By doing this, the OCI API is notified about the character set of data that it receives from the application. OCI can then convert this data correctly to and from the database character set.

NLS\_LANG and the other NLS settings can be specified either as environment variables or as Windows Registry settings. Environment variable values take precedence over Registry values.

Oracle Universal Installer sets a default value for the NLS\_LANG setting in Registry when it creates a new Oracle home on Microsoft Windows. The NLS\_LANG value is based on the language of the Windows user interface, which is the language of Windows menu items and dialog box labels.

 **Caution:**

Failure to set the client character set correctly can cause data loss.

Java applications that connect to Oracle Databases by using Oracle JDBC do not use NLS\_LANG. Instead, Oracle JDBC maps the default locale of the Java VM in which the application runs to the Oracle Database language and territory settings. Oracle JDBC then configures the connected database session using these settings. Because Java works internally in Unicode, the client character set is always set to Unicode. Unless an application explicitly changes it, the default locale of the Java VM is set based on the locale of the user operating system on which the Java VM runs. Check your Java VM documentation for information about configuring the Java VM default locale.

 **Note:**

In 3-tier architecture deployments, application servers that are database clients can have settings in their configuration files that specify the NLS\_LANG value or the Java VM locale. Check the documentation accompanying these servers.

 **See Also:**

*Oracle Database Globalization Support Guide* for more information about configuring user locale preferences

## Recompile Invalid Objects in the Database

After you install, patch, or upgrade a database, recompile invalid objects on the CDB and PDBs with a recompilation driver script.

By default, AutoUpgrade performs a recompilation of invalid Oracle objects, which is controlled by the configuration file `run_utlpr` local parameter (default: `prefix.run_utlpr=yes`). In addition, Oracle provides the recompilation scripts `utlpr.sql` and `utlprp.sql`. These scripts are located in the `Oracle_home/rdbms/admin` directory.

 **Note:**

Starting with AutoUpgrade 23.1, when you run the AutoUpgrade utility, AutoUpgrade runs the `utlprpom.sql` script, and does not run `utlrp.sql`. When AutoUpgrade is used for upgrades to Oracle Database 12c Release 2 (12.2.0.1) and later releases, AutoUpgrade only recompiles invalid objects owned by Oracle-maintained schemas. Because database upgrades do not need to touch user objects, AutoUpgrade maintains this policy when it recompiles invalid objects.

After installing a database, recompile all invalid objects;

1. Change directory to `Oracle_home/rdbms/admin`. For example

```
$ cd $ORACLE_HOME/rdbms/admin
```

2. Use the `catcon.pl` script in the Oracle home to run `utlrp.sql`. For example:

```
$ORACLE_HOME/perl/bin/perl catcon.pl --n 1 --e --b utlrp --d ''.'''
utlrp.sql
```

Note the following conditions of this use case:

- `--n` parameter: is set to 1, so the script runs each PDB recompilation in sequence.
- `--e` parameter: turns echo on.
- `--b` parameter: Sets the log file base name. It is set to `utlrp`.

Expect a time delay for the serial recompilation of PDBs to complete. Depending on the number of PDBs that you are upgrading, the recompilation can extend significantly beyond the time required for the upgrade scripts to complete.

The `utlrp.sql` script automatically recompiles invalid objects in either serial or parallel recompilation, based on both the number of invalid objects, and on the number of CPUs available. CPUs are calculated using the number of CPUs (`cpu_count`) multiplied by the number of threads for each CPU (`parallel_threads_per_cpu`). On Oracle Real Application Clusters (Oracle RAC), this number is added across all Oracle RAC nodes.

After patching or upgrading a database, there is more than one approach you can use to recompile invalid Oracle-owned and user-owned objects:

Recompile all invalid objects (the invalid objects in both Oracle and user schemas) by using `utlrp.sql` or `utlprpom.sql`.

If time is a factor and the type of invalid objects is predominately application owned, then you can recompile Oracle-owned invalid objects first, and defer recompiling application-owned invalid objects to a later time. To recompile invalid objects in Oracle schemas, use `utlprpom.sql`. To recompile the remaining invalid objects, use `utlrp.sql` or `utlprpom.sql`.

 **Note:**

When you use either `utlprpom.sql` or `utlrp.sql`, note that both scripts require you to define the degree of parallelism that the script should use, or determine the number of parallel recompile jobs to use.



The script uses syntax as follows, where *base* is the base name you want to have given to log files, *N* is the number of PDBs on which you want to run recompilation jobs in parallel (degrees of parallelism), *script.sql* is the Oracle recompilation script you chose to use, and *P* is the number of PDBs on which you want to run in parallel:

```
$ORACLE_HOME/perl/bin/perl $ORACLE_HOME/rdbms/admin/catcon.pl -b base -  
d $ORACLE_HOME/rdbms/admin  
    -n N -l /tmp script.sql '--pP'
```

Suppose you are running recompilation in a CDB using the log file base name *recomp*, with a degrees of parallelism setting of 3 jobs per PDB container, the script you choose to use is *utlprp.sql*, and you want to recompile across at most 10 PDBs at a time. In that case, the syntax you use to run the recompilation operation is similar to the following,

```
$ORACLE_HOME/perl/bin/perl $ORACLE_HOME/rdbms/admin/catcon.pl -b recomp -  
d $ORACLE_HOME/rdbms/admin -n 10 -l /tmp utlprp.sql '--p3'
```

### Related Topics

- Syntax and Parameters for *catcon.pl*

## About Installing Oracle Autonomous Health Framework

Install the latest version of Oracle Autonomous Health Framework to perform proactive health checks and collect diagnostics data for the Oracle software stack.

Oracle Autonomous Health Framework includes the functionality from Oracle ORAchk, Oracle EXAchk, and Oracle Trace File Analyzer (TFA). Oracle Autonomous Health Framework extends health check coverage to the entire Oracle software stack, based on critical and reoccurring problems. Oracle Autonomous Health Framework proactively scans for known problems with Oracle products and deployments, including the following:

- Standalone Oracle Database
- Oracle Grid Infrastructure
- Oracle Real Application Clusters
- Maximum Availability Architecture (MAA) Validation
- Upgrade Readiness Validations
- Oracle GoldenGate

Oracle Autonomous Health Framework is pre-installed with Oracle Database. However, Oracle recommends that you update to the latest version of Oracle Autonomous Health Framework by downloading and installing it from My Oracle Support Note 2550798.1.

<https://support.oracle.com/epmos/faces/DocContentDisplay?id=2550798.1&parent=DOCUMENTATION&sourceId=USERGUIDE>

## About Changes in Default SGA Permissions for Oracle Database

Starting with Oracle Database 12c Release 2 (12.2.0.1), by default, permissions to read and write to the System Global Area (SGA) are limited to the Oracle software installation owner.

In previous releases, both the Oracle installation owner account and members of the OSDBA group had access to shared memory. The change in Oracle Database 12c Release 2 (12.2)



and later releases to restrict access by default to the Oracle installation owner account provides greater security than previous configurations. However, this change may prevent DBAs who do not have access to the Oracle installation owner account from administering the database.

The Oracle Database initialization parameter `ALLOW_GROUP_ACCESS_TO_SGA` determines if the Oracle Database installation owner account (`oracle` in Oracle documentation examples) is the only user who can read and write to the database System Global Area (SGA), or if members of the OSDBA group can read the SGA. In Oracle Database 12c Release 2 (12.2) and later releases, the default value for this parameter is `FALSE`, so that only the Oracle Database installation owner has read and write permissions to the SGA. Group access to the SGA is removed by default. This change affects all Linux and UNIX platforms.

If members of the OSDBA group require read access to the SGA, then you can change the initialization parameter `ALLOW_GROUP_ACCESS_TO_SGA` setting from `FALSE` to `TRUE`. Oracle strongly recommends that you accept the default permissions that limit access to the SGA to the `oracle` user account.

### Related Topics

- *Oracle Database Reference*

## Checking Installed Oracle Database Contents and Directory Location

Use these steps to check the contents and directory location of an Oracle Database installation:

1. Go to `$ORACLE_HOME/oui/bin`.
2. Start Oracle Universal Installer.

```
$ ./runInstaller
```

3. Click **Installed Products** to display the Inventory dialog box on the Welcome screen.
4. Select an Oracle Database product from the list to check the installed contents.
5. Click **Details** to find additional information about an installed product.
6. Click **Close** to close the Inventory dialog box.
7. Click **Cancel** to close Oracle Universal Installer, and then click **Yes** to confirm.

## Enabling and Disabling Oracle Database Options After Installation

The `chopt` tool changes your database options after installation.

When you install Oracle Database, some options are enabled and others are disabled. To enable or disable a particular database feature for an Oracle home, shut down the database and use the `chopt` tool.

- [Chopt Tool](#)  
Use the `chopt` tool after installation to add or remove Oracle Database options.

## Chopt Tool

Use the `chopt` tool after installation to add or remove Oracle Database options.

### Purpose

The `chopt` tool is a command-line utility that enables and disables database options.

#### Note:

If you install or clone an Oracle Database image, then all Oracle Database options are enabled by default.

### Prerequisites

You must complete installation before you can use the `chopt` tool.

### File Path

The tool is located in the `ORACLE_HOME/bin` directory

### Syntax

```
chopt [enable | disable] db_option
```

### Options

Command Option	Description
<code>olap</code>	Oracle OLAP
<code>partitioning</code>	Oracle Partitioning
<code>rat</code>	Oracle Real Application Testing

#### Note:

- When you enable or disable OLAP, you must run the `SYS.XOQ_VALIDATE` and `SYS.APS_VALIDATE` procedures to update the database registry. When you disable OLAP, its status in the database registry should be `OPTION OFF` and when you enable OLAP, its status in the database registry should be `VALID`.
- The Oracle Advanced Analytics (OAA) feature is enabled by default for Oracle Database. You cannot disable it using the `chopt` tool.

### Examples

To use the `chopt` tool to modify your Oracle Database, you must shut down the database before you run the `chopt` tool, and then start up the database after you add or remove database options.

**Example 11-1 Enabling Oracle Real Application Testing Using chopt**

The following example shows how to use the `chopt` tool to enable the Oracle Real Application Testing option in an Oracle Database called Sales:

```
cd $ORACLE_HOME/bin
srvctl stop database -d Sales
chopt enable rat
srvctl start database -d Sales
```

## Starting Oracle Enterprise Manager Database Express

Use these steps to log in to Oracle Enterprise Manager Database Express (EM Express).

To start Oracle Enterprise Manager Database Express, use the EM Express URL provided by Oracle Database Configuration Assistant (Oracle DBCA) during the database installation and creation. For information about logging in to Oracle Enterprise Manager Database Express see *Oracle Database 2 Day DBA*.

If Oracle DBCA did not provide the EM Express URL during the database installation and creation, or if you need to change the EM Express port later on, then see *Oracle Database 2 Day DBA*.

**Related Topics**

- [Oracle Database 2 Day DBA](#)
- [Configuring the HTTPS Port for EM Express](#)

## Creating a Fast Recovery Area

During an Oracle Restart installation, you can create only one disk group. During an Oracle Clusterware installation, you can create multiple disk groups. If you plan to add an Oracle Database for a standalone server or an Oracle RAC database, then you should create the fast recovery area for database files.

- [About the Fast Recovery Area and the Fast Recovery Area Disk Group](#)  
The fast recovery area is a unified storage location for all Oracle Database files related to recovery. Enabling rapid backups for recent data can reduce requests to system administrators to retrieve backup tapes for recovery operations.
- [Creating the Fast Recovery Area Disk Group](#)  
Procedure to create the fast recovery area disk group.

## About the Fast Recovery Area and the Fast Recovery Area Disk Group

The fast recovery area is a unified storage location for all Oracle Database files related to recovery. Enabling rapid backups for recent data can reduce requests to system administrators to retrieve backup tapes for recovery operations.

Database administrators can define the `DB_RECOVERY_FILE_DEST` parameter to the path for the fast recovery area to enable on disk backups and rapid recovery of data. When you enable fast recovery in the `init.ora` file, Oracle Database writes all RMAN backups, archive logs, control file automatic backups, and database copies to the fast recovery area. RMAN automatically manages files in the fast recovery area by deleting obsolete backups and archiving files no longer required for recovery.

Oracle recommends that you create a fast recovery area disk group. Oracle Clusterware files and Oracle Database files can be placed on the same disk group, and you can also place fast recovery files in the same disk group. However, Oracle recommends that you create a separate fast recovery disk group to reduce storage device contention.

The fast recovery area is enabled by setting the `DB_RECOVERY_FILE_DEST` parameter. The size of the fast recovery area is set with `DB_RECOVERY_FILE_DEST_SIZE`. As a general rule, the larger the fast recovery area, the more useful it becomes. For ease of use, Oracle recommends that you create a fast recovery area disk group on storage devices that can contain at least three days of recovery information. Ideally, the fast recovery area is large enough to hold a copy of all of your data files and control files, the online redo logs, and the archived redo log files needed to recover your database using the data file backups kept under your retention policy.

Multiple databases can use the same fast recovery area. For example, assume you have created a fast recovery area disk group on disks with 150 GB of storage, shared by 3 different databases. You can set the size of the fast recovery for each database depending on the importance of each database. For example, if database1 is your least important database, database2 is of greater importance, and database3 is of greatest importance, then you can set different `DB_RECOVERY_FILE_DEST_SIZE` settings for each database to meet your retention target for each database: 30 GB for database1, 50 GB for database2, and 70 GB for database3.

## Creating the Fast Recovery Area Disk Group

Procedure to create the fast recovery area disk group.

1. Go to the Oracle Grid Infrastructure home `bin` directory, and start Oracle ASM Configuration Assistant (ASMCA).

For example:

```
$ cd /u01/app/oracle/product/19.0.0/grid/bin
$ ./asmca
```

ASMCA opens the home window.

2. Click **Disk Groups** in the left panel to open the Disk Groups tab.
3. Click **Create** to create a new disk group.

The Create Disk Groups window opens.

4. Provide configuration information for the fast recovery area as prompted:

In the Disk Group Name field, enter a descriptive name for the fast recovery area group. For example: `FRA`.

In the Redundancy section, select the level of redundancy you want to use. For example:  
`Normal`

In the Select Member Disks field, select eligible disks you want to add to the fast recovery area, and click **OK**.

5. When the Fast Recovery Area disk group creation is complete, click **Exit** and click **Yes** to confirm closing the ASMCA application.

# Cloning an Oracle Database Home

Cloning an Oracle home involves creating a copy of the Oracle home and then configuring it for a new environment.

If you are performing multiple Oracle Database installations, then you may want to use cloning to create each Oracle home, because copying files from an existing Oracle Database installation takes less time than creating a new version of them. This method is also useful if the Oracle home that you are cloning has had patches applied to it. When you clone the Oracle home, the new Oracle home has the patch updates.

Perform these steps to clone an Oracle home.



## Note:

During cloning, Oracle Universal Installer (OUI) prompts you to run scripts that require root privileges.

1. Verify that the installation of Oracle Database that you want clone is successful.

You can do this by reviewing the `installActionsdate_time.log` file for the installation session, which is typically located in the `/u01/app/oracle/oraInventory/logs` directory.

If you install patches, then check their status using the following:

```
$ cd $ORACLE_HOME/OPatch
```

```
Include $ORACLE_HOME/OPatch in $PATH
```

```
$ opatch lsinventory
```

2. Stop all processes related to the Oracle home.
3. Create a ZIP or TAR file with the Oracle home (but not the Oracle base) directory.

For example, if the source Oracle installation is in the path `/u01/app/oracle/product/19.0.0/dbhome_1`, then you zip the `dbhome_1` directory by using the following command:

```
# zip -r dbhome_1.zip /u01/app/oracle/product/19.0.0/dbhome_1
```

You can also use the TAR command. For example:

```
# tar -cvf dbhome_1.tar /u01/app/oracle/product/19.0.0/dbhome_1
```

Do not include the `admin`, `fast_recovery_area`, and `oradata` directories that are under the Oracle base directory. These directories are created in the target installation later, when you create a new database there.

4. Copy the ZIP or TAR file to the root directory of the target computer. If you use File Transfer Protocol (FTP), then transfer the ZIP or TAR file in binary mode only.

5. Extract the ZIP or TAR file content using the following command:

```
# unzip -d / dbhome_1.zip
# tar -xvf dbhome_1.tar
```

6. If necessary, change the ownership of the Oracle Database home to the Oracle Database installation owner user (`oracle`) belonging to the Oracle Inventory group (`oinstall`).

```
# chown -R oracle:oinstall /u01/app/oracle/product/19.0.0/dbhome_1
```

7. On the target computer, change the directory to the unzipped Oracle home directory, and remove all the `.ora` (`*.ora`) files present in the unzipped `$ORACLE_HOME/network/admin` directory.

8. Delete unnecessary files from the unzipped Oracle home directory.

The unzipped Oracle home directory contains files that are relevant only to the source Oracle home. The following example shows how to remove these unnecessary files from the unzipped Oracle home directory:

Remove the `.ora` files from the `network/admin` directory, and remove the old database entries from the `dbs` directory.

```
# cd $ORACLE_HOME
# rm -rf network/admin/*.ora
# rm dbs/old_database_entries
```

9. From the `$ORACLE_HOME/clone/bin` directory, run the `clone.pl` file for the unzipped Oracle home.

Use the following syntax (you can also include one or more of the extended Oracle Database groups in the syntax):

```
$ORACLE_HOME/perl/bin/perl $ORACLE_HOME/clone/bin/clone.pl
ORACLE_BASE="target_oracle_base" ORACLE_HOME="target_oracle_home"
OSDBA_GROUP=OSDBA_privileged_group
OSOPER_GROUP=OSOPER_privileged_group
OSBACKUPDBA_GROUP=OSBACKUPDBA_privileged_group
OSDGDBA_GROUP=OSDGDBA_privileged_group
OSKMDBA_GROUP=OSKMDBA_privileged_group
OSRACDBA_GROUP=OSRACDBA_privileged_group -defaultHomeName
```

For example:

```
$ORACLE_HOME/perl/bin/perl $ORACLE_HOME/clone/bin/clone.pl
ORACLE_BASE="/u01/app/oracle" ORACLE_HOME="/u01/app/oracle/product/19.0.0/
dbhome_1"
OSDBA_GROUP=dba OSOPER_GROUP=oper OSBACKUPDBA_GROUP=backupdba
OSDGDBA_GROUP=dgdba OSKMDBA_GROUP=kmdba OSRACDBA_GROUP=racdba -
defaultHomeName
```

 **Note:**

- In this command, if you do not provide the parameters for the operating system groups, then `clone.pl` uses the operating system group values from the source home.
- Run the `$ORACLE_HOME/perl/bin/perl $ORACLE_HOME/clone/bin/clone.pl -help` command for more information about the command option flags.
- The `clone.pl` script is deprecated in Oracle Database 19c and can be removed in a future release. Hence, Oracle recommends that you use the software-only installation option, available in the database installer, instead of `clone.pl` to clone your database.

OUI starts, and then records the cloning actions in the `cloneActionstimestamp.log` file. This log file is typically located in `/u01/app/oracle/oraInventory/logs` directory.

10. Use the following commands to run Net Configuration Assistant to configure the connection information for the new database:

```
$ cd $ORACLE_HOME/bin
$ ./netca
```

11. Use the following commands to run Database Configuration Assistant to create a new Oracle Database for the newly-cloned oracle home:

```
$ cd $ORACLE_HOME/bin
$ ./dbca
```

**Related Topics**

- *Oracle Clusterware Administration and Deployment Guide*
- *Oracle Database Administrator's Guide*

# 12

## Removing Oracle Database Software

These topics describe how to remove Oracle software and configuration files.

Use the `deinstall` command that is included in Oracle homes to remove Oracle software. Oracle does not support the removal of individual products or components.

### **Caution:**

If you have a standalone database on a node in a cluster, and if you have multiple databases with the same global database name (GDN), then you cannot use the `deinstall` command to remove one database only.

- [About Oracle Deinstallation Options](#)  
You can stop and remove Oracle Database software and components in an Oracle Database home with the `deinstall` command.
- [Oracle Deinstallation \(Deinstall\)](#)  
You can run the `deinstall` command from an Oracle home directory after installation.
- [Deinstallation Examples for Oracle Database](#)  
Use these examples to help you understand how to run the `deinstall` command.
- [Downgrading Oracle Restart](#)  
Use this procedure to deconfigure and downgrade Oracle Restart, or to troubleshoot Oracle Restart installation errors.
- [Removing an RPM-based Oracle Database Installation](#)  
Use this procedure to remove and deinstall a database installed using the `yum` command.
- [Deinstalling Previous Release Grid Home](#)  
Use this procedure to deinstall the previous release Grid home.

## About Oracle Deinstallation Options

You can stop and remove Oracle Database software and components in an Oracle Database home with the `deinstall` command.

You can remove the following software using `deinstall`:

- Oracle Database
- Oracle Grid Infrastructure, which includes Oracle Clusterware and Oracle Automatic Storage Management (Oracle ASM)
- Oracle Real Application Clusters (Oracle RAC)
- Oracle Database Client

The `deinstall` command is available in Oracle home directories after installation. It is located in the `$ORACLE_HOME/deinstall` directory.



`deinstall` creates a response file by using information in the Oracle home and using the information you provide. You can use a response file that you generated previously by running the `deinstall` command using the `-checkonly` option. You can also edit the response file template.

If you run `deinstall` to remove an Oracle Grid Infrastructure installation, then the deinstaller prompts you to run the `deinstall` command as the `root` user. For Oracle Grid Infrastructure for a cluster, the script is `rootcrs.sh`, and for Oracle Grid Infrastructure for a standalone server (Oracle Restart), the script is `roothas.sh`.

 **Note:**

- You must run the `deinstall` command from the same release to remove Oracle software. Do not run the `deinstall` command from a later release to remove Oracle software from an earlier release. For example, do not run the `deinstall` command from the 19c Oracle home to remove Oracle software from an existing 11.2.0.4 Oracle home.
- Starting with Oracle Database 12c Release 1 (12.1.0.2), the `roothas.sh` script replaces the `roothas.pl` script in the Oracle Grid Infrastructure home for Oracle Restart, and the `rootcrs.sh` script replaces the `rootcrs.pl` script in the Grid home for Oracle Grid Infrastructure for a cluster.

If the software in the Oracle home is not running (for example, after an unsuccessful installation), then `deinstall` cannot determine the configuration, and you must provide all the configuration details either interactively or in a response file.

In addition, before you run `deinstall` for Oracle Grid Infrastructure installations:

- Dismount Oracle Automatic Storage Management Cluster File System (Oracle ACFS) and disable Oracle Automatic Storage Management Dynamic Volume Manager (Oracle ADVM).
- If Grid Naming Service (GNS) is in use, then notify your DNS administrator to delete the subdomain entry from the DNS.

### Files Deleted by `deinstall`

When you run `deinstall`, if the central inventory (`oraInventory`) contains no other registered homes besides the home that you are deconfiguring and removing, then `deinstall` removes the following files and directory contents in the Oracle base directory of the Oracle Database installation owner:

- `admin`
- `cfgtoollogs`
- `checkpoints`
- `diag`
- `oradata`
- `fast_recovery_area`

Oracle strongly recommends that you configure your installations using an Optimal Flexible Architecture (OFA) configuration, and that you reserve Oracle base and Oracle home paths for

exclusive use of Oracle software. If you have any user data in these locations in the Oracle base that is owned by the user account that owns the Oracle software, then `deinstall` deletes this data.

**▲ Caution:**

`deinstall` deletes Oracle Database configuration files, user data, and fast recovery area (FRA) files even if they are located outside of the Oracle base directory path.

## Oracle Deinstallation (Deinstall)

You can run the `deinstall` command from an Oracle home directory after installation.

### Purpose

`deinstall` stops Oracle software, and removes Oracle software and configuration files on the operating system for a specific Oracle home.

### Syntax

The `deinstall` command uses the following syntax:

```
(./deinstall [-silent] [-checkonly] [-paramfile complete path of input response file]
[-params name1=value name2=value . . .]
[-o complete path of directory for saving files]
[-tmpdir complete path of temporary directory to use]
[-logdir complete path of log directory to use] [-local] [-skipLocalHomeDeletion] [-skipRemoteHomeDeletion] [-help]
```

### Parameters

Parameter	Description
<code>-silent</code>	<p>Use this flag to run <code>deinstall</code> in noninteractive mode. This option requires one of the following:</p> <ul style="list-style-type: none"> <li>A working system that it can access to determine the installation and configuration information. The <code>-silent</code> flag does not work with failed installations.</li> <li>A response file that contains the configuration values for the Oracle home that is being deinstalled or deconfigured.</li> </ul> <p>You can generate a response file to use or modify by running <code>deinstall</code> with the <code>-checkonly</code> flag. <code>deinstall</code> then discovers information from the Oracle home to deinstall and deconfigure. It generates the response file that you can then use with the <code>-silent</code> option.</p> <p>You can also modify the template file <code>deinstall.rsp.tmpl</code>, located in the <code>\$ORACLE_HOME/deinstall/response</code> directory.</p>

Parameter	Description
<code>-checkonly</code>	Use this flag to check the status of the Oracle software home configuration. Running <code>deinstall</code> with the <code>-checkonly</code> flag does not remove the Oracle configuration. The <code>-checkonly</code> flag generates a response file that you can then use with the <code>deinstall</code> command and <code>-silent</code> option.
<code>-paramfile</code> <i>complete path of input response file</i>	Use this flag to run <code>deinstall</code> with a response file in a location other than the default. When you use this flag, provide the complete path where the response file is located.  The default location of the response file is <code>\$ORACLE_HOME/deinstall/response</code> .
<code>-params</code> [ <i>name1=value name2=value name3=value ...</i> ]	Use this flag with a response file to override one or more values to change in a response file you have created.
<code>-o</code> <i>complete path of directory for saving response files</i>	Use this flag to provide a path other than the default location where the response file ( <code>deinstall.rsp.tpl</code> ) is saved.  The default location of the response file is <code>\$ORACLE_HOME/deinstall/response</code> .
<code>-tmpdir</code> <i>complete path of temporary directory to use</i>	Use this flag to specify a non-default location where <code>deinstall</code> writes the temporary files for the deinstallation.
<code>-logdir</code> <i>complete path of log directory to use</i>	Use this flag to specify a non-default location where <code>deinstall</code> writes the log files for the deinstallation.
<code>-local</code>	Use this flag on a multinode environment to deinstall Oracle software in a cluster.  When you run <code>deinstall</code> with this flag, it deconfigures and deinstalls the Oracle software on the local node (the node where <code>deinstall</code> is run). On remote nodes, it deconfigures Oracle software, but does not deinstall the Oracle software.
<code>-skipLocalHomeDeletion</code>	Use this flag in Oracle Grid Infrastructure installations on a multinode environment to deconfigure a local Grid home without deleting the Grid home.
<code>-skipRemoteHomeDeletion</code>	Use this flag in Oracle Grid Infrastructure installations on a multinode environment to deconfigure a remote Grid home without deleting the Grid home.
<code>-help</code>	Use this option to obtain additional information about the command option flags.

## Deinstallation Examples for Oracle Database

Use these examples to help you understand how to run the `deinstall` command.

Run `deinstall` from the `$ORACLE_HOME/deinstall` directory. The deinstallation starts without prompting you for the Oracle home path.

```
$ ./deinstall
```

You can generate a deinstallation response file by running `deinstall` with the `-checkonly` flag. Alternatively, you can use the response file template located at `$ORACLE_HOME/deinstall/response/deinstall.rsp.tmpl`. If you have a response file, then use the optional flag `-paramfile` to provide a path to the response file.

In the following example, the `deinstall` command is in the path `/u01/app/oracle/product/19.0.0/dbhome_1/deinstall`. It uses a response file called `my_db_paramfile.tmpl` in the software owner location `/home/usr/oracle`:

```
$ cd /u01/app/oracle/product/19.0.0/dbhome_1/deinstall
$ ./deinstall -paramfile /home/usr/oracle/my_db_paramfile.tmpl
```

To remove the Oracle Grid Infrastructure home, use the `deinstall` command in the Oracle Grid Infrastructure home.

In this example, the Oracle Grid Infrastructure home is `/u01/app/oracle/product/19.0.0/grid`

```
$ cd /u01/app/oracle/product/19.0.0/grid/deinstall
$ ./deinstall -paramfile /home/usr/oracle/my_grid_paramfile.tmpl
```

## Downgrading Oracle Restart

Use this procedure to deconfigure and downgrade Oracle Restart, or to troubleshoot Oracle Restart installation errors.

Running `roothas.sh` with the command flags `-deconfig -force` enables you to deconfigure Oracle Restart without removing the installed binaries. This feature is useful if you encounter an error during an Oracle Grid Infrastructure for a standalone server installation. For example, when you run the `root.sh` command, and find a missing operating system package. By running `roothas.sh -deconfig -force`, you can deconfigure Oracle Restart, correct the cause of the error, and then run `root.sh` again.

1. As the `oracle` user, create a backup of the SPFILE to a PFILE.

```
CREATE PFILE='/u01/app/oracle/product/19.0.0/dbhome_1/dbs/test_init.ora'
FROM SPFILE='/u01/oracle/dbs/test_spfile.ora';
```

2. List all the Oracle Databases on the server with their version, unique name of the database, and Oracle home information.

```
$ srvctl config database -home
```

3. Downgrade Oracle Database. Refer to *Oracle Database Upgrade Guide* for more information about required pre-downgrade tasks, downgrade tasks, post-downgrade tasks, and compatibility information.

 **Note:**

Downgrade Oracle Database only if the Oracle Database version is higher than the Oracle Restart version to which you are downgrading Oracle Restart.

4. As the `oracle` user, downgrade the Oracle Restart resources corresponding to the Oracle Database, only if you have downgraded your Oracle Database.

```
$ srvctl downgrade database -d db_unique_name -oraclehome $ORACLE_HOME -t  
to_version
```

5. Inspect the Oracle Restart configuration of each database, service, and listener.

```
$ srvctl config database -db db_unique_name  
$ srvctl config service -db db_unique_name  
$ srvctl config listener -listener listener_name
```

Make a note of the configuration information and use this information when adding the components back to Oracle Restart.

6. Stop all databases and listeners that are running before you deconfigure or downgrade Oracle Restart.

```
$ srvctl stop database -db db_unique_name  
$ srvctl stop listener [-listener listener_name]
```

7. As the `root` user, run `roothas.sh` with the `-deconfig -force` flags to deconfigure Oracle Restart.

```
# /u01/app/oracle/product/19.0.0/grid/crs/install/roothas.sh -deconfig -  
force
```

8. As the `grid` user, update the Oracle central inventory (`oraInventory`).

```
$ /u01/app/oracle/product/19.0.0/grid/oui/bin/runInstaller -updateNodeList  
-silent ORACLE_HOME=upgraded_Grid_home -local CRS=false
```

9. As the `root` user, run `roothas.sh` with the `-unlock` flag to unlock the previous release Oracle Restart home.

```
# /u01/app/oracle/product/18.0.0/grid/crs/install/roothas.sh -unlock -  
dstcrshome previous_release_Grid_home
```

10. As the `grid` user, reconfigure the previous release Oracle Restart home using the `gridSetup.sh` command.

```
$ /u01/app/oracle/product/18.0.0/grid/gridSetup.sh
```

11. As the `oracle` user, add the components back to Oracle Restart with the same attributes that you noted down before deconfiguring Oracle Restart.

- a. Add Oracle Database to the Oracle Restart configuration.

```
$ srvctl add database -db db_unique_name -oraclehome Oracle_home
```

- b. Add the listener to the Oracle Restart configuration.

```
$ srvctl add listener -listener listener_name -oraclehome Oracle_home
```

For the `-oraclehome` parameter, provide the Oracle home path from which the listener was running before the downgrade.

- c. Add each service to the database, using the `srvctl add service` command.

```
$ srvctl add service -db db_unique_name -service service_name_list
```

### Related Topics

- [Oracle Database Upgrade Guide](#)

## Removing an RPM-based Oracle Database Installation

Use this procedure to remove and deinstall a database installed using the `yum` command.

1. Log in as `root`.
2. Run the following command to remove the RPM-based database installation:

```
# yum -y remove oracle-database-ee-19c
```

The `yum` command detects the default configured components in the Oracle home such as the database (ORCLCDB) and the listener (LISTENER) and removes these components for you. Apart from the default database (ORCLCDB) and the listener (LISTENER), if the `yum` command detects other configured components in the Oracle home such as additional databases or listeners, then it stops the deinstallation process. A message is displayed that instructs you to remove these configured components manually. To remove these configured components:

1. Login as the Oracle Database installation owner user (`oracle`).
2. To remove any database associated with your installation, use Oracle Database Configuration Assistant (Oracle DBCA).

```
$ cd $ORACLE_HOME/bin
$ ./dbca
```

3. To remove any listeners associated with your installation, run Oracle Net Configuration Assistant (Oracle NETCA).

```
$ cd $ORACLE_HOME/bin  
$ ./netca
```

4. Log in as `root` and run the `yum` command again to remove the rpm-based database installation.

```
# yum -y remove oracle-database-ee-19c
```

#### Related Topics

- [Deleting a Database Using Oracle DBCA](#)
- [Using Oracle Net Configuration Assistant](#)

## Deinstalling Previous Release Grid Home

Use this procedure to deinstall the previous release Grid home.

For upgrades from previous releases, if you want to deinstall the previous release Grid home, then perform the following steps:

1. Log in as the `root` user.
2. Manually change the permissions of the previous release Grid home.

```
# chmod -R 775 /u01/app/oracle/product/18.0.0/grid  
# chown -R oracle:oinstall /u01/app/oracle/product/18.0.0/grid  
# chown oracle /u01/app/oracle/product/18.0.0
```

In this example:

- `/u01/app/oracle/product/18.0.0/grid` is the previous release Oracle Grid Infrastructure for a standalone server home
  - `oracle` is the Oracle Grid Infrastructure installation owner user
  - `oinstall` is the name of the Oracle Inventory group (OINSTALL group)
  - `/u01/app/oracle/product/18.0.0` is the parent directory of the previous Grid home.
3. Log in as the Oracle Grid Infrastructure software owner user (`oracle`) and run the `deinstall` command.

# A

## Completing Preinstallation Tasks Manually

You can complete the preinstallation configuration tasks manually.

Oracle recommends that you use Oracle Universal Installer and Cluster Verification Utility fixup scripts to complete minimal configuration settings. If you cannot use fixup scripts, then complete minimum system settings manually.

- [Configuring Shell Limits and System Configuration Parameters for IBM AIX](#)  
These topics explain how to configure shell limits and system configuration parameters manually if you cannot complete them using the fixup scripts.
- [Checking Asynchronous Input Output Processes](#)  
On IBM AIX 6 and IBM AIX 7, the Asynchronous Input Output (AIO) device drivers are enabled by default. For both IBM AIX 6 and IBM AIX 7, increase the number of `aio_server` processes from the default value. The recommended value for `aio_maxreqs` is 64k (65536). Confirm this value for both IBM AIX 6 and IBM AIX 7.
- [Setting UDP and TCP Kernel Parameters Manually](#)  
If you do not use a Fixup script or CVU to set ephemeral ports, then use NDD to ensure that the kernel TCP/IP ephemeral port range is broad enough to provide enough ephemeral ports for the anticipated server workload.

## Configuring Shell Limits and System Configuration Parameters for IBM AIX

These topics explain how to configure shell limits and system configuration parameters manually if you cannot complete them using the fixup scripts.

### Note:

The parameter and shell limit values shown in this section are recommended values only. For production database systems, Oracle recommends that you tune these values to optimize the performance of the system. See your operating system documentation for more information about tuning kernel parameters.

- [Configuring Shell Limits on IBM AIX](#)  
For IBM AIX on POWER Systems (64-Bit), it is the `ulimit` settings that determine process memory related resource limits. Use these instructions to display and change the shell limit values if they are different from the recommended value.
- [Configuring System Configuration Parameters for IBM AIX](#)  
Use these instructions to verify and set the system configuration values manually if they are different from the minimum recommended value.



## Configuring Shell Limits on IBM AIX

For IBM AIX on POWER Systems (64-Bit), it is the `ulimit` settings that determine process memory related resource limits. Use these instructions to display and change the shell limit values if they are different from the recommended value.

Set shell limits for the Oracle Grid Infrastructure installation owner and for `root`. Verify that `unlimited` is set for both accounts either by using the `smit` utility or by editing the `/etc/security/limits` file. The root user requires these settings because the crs daemon (`crsd`) runs as `root`.

Verify that the shell limits displayed in the following table are set to the values shown:

**Table A-1 Recommended Shell Limit Values**

Shell Limit (As Shown in <code>smit</code> )	Recommended Value
Soft File Descriptors	at least 1024
Hard File Descriptors	at least 65536
Number of processes (Soft)	at least 2047
Number of processes (Hard)	at least 16384
Soft STACK size	at least 10240 KB
Hard STACK size	at least 10240 KB; at most 32768 KB
Soft FILE size	unlimited
Soft CPU time	unlimited
Soft DATA segment	unlimited
Soft Real Memory size	unlimited



**Note:**

This is the default value.

To display the current value specified for these shell limits, and to change them if necessary

1. Enter the following command:

```
# smit chuser
```

2. In the **User NAME** field, enter the user name of the Oracle software owner, for example `oracle`.
3. Scroll down the list and verify the values shown for the limits listed in the previous table.

If necessary, edit the existing value. To edit the values, you can use the `smit` utility.

However, to set the value of Soft Real Memory size, you must edit the file `/etc/security/limits`. If you have permissions to run the `smit` utility, then you automatically have the permissions to edit the limits file.

4. When you have finished making changes, press `F10` to exit.

## Configuring System Configuration Parameters for IBM AIX

Use these instructions to verify and set the system configuration values manually if they are different from the minimum recommended value.

If you cannot use the Fixup scripts, then verify that the kernel parameters shown in the following table are set to values greater than or equal to the minimum value shown. If the current value for any parameter is greater than the value listed in this table, then the Fixup scripts do not change the value of that parameter.

**Table A-2 Minimum System Configuration Parameter Values**

Parameter	Minimum Value
maxuprocs	16384
ncargs	128

To verify and set the values manually:

1. To verify that the maximum number of processes allowed per user is set to 16384 or greater:

 **Note:**

For production systems, this value should be at least 128 plus the sum of the `PROCESSES` and `PARALLEL_MAX_SERVERS` initialization parameters for each database running on the system.

- a. Enter the following command:

```
# smit chgsys
```

- b. Verify that the value shown for `Maximum number of PROCESSES` allowed per user is greater than or equal to 16384.

If necessary, edit the existing value.

- c. When you have finished making changes, press `F10` to exit.

2. To verify that long commands can be run from the shell, perform the following steps:

 **Note:**

Oracle recommends that you set the `ncargs` system attribute to a value greater than or equal to 128. The `ncargs` attribute determines the maximum number of values that can be passed as command line arguments.

- a. Enter the following command:

```
# smit chgsys
```

- b. Verify that the value shown for `ARG/ENV list size` in 4K byte blocks is greater than or equal to 128.  
If necessary, edit the existing value.
- c. When you have finished making changes, press `F10` to exit.

## Checking Asynchronous Input Output Processes

On IBM AIX 6 and IBM AIX 7, the Asynchronous Input Output (AIO) device drivers are enabled by default. For both IBM AIX 6 and IBM AIX 7, increase the number of `aio_server` processes from the default value. The recommended value for `aio_maxreqs` is 64k (65536). Confirm this value for both IBM AIX 6 and IBM AIX 7.

Confirm the `aio_maxreqs` value using the following procedure:

```
# ioo -o aio_maxreqs  
aio_maxreqs = 65536
```

When performing an asynchronous I/O to a file system, each asynchronous I/O operation is tied to an asynchronous I/O server. Thus, the number of asynchronous I/O servers limits the number of concurrent asynchronous I/O operations in the system.

The initial number of servers that are started during a system restart is determined by the `aio_minserver`s parameter. As concurrent asynchronous I/O operations occur, additional asynchronous I/O servers are started, up to a maximum of the value set in the `aio_maxserver`s parameter.

In general, to set the number of asynchronous I/O servers, complete the following procedure:

1. Adjust the initial value of `aio_maxserver`s to 10 times the number of logical disks divided by the number of CPUs that are to be used concurrently but no more than 80.
2. Monitor the performance effects on the system during periods of high I/O activity. If all AIO server processes are started, then increase the `aio_maxserver`s value. Also, continue to monitor the system performance during peak I/O activity to determine if there was a benefit from the additional AIO servers. Too many asynchronous I/O servers increase memory and processor overload of additional processes, but this disadvantage is small.

See your operating system vendor documentation for information about tuning AIO parameters.

To monitor the number of AIO server processes that have started, enter the following:

```
# ps -ek|grep -v grep|grep -v posix_aio_server|grep -c aio_server
```

## Setting UDP and TCP Kernel Parameters Manually

If you do not use a Fixup script or CVU to set ephemeral ports, then use NDD to ensure that the kernel TCP/IP ephemeral port range is broad enough to provide enough ephemeral ports for the anticipated server workload.

Ensure that the lower range is set to at least 9000 or higher, to avoid Well Known ports, and to avoid ports in the Registered Ports range commonly used by Oracle and other server ports. Set the port range high enough to avoid reserved ports for any applications you may intend to use. If the lower value of the range you have is greater than 9000, and the range is large

enough for your anticipated workload, then you can ignore OUI warnings regarding the ephemeral port range.

1. Use the following commands to check your current range for ephemeral ports:

```
# /usr/sbin/no -a | fgrep ephemeral
tcp_ephemeral_low = 32768
tcp_ephemeral_high = 65500
udp_ephemeral_low = 32768
udp_ephemeral_high = 65500
```

In the preceding example, the TCP and UDP ephemeral ports are set to the default range (32768-65536).

2. If you expect your workload to require a high number of ephemeral ports, such as high node counts or heavy use of Parallel Query, then update the UDP and TCP ephemeral port range to a broader range. For example:

```
# /usr/sbin/no -p -o tcp_ephemeral_low=9000 -o tcp_ephemeral_high=65500
# /usr/sbin/no -p -o udp_ephemeral_low=9000 -o udp_ephemeral_high=65500
```

# B

## Response Files

Review the following topics to install and configure Oracle Database, Oracle Grid Infrastructure, and other Oracle products using response files.

- [How Response Files Work](#)  
Response files can assist you with installing an Oracle product multiple times on multiple computers.
- [Reasons for Using Silent Mode or Response File Mode](#)  
Review this section for use cases for running the installer in silent mode or response file mode.
- [Using Response Files](#)  
Review this information to use response files.
- [Preparing Response Files](#)  
Review this information to prepare response files for use during silent mode or response file mode installations.
- [Running Oracle Universal Installer Using a Response File](#)  
After creating the response file, run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation.
- [Running Configuration Assistants Using Response Files](#)  
You can run configuration assistants in response file or silent mode to configure and start Oracle software after it is installed on the system. To run configuration assistants in response file or silent mode, you must copy and edit a response file template.
- [Postinstallation Configuration Using Response File Created During Installation](#)  
Use response files to configure Oracle software after installation. You can use the same response file created during installation to also complete postinstallation configuration.
- [Postinstallation Configuration Using the ConfigToolAllCommands Script](#)  
You can create and run a response file configuration after installing Oracle software. The `configToolAllCommands` script requires users to create a second response file, of a different format than the one used for installing the product.

## How Response Files Work

Response files can assist you with installing an Oracle product multiple times on multiple computers.

When you start Oracle Universal Installer (OUI), you can use a response file to automate the installation and configuration of Oracle software, either fully or partially. OUI uses the values contained in the response file to provide answers to some or all installation prompts.

Typically, the installer runs in interactive mode, which means that it prompts you to provide information in graphical user interface (GUI) screens. When you use response files to provide this information, you run the installer from a command prompt using either of the following modes:

- Silent mode

If you include responses for all of the prompts in the response file and specify the `-silent` option when starting the installer, then it runs in silent mode. During a silent mode installation, the installer does not display any screens. Instead, it displays progress information in the terminal that you used to start it.

- Response file mode

If you include responses for some or all of the prompts in the response file and omit the `-silent` option, then the installer runs in response file mode. During a response file mode installation, the installer displays all the screens, screens for which you specify information in the response file, and also screens for which you did not specify the required information in the response file.

You define the settings for a silent or response file installation by entering values for the variables listed in the response file. For example, to specify the Oracle home name, provide the Oracle home path for the `ORACLE_HOME` environment variable:

```
ORACLE_HOME=/u01/app/oracle/product/19.0.0/dbhome_1
```

## Reasons for Using Silent Mode or Response File Mode

Review this section for use cases for running the installer in silent mode or response file mode.

Mode	Uses
Silent	<p>Use silent mode for the following installations:</p> <ul style="list-style-type: none"> <li>• Complete an unattended installation, which you schedule using operating system utilities such as <code>at</code>.</li> <li>• Complete several similar installations on multiple systems without user interaction.</li> <li>• Install the software on a system that does not have X Window System software installed on it.</li> </ul> <p>The installer displays progress information on the terminal that you used to start it, but it does not display any of the installer screens.</p>
Response file	<p>Use response file mode to complete similar Oracle software installations on more than one system, providing default answers to some, but not all of the installer prompts.</p>

## Using Response Files

Review this information to use response files.

Use the following general steps to install and configure Oracle products using the installer in silent or response file mode:



**Note:**

You must complete all required preinstallation tasks on a system before running the installer in silent or response file mode.

1. Prepare a response file.
2. Run the installer in silent or response file mode.

3. Run the root scripts as prompted by Oracle Universal Installer.
4. If you completed a software-only installation, then run Net Configuration Assistant and Oracle DBCA in silent or response file mode to create the database listener and an Oracle Database instance respectively.

## Preparing Response Files

Review this information to prepare response files for use during silent mode or response file mode installations.

- [Editing a Response File Template](#)  
Oracle provides response file templates for each product and each configuration tool.
- [Recording Response Files](#)  
You can use OUI in interactive mode to record response files, which you can then edit and use to complete silent mode or response file mode installations. This method is useful for Advanced or software-only installations.

## Editing a Response File Template

Oracle provides response file templates for each product and each configuration tool.

### About Response File Templates

For Oracle Database, the response file templates are located in the `$ORACLE_HOME/install/response` directory. For Oracle Grid Infrastructure, the response file templates are located in the `Grid_home/install/response` directory.

Where, `Grid_home` is the Oracle Grid Infrastructure home directory path.



#### Note:

If you copied the software to a hard disk, then the response files are located in the `$ORACLE_HOME/install/response` directory.

All response file templates contain comment entries, sample formats, examples, and other useful instructions. Read the response file instructions to understand how to specify values for the response file variables, so that you can customize your installation.

The following table lists the response files provided with this software:

**Table B-1 Response Files for Oracle Database and Oracle Grid Infrastructure**

Response File	Description
<code>db_install.rsp</code>	Silent installation of Oracle Database.
<code>dbca.rsp</code>	Silent creation and configuration of Oracle Database using Oracle DBCA.
<code>netca.rsp</code>	Silent configuration of Oracle Net using Oracle NETCA.
<code>gridsetup.rsp</code>	Silent configuration of Oracle Grid Infrastructure installations.

 **Caution:**

When you modify a response file template and save a file for use, the response file may contain plain text passwords. Ownership of the response file should be given to the Oracle software installation owner only, and permissions on the response file should be changed to 600. Oracle strongly recommends that database administrators or other administrators delete or secure response files when they are not in use.

To copy and modify a response file:

1. Copy the response file from the response file directory to a directory on your system:  
For example, for Oracle Database:

```
$ cp $ORACLE_HOME/install/response/db_install.rsp local_directory
```

2. Open the response file in a text editor:  

```
$ vi /local_directory/db_install.rsp
```
3. Follow the instructions in the file to edit it.

 **Note:**

The installer or configuration assistant fails if you do not correctly configure the response file. Also, ensure that your response file name has the `.rsp` suffix.

4. Secure the response file by changing the permissions on the file to 600:

```
$ chmod 600 /local_dir/db_install.rsp
```

Ensure that only the Oracle software owner user can view or modify response files or consider deleting them after the installation succeeds.

 **Note:**

A fully-specified response file for an Oracle Database installation contains the passwords for database administrative accounts and for a user who is a member of the OSDBA group (required for automated backups).

## Recording Response Files

You can use OUI in interactive mode to record response files, which you can then edit and use to complete silent mode or response file mode installations. This method is useful for Advanced or software-only installations.

You can save all the installation steps into a response file during installation by clicking **Save Response File** on the Summary page. You can use the generated response file for a silent installation later.

When you record the response file, you can either complete the installation, or you can exit from the installer on the Summary page, before OUI starts to set up the software to the system.



If you use record mode during a response file mode installation, then the installer records the variable values that were specified in the original source response file into the new response file.

**Note:**

OUI does not save passwords while recording the response file.

To record a response file:

1. Complete preinstallation tasks as for a standard installation.

When you run the installer to record a response file, it checks the system to verify that it meets the requirements to install the software. For this reason, Oracle recommends that you complete all of the required preinstallation tasks and record the response file while completing an installation.

2. Ensure that the Oracle software owner user (typically `oracle`) has permissions to create or write to the Oracle home path that you specify when you run the installer.
3. On each installation screen, specify the required information.
4. When the installer displays the Summary screen, perform the following steps:
  - a. Click **Save Response File**. In the window, specify a file name and location for the new response file. Click **Save** to write the responses you entered to the response file.
  - b. Click **Finish** to continue with the installation.

Click **Cancel** if you do not want to continue with the installation. The installation stops, but the recorded response file is retained.

**Note:**

Ensure that your response file name has the `.rsp` suffix.

5. Before you use the saved response file on another system, edit the file and make any required changes. Use the instructions in the file as a guide when editing it.

## Running Oracle Universal Installer Using a Response File

After creating the response file, run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation.

Run Oracle Universal Installer at the command line, specifying the response file you created. The Oracle Universal Installer executables, `runInstaller` and `gridSetup.sh`, provide several options. For help information on the full set of these options, run the `gridSetup.sh` or `runInstaller` command with the `-help` option. For example:

- For Oracle Database:

```
$ $ORACLE_HOME/runInstaller -help
```

- For Oracle Grid Infrastructure:

```
$ /u01/app/oracle/product/19.0.0/grid/gridSetup.sh -help
```

The help information appears in a window after some time.

To run the installer using a response file:

1. Complete the preinstallation tasks for a normal installation.
2. Log in as the software installation owner user.
3. If you are completing a response file mode installation, then set the operating system `DISPLAY` environment variable for the user running the installation.

 **Note:**

You do not have to set the `DISPLAY` environment variable if you are completing a silent mode installation.

4. To start the installer in silent or response file mode, enter a command similar to the following:

- For Oracle Database:

```
$ $ORACLE_HOME/runInstaller [-silent] \  
-responseFile responsefilename
```

- For Oracle Grid Infrastructure:

```
$ /u01/app/oracle/product/19.0.0/grid/gridSetup.sh [-silent] \  
-responseFile responsefilename
```

 **Note:**

Do not specify a relative path to the response file. If you specify a relative path, then the installer fails.

In this example:

- `-silent` runs the installer in silent mode.
  - `responsefilename` is the full path and file name of the installation response file that you configured.
5. If this is the first time you are installing Oracle software on your system, then Oracle Universal Installer prompts you to run the `oraInstRoot.sh` script.

Log in as the `root` user and run the `oraInstRoot.sh` script:

```
$ su root  
password:  
# /u01/app/oraInventory/oraInstRoot.sh
```

 **Note:**

You do not have to manually create the `oraInst.loc` file. Running the `oraInstRoot.sh` script is sufficient as it specifies the location of the Oracle Inventory directory.

6. When the installation completes, log in as the `root` user and run the `root.sh` script. For example:

```
$ su root
password:
# $ORACLE_HOME/root.sh
```

## Running Configuration Assistants Using Response Files

You can run configuration assistants in response file or silent mode to configure and start Oracle software after it is installed on the system. To run configuration assistants in response file or silent mode, you must copy and edit a response file template.

 **Note:**

If you copied the software to a hard disk, then the response file template is located in the `$ORACLE_HOME/install/response` directory.

- [Running Net Configuration Assistant Using Response Files](#)  
You can run NETCA in silent mode to configure and start an Oracle Net Listener on the system, and configure naming methods and Oracle Net service names.
- [Running Oracle DBCA Using Response Files](#)  
You can run Oracle Database Configuration Assistant (Oracle DBCA) in response file mode to configure and start an Oracle database on the system.

## Running Net Configuration Assistant Using Response Files

You can run NETCA in silent mode to configure and start an Oracle Net Listener on the system, and configure naming methods and Oracle Net service names.

To run Oracle Net Configuration Assistant (NETCA) in silent mode, you must copy and edit a response file template. Oracle provides a response file template named `netca.rsp` in the `$ORACLE_HOME/assistants/netca` directory.

To run Net Configuration Assistant using a response file:

1. Copy the `netca.rsp` response file template from the response file directory to a directory on your system:

```
$ cp $ORACLE_HOME/assistants/netca/netca.rsp local_directory
```

2. Open the response file in a text editor:

```
$ vi /local_directory/netca.rsp
```

3. Follow the instructions in the file to edit it.

 **Note:**

Net Configuration Assistant fails if you do not correctly configure the response file.

4. Log in as the Oracle software owner user, and set the `ORACLE_HOME` environment variable to specify the correct Oracle home directory.
5. Enter a command similar to the following to run Net Configuration Assistant in silent mode:

```
$ $ORACLE_HOME/bin/netca -silent -responsefile /local_directory/netca.rsp
```

In this command:

- The `/silent` option indicates to run Net Configuration Assistant in silent mode.
- `local_directory` is the full path of the directory where you copied the `netca.rsp` response file template.

## Running Oracle DBCA Using Response Files

You can run Oracle Database Configuration Assistant (Oracle DBCA) in response file mode to configure and start an Oracle database on the system.

To run Oracle DBCA in response file mode, you must copy and edit a response file template. Oracle provides a response file template named `dbca.rsp` in the `ORACLE_HOME/assistants/dbca` directory. To run Oracle DBCA in response file mode, you must use the `-responseFile` flag in combination with the `-silent` flag. You must also use a graphical display and set the `DISPLAY` environment variable.

To run Oracle DBCA in response file mode:

1. Copy the `dbca.rsp` response file template from the response file directory to a directory on your system:

```
$ cp /directory_path/assistants/dbca/dbca.rsp local_directory
```

In this example, `directory_path` is the path of the directory where you have copied the installation binaries.

As an alternative to editing the response file template, you can also create a database by specifying all required information as command line options when you run Oracle DBCA. For information about the list of options supported, enter the following command:

```
$ $ORACLE_HOME/bin/dbca -help
```

2. Open the response file in a text editor:

```
$ vi /local_dir/dbca.rsp
```

3. Follow the instructions in the file to edit the file.

 **Note:**

Oracle DBCA fails if you do not correctly configure the response file.

4. Log in as the Oracle software owner user, and set the `ORACLE_HOME` environment variable to specify the correct Oracle home directory.
5. To run Oracle DBCA in response file mode, set the `DISPLAY` environment variable.
6. Use the following command syntax to run Oracle DBCA in silent or response file mode using a response file:

```
$ORACLE_HOME/bin/dbca [-silent] -createDatabase -responseFile /local_dir/  
dbca.rsp
```

In this example:

- `-silent` option indicates that Oracle DBCA runs in silent mode.
- `local_dir` is the full path of the directory where you copied the `dbca.rsp` response file template.

During configuration, Oracle DBCA displays a window that contains the status messages and a progress bar.

## Postinstallation Configuration Using Response File Created During Installation

Use response files to configure Oracle software after installation. You can use the same response file created during installation to also complete postinstallation configuration.

- [Using the Installation Response File for Postinstallation Configuration](#)  
Starting with Oracle Database 12c release 2 (12.2), you can use the response file created during installation to also complete postinstallation configuration.
- [Running Postinstallation Configuration Using Response File](#)  
You can use a response file to complete postinstallation tasks on one or more servers simultaneously.

## Using the Installation Response File for Postinstallation Configuration

Starting with Oracle Database 12c release 2 (12.2), you can use the response file created during installation to also complete postinstallation configuration.

Run the installer with the `-executeConfigTools` option to configure configuration assistants after installing Oracle Grid Infrastructure or Oracle Database. You can use the response file located at `$ORACLE_HOME/install/response/product_timestamp.rsp` to obtain the passwords required to run the configuration tools. You must update the response file with the required passwords before running the `-executeConfigTools` command.

Oracle strongly recommends that you maintain security with a password response file:

- Permissions on the response file should be set to 600.
- The owner of the response file should be the installation owner user, with the group set to the central inventory (`oraInventory`) group.

**Example B-1 Response File Passwords for Oracle Grid Infrastructure (grid user)**

```
grid.install.crs.config.ipmi.bmcPassword=password  
grid.install.asm.SYSASMPassword=password  
grid.install.asm.monitorPassword=password  
grid.install.config.emAdminPassword=password
```

If you do not have a BMC card, or you do not want to enable IPMI, then leave the `ipmi.bmcPassword` input field blank.

If you do not want to enable Oracle Enterprise Manager for management, then leave the `emAdminPassword` password field blank.

**Example B-2 Response File Passwords for Oracle Grid Infrastructure for a Standalone Server (oracle user)**

```
oracle.install.asm.SYSASMPassword=password  
oracle.install.asm.monitorPassword=password  
oracle.install.config.emAdminPassword=password
```

If you do not want to enable Oracle Enterprise Manager for management, then leave the `emAdminPassword` password field blank.

**Example B-3 Response File Passwords for Oracle Database (oracle user)**

This example illustrates the passwords to specify for use with the database configuration assistants.

```
oracle.install.db.config.starterdb.password.SYS=password  
oracle.install.db.config.starterdb.password.SYSTEM=password  
oracle.install.db.config.starterdb.password.DBSNMP=password  
oracle.install.db.config.starterdb.password.PDBADMIN=password  
oracle.install.db.config.starterdb.emAdminPassword=password  
oracle.install.db.config.asm.ASMSNMPPassword=password
```

You can also specify `oracle.install.db.config.starterdb.password.ALL=password` to use the same password for all database users.

The database configuration assistants require the SYS, SYSTEM, and DBSNMP passwords for use with Oracle DBCA. You must specify the following passwords, depending on your system configuration:

- If the database uses Oracle Automatic Storage Management (Oracle ASM) for storage, then you must specify a password for the `ASMSNMPPassword` variable. If you are not using Oracle ASM, then leave the value for this password variable blank.
- If you create a multitenant container database (CDB) with one or more pluggable databases (PDBs), then you must specify a password for the `PDBADMIN` variable. If you are not using Oracle ASM, then leave the value for this password variable blank.

## Running Postinstallation Configuration Using Response File

You can use a response file to complete postinstallation tasks on one or more servers simultaneously.

Complete this procedure to run configuration assistants with the `executeConfigTools` command and a response file.

1. Edit the response file and specify the required passwords for your configuration. You can use the response file created during installation, located at `$ORACLE_HOME/install/response/product_timestamp.rsp`. For example:

For Oracle Database (oracle user)

```
oracle.install.asm.SYSASMPassword=password  
oracle.install.config.emAdminPassword=password
```

For Oracle Grid Infrastructure (grid user)

```
grid.install.asm.SYSASMPassword=password  
grid.install.config.emAdminPassword=password
```

2. Change directory to the Oracle home containing the installation software. For example:

For Oracle Grid Infrastructure:

```
cd Grid_home
```

Where, *Grid\_home* is the path to the Oracle Grid Infrastructure home directory `/u01/app/oracle/product/19.0.0/grid`

For Oracle Database:

```
cd $ORACLE_HOME
```

3. Run the configuration script using the following syntax:

For Oracle Grid Infrastructure:

```
$ ./gridSetup.sh -executeConfigTools -responseFile Grid_home/install/  
response/product_timestamp.rsp
```

For Oracle Database:

```
$ ./runInstaller -executeConfigTools -responseFile $ORACLE_HOME/install/  
response/product_timestamp.rsp
```

For Oracle Database, you can also run the response file located in the directory `$ORACLE_HOME/inventory/response/`:

```
$ ./runInstaller -executeConfigTools -responseFile $ORACLE_HOME/inventory/  
response/db_install.rsp
```

The postinstallation configuration tool runs the installer in the graphical user interface mode, displaying the progress of the postinstallation configuration. Specify the `[-silent]` option to run the postinstallation configuration in the silent mode.

For example, for Oracle Grid Infrastructure:

```
$ ./gridSetup.sh -executeConfigTools -responseFile /u01/app/oracle/product/19.0.0/grid/response/grid_2016-01-09_01-03-36PM.rsp [-silent]
```

For Oracle Database:

```
$ ./runInstaller -executeConfigTools -responseFile /u01/app/oracle/product/19.0.0/dbhome_1/inventory/response/db_2016-01-09_01-03-36PM.rsp [-silent]
```

## Postinstallation Configuration Using the ConfigToolAllCommands Script

You can create and run a response file configuration after installing Oracle software. The `configToolAllCommands` script requires users to create a second response file, of a different format than the one used for installing the product.

Starting with Oracle Database 12c Release 2 (12.2), the `configToolAllCommands` script is deprecated and may be desupported in a future release.

- [About the Postinstallation Configuration File](#)  
When you run a silent or response file installation, you provide information about your servers in a response file that you otherwise provide manually during a graphical user interface installation.
- [Creating a Password Response File](#)  
You can create a password response file and use it with configuration assistants to perform silent installation.
- [Running Postinstallation Configuration Using a Password Response File](#)  
Complete this procedure to run configuration assistants with the `configToolAllCommands` script.

### About the Postinstallation Configuration File

When you run a silent or response file installation, you provide information about your servers in a response file that you otherwise provide manually during a graphical user interface installation.

However, the response file does not contain passwords for user accounts that configuration assistants require after software installation is complete. The configuration assistants are started with a script called `configToolAllCommands`. You can run this script in response file mode by using a password response file. The script uses the passwords to run the configuration tools in succession to complete configuration.

If you keep the password file to use for clone installations, then Oracle strongly recommends that you store the password file in a secure location. In addition, if you have to stop an installation to fix an error, then you can run the configuration assistants using `configToolAllCommands` and a password response file.

The `configToolAllCommands` password response file has the following syntax options:



- `oracle.crs` for Oracle Grid Infrastructure components or `oracle.server` for Oracle Database components that the configuration assistants configure
- `variable_name` is the name of the configuration file variable
- `value` is the desired value to use for configuration.

The command syntax is as follows:

```
internal_component_name|variable_name=value
```

For example:

```
oracle.crs|S_ASMPASSWORD=PassWord
```

The database configuration assistants require the SYS, SYSTEM, and DBSNMP passwords for use with Oracle DBCA. You may need to specify the following additional passwords, depending on your system configuration:

- If the database is using Oracle Automatic Storage Management (Oracle ASM) for storage, then you must specify a password for the `S_ASMSNMPPASSWORD` variable. If you are not using Oracle ASM, then leave the value for this password variable blank.
- If you create a multitenant container database (CDB) with one or more pluggable databases (PDBs), then you must specify a password for the `S_PDBADMINPASSWORD` variable. If you are not using Oracle ASM, then leave the value for this password variable blank.

Oracle strongly recommends that you maintain security with a password response file:

- Permissions on the response file should be set to 600.
- The owner of the response file should be the installation owner user, with the group set to the central inventory (`oraInventory`) group.

## Creating a Password Response File

You can create a password response file and use it with configuration assistants to perform silent installation.

Perform the following steps to create a password response file:

1. Create a response file that has a name of the format `filename.properties`, for example:

```
$ touch pwrsp.properties
```

2. Open the file with a text editor, and cut and paste the sample password file contents, as shown in the examples, modifying as needed.

3. Change permissions to secure the password response file. For example:

```
$ ls -al pwrsp.properties
-rw----- 1 oracle oinstall 0 Apr 30 17:30 pwrsp.properties
```

### Example B-4 Password response file for Oracle Grid Infrastructure (grid user)

```
grid.crs|S_ASMPASSWORD=password
grid.crs|S_OMSPASSWORD=password
```

```
grid.crs|S_BMCPASSWORD=password  
grid.crs|S_ASMMONITORPASSWORD=password
```

If you do not have a BMC card, or you do not want to enable IPMI, then leave the `S_BMCPASSWORD` input field blank.

#### **Example B-5 Password response file for Oracle Grid Infrastructure for a Standalone Server (oracle user)**

```
oracle.crs|S_ASMPASSWORD=password  
oracle.crs|S_OMSPASSWORD=password  
oracle.crs|S_ASMMONITORPASSWORD=password
```

#### **Example B-6 Password response file for Oracle Database (oracle user)**

This example provides a template for a password response file to use with the database configuration assistants.

```
oracle.server|S_SYSPASSWORD=password  
oracle.server|S_SYSTEMPASSWORD=password  
oracle.server|S_EMADMINPASSWORD=password  
oracle.server|S_DBSNMPPASSWORD=password  
oracle.server|S_ASMSNMPPASSWORD=password  
oracle.server|S_PDBADMINPASSWORD=password
```

If you do not want to enable Oracle Enterprise Manager for management, then leave those password fields blank.

## Running Postinstallation Configuration Using a Password Response File

Complete this procedure to run configuration assistants with the `configToolAllCommands` script.

1. Create a password response file as described in *Creating a Password File*.
2. Change directory to `$ORACLE_HOME/cfgtoollogs`.
3. Run the configuration script using the following syntax:

```
configToolAllCommands RESPONSE_FILE=/path/name.properties
```

For example:

```
$ ./configToolAllCommands RESPONSE_FILE=/home/oracle/pwdrsp.properties
```

# C

## Optimal Flexible Architecture

Oracle Optimal Flexible Architecture (OFA) rules are a set of configuration guidelines created to ensure well-organized Oracle installations, which simplifies administration, support and maintenance.

- [About the Optimal Flexible Architecture Standard](#)  
Oracle Optimal Flexible Architecture (OFA) rules help you to organize database software and configure databases to allow multiple databases, of different versions, owned by different users to coexist.
- [About Multiple Oracle Homes Support](#)  
Oracle Database supports multiple Oracle homes. You can install this release or earlier releases of the software more than once on the same system, in different Oracle home directories.
- [About the Oracle Inventory Directory and Installation](#)  
The directory that you designate as the Oracle Inventory directory (oraInventory) stores an inventory of all software installed on the system.
- [Oracle Base Directory Naming Convention](#)  
The Oracle Base directory is the database home directory for Oracle Database installation owners, and the log file location for Oracle Grid Infrastructure owners.
- [Oracle Home Directory Naming Convention](#)  
By default, Oracle Universal Installer configures Oracle home directories using these Oracle Optimal Flexible Architecture conventions.
- [Optimal Flexible Architecture File Path Examples](#)  
Review examples of hierarchical file mappings of an Optimal Flexible Architecture-compliant installation.

### About the Optimal Flexible Architecture Standard

Oracle Optimal Flexible Architecture (OFA) rules help you to organize database software and configure databases to allow multiple databases, of different versions, owned by different users to coexist.

In earlier Oracle Database releases, the OFA rules provided optimal system performance by isolating fragmentation and minimizing contention. In current releases, OFA rules provide consistency in database management and support, and simplifies expanding or adding databases, or adding additional hardware.

By default, Oracle Universal Installer places Oracle Database components in directory locations and with permissions in compliance with OFA rules. Oracle recommends that you configure all Oracle components in accordance with OFA guidelines.

Oracle recommends that you accept the OFA default. Following OFA rules is especially of value if the database is large, or if you plan to have multiple databases.

**Note:**

OFA assists in identification of an ORACLE\_BASE with its Automatic Diagnostic Repository (ADR) diagnostic data to properly collect incidents.

## About Multiple Oracle Homes Support

Oracle Database supports multiple Oracle homes. You can install this release or earlier releases of the software more than once on the same system, in different Oracle home directories.

Careful selection of mount point names can make Oracle software easier to administer. Configuring multiple Oracle homes in compliance with Optimal Flexible Architecture (OFA) rules provides the following advantages:

- You can install this release, or earlier releases of the software, more than once on the same system, in different Oracle home directories. However, you cannot install products from one release of Oracle Database into an Oracle home directory of a different release.
- Multiple databases, of different versions, owned by different users can coexist concurrently.
- To install Oracle Database software in multiple Oracle homes, you must extract the image file in each Oracle home, and then run the setup wizard from the respective Oracle home.
- You must install a new Oracle Database release in a new Oracle home that is separate from earlier releases of Oracle Database.

You cannot install multiple releases in one Oracle home. Oracle recommends that you create a separate Oracle Database Oracle home for each release, in accordance with the Optimal Flexible Architecture (OFA) guidelines.

- In production, the Oracle Database server software release is the release number in the format of major and RU release number. For example, with the release number 19.3.0.0.0, the major release is 19 and the RU release number is 3.
- Later Oracle Database releases can access earlier Oracle Database releases. However, this access is only for upgrades. For example, Oracle Database 19c can access an Oracle Database 18c if the 18c database is started up in upgrade mode.
- Structured organization of directories and files, and consistent naming for database files simplify database administration.
- Login home directories are not at risk when database administrators add, move, or delete Oracle home directories.
- For information about release support timelines, refer to My Oracle Support Doc ID 742060.1

**Related Topics**

- [My Oracle Support Note 742060.1](#)

## About the Oracle Inventory Directory and Installation

The directory that you designate as the Oracle Inventory directory (oraInventory) stores an inventory of all software installed on the system.

All Oracle software installation owners on a server are granted the OINSTALL privileges to read and write to this directory. If you have previous Oracle software installations on a server,

then additional Oracle software installations detect this directory from the `/etc/oraInst.loc` file, and continue to use that Oracle Inventory. Ensure that the group designated as the OINSTALL group is available as a primary group for all planned Oracle software installation owners.

If you are installing Oracle software for the first time, then OUI creates an Oracle base and central inventory, and creates an Oracle inventory using information in the following priority:

- In the path indicated in the `ORACLE_BASE` environment variable set for the installation owner user account
- In an Optimal Flexible Architecture (OFA) path (`u[01–99]/app/owner` where *owner* is the name of the user account running the installation), and that user account has permissions to write to that path
- In the user home directory, in the path `/app/owner`, where *owner* is the name of the user account running the installation

For example:

If you are performing an Oracle Database installation, and you set `ORACLE_BASE` for user `oracle` to the path `/u01/app/oracle` before installation, and grant 755 permissions to `oracle` for that path, then Oracle Universal Installer creates the Oracle Inventory directory one level above the `ORACLE_BASE` in the path `ORACLE_BASE/./oraInventory`, so the Oracle Inventory path is `/u01/app/oraInventory`. Oracle Universal Installer installs the software in the `ORACLE_BASE` path. If you are performing an Oracle Grid Infrastructure for a Cluster installation, then the Grid installation path is changed to `root` ownership after installation, and the Grid home software location should be in a different path from the Grid user Oracle base.

If you create the OFA path `/u01`, and grant `oracle` 755 permissions to write to that path, then the Oracle Inventory directory is created in the path `/u01/app/oraInventory`, and Oracle Universal Installer creates the path `/u01/app/oracle`, and configures the `ORACLE_BASE` environment variable for the Oracle user to that path. If you are performing an Oracle Database installation, then the Oracle home is installed under the Oracle base. However, if you are installing Oracle Grid Infrastructure for a cluster, then be aware that ownership of the path for the Grid home is changed to `root` after installation and the Grid base and Grid home should be in different locations, such as `/u01/app/19.0.0/grid` for the Grid home path, and `/u01/app/grid` for the Grid base. For example:

```
/u01/app/oraInventory, owned by grid:oinstall
/u01/app/oracle, owned by oracle:oinstall
/u01/app/oracle/product/19.0.0/dbhome_1/, owned by oracle:oinstall
/u01/app/grid, owned by grid:oinstall
/u01/app/19.0.0/grid, owned by root
```

If you have neither set `ORACLE_BASE`, nor created an OFA-compliant path, then the Oracle Inventory directory is placed in the home directory of the user that is performing the installation, and the Oracle software is installed in the path `/app/owner`, where *owner* is the Oracle software installation owner. For example:

```
/home/oracle/oraInventory
/home/oracle/app/oracle/product/19.0.0/dbhome_1
```

## Oracle Base Directory Naming Convention

The Oracle Base directory is the database home directory for Oracle Database installation owners, and the log file location for Oracle Grid Infrastructure owners.

Name Oracle base directories using the syntax `/pm/h/u`, where *pm* is a string mount point name, *h* is selected from a small set of standard directory names, and *u* is the name of the owner of the directory.

You can use the same Oracle base directory for multiple installations. If different operating system users install Oracle software on the same system, then you must create a separate Oracle base directory for each installation owner. For ease of administration, Oracle recommends that you create a unique owner for each Oracle software installation owner, to separate log files.

Because all Oracle installation owners write to the central Oracle inventory file, and that file mountpoint is in the same mount point path as the initial Oracle installation, Oracle recommends that you use the same `/pm/h` path for all Oracle installation owners.

**Table C-1 Examples of OFA-Compliant Oracle Base Directory Names**

Example	Description
<code>/u01/app/oracle</code>	Oracle Database Oracle base, where the Oracle Database software installation owner name is <code>oracle</code> . The Oracle Database binary home is located underneath the Oracle base path.
<code>/u01/app/grid</code>	Oracle Grid Infrastructure Oracle base, where the Oracle Grid Infrastructure software installation owner name is <code>grid</code> .

### Caution:

The Oracle Grid Infrastructure Oracle base should not contain the Oracle Grid Infrastructure binaries for an Oracle Grid Infrastructure for a cluster installation. Permissions for the file path to the Oracle Grid Infrastructure binary home are changed to `root` during installation.

### Note:

Oracle home or Oracle base cannot be `symlinks`, nor can any of their parent directories, all the way to up to the `root` directory.

## Oracle Home Directory Naming Convention

By default, Oracle Universal Installer configures Oracle home directories using these Oracle Optimal Flexible Architecture conventions.

The directory pattern syntax for Oracle homes is `/pm/s/u/product/v/type_[n]`. The following table describes the variables used in this syntax:

Variable	Description
<i>pm</i>	A mount point name.
<i>s</i>	A standard directory name.
<i>u</i>	The name of the owner of the directory.
<i>v</i>	The version of the software.
<i>type</i>	The type of installation. For example: Database ( <code>dbhome</code> ), Client ( <code>client</code> ), or Oracle Grid Infrastructure ( <code>grid</code> )
<i>n</i>	An optional counter, which enables you to install the same product more than once in the same Oracle base directory. For example: Database 1 and Database 2 ( <code>dbhome_1</code> , <code>dbhome_2</code> )

For example, the following path is typical for the first installation of Oracle Database on this system:

```
/u01/app/oracle/product/19.0.0/dbhome_1
```



**Note:**

Oracle home or Oracle base cannot be `symlinks`, nor can any of their parent directories, all the way to up to the `root` directory.

## Optimal Flexible Architecture File Path Examples

Review examples of hierarchical file mappings of an Optimal Flexible Architecture-compliant installation.

```
/u02/u03 /u04
```



**Note:**

- The Grid homes are examples of Grid homes used for an Oracle Grid Infrastructure for a standalone server deployment (Oracle Restart), or a Grid home used for an Oracle Grid Infrastructure for a cluster deployment (Oracle Clusterware). You can have either an Oracle Restart deployment, or an Oracle Clusterware deployment. You cannot have both options deployed at the same time.
- Oracle Automatic Storage Management (Oracle ASM) is included as part of an Oracle Grid Infrastructure installation. Oracle recommends that you use Oracle ASM to provide greater redundancy and throughput.

**Table C-2 Optimal Flexible Architecture Hierarchical File Path Examples**

Directory	Description
/	Root directory
/u01/	User data mount point 1
/u01/app/	Subtree for application software
/u01/app/oraInventory	Central OraInventory directory, which maintains information about Oracle installations on a server. Members of the group designated as the OINSTALL group have permissions to write to the central inventory. All Oracle software installation owners must have the OINSTALL group as their primary group, and be able to write to this group.
/u01/app/oracle/	Oracle base directory for user <code>oracle</code> . There can be many Oracle Database installations on a server, and many Oracle Database software installation owners.  Oracle software homes that an Oracle installation owner owns should be located in the Oracle base directory for the Oracle software installation owner, unless that Oracle software is Oracle Grid Infrastructure deployed for a cluster.
/u01/app/grid	Oracle base directory for user <code>grid</code> . The Oracle home (Grid home) for Oracle Grid Infrastructure for a cluster installation is located outside of the Grid user. There can be only one Grid home on a server, and only one Grid software installation owner.  The Grid home contains log files and other administrative files.
/u01/app/oracle/admin/	Subtree for database administration files
/u01/app/oracle/admin/TAR	Subtree for support log files
/u01/app/oracle/admin/db_sales/	Admin subtree for database named "sales"
/u01/app/oracle/admin/db_dwh/	Admin subtree for database named "dwh"



**Table C-2 (Cont.) Optimal Flexible Architecture Hierarchical File Path Examples**

Directory	Description
/u01/app/oracle/ fast_recovery_arena/	Subtree for recovery files
/u01/app/oracle/ fast_recovery_arena/db_sales	Recovery files for database named "sales"
/u01/app/oracle/ fast_recovery_arena/db_dwh	Recovery files for database named "dwh"
/u02/app/oracle/ oradata /u03/app/oracle/ oradata /u04/app/oracle/ oradata	Oracle data file directories
/u01/app/oracle/ product/	Common path for Oracle software products other than Oracle Grid Infrastructure for a cluster
/u01/app/oracle/ product/19.0.0/ dbhome_1	Oracle home directory for Oracle Database 1, owned by Oracle Database installation owner account oracle
/u01/app/oracle/ product/19.0.0/ dbhome_2	Oracle home directory for Oracle Database 2, owned by Oracle Database installation owner account oracle
/u01/app/oracle2/ product/19.0.0/ dbhome_2	Oracle home directory for Oracle Database 2, owned by Oracle Database installation owner account oracle2

**Table C-2 (Cont.) Optimal Flexible Architecture Hierarchical File Path Examples**

Directory	Description
/u01/app/oracle/ product/19.0.0/ grid	Oracle home directory for Oracle Grid Infrastructure for a standalone server, owned by Oracle Database and Oracle Grid Infrastructure installation owner <code>oracle</code> .
/u01/app/19.0.0/ grid	Oracle home directory for Oracle Grid Infrastructure for a cluster (Grid home), owned by user <code>grid</code> before installation, and owned by <code>root</code> after installation.
/u01/app/oracle/ product/19.0.0/ client_1	Oracle home directory for Oracle Database Client 1, owned by Oracle Database installation owner account <code>oracle</code>

# D

## Configuring Read-Only Oracle Homes

Understand how read-only Oracle homes work and how you can configure read-only Oracle homes.

- [Evolution of Oracle Homes](#)  
Learn about read-only Oracle home concepts like Oracle base home, Oracle base config, and orabasetab.
- [Enabling a Read-Only Oracle Home](#)  
Configure your Oracle home as a read-only Oracle home after you have performed a software-only Oracle Database installation.
- [Copying demo Directories to Oracle Base Home](#)  
In a read-only mode ORACLE\_HOME, you must copy the `demo` directories listed in this topic from ORACLE\_HOME to ORACLE\_BASE\_HOME.
- [Determining if an Oracle Home is Read-Only](#)  
Run the `orabasehome` command to determine if your Oracle home is a read/write or read-only Oracle home.
- [File Path and Directory Changes in Read-Only Oracle Homes](#)  
Examples of hierarchical file mappings in a read-only Oracle home as compared to a read/write Oracle home.

## Evolution of Oracle Homes

Learn about read-only Oracle home concepts like Oracle base home, Oracle base config, and orabasetab.

- [About Read-Only Oracle Homes](#)  
Starting with Oracle Database 18c, you can configure an Oracle home in read-only mode.
- [About Oracle Base Homes](#)  
Both, in a read-only ORACLE\_HOME and read/write ORACLE\_HOME, the user-specific files, instance-specific files, and log files reside in a location known as the ORACLE\_BASE\_HOME.
- [About Oracle Base Config](#)  
Both, in a read-only ORACLE\_HOME and read/write ORACLE\_HOME, the configuration files reside in a location known as ORACLE\_BASE\_CONFIG.
- [About orabasetab](#)  
The `orabasetab` file is used to define fundamental directories based on \$ORACLE\_HOME, ORACLE\_BASE, ORACLE\_BASE\_HOME and ORACLE\_BASE\_CONFIG.
- [Location of Networking Files in a Read-Only Oracle Home](#)  
Learn about the search order and location of networking files like `sqlnet.ora`, `tnsnames.ora`, or `listener.ora` in a read-only Oracle home.

## About Read-Only Oracle Homes

Starting with Oracle Database 18c, you can configure an Oracle home in read-only mode.

A read-only Oracle home simplifies provisioning by implementing separation of installation and configuration.

In a read-only Oracle home, all the configuration data and log files reside outside of the read-only Oracle home.

Apart from the traditional `ORACLE_BASE` and `ORACLE_HOME` directories, the following directories contain files that used to be in `ORACLE_HOME`:

- `ORACLE_BASE_HOME`
- `ORACLE_BASE_CONFIG`

 **Note:**

This feature does not affect how database administrators monitor, diagnose, and tune their system performance.

## About Oracle Base Homes

Both, in a read-only `ORACLE_HOME` and read/write `ORACLE_HOME`, the user-specific files, instance-specific files, and log files reside in a location known as the `ORACLE_BASE_HOME`.

In a read/write `ORACLE_HOME`, the `ORACLE_BASE_HOME` path is the same as the `ORACLE_HOME` directory. However, in a read-only `ORACLE_HOME`, the `ORACLE_BASE_HOME` directory is not co-located with `ORACLE_HOME` but is located at `ORACLE_BASE/homes/HOME_NAME`.

Where, `HOME_NAME` is the internal name for `ORACLE_HOME`.

For example, the networking directories `network/admin`, `network/trace`, and `network/log` are located in the `ORACLE_BASE_HOME` directory. In a read/write `ORACLE_HOME` the networking directories appear to be in `ORACLE_HOME` because `ORACLE_BASE_HOME` is co-located with `ORACLE_HOME`, whereas in a read-only `ORACLE_HOME` the networking directories are located in `ORACLE_BASE/homes/HOME_NAME`.

To print the `ORACLE_BASE_HOME` path, run the `orabasehome` command from the `$ORACLE_HOME/bin` directory:

```
$ setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/dbhome_1
$ cd $ORACLE_HOME/bin
$ ./orabasehome
```

For example:

```
$ ./orabasehome
/u01/app/oracle/homes/OraDB19Home1
```

Where, `/u01/app/oracle` is `ORACLE_BASE` and `OraDB19Home1` is `HOME_NAME`

## About Oracle Base Config

Both, in a read-only ORACLE\_HOME and read/write ORACLE\_HOME, the configuration files reside in a location known as ORACLE\_BASE\_CONFIG.

In a read/write ORACLE\_HOME, the ORACLE\_BASE\_CONFIG path is the same as the ORACLE\_HOME path because it is located at \$ORACLE\_HOME. However, in a read-only ORACLE\_HOME, the ORACLE\_BASE\_CONFIG path is the same as ORACLE\_BASE.

ORACLE\_BASE\_CONFIG/dbs contains the configuration files for ORACLE\_HOME. Each file in the dbs directory contains \$ORACLE\_SID so that the directory can be shared by many different ORACLE\_SIDs.

To print the ORACLE\_BASE\_CONFIG path, run the orabaseconfig command from the \$ORACLE\_HOME/bin directory:

```
$ setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/dbhome_1
$ cd $ORACLE_HOME/bin
$ ./orabaseconfig
```

For example:

```
$ ./orabaseconfig
/u01/app/oracle
```

Where, /u01/app/oracle is ORACLE\_BASE.

## About orabasetab

The orabasetab file is used to define fundamental directories based on \$ORACLE\_HOME, ORACLE\_BASE, ORACLE\_BASE\_HOME and ORACLE\_BASE\_CONFIG.

The orabasetab file resides in ORACLE\_HOME/install/orabasetab. To determine if an ORACLE\_HOME is read-only or read/write, you can check for the presence of the orabasetab file. The orabasetab file also defines the ORACLE\_BASE and the HOME\_NAME of the Oracle home. HOME\_NAME is the internal name for ORACLE\_HOME.

The last line in the orabasetab file, which starts with \$ORACLE\_HOME, defines the directories for \$ORACLE\_HOME. The last line consists of four fields, each separate by a colon delimiter (:).

1. The first field matches the current \$ORACLE\_HOME.
2. The second field defines the ORACLE\_BASE for the current ORACLE\_HOME.
3. The third field defines the HOME\_NAME which is used in constructing the ORACLE\_BASE\_HOME path in a read-only ORACLE\_HOME.
4. The fourth field displays N in a read/write ORACLE\_HOME and Y in a read-only ORACLE\_HOME.

In a read-only ORACLE\_HOME, the ORACLE\_BASE\_HOME path is ORACLE\_BASE/homes/HOME\_NAME and ORACLE\_BASE\_CONFIG is the same as ORACLE\_BASE.

In a read/write ORACLE\_HOME, ORACLE\_HOME, ORACLE\_BASE\_HOME and ORACLE\_BASE\_CONFIG are all the same.

### Viewing an orabasetab File

1. Log in as the Oracle installation owner user account (`oracle`).
2. Go to the `$ORACLE_HOME/install` directory.

```
$ cd /u01/app/oracle/product/19.0.0/dbhome_1/install
```

3. View the contents of the `orabasetab` file.

```
$ cat orabasetab
/u01/app/oracle/product/19.0.0/dbhome_1:/u01/app/oracle:OraDB19Home1:Y:
```

In this example, a `Y` in the fourth field at the end of the line indicates you have a read-only Oracle home.

## Location of Networking Files in a Read-Only Oracle Home

Learn about the search order and location of networking files like `sqlnet.ora`, `tnsnames.ora`, or `listener.ora` in a read-only Oracle home.

The networking directories `network/admin`, `network/trace`, and `network/log` are located in the `ORACLE_BASE_HOME` directory. In a read/write `ORACLE_HOME` the networking directories appear to be in `ORACLE_HOME` because `ORACLE_BASE_HOME` is co-located with `ORACLE_HOME`, whereas in a read-only `ORACLE_HOME` the networking directories are located in `ORACLE_BASE/homes/HOME_NAME`.

### tnsnames.ora

The order for checking the `tnsnames.ora` file in a read-only Oracle home is:

1. The directory specified by the `TNS_ADMIN` environment variable.
2. The `/etc` directory.
3. The `ORACLE_BASE_HOME/network/admin` directory.
4. The `ORACLE_HOME/network/admin` directory.

### sqlnet.ora

The order for checking the `sqlnet.ora` file in a read-only Oracle home is:

1. The directory specified by the `TNS_ADMIN` environment variable.
2. The `ORACLE_BASE_HOME/network/admin` directory.
3. The `ORACLE_HOME/network/admin` directory.

### Password Files

The search order for password files for Oracle homes is `ORACLE_BASE_CONFIG/dbs` followed by `ORACLE_HOME/dbs`. This helps prioritize to search for the password file outside of `ORACLE_HOME` when read-only Oracle home is enabled.

### Related Topics

- Overview of Local Naming Parameters

## Enabling a Read-Only Oracle Home

Configure your Oracle home as a read-only Oracle home after you have performed a software-only Oracle Database installation.

To enable a read-only Oracle home:

1. Perform a software-only Oracle Database installation.
2. Run the `roohctl -enable` script.
3. Run Oracle Database Configuration Assistant (Oracle DBCA) to create a database.

 **Note:**

Ensure that you enable read-only Oracle home before you create the database.

### Software-Only Database Installation

1. Log in as the Oracle installation owner user account (`oracle`) that you want to own the software binaries.
2. Download the Oracle Database installation image files (`db_home.zip`) to a directory of your choice. For example, you can download the image files to the `/tmp` directory.
3. Create the Oracle home directory and extract the image files that you have downloaded in to this Oracle home directory. For example:

```
$ mkdir -p /u01/app/oracle/product/19.0.0/dbhome_1
$ chown oracle:oinstall /u01/app/oracle/product/19.0.0/dbhome_1
$ cd /u01/app/oracle/product/19.0.0/dbhome_1
$ unzip -q /tmp/db_home.zip
```

 **Note:**

Ensure that the Oracle home directory path you create is in compliance with the Oracle Optimal Flexible Architecture recommendations. Also, unzip the installation image files only in this Oracle home directory that you created.

4. From the Oracle home directory, run the `runInstaller` command to start the Oracle Database installer.
5. In the Select Configuration Option screen, select **Set Up Software Only**.
6. Select your installation type. Installation screens vary depending on the installation option you select. Respond to the configuration prompts as needed.

 **Note:**

Click **Help** if you have any questions about the information you are asked to submit during installation.

### Run the roohctl Script

1. Go to the `bin` directory

```
$ cd /u01/app/oracle/product/19.0.0/dbhome_1/bin
```

2. Run the `roohctl` script to enable read-only Oracle home.

```
$ ./roohctl -enable
```

3. On Oracle Real Application Clusters (Oracle RAC) installations, run the preceding `roohctl` script on every node of the cluster. Alternatively, run the `roohctl` script with the `nodelist` option and provide the list of cluster nodes:

```
$ ./roohctl -enable -nodelist comma_separated_list_of_nodes
```

### Run Oracle Database Configuration Assistant

1. Ensure that you are still in the `bin` directory and run Oracle DBCA.

```
$ ./dbca
```

2. In the Select Database Operation screen, select **Create a Database**.
3. The configuration screens vary depending on the options you select. Respond to the prompts as needed.



#### Note:

Click **Help** if you have any questions about the information you are asked to submit during database creation.

### Related Topics

- [Oracle Database 2 Day DBA](#)

## Copying demo Directories to Oracle Base Home

In a read-only mode `ORACLE_HOME`, you must copy the `demo` directories listed in this topic from `ORACLE_HOME` to `ORACLE_BASE_HOME`.

Oracle Database contains various `demo` directories that include a variety of examples and product demonstrations that you can use to learn about the products, options, and features of Oracle Database. In a read-only mode `ORACLE_HOME`, you cannot use these `demo` directories in `ORACLE_HOME` because writes are performed to these `demo` directories when they are used.

Many of the `demo` directories are not available by default. You must install Oracle Database Examples to view and use the examples and product demonstrations.

Copy the respective `demo` directory to the corresponding location in `ORACLE_BASE_HOME`. Now, you can use this copy of the `demo` directory.



You must copy the following demo directories from ORACLE\_HOME to ORACLE\_BASE\_HOME:

- jdbc/demo
- odbc/demo
- ord/http/demo
- precomp/demo
- rdbms/demo
- sqlj/demo
- sqlplus/demo
- xdk/demo

You must also create symbolic links for the odbc/demo, precomp/demo, rdbms/demo, and xdk/demo demo directories. See the "Creating Symbolic Links" section in this topic.

### Copying demo Directories

For example, to copy the rdbms/demo directory from ORACLE\_HOME to ORACLE\_BASE\_HOME, perform the following:

1. Login as the Oracle software owner user (oracle).
2. Check if the rdbms/demo directory is copied to ORACLE\_BASE\_HOME.

```
$ ls -l -d $(orabasehome)/rdbms/demo
```

3. If the rdbms/demo directory has not been copied, then create it and copy it.

```
$ mkdir -p $(orabasehome)/rdbms
$ cp -r $ORACLE_HOME/rdbms/demo $(orabasehome)/rdbms/demo
```

Similarly, copy all the demo directories listed earlier from ORACLE\_HOME to ORACLE\_BASE\_HOME.

### Creating Symbolic Links

You must create symbolic links for the odbc/demo, precomp/demo, rdbms/demo, and xdk/demo demo directories.

For rdbms/demo, replace \$ORACLE\_HOME/rdbms/demo with a symbolic link to the copy.

1. Ensure that the symbolic link does not already exist.

```
$ ls -l -d $ORACLE_HOME/rdbms/demo
```

2. If \$ORACLE\_HOME/rdbms/demo is still the original demo directory, rename it and replace it with the symbolic link.

```
$ cd $ORACLE_HOME/rdbms
$ mv demo demo.installed
$ ln -s $(orabasehome)/rdbms/demo $ORACLE_HOME/rdbms/demo
```

For odbc/demo, replace \$ORACLE\_HOME/odbc/demo with a symbolic link to the copy.

1. Ensure that the symbolic link does not already exist.

```
$ ls -l -d $ORACLE_HOME/odbc/demo
```

2. If `$ORACLE_HOME/odbc/demo` is still the original `demo` directory, rename it and replace it with the symbolic link.

```
$ cd $ORACLE_HOME/odbc
$ mv demo demo.installed
$ ln -s $(orabasehome)/odbc/demo $ORACLE_HOME/odbc/demo
```

For `precomp/demo`, replace `$ORACLE_HOME/precomp/demo` with a symbolic link to the copy.

1. Ensure that the symbolic link does not already exist.

```
$ ls -l -d $ORACLE_HOME/precomp/demo
```

2. If `$ORACLE_HOME/precomp/demo` is still the original `demo` directory, rename it and replace it with the symbolic link.

```
$ cd $ORACLE_HOME/precomp
$ mv demo demo.installed
$ ln -s $(orabasehome)/precomp/demo $ORACLE_HOME/precomp/demo
```

The `xdk/demo` directory requires a symbolic link at `$ORACLE_HOME/xdk/include` pointing to `$(orabasehome)/xdk/include` after you copy the `xdk/demo` directory.

1. Ensure that the symbolic link does not already exist:

```
$ ls -l -d $ORACLE_HOME/xdk/include
```

2. If the symbolic link does not exist, then, run the following command:

```
$ ln -s $ORACLE_HOME/xdk/include $(orabasehome)/xdk/include
```



#### Note:

In the `plssql/demo` directory, `ncmpdemo.sql` is unusable in read-only mode.

### Copying the `init.ora` File

Copy the `init.ora` file from `ORACLE_HOME` to `ORACLE_BASE_HOME`.

1. Login as the Oracle software owner user (`oracle`).
2. Check if the `init.ora` file exists in `ORACLE_BASE_HOME`.

```
$ ls $(orabasehome)/init.ora
```

If an `init.ora` file exists in `ORACLE_BASE_HOME`, then update this `init.ora` file to be in-sync with the `$ORACLE_HOME/init.ora` file.

3. If the `init.ora` file does not exist in `ORACLE_BASE_HOME`, then copy it from `ORACLE_HOME`.

```
$ cp $ORACLE_HOME/init.ora $(orabasehome)/init.ora
```

### Related Topics

- *Oracle Database Examples Installation Guide*

## Determining if an Oracle Home is Read-Only

Run the `orabasehome` command to determine if your Oracle home is a read/write or read-only Oracle home.

If the output of the `orabasehome` command is the same as `$ORACLE_HOME`, then your Oracle home is in read/write mode. If the output displays the path `ORACLE_BASE/homes/HOME_NAME`, then your Oracle home is in read-only mode.

1. Set the `ORACLE_HOME` environment variable:

Bourne, Bash or Korn shell:

```
$ ORACLE_HOME=/u01/app/oracle/product/19.0.0/dbhome_1  
$ export ORACLE_HOME
```

C shell:

```
% setenv ORACLE_HOME /u01/app/oracle/product/19.0.0/dbhome_1
```

2. Go to the `bin` directory and run the `orabasehome` command:

```
$ cd $ORACLE_HOME/bin  
$ ./orabasehome  
/u01/app/oracle/homes/OraDB19Home1
```

In this example, the Oracle home is in read-only mode.

## File Path and Directory Changes in Read-Only Oracle Homes

Examples of hierarchical file mappings in a read-only Oracle home as compared to a read/write Oracle home.

This example shows an Optimal Flexible Architecture-compliant Oracle Database installation, for the user `oracle`, with the `ORACLE_HOME`, `ORACLE_BASE`, `ORACLE_BASE_HOME`, and `ORACLE_BASE_CONFIG` logical locations. The database files are mounted on `/u01` and the `HOME_NAME` is `OraDB19Home1`.

This example also shows the changes in the Oracle Database software defined paths of configuration files, log files, and other directories in a read-only Oracle home when compared to a read/write Oracle home.

**Table D-1 read/write and Read-Only Oracle Home File Path Examples**

<b>Directory</b>	<b>Read/Write Oracle Home File Path</b>	<b>Read-Only Oracle Home File Path</b>
ORACLE_HOME	/u01/app/oracle/ product/19.0.0/ dbhome_1	/u01/app/oracle/ product/19.0.0/ dbhome_1
ORACLE_BASE	/u01/app/oracle/	/u01/app/oracle/
ORACLE_BASE_HOME	ORACLE_HOME (or) /u01/app/oracle/ product/19.0.0/ dbhome_1	ORACLE_BASE/homes/ HOME_NAME (or) /u01/app/oracle/homes/ OraDB19Home1
ORACLE_BASE_CONFIG	ORACLE_HOME (or) /u01/app/oracle/ product/19.0.0/ dbhome_1	ORACLE_BASE (or) /u01/app/oracle/
network	ORACLE_HOME/network (or) /u01/app/oracle/ product/19.0.0/ dbhome_1/network	ORACLE_BASE_HOME/network (or) /u01/app/oracle/homes/ OraDB19Home1/network
dbms	ORACLE_HOME/dbms (or) /u01/app/oracle/ product/19.0.0/ dbhome_1/dbms	ORACLE_BASE/dbms (or) /u01/app/oracle/dbms

# E

## Managing Oracle Database Port Numbers

Review default port numbers. If needed, use these steps to change assigned ports after installation.

- [About Managing Ports](#)  
During installation, Oracle Universal Installer assigns port numbers to components from a set of default port numbers.
- [Oracle Database Component Port Numbers and Protocols](#)  
This table lists the port numbers and protocols configured for Oracle Database components during a single-instance installation. By default, the first port in the range is assigned to the component, if it is available.

### About Managing Ports

During installation, Oracle Universal Installer assigns port numbers to components from a set of default port numbers.

Many Oracle Database components and services use ports. As an administrator, it is important to know the port numbers used by these services, and to ensure that the same port number is not used by two services on your host. Enter the following command to identify the ports currently used on your computer:

```
$/bin/netstat -a
```

Most port numbers are assigned during installation. Every component and service has an allotted port range, which is the set of port numbers Oracle Database attempts to use when assigning a port. Oracle Database starts with the lowest number in the range and performs the following checks:

- Is the port used by another Oracle Database installation on the host?  
The installation may be up or down at the time. Oracle Database can still detect if the port is used.
- Is the port used by a process that is currently running?  
This can be any process on the host, even a non-Oracle Database process.
- Is the port listed in the `/etc/services` file?

If the answer to any of the preceding questions is yes, then Oracle Database moves to the next highest port in the allotted port range, and continues checking until it finds a free port.

### Oracle Database Component Port Numbers and Protocols

This table lists the port numbers and protocols configured for Oracle Database components during a single-instance installation. By default, the first port in the range is assigned to the component, if it is available.

**Table E-1 Protocols and Default Port Numbers for Oracle Database Components**

Component	Description	Default Port Number	Port Range	Protocol
Oracle Net Services Listener	Enables Oracle client connections to the database over the Oracle Net Services protocol. You can configure it during installation. To reconfigure this port, use Net Configuration Assistant.	1521	Port number changes to the next available port. Modifiable manually to any available port.	TCP
Oracle Connection Manager	Listening port for Oracle client connections to Oracle Connection Manager. It is not configured during installation, but can be configured manually by editing the <code>cman.ora</code> parameter file. This file is located under the <code>/network/admin</code> directory.	1630	1630	TCP
Oracle XML DB	The Oracle XML DB HTTP port is used if web-based applications must access an Oracle database from an HTTP listener. You must configure this port manually.	0	Configured Manually	HTTP
Oracle XML DB	The Oracle XML DB FTP is used when applications must access an Oracle database from an FTP listener. You must configure this port manually.	0	Configured Manually	FTP

**Related Topics**

- Using HTTP(S) on a Standard Port
- Using FTP on the Standard Port
- *Oracle Real Application Clusters Installation Guide for Linux and UNIX*

# Index

## Symbols

---

/tmp directory, [2-2](#)  
/usr/sbin/no, [7-2](#)

## Numerics

---

19c deprecated features, [xiv](#)

## A

---

aio\_maxreqs, [A-4](#)  
aioserver, [A-4](#)  
aliases, multiple on computers, [5-4](#)  
apply patches during install  
    apply patches during upgrade, [9-11](#), [10-7](#)  
asmdba groups  
    creating, [4-9](#)  
asmoper group  
    creating, [4-9](#)  
Asynchronous Input Output Processes, [A-4](#)  
Automatic Diagnostic Repository (ADR), [C-1](#)  
Automatic Memory Management, [10-5](#)

## B

---

backupdba group  
    creating, [4-10](#)  
Bash shell  
    default user startup file, [4-13](#)  
bash\_profile file, [4-13](#)  
binary files  
    supported storage options for, [6-1](#)  
Bourne shell  
    default user startup file, [4-13](#)

## C

---

C shell  
    default user startup file, [4-13](#)  
CDBs  
    character sets, [10-4](#)  
central inventory, [1-4](#), [C-5](#)  
    See also Oracle inventory directory  
    See also OINSTALL directory  
changing shell limit values, [A-2](#)

character sets, [10-4](#)  
Checking Asynchronous Input Output Processes,  
    [A-4](#)  
checklists  
    and installation planning, [1-1](#)  
client-server configurations, [C-2](#)  
cloning, [11-16](#)  
command syntax conventions, [xii](#)  
commands  
    asmcmd, [8-6](#)  
    root.sh, [11-8](#)  
    runcluvfy.sh, [9-6](#)  
    setup.exe, [9-6](#)  
    umask, [4-13](#)  
    useradd, [4-12](#)  
computers with multiple aliases, [5-4](#)  
computers, non-networked, [5-3](#)  
copying demo directory, [D-6](#)  
custom database  
    failure groups for Oracle Automatic Storage  
        Management, [8-2](#)  
    requirements when using Oracle Automatic  
        Storage Management, [8-2](#)

## D

---

DAS (direct attached storage) disks, [8-8](#)  
data files  
    minimum disk space for, [6-6](#)  
    recommendations for file system, [6-6](#)  
    supported storage options for, [6-1](#)  
data loss  
    minimizing with Oracle ASM, [8-2](#)  
database cloning, [11-16](#)  
Database Configuration Assistant  
    running in silent mode, [B-7](#)  
databases  
    Oracle Automatic Storage Management  
        requirements, [8-2](#)  
DB\_RECOVERY\_FILE\_DEST, [11-14](#)  
DB\_RECOVERY\_FILE\_DEST\_SIZE, [11-14](#)  
dba group  
    creating, [4-9](#)  
    description, [4-6](#)  
    SYSDBA privilege, [4-6](#)

dba groups  
 creating, [4-11](#)

DBCA  
 configuring Automatic memory Management,  
[10-5](#)

dbca.rsp file, [B-3](#)

DBSNMP user  
 password requirements, [11-3](#)

default file mode creation mask  
 setting, [4-13](#)

deinstall, [12-1](#), [12-3](#), [12-7](#)  
 See also removing Oracle software

deinstall command, [12-1](#)

deinstallation, [12-1](#)  
 examples, [12-5](#)  
 previous releases, [12-8](#)  
 upgrades, [12-8](#)

deinstalling an rpm-based installation, [12-7](#)

demo directory, [D-6](#)

deprecated features, [xiv](#)

df command, [4-13](#)

dgdba group  
 creating, [4-10](#)

diagnostic data, [C-1](#)

Direct NFS  
 disabling, [7-5](#)  
 enabling, [7-5](#)  
 oranfstab file, [7-2](#)

directory  
 creating separate data file directories, [8-8](#)  
 database file directory, [6-6](#)

disk group  
 Oracle ASM, [8-2](#)

disk groups  
 checking, [8-6](#)  
 recommendations for, [8-2](#)

disk space  
 Oracle ASM, [8-5](#)  
 requirements for preconfigured database in  
 Oracle Automatic Storage  
 Management, [8-2](#)

disks  
 supported for Oracle Automatic Storage  
 Management, [8-8](#)

display variable, [1-4](#)

## E

---

EM Express, [11-14](#)

enabling IOCP, [3-13](#)

enterprise.rsp file, [B-3](#)

environment variables  
 ORACLE\_BASE, [4-13](#)  
 ORACLE\_HOME, [4-13](#)  
 ORACLE\_HOSTNAME, [5-3](#)  
 ORACLE\_SID, [4-13](#)

environment variables (*continued*)  
 removing from shell startup file, [4-13](#)  
 SHELL, [4-13](#)  
 TEMP and TMPDIR, [4-13](#)

errors  
 X11 forwarding, [4-16](#)

examples  
 Oracle ASM failure groups, [8-2](#)

executeConfigTools, [B-11](#)

external redundancy  
 Oracle Automatic Storage Management level,  
[8-2](#)

## F

---

failure group  
 characteristics of Oracle ASM failure group,  
[8-2](#)  
 examples of Oracle Automatic Storage  
 Management failure groups, [8-2](#)  
 Oracle ASM, [8-2](#)

fast recovery area, [11-15](#)  
 filepath, [C-5](#)  
 Grid home  
 filepath, [C-5](#)

file mode creation mask  
 setting, [4-13](#)

file paths, [D-9](#)

file system  
 using for data files, [6-6](#)

file system options, [6-5](#)

files  
 bash\_profile, [4-13](#)  
 dbca.rsp, [B-3](#)  
 editing shell startup file, [4-13](#)  
 enterprise.rsp, [B-3](#)  
 login, [4-13](#)  
 profile, [4-13](#)  
 response files, [B-3](#)

filesets, [3-5](#)

free disk space, [2-2](#)

## G

---

globalization  
 localization for client connections, [11-8](#)  
 NLS\_LANG  
 and client connections, [11-8](#)

Grid user  
 creating, [4-12](#)

groups  
 creating an Oracle Inventory Group, [4-3](#)  
 creating the asmdba group, [4-9](#)  
 creating the asmoper group, [4-9](#)  
 creating the backupdba group, [4-10](#)  
 creating the dba group, [4-9](#)



groups (*continued*)

- creating the dgdba group, [4-10](#)
- creating the kmdba group, [4-11](#)
- creating the racdba group, [4-11](#)
- OINSTALL group, [1-2](#)
- OSBACKUPDBA (backupdba), [4-6](#)
- OSDBA (dba), [4-6](#)
- OSDBA group (dba), [4-6](#)
- OSDGDBA (dgdba), [4-6](#)
- OSKMDBA (kmdba), [4-6](#)
- OSOPER (oper), [4-6](#)
- OSOPER group (oper), [4-6](#)

---

**H**

- hardware requirements, [1-1](#)
  - display, [1-1](#)
- host name resolution, [3-12](#)
- host name, setting before installation, [5-4](#)
- hugepages, [1-2](#)

---

**I**

- I/O Completion Ports, [3-13](#)
- image
  - install, [9-2](#), [10-2](#)
- init.ora
  - and SGA permissions, [11-11](#)
- installation
  - computer aliases, multiple, [5-4](#)
  - laptops, [5-3](#)
  - Oracle Automatic Storage Management, [8-2](#)
  - response files, [B-3](#)
    - preparing, [B-3](#), [B-4](#)
    - templates, [B-3](#)
  - silent mode, [B-5](#)
- installation option
  - Automatic Memory Management, [10-5](#)
- installation planning, [1-1](#)
- installation types
  - and Oracle Automatic Storage Management, [8-2](#)
- installer
  - supported languages, [10-6](#)
- Installing
  - Oracle Restart, [9-3](#)
- invalid objects
  - recompiling, [11-9](#)
- IOCP, [3-13](#)

---

**J**

- JDK requirements, [3-5](#)

---

**K**

- kernel parameters
  - tcp and udp, [A-4](#)
- kernel parameters configuration, [A-1](#)
- kmdba group
  - creating, [4-11](#)
- Korn shell
  - default user startup file, [4-13](#)

---

**L**

- laptops, installing Oracle Database on, [5-3](#)
- local device
  - using for data files, [6-6](#)
- locking and unlocking users, [11-7](#)
- login file, [4-13](#)
- loopback adapters, [5-4](#)
  - non-networked computers, [5-3](#)
- LVM
  - recommendations for Oracle Automatic Storage Management, [8-2](#)

---

**M**

- mask
  - setting default file mode creation mask, [4-13](#)
- mixed binaries, [3-5](#)
- mode
  - setting default file mode creation mask, [4-13](#)
- multihomed computers, installing on, [5-3](#)
- multihomed Oracle servers
  - resolving to,, [5-4](#)
- multiple aliases, computers with, [5-4](#)
- Multiple Oracle Homes Support
  - advantages, [C-2](#)
- multitenant container database
  - character sets, [10-4](#)
- multiversioning, [C-2](#)
- My Oracle Support credentials, [10-8](#)

---

**N**

- Net Configuration Assistant (NetCA)
  - response files, [B-7](#)
  - running at command prompt, [B-7](#)
- netca.rsp file, [B-3](#)
- network adapters, [5-4](#)
  - computers with multiple aliases, [5-4](#)
  - non-networked computers, [5-3](#)
  - primary, on computers with multiple aliases, [5-4](#)
    - See also* loopback adapters
- network cards, multiple, [5-3](#)
- network setup
  - computers with multiple aliases, [5-4](#)

- network setup (*continued*)
    - host name resolution, [3-12](#)
  - network topics
    - laptops, [5-3](#)
    - multiple network cards, [5-3](#)
    - non-networked computers, [5-3](#)
  - NFS
    - and data files, [6-7](#)
    - buffer size requirements, [7-1](#)
    - for data files, [6-7](#)
  - NFS mounts
    - Direct NFS Client
      - requirements, [6-7](#)
    - mtab, [6-7](#)
    - oranstab, [6-7](#)
  - non-networked computers, [5-3](#)
  - noninteractive installation
    - Oracle ASM requirements, [8-6](#)
  - noninteractive mode
    - See response file mode
- ## O
- 
- OFA, [C-1](#)
    - See also Optimal Flexible Architecture
  - OINSTALL directory, [C-5](#)
  - oinstall group
    - creating, [4-3](#)
  - OINSTALL group1, [1-4](#)
    - See also Oracle Inventory directory
  - oper group
    - description, [4-6](#)
  - operating system
    - different on cluster members, [3-5](#)
    - requirements, [3-5](#)
  - operating system privileges groups, [1-4](#)
  - operating system requirements, [1-2](#)
  - Optimal Flexible Architecture, [C-1](#)
    - about, [C-1](#)
  - orabasehome, [D-9](#)
  - orabasetab, [D-3](#)
  - Oracle ACFS
    - enabling, [9-11](#)
    - Installing Oracle RAC binaries not supported
      - on Oracle Flex Cluster, [6-4](#)
    - restrictions for Oracle Restart, [6-4](#)
    - supported IBM AIX versions, [6-4](#)
  - Oracle ADVN
    - supported IBM AIX versions, [6-4](#)
  - Oracle ASM, [6-2](#), [8-2](#)
    - configuring disk devices, [8-7](#)
    - disk groups, [8-2](#)
    - disk space, [8-5](#)
    - failure groups, [8-2](#)
    - recommendations for disk groups, [8-2](#)
  - Oracle ASM (*continued*)
    - See also Oracle Automatic Storage Management
  - Oracle ASM disk space, [8-5](#)
  - Oracle Automatic Storage Management, [8-2](#)
    - allocation units (AU) and ASM disks, [8-2](#)
    - characteristics of failure groups, [8-2](#)
    - DAS disks, [8-8](#)
    - disk space, [8-5](#)
    - disks, supported, [8-8](#)
    - failure groups
      - examples, [8-2](#)
      - identifying, [8-2](#)
    - part of Oracle Grid Infrastructure for a standalone server installation, [10-1](#)
    - partition creation, [8-8](#)
    - redundancy levels, [8-2](#)
    - SAN disks, [8-8](#)
    - space required for preconfigured database, [8-2](#)
  - Oracle base, [C-1](#), [C-5](#)
  - Oracle base config, [D-3](#)
  - Oracle base home, [D-2](#)
  - Oracle Connection Manager, [E-1](#)
  - Oracle Database
    - minimum disk space requirements, [6-6](#)
    - requirements with Oracle Automatic Storage Management, [8-2](#)
  - Oracle Database Configuration Assistant, [B-8](#)
    - response file, [B-3](#)
  - Oracle DBCA, [B-8](#)
  - Oracle Disk Manager
    - and Direct NFS, [7-5](#)
  - Oracle Enterprise Manager Database Express, [11-14](#)
  - Oracle Fleet Patching and Provisioning Databases, [10-2](#)
  - Oracle Flex Clusters
    - Oracle Restart
      - restrictions for, [6-4](#)
      - restrictions for Oracle ACFS, [6-4](#)
  - Oracle FPP, [10-2](#)
  - Oracle Grid Infrastructure
    - restrictions for Oracle ACFS, [6-4](#)
  - Oracle Grid Infrastructure for a standalone server, [6-2](#)
  - Oracle home
    - ASCII path restriction for, [1-2](#)
    - file path, [C-5](#)
    - Grid home
      - filepath, [C-5](#)
      - naming conventions, [C-4](#)
  - Oracle home directory
    - multiple homes, network considerations, [5-3](#)
  - Oracle host name, setting before installation, [5-4](#)

Oracle Inventory, [1-4](#)  
 identifying existing, [4-2](#)

Oracle Inventory Directory  
 OINSTALL group, [C-2](#)

Oracle Net Configuration Assistant  
 response file, [B-3](#)

Oracle Net Services Listener, [E-1](#)

Oracle Optimal Flexible Architecture  
 See Optimal Flexible Architecture

Oracle Restart, [6-2](#)  
 deconfiguring, [12-5](#)  
 downgrading, [12-5](#)  
 gridSetup.sh, [9-3](#)  
 Installing, [9-3](#)  
 troubleshooting, [12-5](#)

Oracle Software Owner user  
 creating, [4-3](#), [4-12](#)

Oracle Software Owner users  
 determining default shell, [4-13](#)

Oracle Universal Installer  
 response files  
 list of, [B-3](#)

Oracle Upgrade Companion, [3-2](#)

oracle user, [1-4](#)  
 creating, [4-3](#)

Oracle user  
 determining default shell, [4-13](#)  
 modifying, [4-16](#)

Oracle XML DB, [E-1](#)

ORACLE\_BASE environment variable  
 removing from shell startup file, [4-13](#)

ORACLE\_BASE\_CONFIG, [D-3](#), [D-9](#)

ORACLE\_BASE\_HOME, [D-2](#), [D-9](#)

ORACLE\_HOME, [D-9](#)

ORACLE\_HOME environment variable  
 removing from shell startup file, [4-13](#)

ORACLE\_HOSTNAME, [5-3](#)

ORACLE\_HOSTNAME environment variable  
 computers with multiple aliases, [5-4](#)  
 multihomed computers, [5-3](#)  
 setting before installation, [5-4](#)

ORACLE\_SID environment variable  
 removing from shell startup file, [4-13](#)

oraInventory, [C-5](#)

oranfstab configuration file, [7-2](#)

oranfstab file, [7-5](#)

OSBACKUPDBA group  
 creating, [4-10](#)

OSBACKUPDBA group (backupdba), [4-6](#)

OSDBA, [1-4](#)

OSDBA for ASM  
 creating for Oracle Grid Infrastructure, [4-9](#)

OSDBA groups  
 creating, [4-9](#)  
 creating for Oracle Grid Infrastructure, [4-9](#)  
 description for database, [4-6](#)

OSDBA groups (*continued*)  
 SYSDBA privilege, [4-6](#)

OSDGDBA group  
 creating, [4-10](#)

OSDGDBA group (dgdba), [4-6](#)

OSKMDBA group  
 creating, [4-11](#)

OSKMDBA group (kmdba), [4-6](#)

OSOPER group  
 creating, [4-10](#)

OSOPER groups  
 description for database, [4-6](#)  
 SYSOPER privilege, [4-6](#)

OSRACDBA group  
 creating, [4-11](#)

OTN website  
 downloading installation software from, [10-3](#)

## P

parameter file  
 and permissions to read and write the SGA,  
[11-11](#)

partition  
 using with Oracle Automatic Storage  
 Management, [8-2](#)

partitions  
 creation for Oracle Automatic Storage  
 Management disks, [8-8](#)

passwords, [11-3](#), [11-6](#)  
 change after install, [11-3](#)  
 resetting  
 with SQL\*Plus, [11-7](#)  
 unlocking  
 with SQL\*Plus, [11-7](#)

patch updates, [11-2](#)

PGA, [10-5](#)

physical RAM, [2-2](#)

ports  
 Oracle Connection Manager, [E-1](#)  
 Oracle Net Services Listener, [E-1](#)  
 Oracle XML DB, [E-1](#)

postinstallation  
 recommended tasks  
 root.sh script, backing up, [11-8](#)

postinstallation -executeConfigTools option, [B-9](#)

postinstallation configToolAllCommands script,  
[B-12](#)

preconfigured database  
 Oracle Automatic Storage Management disk  
 space requirements, [8-2](#)  
 requirements when using Oracle Automatic  
 Storage Management, [8-2](#)

preinstallation: rootpre.sh, [4-19](#)

profile file, [4-13](#)

## R

---

racdba group  
 creating, [4-11](#)

RAID, [6-6](#)  
 using for Oracle data files, [6-6](#)

read only Oracle home, [D-5](#)

read-only oracle home, [D-2](#), [D-9](#)

read-only Oracle home, [D-1](#), [D-3](#), [D-6](#), [D-9](#)

read/write oracle home, [D-9](#)

recommendations  
 on performing software-only installations, [9-6](#)

recompiling invalid objects, [11-9](#)

redundancy level  
 and space requirements for preconfigured database, [8-2](#)  
 for Oracle Automatic Storage Management, [8-2](#)

redundant array of independent disks  
 See RAID

release update revisions, [11-2](#)

release updates, [11-2](#)

releases  
 multiple, [C-2](#)

removing Oracle software, [12-1](#)  
 examples, [12-5](#)

requirements, [8-2](#)

response file, [B-8](#)

response file installation  
 preparing, [B-3](#)  
 response files  
 templates, [B-3](#)  
 silent mode, [B-5](#)

response file mode, [B-1](#)  
 about, [B-1](#)  
 reasons for using, [B-2](#)  
 See also response files, silent mode

response files, [B-1](#), [B-8](#)  
 about, [B-1](#)  
 creating with template, [B-3](#)  
 dbca.rsp, [B-3](#)  
 enterprise.rsp, [B-3](#)  
 general procedure, [B-2](#)  
 Net Configuration Assistant, [B-7](#)  
 netca.rsp, [B-3](#)  
 passing values at command line, [B-1](#)  
 specifying with Oracle Universal Installer, [B-5](#)  
 See also silent mode.

roohctl -enable, [D-5](#)

root user  
 logging in as, [2-1](#)

root.sh script  
 backing up, [11-8](#)

rootcrs.sh, [12-1](#)

roothas.pl, [9-8](#), [9-11](#)

roothas.sh, [9-10](#), [9-11](#), [12-1](#)

rootpre.sh, [4-19](#)

RPM-based database installation, [12-7](#)

running multiple Oracle releases, [C-2](#)

running rootpre.sh, [4-19](#)

## S

---

SAN (storage area network) disks, [8-8](#)

sb\_max, [7-2](#)

seamless patching, [D-2](#)

security  
 selecting passwords, [11-3](#)

SGA, [10-5](#)

shell  
 determining default shell for Oracle user, [4-13](#)

SHELL environment variable  
 checking value of, [4-13](#)

shell limits, [A-1](#)  
 changing, [A-2](#)  
 displaying, [A-2](#)

shell startup file  
 editing, [4-13](#)  
 removing environment variables, [4-13](#)

silent mode  
 about, [B-1](#)  
 reasons for using, [B-2](#)

silent mode installation, [B-5](#)

smit command, [4-12](#)

software requirements, [3-5](#)

software security updates, [10-8](#)

ssh  
 and X11 Forwarding, [4-16](#)

starting, [11-14](#)

startup file  
 for shell, [4-13](#)

storage area network disks, [8-8](#)

stty  
 suppressing to prevent installation errors, [4-17](#)

supported languages  
 installer, [10-6](#)

swap space, [2-2](#)  
 allocation, [1-2](#)

SYS user  
 password requirements, [11-3](#)

SYSBACKUPDBA system privileges, [4-6](#)

SYSDBA privilege  
 associated group, [4-6](#)

SYSDGDBA system privileges, [4-6](#)

SYSKMDBA system privileges, [4-6](#)

SYSOPER privilege  
 associated group, [4-6](#)

system architecture, [2-2](#)

system configuration parameters, [A-1](#)  
 verifying, [A-3](#)

system global area  
 permissions to read and write, [11-11](#)  
 system privileges  
 SYSBACKUPDBA, [4-6](#)  
 SYSDGDBA, [4-6](#)  
 SYSKMDBA, [4-6](#)  
 system privileges accounts  
 locked after install, [11-3](#)  
 system requirements, [1-1](#)  
 SYSTEM user  
 password requirements, [11-3](#)

## T

---

TEMP environment variable  
 commands  
 env, [4-13](#)  
 env command, [4-13](#)  
 environment  
 checking settings, [4-13](#)  
 setting, [4-13](#)  
 umask, [4-13](#)  
 umask command, [4-13](#)  
 terminal output commands  
 suppressing for Oracle installation owner  
 accounts, [4-17](#)  
 TMPDIR environment variable  
 setting, [4-13](#)  
 troubleshooting  
 disk space errors, [1-2](#)  
 environment path errors, [1-2](#)  
 garbage strings in script inputs found in log  
 files, [4-17](#)  
 host name resolution for multihomed servers,  
[5-3](#)  
 installation owner environment variables and  
 installation errors, [4-18](#)  
 inventory corruption, [4-16](#)  
 ssh errors, [4-17](#)  
 stty errors, [4-17](#)  
 unset environment variables, [1-2](#)

troubleshooting (*continued*)  
 typographic conventions, [xiii](#)

## U

---

umask command, [4-13](#)  
 uninstall  
 See removing Oracle software  
 UNIX commands  
 smit, [4-12](#)  
 xhost, [2-1](#)  
 UNIX workstation  
 installing from, [2-1](#)  
 unset installation owners environment variables,  
[4-18](#)  
 upgrade, [3-3](#)  
 Oracle Automatic Storage Management, [10-1](#)  
 upgrades  
 best practices, [3-2](#)  
 upgrading  
 options, [3-3](#)  
 useradd command, [4-12](#)  
 users  
 creating the oracle user, [4-3](#)  
 locking and unlocking, [11-7](#)  
 utlrp.sql, [11-9](#)

## V

---

verifying system parameter values, [A-3](#)

## X

---

X Window System  
 enabling remote hosts, [2-1](#)  
 X11 forwarding errors, [4-16](#)  
 xhost command, [2-1](#)  
 xtitle  
 suppressing to prevent installation errors,  
[4-17](#)