

# Oracle Linux 10

## Installing Oracle Linux



G14595-01  
June 2025



Oracle Linux 10 Installing Oracle Linux,

G14595-01

Copyright © 2025, Oracle and/or its affiliates.

# Contents

## Preface

---

|  |    |
|--|----|
| Documentation License                      | vi |
| Conventions                                | vi |
| Documentation Accessibility                | vi |
| Access to Oracle Support for Accessibility | vi |
| Diversity and Inclusion                    | vi |

## 1 Preparing to Install

---

|                                   |     |
|-----------------------------------|-----|
| System Requirements               | 1-1 |
| System Configuration              | 1-2 |
| Default Disk Partition Layout     | 1-3 |
| Obtaining Installation ISO Images | 1-4 |
| Preparing Installation Media      | 1-4 |
| USB Flash Drive                   | 1-4 |
| DVD or CD                         | 1-6 |
| Network Drive                     | 1-7 |
| Driver Update Disk                | 1-7 |

## 2 Customizing Boot Loader Actions

---

|                             |     |
|-----------------------------|-----|
| Configuring the Boot Loader | 2-1 |
| Installation Boot Options   | 2-1 |
| Installation Source         | 2-2 |
| Installation Type           | 2-3 |
| Kickstart Installations     | 2-3 |
| Miscellaneous Boot Options  | 2-3 |
| Network Configuration       | 2-3 |
| Remote Installations        | 2-4 |

## 3 Installing Oracle Linux Manually

---

|                             |     |
|-----------------------------|-----|
| Installing in Graphics Mode | 3-1 |
| Welcome Screen              | 3-1 |

|                                |      |
|--------------------------------|------|
| Installation Summary           | 3-2  |
| Localization                   | 3-3  |
| Keyboard Layout                | 3-3  |
| Languages                      | 3-3  |
| Date and Time                  | 3-4  |
| Software                       | 3-5  |
| Installation Source            | 3-5  |
| Software Selection             | 3-6  |
| System                         | 3-6  |
| Installation Destination       | 3-7  |
| KDUMP                          | 3-8  |
| Network and Host Name          | 3-9  |
| User Settings                  | 3-9  |
| Root Password                  | 3-10 |
| User Creation                  | 3-11 |
| Completing the Installation    | 3-12 |
| Installing in Text Mode        | 3-12 |
| Postinstallation Configuration | 3-13 |

## 4 Automating the Installation by Using Kickstart

---

|  |     |
|--|-----|
| Customizing the Kickstart Configuration File | 4-1 |
| Installation Options                         | 4-2 |
| Packages to Install                          | 4-3 |
| Preinstallation Options                      | 4-4 |
| Postinstallation Options                     | 4-5 |
| Starting the Kickstart Installation          | 4-5 |
| Installing Over the Network                  | 4-6 |
| Installing Locally                           | 4-6 |

## 5 Using a Driver Update Disk During Installation

---

## 6 Installing a System With a Btrfs root File System

---

|                                  |     |
|----------------------------------|-----|
| Using the GUI Installer          | 6-1 |
| Using the Text Installer         | 6-3 |
| Verifying the Btrfs Installation | 6-3 |

## 7 Troubleshooting Oracle Linux Installations

---

|                              |     |
|------------------------------|-----|
| Troubleshooting Menu Options | 7-1 |
|------------------------------|-----|

## A Creating a Network Installation Setup

---

|   |     |
|---|-----|
| Setting Up the Network Server                 | A-1 |
| Configuring NFS                               | A-1 |
| Configuring dnsmasq                           | A-3 |
| Configuring PXE Boot Loading                  | A-5 |
| Configuring PXE Boot Loading for BIOS Clients | A-5 |
| Configuring PXE Boot Loading for UEFI Clients | A-7 |
| Using Different Kinds of Clients              | A-9 |

# Preface

[Oracle Linux 10: Installing Oracle Linux](#) provides information about how to install the Oracle Linux 10 release.

## Documentation License

The content in this document is licensed under the [Creative Commons Attribution–Share Alike 4.0 \(CC-BY-SA\)](#) license. In accordance with CC-BY-SA, if you distribute this content or an adaptation of it, you must provide attribution to Oracle and retain the original copyright notices.

## Conventions

The following text conventions are used in this document:

| Convention      | Meaning  |
|-----------------|--|
| <b>boldface</b> | Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.         |
| <i>italic</i>   | Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.                          |
| monospace       | Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter. |

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <https://www.oracle.com/corporate/accessibility/>.

## Access to Oracle Support for Accessibility

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <https://www.oracle.com/corporate/accessibility/learning-support.html#support-tab>.

## Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and

the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

# 1

## Preparing to Install

Whether you're installing on a single system or on many systems, plan ahead to ensure a successful installation.

- [System Requirements](#)
- [System Configuration](#)
- [Obtaining Installation ISO Images](#)
- [Preparing Installation Media](#)



### Note:

To upgrade from the latest version of the previous major Oracle Linux release to the current major release version, use the Leapp utility. See [Oracle Linux 10: Upgrading Systems With Leapp](#).

## System Requirements

Verify that the system fulfills the following minimum requirements. In general, having more resources in the system improves a system's performance.

- Minimum of 2 logical CPUs up to 2048 logical CPUs
- Minimum x86-64-v3 micro architecture level for CPUs when installing on x86\_64 hardware



### Tip:

If you're unsure whether the hardware satisfies the required micro architecture level, consider installing an earlier version of Oracle Linux and run the following command:

```
sudo /lib64/ld-linux-x86-64.so.2 --help | grep x86-64-v
```

If the output includes **(supported, searched)**, next to the micro architecture level, then that level is supported on the CPU. For example, the following shows that micro architecture levels 2 and 3 are supported but not 4:

```
sudo /lib64/ld-linux-x86-64.so.2 --help | grep x86-64-v
x86-64-v4
x86-64-v3 (supported, searched)
x86-64-v2 (supported, searched)
```

- The ARMv8 instruction set when installing on aarch64 hardware

 **Tip:**

To check whether the hardware satisfies the requirement for aarch64 v8, run the following command:

```
uname -m
```

If the output is `aarch64` or `arm64`, the system supports aarch64.

- 1.5 GB of memory per logical CPU, up to a maximum of 64 TB
- At least 10 GB of disk space (20 GB is the recommended minimum)
- On UEFI systems, ensure that the target disk uses GPT (GUID Partition Table), as some UEFI firmwares don't accept UEFI/MBR boot

See the following extra resources for information related to installation issues and system requirements:

- <https://linux.oracle.com/hardware-certifications>
- The Release Notes for the Oracle Linux version you're installing at [General Oracle Linux documentation](#)
- [Unbreakable Enterprise Kernel documentation](#)

## System Configuration

The configuration of the system itself also has an impact on the installation. Consider the following:

### Storage

- Storage device and partition on which the OS is installed. The installation program displays a warning if disk space is insufficient.
- Storage space for each file system (`/`, `/boot`, `/home`, `/var/tmp`, and so on), the file system type, and whether to encrypt the block device underlying each file system.
- Layout and configuration of the storage devices such as use of logical volume management RAID configuration, encryption, and others.
- For iSCSI or FCoE connections: the WWID or the port, target, and LUN to be used.

 **Note:**

Oracle Linux provides a default partitioning schema for automatic partitioning in the installation destination. See [Default Disk Partition Layout](#).

### Network

- Required network setup using DHCP or static addresses, FQDN, or host name, and so on.

- Other specialized network interfaces to be configured during installation, such as VLANs, and network bonding.

### Software

- URLs of any other repositories and proxy settings to be used during installation.
- Software packages to be installed based on system's intended purpose, such as a web server.

## Default Disk Partition Layout

Oracle Linux, at installation, provides a default disk partition layout.

The default partitioning schema uses XFS as the default file system on each volume, except `/boot/EFI`, which uses VFAT.

Using LVM for `/`, `/home`, and `/swap` makes it easier to resize these allocations after installation if more disk space is made available.

The default partition schema is described in the following table:

**Table 1-1 Default Partitioning**

| Volume                 | Description                | File system type | Size  |
|------------------------|----------------------------|------------------|---|
| <code>/boot</code>     | Boot partition             | XFS              | 1 GiB (fixed)   |
| <code>/boot/EFI</code> | EFI system partition (EFS) | VFAT             | 600 MiB (fixed)   |
| LVM Group              |                            |                  |   |
| <code>/swap</code>     | Swap volume                | XFS              | Swap size is calculated based on the amount of memory available: <ul style="list-style-type: none"> <li>• If memory is less than 2 GiB, swap is twice the amount of memory available.</li> <li>• If memory is greater than or equal to 2 GiB, but less than 8 GiB, then swap is equal to the amount of memory available.</li> <li>• If memory is greater than or equal to 8 GiB, but less than 64 GiB, swap is equal to half the amount of memory available.</li> <li>• if memory is greater than or equal to 64 GiB, then swap is set to a fixed size of 4 GiB.</li> </ul> |

**Table 1-1 (Cont.) Default Partitioning**

| Volume | Description | File system type | Size  |
|--------|-------------|------------------|---|
| /      | Root volume | XFS              | 70 GiB or 50% of available disk space after <code>/boot</code> and <code>/swap</code> are configured - whichever is smaller. Minimum size is 1 GiB. |
| /home  | Home volume | XFS              | Remainder of disk space. If the total available disk space is 50 GiB or less, a home partition isn't created. Minimum size is 1 GiB.                |

## Obtaining Installation ISO Images

To install Oracle Linux, download the installation images from one of the following locations:

- Oracle Linux yum server at <https://yum.oracle.com/oracle-linux-isos.html>.
- Oracle Software Delivery Cloud at <https://edelivery.oracle.com>.

The following installation images are available for both the x86\_64 platform and the aarch64 platform, unless indicated otherwise:

- Full ISO of Oracle Linux for typical on-premises installations.
- Boot ISO of Oracle Linux for network installations.
- Boot ISO of the supported UEK release for installations in which you want to use the Btrfs file system or for installing on hardware that's supported only on UEK. For instructions to install Oracle Linux with the Btrfs file system, see [Installing a System With a Btrfs root File System](#).
- Source DVDs that contain the source code for the software packages in the release.

## Preparing Installation Media

Before you can use an ISO image to install Oracle Linux, you must first store it on bootable installation media, such as the following:

- [USB Flash Drive](#)
- [DVD or CD](#)
- [Network Drive](#)
- [Driver Update Disk](#)

### USB Flash Drive

You can install Oracle Linux by using a boot image on portable devices such as a USB flash drive or an SD card, if the system's firmware can boot from those devices.

To create a bootable drive, use the `dd` or `xorriso-dd-target` command. Or, use a separate third-party utility to write the ISO image to a drive. See, for example, [Create USB Installation Media for Oracle Linux with Fedora Media Writer](#).

**▲ Caution:**

This procedure destroys any existing data on the drive. Ensure that you specify the correct device name for the USB drive on the system.

1. Insert a USB flash drive into an Oracle Linux system.
2. Use the `xorriso-dd-target` command to list available block devices and to identify likely candidate devices for use.

```
xorriso-dd-target -with_sudo -list_all
```

The command presents a password prompt as it uses `sudo` to access all devices on the system. Output similar to the following is displayed:

```
sda : YES : usb+ has_vfat+ : SanDisk Cruzer Switch
nvme0n1 : NO : not_usb- has_vfat+ has_xfs- has_crypto_LUKS- has_swap- :
PM9A1 NVMe Samsung 512GB
```

The command identifies removable block devices with disposable content. In the example output, the command identified a USB device at `/dev/sda`, that could be used to write an ISO image.

3. Ensure that any file systems on the device are unmounted.

For example, to unmount the first partition on `/dev/sda`:

```
sudo umount /dev/sda1
```

4. Write the contents of the ISO image file to the USB device.

Do one of the following to write the ISO image file to the USB device:

- Use the `dd` command directly:

```
sudo dd if=./full_image.iso of=/dev/sda bs=512k
```

- Use the `xorriso-dd-target` command to guide you through this process:

```
xorriso-dd-target -with_sudo -plug_test -DO_WRITE -image_file ./
full_image.iso
```

The command guides you through testing for appropriate devices and finally prompts you to select and approve writing to the device. Example output follows:

```
sudo /bin/lsblk seems ok.
```

```
Caused by option -plug_test: Attempt to find the desired device
by watching it appear after being plugged in.
```

```
Step 1:
Please make sure that the desired target device is plugged _out_ now.
If it is currently plugged in, make sure to unmount all its filesystems
and then unplug it.
Press the Enter key when ready.
```

```
Found and noted as _not_ desired:  nvme0n1
```

```
Step 2:
Please plug in the desired target device and then press the Enter key.
```

```
Waiting up to 10 seconds for a new device to be listed .... found: sda
Now waiting 5 seconds to let it settle .....
Found and noted as desired device:  sda
```

```
sda : YES : usb+ has_vfat+ : SanDisk Cruzer Switch
```

```
Step 3:
Last chance to abort. Enter the word 'yes' to start REAL WRITING.
yes
Looking for mount points of sda:
Performing:
  sudo /bin/dd if=/dev/zero of=/dev/'sda' bs=512 seek='30595071'
count=1 status=none
  sudo /bin/dd if='OracleLinux.iso' of=/dev/'sda' bs=1M status=progress
oflag=dsync ; sync
```

The USB flash drive is now ready to be used to boot a system and start the installation.

## DVD or CD

Because of storage limits, optical media such as CDs or DVDs might not have capacity to accommodate most installation ISO images. However they can be used to store the boot ISO image.

1. Insert an empty recordable CD or DVD into the CD or DVD writer device.
2. Open a terminal and use `cdrecord` to write the ISO file to the device.

To write the downloaded ISO image file to a CD or DVD, use a command such as `cdrecord`, for example:

```
sudo cdrecord -v -eject speed=16 dev=/dev/sr0 file_name.iso
```

To display the device that corresponds to the CD or DVD writer, use the `cdrecord --devices` command.

The CD or DVD is now ready to be used to boot a system and start the installation.

## Network Drive

You can copy installation media to a network drive to use as part of a network installation process. For the network drive, the image that you download can either be the full ISO image or the boot image. The network server can be of any type, for example NFS, or a web server.

To copy the ISO image to a network drive, follow these steps:

1. Mount the ISO image to a location on a system that has access to the network drive location.

For example you can loopback mount an ISO to the `/mnt` path as follows:

```
sudo mount -o loop full_image.iso /mnt
```

2. Copy the contents of the ISO image to the network drive location.

```
sudo cp -a -T path-to-mounted-ISO-image network_dir
```

For example, if you're using a web server to host the network drive, and have an ISO image mounted at `/mnt`, you might run the following command:

```
sudo cp -a -T /mnt /var/www/html/OSimage/OL10
```

3. Unmount the ISO image after you have finished copying the contents.

For example, run:

```
sudo umount /mnt
```

Using a network drive is part of network installation, which requires you to build a network configuration that provides network installation functionality. For details, see [Creating a Network Installation Setup](#).

## Driver Update Disk

A Driver Update Disk (DUD) provides a mechanism for delivering updated device drivers during system installation. On some systems, hardware might not be fully supported for an Oracle Linux release. In these cases, a DUD might be released later to help install Oracle Linux on newer hardware.

DUDs are released as modules and become available for previously unsupported hardware. The DUD is provided in the form of an ISO and is available in the Oracle Software Delivery Cloud or through MyOracle Support.

The DUD must be written to appropriate media or copied to another storage device before it can be used for installation.

You can prepare a DUD in the same way that you prepare other installation media, by copying it to a USB, CD, or DVD device, or by storing it in an accessible network location. See [Preparing Installation Media](#) for more information.

# 2

## Customizing Boot Loader Actions

Boot options control how the installation proceeds. You can choose to add more boot options to the default settings before you start the installation.

- [Configuring the Boot Loader](#)
- [Installation Boot Options](#)

### Configuring the Boot Loader

You can configure the boot loader to use specific boot options that control installation at the point of boot. For example, you can provide the network location of an install ISO, or the location of a Kickstart file used to automate installation.

Boot options are specified at the boot command line of the boot menu.

1. Boot the system.
2. Access the boot options in the boot menu.

When the boot menu is displayed, select any installation option, then press either the `e` key on UEFI-based systems or the `Tab` key on BIOS-based systems.

The boot options line is displayed with some default options already defined.

3. Add any required options at the end of the line that starts with `linux`.

Separate boot options with a space. Options that require parameters must be in the `option=parameter` format.

For a list of common boot options, see [Installation Boot Options](#).

4. Save the changes.

Save the changes by pressing either `Ctrl+X` on UEFI-based systems or `Return` on BIOS-based systems.

To discard changes and return to the boot menu, press `Esc`.

This example shows settings for the `inst.repo` and `inst.ks` options:

```
inst.repo=nfs:nfs.example.com:/ISOs/OL10/full_image.iso \  
inst.ks=nfs:nfs.example.com:/kickstart/OL10/server-ks.cfg ip=dhcp
```

With these directives, the installation program is instructed to do the following:

- Use the full installation image stored on an NFS share directory.
- Start the installation automatically by using a Kickstart file also stored on an NFS share directory.

### Installation Boot Options

This list contains some commonly used boot options that further control how the installation proceeds. You specify these options at the installation menu before you start the installation process.

The following resources provide more information about boot options:

- <https://anaconda-installer.readthedocs.io/en/latest/boot-options.html>
- The `dracut.cmdline(7)` manual page provides Dracut kernel command line options.

## Installation Source

### **inst.repo=cdrom[:*device*]**

Specifies a CD or DVD drive as the location that contains everything needed to install the software.

The installation program searches all the system's CD or DVD drives, unless a *device* is specified.

If access to a network is required and no network boot options are specified, the installation program enables DHCP on all available network devices.

### **inst.repo=ftp://*user* : *password*@*FTP\_server*/*path***

Specifies an FTP server as the location that contains everything needed to install the software.

If access to a network is required and no network boot options are specified, the installation program enables DHCP on all available network devices.

### **inst.repo=hd:*device*:*path***

Specifies a local disk as the location that contains everything needed to install the software.

You can specify the *device* by its device name (`sdb2`), label (`LABEL=label`), or UUID (`UUID=uuid`).

### **inst.repo=[http|https]://*HTTP\_server*/*path***

Specifies a web server as the location that contains everything needed to install the software.

If the system has access to the Internet, you can use the BaseOS repository on the Oracle Linux yum server for the Oracle Linux release that you're installing. For example: `https://yum.oracle.com/repo/OracleLinux/OL10/baseos/latest/x86_64`

### **inst.repo=nfs:[*options*]:*NFS\_server*:*path***

Specifies an NFS share as the location that contains everything needed to install the software.

Use *options* to specify a comma-separated list of NFS mount options.

The NFS share can be the path to an ISO image or a directory.

### **inst.stage2=[*installation\_source*]**

Specifies the location to fetch the installer runtime image; packages are ignored. If this option isn't specified, `inst.repo` is used instead. The path specified for *installation\_source* can match any of the protocol and path options used for `inst.repo`.

The directory path specified for the *installation\_source* should contain a valid `.treeinfo` file that specifies the location of the runtime image. If a `.treeinfo` file isn't present at the source, the installer uses `LiveOS/squashfs.img` as the default location at the specified source.

#### **! Important:**

When specifying a runtime image in UEK network installations, use the UEK ISO for the installation repository too. Don't combine using the standard Oracle Linux ISO image as the installation repository while simultaneously specifying the Oracle Linux UEK Boot ISO for the runtime image.

## Installation Type

**inst.graphical**

Specifies a graphical-based installation. This is the default.

**inst.text**

Specifies a limited text-based user interface for the installation.

**inst.disklabel**

Specifies the preferred disk label type. The default is `mbr` (MBR). For a GPT disk label that uses the GUID partition table when the boot loader is installed, specify `gpt`. Use a GPT disk label only on BIOS-based systems with a disk smaller than 2 TiB.

## Kickstart Installations

**inst.ks=cdrom[:device]/path**

Specifies a Kickstart file on a CD or DVD drive.

**inst.ks=ftp://user : password@FTP\_server/path**

Specifies a Kickstart file on an FTP server.

**inst.ks=hd:device:path**

Specifies a Kickstart file a local disk.

You can specify the *device* by its device name (`sdb2`), label (`LABEL=label`) or UUID (`UUID=uuid`).

**inst.ks=[http|https]://HTTP\_server/path**

Specifies a Kickstart file on a web server.

**inst.ks=nfs:[options:]NFS\_server:path**

Specifies a Kickstart file on an NFS share.

Use *options* to specify a comma-separated list of NFS mount options.

## Miscellaneous Boot Options

**inst.keymap=layout**

Specifies the keyboard layout for installation.

**inst.lang=language**

Specifies the language for installation.

## Network Configuration

**ip=[interface:]dhcp|dhcp6|auto6|ibft**

Specifies a network automatic configuration method. If *interface* isn't specified, all interfaces are configured. Use `ibft` to use the MAC address of the interface specified by the iSCSI Boot Firmware Table (iBFT) in the system BIOS or firmware.

**ip=ip::gateway:netmask:hostname:interface:none**

Specifies a static IP configuration for *interface*. Enclose IPv6 addresses in square brackets, for example `[2509:f0d0:1001::0004]`.

**nameserver=*IP***

Specifies the IP address of a DNS server to use during installation. More than one `nameserver` options can be used.

**bootdev=*interface***

Specifies the primary network interface. Required if you use more than one `ip` option.

**inst.dhcpclass**

Specifies a vendor class identifier to DHCP.

## Remote Installations

**inst.vnc**

Specifies a remote graphical-based installation by starting a VNC server.

A VNC client can connect by using a command such as `vncviewer server:port`, where `server` is the IP address of the system being installed.

After installation, the system starts in text mode even if a graphical desktop environment is selected as the base environment.

**inst.vncconnect=*client[:port]***

Specifies the VNC client and optional port that's listening for connections from a VNC server (`vncviewer -listen`). The default port is 5900.

**inst.vncpassword=*password***

Specifies the password for client connections using VNC.

# 3

## Installing Oracle Linux Manually

Installation begins when you boot the system from the installation media. The installation menu displays 3 options:

- Install Oracle Linux
- Test this media & Install Oracle Linux (default)
- Troubleshooting

Two modes are available to manually install Oracle Linux:

- **Graphics mode** where a graphical user interface guides you through the installation process. Selecting either the first or the second option in the menu starts the installation in graphic mode by default.
- **Text mode** which has limited options for installing the OS.

### Installing in Graphics Mode


The graphics installation mode consists of a series of graphical screens which you interact with to configure the installation.

- [Welcome Screen](#)
- [Installation Summary](#)
- [Localization](#)
- [Software](#)
- [System](#)
- [User Settings](#)

### Welcome Screen

The Welcome Screen is the first screen to appear after the system completes the boot process.

**Figure 3-1 Welcome Screen**




On this screen, select the preferred language to be used during the installation process. You can further select a specific locale, if any, for the selected language. Then select **Continue** to proceed.

## Installation Summary

The Installation Summary screen appears after you have selected the installation language. It functions as the home or main screen.

**Figure 3-2** Installation Summary



The screen provides four categories of options: LOCALIZATION, SOFTWARE, SYSTEM, and USER SETTINGS. Select an option under any of these categories to open a new screen where you can configure the selected option.

Most options under each category have default values and can be ignored to keep the default values. However, you **must** visit the options flagged with a warning icon.

After defining directives in a specific screen, select **Done** to return to the Installation Summary screen. Then you can configure other options. As you visit each configuration screen, pay attention to any warning messages that are displayed at the bottom of the screen.

You can continue to change installation configuration options until the installation begins. The installation doesn't begin until you select **Begin Installation** at the bottom of the screen. The **Begin Installation** button remains disabled until all the configuration warning flags have been cleared.

 **Note:**

At the top upper right of the screen is the Keyboard switch. This switch appears in all the option screens to enable you to change to a different keyboard layout at any time during configuration. You must add the required layout to the list of available layouts first, as described in [Keyboard Layout](#).

## Localization


Under Localization, you configure the following options:

- [Keyboard Layout](#)
- [Languages](#)
- [Date and Time](#)

After configuring any of these options, select **Done** to return to the Installation Summary screen.

## Keyboard Layout


**Figure 3-3 Keyboard Layout**



On the leftmost pane, you can add other keyboard layouts to the preselected default layout. You can also revise the order of the listed layouts. The layout at the top of the list becomes the default layout.

## Languages

Configuring languages consists of specifying other locales of the selected language that you want the system to use. This option is similar to the configuration of the keyboard layout at the beginning of the installation.


**Figure 3-4 Installing Extra Languages**

From the list of languages on the left side, select other languages for the system. Then, on the right side, select from the available locales for that language.

## Date and Time

The Time & Date screen lets you set the following:

- Time zone for the system
- Actual time and the format for displaying time
- Current date

**Figure 3-5 Time & Date**

To select the system's time zone, select the appropriate location from the Region and City dropdown lists.

To enable automatic date and time, select the **Configure NTP** button and specify the NTP server.

You can skip configuring NTP until later by using the Chrony suite. See [Oracle Linux 10: Setting Up Networking With NetworkManager](#). See also [Configure Chrony on Oracle Linux](#).

## Software

Under Software, you configure the following options:

- [Installation Source](#)
- [Software Selection](#)

After configuring any of these options, select **Done** to return to the Installation Summary screen.

## Installation Source

The Installation Source window identifies the source image that you use to install Oracle Linux.

**Figure 3-6 Installation Source**



Which installation source would you like to use?

Auto-detected installation source

On the network:

Closest mirror ▼  Proxy setup...

URL type: repository URL ▼


If you use the *full ISO image* as the source, the install program detects that image. By default, the **Auto-detected installation media** button is selected and **Appstream** is listed as an extra installation repository. Because the image contains all the packages required for a system installation, you can use the default configuration to proceed with the installation.

If you use the *boot ISO image* as the source, the **On the network** button is selected as the installation mode and the **Closest mirror** option is selected as the repository source. Optionally, you can specify a local mirror as a repository source, in which case you would need to provide the mirror's path. If no path is specified, the Oracle Linux yum server is used by default. The installer automatically uses the required repositories from the network mirror to install the OS. However, the repositories aren't listed in the window. Because the installation image is configured to automatically use the Oracle Linux yum server if no mirror path is specified, you can use the default configuration to proceed with the installation.

## Software Selection

Software selection refers to the profile or base environment to be used during the installation.

**Figure 3-7 Software Selection**



Each **Base Environment** represents a typical type of usage for the system and installs the required packages and software. The **Server with GUI** environment is selected by default. Select the base environment that best fits the purpose of the system on which you're installing Oracle Linux.

From the right side, you can add extra software profiles to the selected base environment. These profiles consists of groups of related packages that enable the required functionality.

## System

Under System, you configure the following options:


- [Installation Destination](#)
- [KDUMP](#)
- [Network and Host Name](#)

After configuring any of these options, select **Done** to return to the Installation Summary screen.

## Installation Destination

The installation destination is used to configure the disks where Oracle Linux is installed. Even if you accept the default settings, you must still open the Installation Destination screen to clear the option's warning icon.

**Figure 3-8 Installation Destination**



You can configure the installer to use local storage devices in the **Local Standard Disks** section of the window. A check mark icon on the disk device is displayed for any selected devices.

If you need to add network based or specialized storage such as iSCSI or NVDIMM devices, you can select the **Add a disk...** button in the **Specialized & Network Disks** section of the window.

You can configure other options for the target destination in the **Storage Configuration** section of the window:

- Selecting the **Automatic** radio button performs automatic partitioning, using the default partitioning schema. See [Default Disk Partition Layout](#).
  - **I would like to make additional space available:** Set this checkbox to reclaim space from an existing partitioning layout.
  - **Encrypt my data:** Set this checkbox to encrypt partitions using Linux Unified Key Setup (LUKS). You're prompted to set a LUKS encryption passphrase when you select the **Done** button.
- Selecting the **Custom** radio button lets you use custom partitioning. If you set this option, the **Manual Partitioning** configuration page is displayed after you select the **Done** button.

### Manual Partitioning

Detected mount points are listed in the left side of the window. Mount points are grouped by any detected OS installations. Options for each mount point are displayed on the right side when you select a mount point on the left side.

If the system contains existing file systems, ensure that enough space is available for the installation. To remove any partitions, select them in the list and select the - button.

If no partitions exist on the disk and you want to create a set of partitions as a starting point, select a partitioning scheme from the left side, and select **Click here to create them automatically**. The installer automatically creates standard partitions and mount points that you can customize and adjust.


The following options are available when configuring a mount point:

- **Mount point:** If a file system is the root file system, enter /, enter /boot for the /boot file system, and so on. No mount point is required for a swap file system.
- **Desired Capacity:** Set the value to the size of the file system that you want to create. You can use common size units such as KiB or GiB. The default size unit is MiB.
- **Device Type:** Set the device type to one of Standard Partition, LVM, or LVM Thin Provisioning. You can configure RAID options if two or more disks are configured for manual partitioning and you select an LVM device type. You can also configure the LVM **Volume Group**, if an LVM device type is selected.
- **File System:** Select the file system type that you want to use for the partition. Note that Oracle Linux also includes the Btrfs file system type, but to configure a Btrfs file system you must use the *UEK boot image* to load the installer. See [Installing a System With a Btrfs root File System](#) for more information.
- **Reformat:** Set this checkbox format the partition. If the partition isn't a newly created one, you can unset the checkbox to retain existing data.
- **Label:** Optionally label the partition to easily recognize individual partitions in other tooling.
- **Name:** You can name a partition, but standard partitions are named automatically when they're created.

## KDUMP

In the event of a system crash, Kdump captures information that helps diagnose the cause.


**Figure 3-9 Kdump**



Kdump is enabled by default and the amount of memory reserved for Kdump is calculated automatically. Select the **Manual** option to set the amount of reserved memory yourself.

## Network and Host Name

**Figure 3-10 Network & Host Name**



By default, network configuration uses DHCP for IPv4 addresses. IPv6 addresses are configured automatically. The default settings are enough for the system to provide basic network functionality. However, you can customize the network configuration, for example, by providing a custom host name, or including a fully qualified domain name (FQDN). You can further opt to use static addresses instead of using DHCP, configure proxy settings, network bonds, and so on. To perform custom configuration, select **Configure** and follow the prompts on the other configuration screens.

## User Settings

Under User Settings, you configure the following options:

- [Root Password](#)
- [User Creation](#)

After completing root and user configuration, select **Done** to return to the Installation Summary screen.

## Root Password

The Root Account window lets you enable or disable the root account.

**Figure 3-11** Setting the root account

The root account is used for administering the system.

The root user (also known as super user) has complete access to the entire system. For this reason, logging into this system as the root user is best done only to perform system maintenance or administration.

**Disable root account**

Disabling the root account will lock the account and disable remote access with root account. This will prevent unintended administrative access to the system.

**Enable root account**

Enabling the root account will allow you to set a root password and optionally enable remote access to root account on this system.

Root Password:

**empty password**

Confirm:

Allow root SSH login with password

By default, the root account is disabled for security reasons. If you enable the root account, you must also set and confirm the root password.

Password strength is monitored and the following rules are applied:

- Password must be eight characters or longer
- Password contains numbers, letters (uppercase and lowercase) and symbols
- Password is case-sensitive


If you have entered a weak password, you must confirm it by pressing the **Done** button twice.

A checkbox lets you configure whether to enable access to the root account over SSH. This option is disabled by default.

## User Creation

This option lets you configure a user's credentials to enable access to the system. You can optionally configure the user to have administrative privileges. If the root account is disabled, you must configure the user as an administrator.

**Figure 3-12 Create User**



The screenshot shows a user creation interface with the following elements:

- Full name:** A text input field.
- User name:** A text input field.
- Privileges:** Two checked checkboxes: "Add administrative privileges to this user account (wheel group membership)" and "Require a password to use this account".
- Password:** A text input field with a strength indicator below it showing "empty password".
- Confirm password:** A text input field.
- Advanced...:** A button at the bottom.

The following options are available:

- **Full name:** Enter the full name of the user account. This field is used to show the user account in the graphical login manager.
- **User name:** Enter the username that the user uses to sign in to the system on the command line or by using SSH.
- **Add administrative privileges to this user account:** Set the checkbox if the user requires administrative privileges. The user is added to the `wheel` group, which is in the `sudoers` configuration by default.

An administrator user can use the `sudo` command to perform tasks that are only available to `root` by using the user password, instead of the `root` password.

- **Require a password to use this account:** Set this checkbox to require a password to sign in to the system. Always set this checkbox, especially if you configure the user account with administrative privileges.
- **Password:** Enter the user password into this field.
- **Confirm password:** Enter a matching user password into this field.

Password strength is monitored and the following rules are applied:

- Password must be eight characters or longer
- Password contains numbers, letters (uppercase and lowercase) and symbols
- Password is case-sensitive

Weak passwords are allowed, but require that you press the **Done** button twice.

After the options are configured, the **Advanced** button becomes available to let you configure other user account options, such as the home directory location for the user, different values for user ID or group ID, and a list of groups that the account belongs to.

## Completing the Installation

From the Installation Summary screen, select **Begin Installation**. This button becomes available only when warning flags on option icons have been cleared.

The installation takes a while. After it finishes, reboot the system as prompted. Then sign in to the system by using the credentials you set in User Settings.

For details of other configuration options, see [Postinstallation Configuration](#).

## Installing in Text Mode

The Oracle Linux installation program can also run in text mode. Text mode is used automatically under certain circumstances, for example, if the system has insufficient memory or the video card isn't supported. You can manually switch to the text mode by specifying `inst.text` as a boot option on the boot command line. See [Configuring the Boot Loader](#) for more information.

### ! Important:

Text mode provides a limited subset of functionality that's available in the graphical installer. Most notably, it doesn't provide all the custom partitioning options for full control over disk layout. We recommend either using the graphical installer or using Kickstart to automate an installation.

Figure 3-13 Text-Based Installation Menu

```
=====
1) [x] Language settings                2) [x] Time settings
   (English (United Kingdom))          (Europe/London timezone)
3) [!] Installation source              4) [!] Software selection
   (Setting up installation             (Processing...)
   source...)
5) [!] Installation Destination         6) [x] Kdump
   (Processing...)                    (Kdump is enabled)
7) [x] Network configuration           8) [!] Root password
   (Connected: enp1s0)                (Root account is disabled)
9) [!] User creation
   (No user will be created)

Please make a selection from the above ['b' to begin installation, 'q' to quit,
'r' to refresh]:
```

The numbered options on the menu are the same as the on-screen options in graphic based installations. Each option is preceded by a flag surrounded by brackets:

- [ ] - Option isn't configured.
- [x] - Option is configured with the default setting.  
The setting is displayed between parentheses under the option.

- [!] - Option is configured but needs examination in case you want to specify a different setting.

To configure an option, type the option's number. The screen displays numbered values that are available for that option. Select the value by typing the value's number. Then type `c` to continue. Continuing either returns you to the main menu screen, or displays other related options for you to configure. Type `c` also to skip screens.

After configuring all the necessary menu options, type `b` to begin installing. At the end of the installation, the system reboots.

Follow all the remaining prompts. At the end of the process, sign in to the system and review the license agreement at `/usr/share/oraclelinux-release/EULA`.

For other configuration options you can set on the system, see [Postinstallation Configuration](#).

## Postinstallation Configuration

### Configuring Login

If you selected System with GUI as the OS profile to install and configured root passwords without creating users, then when you initially sign in as root, you're prompted to create a user. Setting up the first user can be completed in two ways:

- Create a regular user account, which is the default user setup screen. Enter the required user information as prompted, then select **Next** to complete the process.
- Create a domain account. For this option, select **Enterprise Login** on the default screen. A new window opens that prompts for the domain credentials. Use this option if the environment is configured with Active Directory or Identity Management domains for storing all user information. In this manner, the user can use domain credentials to sign in to the system's GNOME desktop.

### Registering the System

After you install Oracle Linux on a system, you have the option to register the system with the Unbreakable Linux Network (ULN), if you have an account. Registering lets the system obtain extra packages, updates, and fixes. To register the system, select one of the following methods:

- Visit <https://linux.oracle.com>. To obtain Oracle Linux updates from ULN, you must have an Oracle Linux support subscription.
- Use the `uln_register` shell command, which opens an interactive process.
- Use the Oracle Linux GNOME desktop menu. From the menu, select **Activities** and then search for `ULN Registration`. Click the **ULN Registration** shortcut icon to start the graphical registration wizard.

For more information about installing packages and managing software on the system, see [Oracle Linux: Managing Software on Oracle Linux](#).

If you have an Oracle Linux Premier Support account, you can opt to use Ksplice, to keep systems secure and highly available by automatically updating them with the latest kernel security errata and other critical updates. For more information, see [Oracle Linux: Ksplice User's Guide](#).

## Updating Software Packages

After installation is complete, we recommend updating all software packages to the latest available versions on the Oracle yum servers, or from ULN, because software packages are often updated for errata bug and security fixes, and package updates might already be available for packages that are provided on the installation media. To update all packages, run:

```
sudo dnf update -y
```

## Next Steps

After a basic Oracle Linux installation, you might want to further configure the system for optimization and customization purposes, such as setting system date and time, scheduling tasks, obtaining updates, and so on. For reference, go to the Oracle Linux tutorial page at <https://docs.oracle.com/en/operating-systems/oracle-linux/tutorials.html> which lists tutorials for different administrative tasks. Tutorials are available for tasks that you run at the command line or through the Cockpit web console.

For more detailed information about different features of Oracle Linux, go to the Oracle Linux library at [General Oracle Linux documentation](#).

# 4

## Automating the Installation by Using Kickstart

The Kickstart feature lets you automate the OS installation. A Kickstart installation uses a configuration file that instructs the installer how to perform a specific installation. The feature offers the following benefits:

- No user intervention is required during the installation process.
- It's easier to install a standard configuration when installing on many systems.
- The configuration file is useful for troubleshooting a boot problem with an installed system.

You can use Kickstart to install Oracle Linux locally. However, the best use of this feature is in the installation of the OS on many systems over the network. In a network installation, a Kickstart operation would include the following components:

- Kickstart configuration file
- A network configured so that different client systems can access the required installation and configuration files specific to those clients, over that network.

For an example of a network installation configuration, see [Creating a Network Installation Setup](#).

## Customizing the Kickstart Configuration File

The Kickstart configuration file consists of installation instructions in the form of options and any required parameters.

To create a Kickstart configuration file, choose one of the following methods:

- Use the `/root/anaconda-ks.cfg` file of an existing Oracle Linux system.  
  
Every Oracle Linux installation creates a file called `/root/anaconda-ks.cfg`. The file contains configuration definitions based on the system on which Oracle Linux is installed, which can be read by Kickstart. The file can be used, unmodified, to repeat the installation, or as a template that can be customized to apply to other Oracle Linux installations, such as which OS versions to install on specific clients.  
  
If the system contains the `pykickstart` package, the following useful tools can help with customization:
  - `ksverdiff` identifies removed or deprecated options.
  - `ksvalidator` checks that the syntax in the file is correct.
- Install an Oracle Linux release manually, which generates the `/root/anaconda-ks.cfg` file. Use the file to automatically install the same Oracle Linux release on other clients. You might need to adjust some configuration options in the file depending on the installation requirements of those clients.

For more information, see <https://pykickstart.readthedocs.io/en/latest/>.

The configuration file is divided into parts. Each part contains a group of options as follows:

- [Installation Options](#)

- [Packages to Install](#)
- [Preinstallation Options](#)
- [Postinstallation Options](#)

## Installation Options

Installation options define parameters for system storage, keyboard definitions, language setting, network information, and so on. In the following example, the option definition in bold lets PXE bring up the network interface and is important in network installations. It also shows how to specify using the Btrfs file system, which is available in UEK.

### Note:

To use the Btrfs file system that's available in UEK, ensure that you're using the UEK installation media as described in [Installing a System with a Btrfs root file system](#). Then you can use the `autopart` Kickstart option to automatically partition disks using Btrfs, as shown in the following example under `# Partition Information`.

If you're using local mirror repositories, ensure that these are current and that the Kickstart configuration includes the UEK repository required for Btrfs to function. Either use the Oracle Linux yum server to mirror the required repositories or, if you're unable to access the Oracle Linux yum server, you can mirror the repositories included on the full installation ISO, but you must use the UEK installation ISO to boot the installer. In the following example, the system is assumed to have Internet access and uses the publicly available Oracle Linux yum server repositories directly.

Or you can partition the disks to use Btrfs manually, as described in the upstream documentation.

```
#platform=x86, AMD64, or Intel EM64T
    #version=OL10
# Firewall configuration
firewall --enabled --service=ssh

# Use Oracle Linux yum server repositories as installation source
repo --name="ol10_AppStream" --baseurl="https://yum.oracle.com/repo/
OracleLinux/OL10/appstream/x86_64/"
url --url="https://yum.oracle.com/repo/OracleLinux/OL10/baseos/x86_64"

# Root password
rootpw --iscrypted SHA512_password_hash

# Use graphical install
graphical
firstboot --disable

# Keyboard layouts
keyboard --vckeymap=us --xlayouts='us'

# System language
lang en_US.UTF-8
```

```
# SELinux configuration
selinux --enforcing

# Installation logging
logging

# System timezone
timezone America/Los_Angeles

# Network information
network --bootproto=dhcp --device=em1 --onboot=yes
--hostname=hostname

# System bootloader configuration
bootloader --location=mbr --boot-drive=sda

# Non-administrative user
user --name=user --homedir=/home/user --password=SHA512_password_hash --
iscrypted

# Partition information

clearpart --all --initlabel --drives=sda
autopart --type=btrfs
```

## Packages to Install

Packages to be installed are listed under the group heading `%packages`. The list stops at the `%end line`.

```
%packages
@base
@core
@desktop-debugging
@dial-up
@fonts
@gnome-desktop
@guest-agents
@guest-desktop-agents
@input-methods
@internet-browser
@multimedia
@print-client
@print-server
@x11
mtools
pax
python-dmidecode
oddjob
wodim
sgpio
genisoimage
device-mapper-persistent-data
abrt-gui
samba-winbind
```

```
certmonger
openldap-clients
pam_krb5
krb5-workstation
ldapjdk
slapi-nis
libXmu
perl-DBD-SQLite
perl-Mozilla-LDAP
%end
```

The list includes package groups and individual packages. Names of package groups use the `@` prefix, such as `@base`, to distinguish them from individual packages.

To help decide which packages to include in the file, use the `dnf group list` command on an existing Oracle Linux server. The command displays both the installed package groups and the package groups that are available to install.

To specify more than one package for a match, you can use the wildcard character (`*`). To exclude a package from the installation, insert the `-` character as a prefix to the package name.

The `%packages` keyword can take options, such as the following useful ones:

**--ignoremissing**

Installs the available packages without prompting about missing packages. Without this option, Kickstart would interrupt the installation and prompt you to continue or cancel the installation.

**--multilib**

Sets the `multilib` policy in `dnf` configuration to `all` so that 32-bit packages can be installed on the system.

Instead of listing packages directly in the configuration file, you can compile these names into a separate file and store it in an accessible location, such as locally in a Kickstart's ramdisk file system, or on an HTTP server or an NFS share. Then in the configuration file, specify the full path to this secondary file in an `%include` statement, for example:

```
%packages --ignoremissing
%include /tmp/package-list
%end
```

## Preinstallation Options

Preinstallation options define any actions that the installer must perform before beginning the installation process. These options are specified under the `%pre` heading and ended by the `%end` line. This section isn't mandatory.

In the following example, the installer is instructed to run the script `config-partitions` that's stored on an HTTP server. It then downloads a list of packages from the web server for use with a `%include /tmp/package-list` statement in the `%packages` section. The `wget` command saves the package list in Kickstart's file system, which exists as a ramdisk in memory.

```
%pre
%include http://server-ip-address/scripts/config-partitions
```

```
wget -q -O- http://server-ip-address/scripts/package-list > /tmp/package-list
%end
```

Any included script or file must be accessible at the specified path or URL. If no name service is available to identify hosts, then use IP addresses.

## Postinstallation Options

Postinstallation options define any actions to be completed by the installer at the end of the installation. This section isn't mandatory.

These options are specified under the `%post` heading and ended by the `%end` line.

The `root` account is locked by default. To enable SSH root logins to the system, add the following line to the kickstart file.

```
%post
echo "PermitRootLogin yes" > /etc/ssh/sshd_config.d/01-permitrootlogin.conf
%end
```

By default, Kickstart runs postinstallation tasks in a `chroot` environment that's based on the root file system of the newly installed system. If you need to access any files that are outside the `chroot` environment, specify the `--nochroot` option to the `%post` heading. You can then access files in the Kickstart file system with the newly installed system's root file system mounted at `/mnt/sysimage`.

In the following example, the script `/tmp/post-config` is run at the end of the installation.

```
%post --nochroot
%include /tmp/post-config
%end
```

If you configure the installed system's network interface to obtain its settings using DHCP, you must either use IP addresses instead of domain names or set up a temporary `resolv.conf` file, for example:

```
%post
wget -q -O- http://192.168.1.100/scripts/resolv.conf > /etc/resolv.conf
%include http://instsvr.example.com/scripts/post-config
.
.
.
%end
```

## Starting the Kickstart Installation

Before starting the Kickstart installation, ensure that you have prepared the following:

- Access to the full installation media, which can be on a local CD-ROM drive or USB drive. See the [instructions on media preparation](#).
- Access to the Kickstart configuration file.

Then, follow the steps in the appropriate guide:

- [Installing Over the Network](#)
- [Installing Locally](#)

## Installing Over the Network

This task describes how to install the OS using a Kickstart file over the network.

1. Boot the system.
2. During the boot sequence, access the system's BIOS.
3. On the BIOS screen, change the system settings to boot from the network.
4. Save the changes and continue with the boot process.
5. When the boot menu appears, select an installation option then press either the `e` (UEFI-based systems) or `Tab` (BIOS-based systems) key to access the boot prompt.
6. Add the the location of the Kickstart file in the network.

The location must specify the network server's protocol and FQDN or IP address. For example, if you're using an NFS server, then you might enter the following line:

```
nfs:options:fqdn/path-to-file
```

### Note:

Another way of installing from the network is by using a boot server. In this scenario, the installation automatically begins when you turn on the system. See [Creating a Network Installation Setup](#).

7. Save the boot configuration revisions and continue the boot process. At the end of the boot process, the installation proceeds immediately.

## Installing Locally

This task describes how to install an OS using a local Kickstart file.

1. Boot the system from the local boot media.
2. When the boot menu appears, select an installation option. Then press either the `e` (UEFI-based systems) or `Tab` (BIOS-based systems) key to access the boot prompt.
3. Specify the location of the Kickstart file.

Add the appropriate option that identifies the location of the Kickstart file, for example:

```
inst.ks=cdrom:/dev/sbd1/tmp/ks.cfg
```

For more information about boot options, see [Customizing Boot Loader Actions](#).

4. Save the boot configuration revisions and continue the boot process. At the end of the boot process, the installation proceeds immediately.

# 5

## Using a Driver Update Disk During Installation

To use the DUD during an installation, select one of the following methods depending on where the DUD image is stored.

- Use a DUD image in an attachable media (USB)
  1. Boot the system from the standard Oracle Linux installation media.
  2. While the system is booting, but before the installer starts, attach the media that contains the DUD image.

As an example, attach the media when the system displays the GRUB boot prompt.

The installer recognizes the DUD and uses it. The installer might also prompt you to select the drivers to install.

### Note:

The kernel used by the installer might not include support for USB 3.0. When using the DUD on USB media, ensure that you use a USB 2.0 compatible port when connecting the USB media to the system.

- Use a DUD image on the network
  1. While the system is booting, press the `e` key to edit the boot options.
  2. Add the following line to the boot options:

```
inst.dd=network-location
```

The network location can be a URL, such as `http://www.example.com/dd.iso`, or the full path of the NFS share directory.

If you're using DUD in a Kickstart installation, indicate the DUD location in the Kickstart file. The specific entry to add depends on the location of the DUD image.

- DUD image is in an attached block device:

```
driverdisk /dev/sdb1
```

- DUD image is on the network location:

```
driverdisk --source=network-location
```

The network location can be a URL, such as `http://www.example.com/dd.iso`, or the full path of the NFS share directory.

# 6

## Installing a System With a Btrfs root File System

Oracle Linux uses XFS as the default file system, but you can also use ext4, and shared file systems such as NFS and Samba.

The Btrfs file system is available in Oracle Linux, but only on UEK. Thus, to install Oracle Linux with Btrfs, you must use the UEK ISO image.



### Note:

UEK is the only kernel available for aarch64 hardware.

For more information about file systems in Oracle Linux, see [Oracle Linux 10: Performing File System Administration](#).

Similarly to any installation of a standard Oracle Linux release, installing the OS with a Btrfs file system can also be completed in two modes:

- [Using the GUI Installer](#)
- [Using the Text Installer](#)

You can also install a system with a Btrfs root file system using Kickstart automation as described in [Automating the Installation by Using Kickstart](#). If you choose to perform an automated installation with a network installation setup, as described in [Creating a Network Installation Setup](#), ensure that you configure the network boot to use the installation kernel and ram-disk image provided in the UEK ISO image and that you have mirrored all required repositories, or you might get an error stating that Btrfs isn't available for the partitioning type.

## Using the GUI Installer

The following steps are limited to what's relevant to a Btrfs installation. For the complete procedure, see [Installing in Graphics Mode](#).

1. Boot the system from the installation media using the Unbreakable Enterprise Kernel boot ISO file.
2. On the Installation Summary screen, select **Installation Destination**, then select the local disks and add any **Specialized & Network** disks that you want to use for the installation.
3. Under Storage Configuration, select **Custom** and then click **Done**.

The Manual Partitioning screen is displayed. Custom partitioning can be either automatic, where mount points are automatically created, or manual, where you individually create and configure mount points.

### Automatic Partitioning

- a. From the list of partitioning schemes, select **Btrfs**.

- b. Click **Click here to create them automatically**.

The following mount points are created:

- /home
- /boot
- / (root)
- swap


- c. Optionally, select each mount point and verify in the corresponding information that the mount point's device type is `Btrfs`.

 **Note:**

The swap partition can't be configured as a Btrfs file system.

The mount point information might resemble the following example:

**Figure 6-1 Mount Points**



- d. Optionally for each mount point, configure the respective volumes.
- e. Click **Done**, then on the partition summary that's displayed, click **Accept Changes**.

**Manual Partitioning**

- a. From the list of partitioning schemes, select `Btrfs`.
- b. Click **+** to create the mount point.  
The **Add A New Mount Point** window opens.
- c. Select the mount point and enter its size as prompted, then click **Add mount point**.

As a minimum, create mount points for `/`, `/boot`, `/home`, and `swap`.

- d. Select each mount point you created and verify that their corresponding information is correct.

 **Note:**

The `swap` partition can't be configured as a Btrfs file system.

- e. Optionally, change the volume of each mount point, as needed.
  - f. Click **Done** and on the partition summary that's displayed, click **Accept Changes**.
4. Complete the configuration of any other sections in the Installation Summary screen.
  5. Click **Begin Installation**.

## Using the Text Installer

The following steps are limited to what's relevant to a Btrfs installation. For the complete procedure, see [Installing in Text Mode](#).

1. From the text based installation menu, type `5` to configure Installation Destination.
  - a. **Installation Destination:** If the preferred disk is already selected, type `c` to continue. Otherwise, type the number corresponding to the disk you want to use, press Enter, then type `c` to continue.
  - b. **Partitioning Options:** If the preferred option is already selected, type `c` to continue. Otherwise, type the number corresponding to the preferred option, press Enter, then type `c` to continue.
  - c. **Partition Scheme Options:** Type `2` to use Btrfs, press Enter, then type `c` to return to the main menu.
2. Configure all the remaining settings that are flagged with the warning symbol (!).
3. After you have completed configuring all the installation options, type `b` to begin the installation.

## Verifying the Btrfs Installation

When the entire installation process has completed and you can sign in to the system, you can use various tools to verify the file system configuration. The following example shows the output of the `sudo df -Thk` command:

```
sudo df -Thk
```

```
Filesystem Type 1K-blocks    Used Available Use% Mounted on
...
/dev/sda3 btrfs    209606660 67708388 141898272  33% /
/dev/sda2 btrfs     4128768    756460   3372308   19% /boot
/dev/sda1 vfat      1033224    12556   1020668    2% /boot/efi
/dev/sda4 btrfs    267254276 95711592 171542684  36% /home
...
```

Optionally, you can complete other tasks as described in [Postinstallation Configuration](#).

# 7

## Troubleshooting Oracle Linux Installations

This chapter describes some options for troubleshooting Oracle Linux installations. Also check the Oracle Linux release notes of the specific Oracle Linux release you're installing in [Oracle Linux](#) for any known issues.

For known hardware issues, see the release notes for your UEK release in the [Unbreakable Enterprise Kernel documentation](#).

### Troubleshooting Menu Options

The boot menu on the Oracle Linux installation media contains a Troubleshooting option with the following options:

**Install the Oracle Linux release in basic graphics mode**

Use this option if the screen goes blank or appears distorted when you try to install Oracle Linux in graphics mode.

**Rescue an Oracle Linux system**

Use this option to boot an installed system in a mode that lets you edit partitions or configuration files to fix various boot problems.

**Boot from local drive**

Use this option to boot an installed system from the hard disk.

### Debug and Log Information

During an installation, you can press **Ctrl+Alt+F1** to display the virtual console for the installation program. This console contains messages and debugging information output for the installation program. Other virtual consoles are available to display log information from different sources, as described in the following section. Press **Ctrl+b**, and then press either **n** (for next) or **b** (for back) to switch between the virtual consoles. To return to the graphical installation program, press **Ctrl+Alt+F6**.

During an installation, several log files are generated, which capture messages from the following sources:

**Anaconda program**

The `/tmp/anaconda.log` file contains Anaconda logs relating to the installation. During the installation you can access the messages stored in this log by pressing **Ctrl+Alt+F1** to display the virtual console, then press **Ctrl+b**, and then press **3**. If the installation succeeds, the log file is copied to `/var/log/anaconda/anaconda.log`.

**Hardware detection and configuration**

The `/tmp/syslog` file contains messages relating to the system hardware. If the installation succeeds, the log file is copied to `/var/log/anaconda/syslog`.

### **Dbus information**

The `/tmp/dbus.log` file contains messages relating to communication between background services and installer components using `dbus` (Desktop Bus).

If the installation succeeds, the log file is copied to `/var/log/anaconda/dbus.log`.

### **Kickstart**

The `/tmp/ks-name.log` file contains logs from Kickstart installations.

If the installation succeeds, the log file is copied to `/var/log/anaconda/ks-script-name.log`.

### **Other programs**

The `/tmp/program.log` file contains logs from all other programs used during the installation.

During the installation you can view the messages stored in this log by pressing **Ctrl+Alt+F1** to display the virtual console, then press **Ctrl+b**, and then press 5.

If the installation succeeds, the log file is copied to `/var/log/anaconda/program.log`.

### **Package installation**

The `/tmp/packaging.log` file contains package installation messages output by the `dnf` and `rpm` commands.

If the installation succeeds, the log file is copied to `/var/log/anaconda/packaging.log`.

### **Storage detection and configuration**

The `/tmp/storage.log` file contains logs from the storage modules.

During the installation you can view the messages stored in this log by pressing **Ctrl+Alt+F1** to display the virtual console, then press **Ctrl+b**, and then press 4.

If the installation succeeds, the log file is copied to `/var/log/anaconda/storage.log`.

If the installation fails, the messages from these log files are combined into a single log file at `/tmp/anaconda-tb-name`.

To access a shell prompt as the `root` user during the installation, press **Ctrl+Alt+F1** to display the virtual console. Then, press **Ctrl+b**, followed by pressing the number 2. You can use the shell prompt to access the log files and to copy them to a local storage device such as a USB device. Or, you can copy the log files to a network location by using the `scp` command.

# A

## Creating a Network Installation Setup

Network installations are helpful in scenarios where you must install the OS on multiple systems.

If you use a boot ISO or the Preboot eXecution Environment (PXE) to install the OS, you can set up a network installation configuration that consists of the following components:

- A network installation server that serves the network configuration, consisting of the PXE configuration files, kernel, and boot images, and kernel boot directives. In this example, `dnsmasq` is used to provide these services.
- A network accessible file system server over a protocol such as NFS or HTTP, where packages, the Kickstart file, and other required configuration files might be stored. In this document, NFS is used as the file system. Note that if systems have direct access to the Internet, you can configure the Kickstart installation to use the BaseOS and AppStream repositories directly available on the Oracle Linux yum server for the package installation. You can also create a yum mirror of these repositories as described in [Oracle Linux: Managing Software on Oracle Linux](#) so that systems that don't have direct access to the Internet have access to a complete set of packages. However, you would still need to provide a mechanism to serve the Kickstart file up to the system when it boots.

The two components can be on separate systems. Also, they aren't required to run the latest Oracle Linux version. A previous release would suffice. For convenience, the scenario in this example assumes that the two components are hosted in one system. It also assumes that Kickstart installation is used.

## Setting Up the Network Server

Preparing a server for a network installation consists of the following general tasks:

- [Configuring NFS](#)
- [Configuring dnsmasq](#)

## Configuring NFS

If you have an existing NFS server, you can use this service to host the extracted contents of an ISO and any Kickstart configuration files. Ensure that the exported share directories are accessible to the IP ranges specified for the PXE boot hosts.

If you don't have an available NFS server, use the following procedure to install and configure the service to enable network installation.

### Note:

These NFS configuration steps are limited only to what's relevant to a network installation.

1. Install the `nfs-utils` package:

```
sudo dnf install nfs-utils -y
```

2. If you're running a firewall service, add the `nfs` service to the firewall rules.

```
sudo firewall-cmd --add-service nfs --permanent
```

If you're using a different firewall service or you have an external firewall device, ensure that you configure rules that grant PXE boot hosts access to the NFS service on this system.

3. Create a directory to store the ISO image, for example:

```
sudo mkdir /var/nfs-exports/ISOs
```

4. Export the NFS share directory.

```
sudo exportfs -i -o ro [subnet]:/var/nfs-exports/ISOs
```

This syntax grants world access to the NFS share with read-only permissions. Adding *subnet*, for example: `192.0.2.0/24:/var/nfs-exports/ISOs`, limits access only to the subnet's clients.

Or, you can add an entry for exporting the share directory in the `/etc/exports` file, for example:

```
/var/nfs-exports/ISOs 192.0.2.0/24(ro)
```

Then, reload the `/etc/exports` to implement the entry:

```
sudo exportfs -ra
```

For more information, see the `exportfs(8)`, `exports(5)`, and `showmount(8)` manual pages.

5. Enable and start the `nfs-server` service:

```
sudo systemctl enable --now nfs-server
```

6. Extract the downloaded ISO image to a subdirectory of the NFS share directory:

```
sudo cp -a T path-to-download-image /var/nfs-exports/ISOs/ol10
```

7. If using Kickstart, put the Kickstart files in a subdirectory of the NFS share directory, such as `/var/nfs-exports/ISOs/ksfiles`.

8. (Optional) From a different system with the `nfs-utils` package installed, verify that the NFS share directory is accessible, for example:

```
sudo mount -t nfs NFS-server-ip:/var/nfs-exports/ISOs /mnt
```

## Configuring dnsmasq

The dnsmasq router advertisement server is designed to act as a DNS forwarder, DHCP server, and TFTP server. Dnsmasq is applicable in most network installation scenarios and avoids needing to configure separate DHCP and TFTP services.

For more information about dnsmasq, see the `dnsmasq(8)` manual page, the `/usr/share/doc/dnsmasq-version` file, and <https://thekelleys.org.uk/dnsmasq/doc.html>.

1. Install the `dnsmasq` package.

Run the following command to install `dnsmasq`:

```
sudo dnf install dnsmasq -y
```

2. Configure parameters in the `/etc/dnsmasq.conf` file.

At a minimum, you must have the `enable-tftp` entry and a defined TFTP server directory for `tftp-root`. See the entries in bold in the following example:

```
interface=em1
dhcp-range=10.0.0.101,10.0.0.200,6h
dhcp-host=80:00:27:c6:a1:16,10.0.0.253,svr1,infinite
dhcp-boot=pxelinux/pxelinux.0
dhcp-match=set:efi-x86_64,option:client-arch,8
dhcp-boot=tag:efi-x86_64,shim.efi
enable-tftp
tftp-root=/var/lib/tftpboot
```

 **Note:**

If SELinux is enabled in enforcing mode on the system and you configured a TFTP server directory other than `/var/lib/tftpboot`, install the `policycoreutils-python` and `policycoreutils` packages to enable you to run the following commands:

```
sudo /usr/sbin/semange fcontext -a -t tftpdirt "/var/
tftpboot(/.*)?"
sudo /sbin/restorecon -R -v /var/tftpboot
```

These commands define the default file type of the TFTP server directory hierarchy as `tftpdirt` and apply the file type to the entire directory hierarchy.

The following list describes the other parameters in the `/etc/dnsmasq.conf` file:

**interface**

Specifies the interface to be monitored for incoming client requests.

**dhcp-range**

Identifies a range of available IP addresses. The `6h` setting in the example specifies a six-hour lease of the addresses.

To configure static addresses with infinite leases, instead of a pool, specify a static network address and use the `static` and `infinite` keywords, for example:

```
dhcp-range=10.0.0.253,static,infinite
```

**dhcp-host**

Specifies a reserved IP address for a client system. The system is identified by its name and MAC address.

**dhcp-boot**

Specifies the location of the boot loader file for clients, such as `pxelinux/pxelinux.0` for BIOS-based clients. For UEFI-based clients, include the `tag:efi-x86_64` keyword in the setting before specifying the boot loader, for example:

```
dhcp-boot=tag:efi-x86_64,shim.efi
```

You must create separate entries for BIOS-based and UEFI-based clients.

**dhcp-match**

Matches DHCP clients on criteria such as the vendor class identifier or architecture type and sets a tag that can be used to select the appropriate DHCP boot type.

Uncomment the `tftp-no-blocksize` line in the file as shown:

```
# This option stops dnsmasq from negotiating a larger blocksize for TFTP
# transfers. It will slow things down, but may rescue some broken TFTP
# clients
tftp-no-blocksize
```

3. (Optional) To use dnsmasq as a caching-only name server, do the following:
  - a. In the `/etc/resolv.conf` file, configure a name server entry for 127.0.0.1 that precedes other name server entries, for example:

```
nameserver 127.0.0.1
nameserver 10.0.0.8
nameserver 10.0.0.4
```

The dnsmasq server ignores the 127.0.0.1 entry and forwards DNS queries to the other listed name servers.

- b. Configure the firewall to accept DNS requests:

```
sudo firewall-cmd --add-service=dns --permanent
```

4. Enable and start the dnsmasq service.

Run the following command to start the dnsmasq service and make it start automatically on system boot:

```
sudo systemctl enable --now dnsmasq
```

## Configuring PXE Boot Loading

The steps to configure a PXE boot loader depends on the type of system that's used for the boot server.

- [Configuring PXE Boot Loading for BIOS Clients](#)
- [Configuring PXE Boot Loading for UEFI Clients](#)

### ! Important:

You must use the correct kernel and ram-disk image for the type of installation that you want. For example, if you intend to install a system with a Btrfs root partition, you must use the UEK boot ISO to obtain the correct kernel and image for the system to provide Btrfs.

## Configuring PXE Boot Loading for BIOS Clients

1. Install the `syslinux-tftpboot` package, which contains the required installation files.

Run the following command to install `syslinux-tftpboot`:

```
sudo dnf install syslinux-tftpboot -y
```

This package writes the `pxelinux.0` boot loader and various menu modules to the `/tftpboot` directory.

2. Create the `pxelinux/pxelinux.cfg` directory under the TFTP server directory.

Run the following command to create the `pxelinux/pxelinux.cfg` directory:

```
sudo mkdir -p /var/lib/tftpboot/pxelinux/pxelinux.cfg
```

3. Copy the boot loader and menu modules to the `pxelinux` subdirectory.

Run the following command to copy the required files:

```
sudo cp -a /tftpboot/. /var/lib/tftpboot/pxelinux
```

4. Copy the required installation files to the `pxelinux` subdirectory.

From the NFS share directory, copy the installation kernel (`vmlinuz`), and the ram-disk image file (`initrd.img`) to the `pxelinux` subdirectory.

```
sudo cp /var/nfs-exports/ISOs/ol10/vmlinuz /var/lib/tftpboot/pxelinux/vmlinuz
sudo cp /var/nfs-exports/ISOs/ol10/initrd.img /var/lib/tftpboot/pxelinux/initrd.img
```

5. In the `pxelinux.cfg` subdirectory, create a PXE menu configuration file.

You can assign any name to the file, such as `pxe.conf`. The following example shows typical entries in the file:

```
MENU TITLE PXE Server
NOESCAPE 1
ALLOWOPTIONS 1
PROMPT 0
menu width 80
menu rows 14
MENU TABMSGROW 24
MENU MARGIN 10
menu color border          30;44          #ffffffff #00000000 std
```

#### 6. Create the `pxelinux.cfg/default` PXE configuration file.

The following example shows typical entries in the file:

```
DEFAULT vesamenu.c32
TIMEOUT 400
ONTIMEOUT BootLocal
PROMPT 0
MENU INCLUDE pxelinux.cfg/pxe.conf
NOESCAPE 1
LABEL BootLocal
    localboot 0
    TEXT HELP
    Boot to local hard disk
    ENDTEXT

LABEL OL10
    MENU LABEL OL10
    kernel vmlinuz
    append initrd=initrd.img inst.repo=/var/nfs-exports/ISOs/ol10/ \
    inst.ks.sendmac inst.ks=/var/nfs-exports/ISOs/ksfiles/kstart-file
    TEXT HELP
    Install Oracle Linux 10
    ENDTEXT
```

Based on these entries, the boot loader would automatically try to boot from the local drive if no user intervention occurs during the `TIMEOUT` period. If no OS is installed, then the boot loader would boot from the network and start the installation process.

This list explains some directives used in the configuration file:

- `DEFAULT` identifies the module you want to use for displaying the boot loader menu. For a basic text UI, specify the `menu.c32` module. However, if you add directives for a graphical UI (such as images and colors), then specify the `vesamenu.c32` module instead.
- `TIMEOUT` specifies the period in `timeout/10` seconds before the boot loader boots the client according to the subsequent directives. The next directive (`ontimeout`) specifies the action when the wait period expires.
- `PROMPT` specifies whether the `boot: prompt` is displayed by default. If `PROMPT` is set to 1, the `boot: prompt` is displayed. If `PROMPT` is set to 0, the `boot: prompt` isn't displayed unless the user presses the `Shift` or `Alt` key at the console.

- `MENU INCLUDE` supplies the path to the boot configuration file you created.
- `kernel` defines the name of the kernel executable.
- `append` defines any parameters to append when loading the kernel, such as the name of the ram-disk image and the location of a file. Note that the `inst.repo` variable can be set to point to the BaseOS repository on the Oracle Linux yum server if the system has access to the Internet. For example, `inst.repo` can be set to `https://yum.oracle.com/repo/OracleLinux/OL10/baseos/latest/x86_64` for an `x86_64` platform system.

**! Important:**

The kernel and ram-disk image file paths are assumed to be relative to the subdirectory that contains the boot loader, such as `pxelinux`. If you place the `vmlinuz` and `initrd.img` files in a subdirectory such as `pxelinux/OL10`, ensure you have the correct relative paths.

## Configuring PXE Boot Loading for UEFI Clients

1. Download the `grub2-efi` and `shim` packages.

Create a temporary directory and then download the required packages:

```
mkdir /tmp/boot_rpms
sudo dnf download shim grub2-efi --downloadaddir=/tmp/boot_rpms
```

2. Go to the package location and extract their contents.

Run the following commands to extract the contents of the `grub2-efi` and `shim` packages:

```
cd /tmp/boot_rpms
sudo rpm2cpio grub2-efi-version.rpm | cpio -idmv
sudo rpm2cpio shim-version.rpm | cpio -idmv
```

3. Create a subdirectory under the TFTP server directory.

For example, the following command creates the `efi` subdirectory under `/var/lib/tftpboot`:

```
sudo mkdir -p /var/lib/tftpboot/efi
```

4. Copy the boot loader and other related files to the `efi` subdirectory.

Run the following command to copy the required files to `/var/lib/tftpboot/efi`:

```
sudo cp /tmp/boot_rpms/boot/efi/EFI/redhat/grubx64.efi /var/lib/tftpboot/efi
sudo cp /tmp/boot_rpms/boot/efi/EFI/redhat/shim*.efi /var/lib/tftpboot/efi
sudo cp /tmp/boot_rpms/boot/efi/EFI/redhat/MokManager.efi /var/lib/tftpboot/efi
```

 **Note:**

The `shim.efi` and `MokManager.efi` files are needed to support Secure Boot on clients. The `MokManager.efi` provides utilities for managing the keys used to sign EFI binaries. As a passthrough boot loader, you would then specify `shim.efi` when setting `dhcp-boot` for UEFI-based clients in the `/etc/dnsmasq.conf` file. See [Configuring dnsmasq](#).

5. From the NFS share directory, copy the installation kernel (`vmlinuz`) and the ram-disk image file (`initrd.img`) to the `efi` subdirectory.

Run the following commands to copy the required files to `/var/lib/tftpboot/efi`:

```
sudo cp /var/nfs-exports/ISOs/ol10/vmlinuz -O /var/lib/tftpboot/efi/vmlinuz
sudo cp /var/nfs-exports/ISOs/ol10/initrd.img /var/lib/tftpboot/efi/
initrd.img
```

6. Create the `/var/lib/tftpboot/efi/grub.cfg` boot loader configuration file.

The configuration file includes the options for booting from the network and for booting locally. The client boots from the network to begin the installation process. Then after the client reboots at the end of the installation, the system boots from the local drive.

The following example shows typical entries in the file:

```
set default 0
set timeout=10

menuentry 'ol10 localboot' {
  echo "Booting from local disk"
  set root=(hd0,gpt1)
  chainloader efi/shim.efi
  boot
}

menuentry 'ol10' {
  echo "Loading vmlinuz"
  linuxefi vmlinuz inst.repo=/var/nfs-exports/ISOs/ol10/ inst.ks.sendmac \
  inst.ks=/var/nfs-exports/ISOs/ksfiles/kstart-file
  echo "Loading /initrd.img"
  initrdefi initrd.img
  echo "Booting installation kernel"
}
```

 **Caution:**

Boot loader configuration isn't uniform across UEFI-based systems. Because of variables such as differing disk layout, a specific boot loader setup doesn't universally apply to all systems. The previous example illustrates only one way of configuring the boot loader. You must create boot loader configurations appropriate to the systems that you're setting up.

- `linuxefi` defines the name of the kernel executable and any parameters to append when loading the kernel, such as the location of the installation packages and the location of a file.
- `initrdefi` defines the name of the ram-disk image.

### Important:

The kernel and ram-disk image file paths are assumed to be relative to the subdirectory that contains the boot loader, such as `efi`. If you place the `vmlinuz` and `initrd.img` files in a subdirectory, such as `efi/OL10`, ensure you have the correct relative paths.

## Using Different Kinds of Clients

To use different types of clients, you can create a configuration file with the name based on the following:

- Client's UUID, for example, `a8943708-c6f6-51b9-611e-74e6ac80b93d`

### Note:

A UUID-based file name is valid only for BIOS-based clients. Don't use it for UEFI-based clients.

- Client's MAC address prefixed by `01-`, which represents the ARP hardware type for Ethernet, and using dashes to separate byte values instead of colons, for example, `01-80-00-27-c6-a1-16`.

Use lowercase characters when typing the MAC address.

- Client's IP address expressed in hexadecimal without any leading `0x`, for example, `0A0000FD` represents the IP address `10.0.0.253`.

To reduce the number of configuration files, you can group clients by IP address range, for example, `0A0000E` represents the IP address range `10.0.0.224` through `10.0.0.239`.

If you're serving both types of clients, ensure that the file names are distinct from each other. Where the configuration file for BIOS-based clients is `A000FC`, for example, the file name for UEFI-based clients can be `grub.cfg-A000FC`, and so on.

Place the configuration files in their respective boot loader subdirectories such as `pxelinux/pxelinux.cfg` for BIOS-based clients or `efi` subdirectory for UEFI-based clients.

The boot loader searches for a configuration file in the following order, until a matching file name is found:

- `UUID` (for example, `a8943708-c6f6-51b9-611e-74e6ac80b93d`)
- `01-MAC_address` (for example, `[grub2-cfg-]01-80-00-27-c6-a1-16`)
- Full 32 bits of the IP address (for example, `[grub.cfg-]0A0000FD`)
- Most significant 28 bits of the IP address (for example, `[grub.cfg-]0A0000F`)
- Most significant 24 bits of the IP address (for example, `[grub.cfg-]0A0000`)

- Most significant 20 bits of the IP address (for example, `[grub.cfg-]0A000`)
- Most significant 16 bits of the IP address (for example, `[grub.cfg-]0A00`)
- Most significant 12 bits of the IP address (for example, `[grub.cfg-]0A0`)
- Most significant 8 bits of the IP address (for example, `[grub.cfg-]0A`)
- Most significant 4 bits of the IP address (for example, `[grub.cfg-]0`)
- Default configuration file (either `default` for BIOS-based clients or `grub.cfg` for UEFI-based clients).

If several configuration files for a client type have identical content, you can use the `ln` command to link the files to a primary copy, for example:

```
sudo ln primary-ol-verson [grub.cfg-]0A0000FC
```

```
sudo ln primary-ol-verson [grub.cfg-]0A0000FD
```

```
sudo ln primary-ol-verson [grub.cfg-]0A0000FE
```

For more information about pxelinux, see <https://wiki.syslinux.org/wiki/index.php?title=PXELINUX>.

For more information about GRUB 2, run the `info grub` command to access the GRUB 2 manual.