Managing Remote Systems in Oracle® Solaris 11.3



Managing Remote Systems in Oracle Solaris 11.3

Part No: E54791

Copyright © 2002, 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing,

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Référence: E54791

Copyright © 2002, 2017, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer un risque de dommages corporels. Si vous utilisez ce logiciel ou ce matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour des applications dangereuses.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée de The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info ou le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs si vous êtes malentendant.

Contents

U	sing This Documentation
1	About Managing Remote Systems
	What Is the FTP Server?
	What Is a Remote System?
	About FTP Servers in Oracle Solaris 11 Release
	Differences From Standard ProFTPD
	ProFTPD Components
	ProFTPD Commands
	ProFTPD Files
	ProFTPD User
2	Administering the FTP Server
	Task Map for Administering the FTP Server
	Administering the FTP Server
	▼ How to Start an FTP Server Using SMF
	▼ How to Shut Down the FTP Server Using SMF
	▼ How to Shut Down the FTP Connection
	▼ How to Change the ProFTPD Configuration
3	Accessing Remote Systems 17
	Task Map for Accessing Remote Systems
	Accessing a Remote System by Using Secure Shell
	▼ How to Access a Remote System by Using Secure Shell
	Logging In to a Remote System to Copy a File (sftp) 19
	Essential sftp Commands
	▼ How to Open and Close an sftp Connection to a Remote System
	▼ How to Copy Files From a Remote System (sftp)

	▼ How to Copy Files to a Remote System (sftp)	22
Rer	note Copying With the scp Command	23
	Security Considerations for Copy Operations	23
	Specifying the Source and Target for Copy Operations	24
	▼ How to Copy a File Between Two Systems (scp)	24
Index		27

Using This Documentation

- **Overview** Describes how to administer and use the FTP service to transfer files.
- **Audience** Oracle Solaris system administrators.
- **Required knowledge** Basic and some advanced network administration skills.

Product Documentation Library

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E53394-01.

Feedback

Provide feedback about this documentation at http://www.oracle.com/goto/docfeedback.

· · · CHAPTER 1

About Managing Remote Systems

This chapter includes information about working with remote files.

- "What Is the FTP Server?" on page 9
- "What Is a Remote System?" on page 9
- "About FTP Servers in Oracle Solaris 11 Release" on page 10
- "Differences From Standard ProFTPD" on page 10
- "ProFTPD Components" on page 10

What Is the FTP Server?

The Oracle Solaris release includes ProFTPD. The software implements the server side of the FTP protocol, which is widely used for distribution of bulk data over the Internet. For more information about the ProFPTD project, see http://www.proftpd.org.

What Is a Remote System?

For the purpose of this chapter, a *remote system* is a workstation or server that is connected to the local system with any type of physical network and configured for TCP/IP communication.

On systems running an Oracle Solaris release, TCP/IP configuration is established automatically during startup. For more information, see *Administering TCP/IP Networks, IPMP*, and IP Tunnels in Oracle Solaris 11.3.

About FTP Servers in Oracle Solaris 11 Release

The old FTP server based on the wu-ftpd distribution has been replaced by the proftpd server. The migration of configuration information from the old service to the new is described in /usr/share/doc/proftpd/proftpd migration.txt.

Differences From Standard ProFTPD

The following list discusses the items that are different in the Oracle Solaris 11 implementation of ProFTPD:

- The Oracle Solaris version of ProFTPD runs in stand-alone mode by default.
- This release does not use the logrotate command to rotate the service logs.

ProFTPD Components

The following section provides information about the commands, files, and other important components of the ProFTPD service. You can find additional documentation for the ProFTPD service in the /usr/share/doc/proftpd directory on a system running the Oracle Solaris 11 release.

ProFTPD Commands

The following table describes the commands and daemons that are associated with the ProFTPD service.

TABLE 1 ProFTPD Commands

File Name	Function
/usr/bin/ftp	Provides the user interface to the ProFTPD service. See the ftp(1) man page for more information.
/usr/bin/ftpcount	Shows the current number of connections per proftpd server, as well as per virtual host or anonymous configuration. See the ftpcount(1) man page for more information.
/usr/bin/ftpdctl	Controls the proftpd service daemon. See the ftpdctl(8) man page for more information.
/usr/bin/ftptop	Displays the current status of FTP sessions in a continuously updating format. See the <pre>ftptop(1)</pre> man page for more information.

File Name	Function
/usr/bin/ftpwho	Shows process information for all active proftpd connections and a count of all connected users to each proftpd server. See the ftpwho(1) man page for more information.
/usr/sbin/ftprestart	Restarts FTP connections by using the ftpshut -R command. See the ftpshut(8) man page for more information.
/usr/sbin/ftpscrub	Removes processes that are no longer live from the scoreboard file on demand. See the ftpscrub(8) man page and ProFTPD: ScoreboardFile for more information.
/usr/sbin/ftpshut	Shuts down FTP connections at a given time. See the ftpshut(8) man page for more information.
/usr/lib/inet/proftpd	Provides FTP services. See the proftpd(8) man page for more information.

ProFTPD Files

The following table lists many of the files that are associated with the ProFTPD service and their functions.

TABLE 2 ProFTPD Files

File Name	Function
~/.ftpaccess	Provides an additional control mechanism for each virtual host. The file should be placed in the home directory for the virtual host. See ProFTPD Developer's Guide: .ftpaccess files for more information.
/etc/proftpd.conf	Includes most of the configuration parameters that need to be defined in order for the ProFTPD service to function.
/etc/shutmsg	Includes information used by the ftpshut command.
/etc/ftpd/ftpusers	Lists the users to be disallowed FTP login privileges. Provided for backward compatibility with the wu-ftpd service.
/var/log/xferlog	Lists log information for ProFTPD.
/var/run/proftpd.scoreboard	Includes tracking information for each current session, which is used by commands like ftpcount, ftptop, and ftpwho. See ProFTPD: ScoreboardFile for more information.

ProFTPD User

A user and a group named ftp are created by the ProFTPD installation process. The ProFTPD server runs under these credentials.



Administering the FTP Server

This chapter includes tasks to set up and administer an FTP server.

- "Task Map for Administering the FTP Server" on page 13
- "Administering the FTP Server" on page 13

Task Map for Administering the FTP Server

The following table describes the procedures that are needed to use the FTP server.

TABLE 3 Administering the FTP Server (Task Map)

Task	Description	For Instructions
Start the FTP server.	Follow this procedure after changing the proftpd.conf file.	"How to Start an FTP Server Using SMF" on page 14
Stop the FTP server.	Follow this procedure before changing the proftpd.conf file.	"How to Shut Down the FTP Server Using SMF" on page 14
Shut down the FTP server connections.	Run the ftpshut to shut down the FTP connections during file system maintenance or other events that do not require that the service be stopped but access to the files needs to be denied.	"How to Shut Down the FTP Connection" on page 14
Reconfigure the FTP server.	Follow this procedure when changing the proftpd.conf file.	"How to Change the ProFTPD Configuration" on page 15

Administering the FTP Server

The following procedures show how to start and stop the FTP server, how to disable the FTP connection, and how to make changes to the ProFTPD configuration file.

▼ How to Start an FTP Server Using SMF

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Start the FTP server.

svcadm enable network/ftp

▼ How to Shut Down the FTP Server Using SMF

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Stop the FTP server.

svcadm disable network/ftp

▼ How to Shut Down the FTP Connection

The ftpshut(8) command closes down the FTP server at a particular time. If you want to stop serving FTP only, but not stop the daemon (so it can report the service is not available to clients) then use this procedure. The ftpshut command will block connections and stop the current connection, but not shutdown the server daemon itself.

When you run ftpshut, a file is generated from command-line options that specify when shutdown occurs, the point at which new connections are refused, and when existing connections are dropped. Users are notified of a server shutdown based on this information. The location of the file that is created by ftpshut is /etc/shutmsg.

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Run the ftpshut command.

```
# ftpshut [-l min] [-d min] time [warning-message...]
```

ftpshut	Command that provides a procedure for notifying users that the FTP server is shutting down.
-1	Flag that is used to adjust the time that new connections to the FTP server are denied
-d	Flag that is used to adjust the time that existing connections to the FTP server are disconnected
time	Shutdown time that is specified by the word now for immediate shutdown, or in one of two formats (+ <i>number</i> or <i>HHMM</i>) for a future shutdown
[warning- message]	Shutdown notification message; see the ftpshut(8) man page for more information

3. Restore access to the files.

Use the ftprestart command to restart the connections to the FTP server. For further information, see ftpshut(8) and ftprestart(8).

▼ How to Change the ProFTPD Configuration

Most configuration variations are made by making changes to the /etc/proftpd.conf file. Use the following steps when making changes to this file.

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Make changes to the configuration file.

See the examples below for suggestions about what information to add to the configuration file.

3. Restart the FTP server.

svcadm restart network/ftp

Example 1 ProFTPD Configuration File Changes for a Virtual Host

For a virtual host that is using a fixed IP address, use the following directive. You may add multiple IP addresses separated by spaces if needed.

```
<VirtualHost 192.0.2.1>
  ServerName "My virtual FTP server"
</VirtualHost>
```

Example 2 ProFTPD Configuration File Changes for Anonymous Access

To provide anonymous ftp access to your site, use these directives:

```
# Deny login access
    <Limit LOGIN>
        DenyAll
      </Limit>
      <Anonymous ~ftp>

# Allow anonymous logins
      <Limit LOGIN>
        AllowAll
      </Limit> ....
      </Anonymous>
```



Accessing Remote Systems

This chapter describes all the tasks that are required to log in to remote systems and work with their files. This is a list of the topics in this chapter.

- "Task Map for Accessing Remote Systems" on page 17
- "Accessing a Remote System by Using Secure Shell" on page 18
- "Logging In to a Remote System to Copy a File (sftp)" on page 19
- "Remote Copying With the scp Command" on page 23

Task Map for Accessing Remote Systems

This chapter provides tasks that are described in the following table. You can use these tasks to log in and copy files from remote systems.

TABLE 4 Accessing Remote Systems (Task Map)

Task	Description	For Instructions
Working on a remote system by using secure shell.	Use the ssh command to access a remote system.	"How to Access a Remote System by Using Secure Shell" on page 18
Log in to a remote system (sftp) to access files.	Use the sftp command to send and receive files on a remote system: Open and close an sftp connection. Copy files to and from a remote system.	"How to Open and Close an sftp Connection to a Remote System" on page 20 "How to Copy Files From a Remote System (sftp)" on page 21 "How to Copy Files to a Remote System (sftp)" on page 22
Copy remote files with scp.	Use the scp command to copy files to and from a remote system.	"How to Copy a File Between Two Systems (scp)" on page 24

Accessing a Remote System by Using Secure Shell

The Secure Shell feature of Oracle Solaris provides secure access to a remote system over an unsecured network. In Secure Shell, authentication is provided by the use of passwords and public keys. All network traffic is encrypted. Secure Shell prevents an intruder from intercepting the communication.

Authentication establishes your identity. Authentication for ssh logins is provided by a combination of system passwords and public host keys. Authentication operations can be performed either by the remote system or by the network environment. The /etc/ssh_known_hosts file and the ~/.ssh/known_hosts file contain the list of known host keys on the system or account. By default, the ssh command verifies the remote host's key. If there is no host key for the remote host in either file, the user is asked whether they trust the new remote host's key. If the user confirms, the remote host's key is then added to the user's ~/.ssh/known_hosts file before the user is prompted for their password.

For more information about Secure Shell authentication, refer to "Secure Shell Authentication" in *Managing Secure Shell Access in Oracle Solaris 11.3*.

▼ How to Access a Remote System by Using Secure Shell

Log in to a remote system.

ssh [-l login-name] hostname | login-name@hostname

login-name Non-default user name which can be used to log in to the remote system

hostname Name of the remote system

If the system's host key is verified, the user is prompted for the password. If the password is typed incorrectly, the user is prompted for the password again.

If the login to the system is successful, information about the user's last remote login to the system is displayed. The information displayed might include the version of the operating system running on the remote system, latest failed login attempts, and a notification about new email waiting for the user in the user's home directory.

2. Log out of a remote system.

Use one of the following commands to log out of the remote system:

exit

- logout
- Control-D

Example 3 Working on a Remote System by Using ssh

The following example shows the output of a remote login to host1. The system's host key has not been identified in either the /etc/ssh_known_hosts file or the ~/.ssh/known_hosts file. The user has typed an incorrect password at the first attempt.

```
# ssh -l amy host1
The authenticity of host 'host1 (2001:db8:100:12)' can't be established.
RSA key fingerprint is 06:55:4d:4e:d2:4a:e6:d9:8a:c4:13:15:18:9a:ef:dd.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added 'host1' (RSA) to the list of known hosts.
Password:
Password:
Warning: 1 failed authentication attempt at Wed Jun 27 12:47 2012 since last successful authentication.
Last login: Wed Jun 27 12:19:04 2012 from host2.example
Oracle Corporation SunOS 5.11 11.1 June 2012
# exit
```

Logging In to a Remote System to Copy a File (sftp)

The sftp command is an interactive file transfer program with a user interface similar to ftp. However, sftp uses the SSH File Transfer Protocol to create a secure connection to the server. Not all options available with the ftp command are included in the sftp command, but many of them are.

Essential sftp Commands

The following table lists essential sftp commands.

TABLE 5 Essential sftp Commands

Command	Description
sftp remote-system	Establishes an sftp connection to a remote system. For instructions, see "How to
	Open and Close an sftp Connection to a Remote System" on page 20.

Command	Description
sftp remote-system:file	Copies the named <i>file</i> from <i>remote-system</i> .
bye	Quits the sftp session.
help	Lists all sftp commands.
ls	Lists the contents of the remote working directory.
lls	Lists the contents of the local working directory.
pwd	Displays the name of the remote working directory.
cd	Changes the remote working directory.
lcd	Changes the local working directory.
mkdir	Creates a directory on the remote system.
rmdir	Deletes a directory on the remote system.
get	Copies a file from the remote working directory to the local working directory.
put	Copies a file from the local working directory to the remote working directory.
delete	Deletes a file from the remote working directory.

For more information, see the sftp(1) man page.

▼ How to Open and Close an sftp Connection to a Remote System

1. Open a connection to a remote system by using the sftp command.

\$ sftp remote-system

If the connection succeeds, a confirmation message and prompt are displayed.

2. If prompted, type your password.

Password: password

If the sftp interface accepts your password, it displays a confirmation message and the (sftp>) prompt.

You can now use any of the commands that are supplied by the sftp interface, including help. The principal commands are summarized in Table 5, "Essential sftp Commands," on page 19.

3. Close the sftp connection.

sftp> bye

Example 4 Opening an sftp Connection to a Remote System

This sftp session was established to connect to the remote system host1:

\$ sftp host1

Connecting to host1.
Password: password
sftp>

▼ How to Copy Files From a Remote System (sftp)

1. Establish an sftp connection.

See "How to Open and Close an sftp Connection to a Remote System" on page 20.

(Optional) Change to a directory on the local system where you want the files copied to.

sftp> lcd target-directory

Change to the source directory.

sftp> **cd** source-directory

4. Ensure that you have read permission for the source files.

sftp> ls -l

5. To copy a file, use the get command.

Metacharacters may be used with the get command.

sftp> **get** filename

6. Close the sftp connection.

sftp> **bye**

Example 5 Copying a File From a Remote System (sftp)

In this example, the user opens an sftp connection to the system host1, and uses the get command to copy a single file from the /tmp directory.

▼ How to Copy Files to a Remote System (sftp)

1. Change to the source directory on the local system.

The directory from which you type the sftp command is the local working directory and thus the source directory for this operation.

2. Establish an sftp connection.

See "How to Open and Close an sftp Connection to a Remote System" on page 20.

3. You can change to the target directory.

```
sftp> cd target-directory
```

4. Ensure that you have write permission in the target directory.

```
sftp> ls -l target-directory
```

5. To copy a single file, use the put command.

Metacharacters may be used with the get command.

```
sftp> put filename
```

6. Close the sftp connection.

```
sftp> bye
```

Example 6 Copying a File to a Remote System (sftp)

In this example, the user opens an sftp connection to the system host1, and uses the put command to copy a file from their system to the /tmp directory on system host1.

Remote Copying With the scp Command

The scp command copies files or directories between a local and a remote system or between two remote systems. You can use this command from a remote system (after logging in with the ssh command) or from the local system. The scp command uses ssh for data transfer. Thus, the scp command uses the same authentication and provides the same security as the ssh command.

With scp, you can perform the following remote copy operations:

- Copy a file or directory from your local system to a remote system
- Copy a file or directory from a remote system to your local system
- Copy a file or directory between remote systems from your local system

Security Considerations for Copy Operations

To copy files or directories between systems, you must have permission to log in and copy files.

The scp command, as a component of the ssh command, requires that you have either a user account or host key access to the target system. Consult Chapter 1, "Using Secure Shell" in *Managing Secure Shell Access in Oracle Solaris 11.3* for further information.



Caution - Both the cp and scp commands can overwrite files without warning. Ensure that file names are correct before executing the command.

Specifying the Source and Target for Copy Operations

With the scp command, you can specify the source (the file or directory to be copied) and the target (the location in which to copy the file or directory). You can shorten the path strings by using the tilde character (~) and the shell wildcard characters (*, ?, and so forth).

The tilde character (~) is expanded by all shell programs to be the current user's home directory. The current user is the user under which the shell is executing. If the home directory for the user jack is /export/home/jack, then for the user jack, ~/myfile.txt expands to /export/home/jack/myfile.txt.

This expansion also works for remote paths. If the user jack wants to copy a file from his home directory, then these three path descriptions are equivalent:

- host3:/export/home/jack/myfile.txt
- host3:~/myfile.txt
- host3:myfile.txt

This expansion is also useful when referring to another user's remote home directory. In this case, you would include the user's name after the tilde character. For the user jack, host3: ~jill/myfile.txt is equivalent to host3:/export/home/jill/myfile.txt, but it is shorter to type.

▼ How to Copy a File Between Two Systems (scp)

1. Ensure that you have permission to copy files on the target system.

The scp command requires authentication. Depending upon the method of authentication used, you must have either an account on the target system, or an authorized public key on the target system. You should at least have read permission on the source system and write permission on the target system.



Caution - If you do not have an account on the target system, or if the target system is not configured to allow public keys, you will receive an authentication error. For example:

\$ scp host3:/var/tmp/testdir/letter.txt .

Permission denied (gssapi-keyex,gssapi-with-mic,publickey,keyboard-interactive)

Ensure that you have either a user account or public key access configured on the target system for authentication. See "Secure Shell Authentication" in *Managing Secure Shell Access in Oracle Solaris* 11.3.

2. Determine the location of the source and target.

If you don't know the path of the source or target, you can first log in to the remote system with the ssh command, as described in "Accessing a Remote System by Using Secure Shell" on page 18. Then, navigate through the remote system until you find the location. You can then perform the next step without logging out of the remote system.

3. Copy the file or directory.

Example 7 Using the scp Command to Copy a Remote File to a Local System

In this example, scp is used to copy the file letter.doc from the /home/jones directory of the remote system host1 to the working directory on the local system.

In this example, this is the first time the system host1 is accessed, hence, the RSA key fingerprint message.

Here, the "." symbol at the end of the command line refers to the current working directory on the local system.

Example 8 Using the scp Command to Copy a Local File to a Remote System

In this example, scp is used to copy the file notice.doc from the home directory (/home/smith) of the local system earth to the /home/jones directory of the remote system, host1.

<pre>\$ scp notice.doc</pre>	host1:/hor	ne/jones		
Password:				
notice.doc	100%	**********	0	00:00

Because no remote file name is provided, the file notice.doc is copied into the /home/jones directory with the same name.

In the following example, the scp operation from the previous example is repeated, but scp is executed from a different working directory on the local system (/tmp). Note the use of the "~" symbol to refer to the current user's home directory:

Index

Numbers and Symbols	description, 10
~ (tilde)	ftpcount command
abbreviated path names, 24	description, 10
	ftpdctl command
	description, 10
Α	ftprestart command
authentication	description, 11
remote logins	ftpscrub command
using sftp command, 20	description, 11
	ftpshut command
	description, 11
•	ftptop command
C	description, 11
copying files (remote)	ftpusers file
using scp command, 23	description, 11
using sftp command, 20	ftpwho command
	description, 11
E	
/etc/ftpd/ftpusers file	G
description, 11	get command (sftp)
/etc/proftpd.conf file	example, 21
description, 11	1 ,
/etc/shutmsg file	
description, 11	L
	logging in
	remote logins
F	opening sftp connection, 20, 21
~/.ftpaccess file	sftp command, 20
description, 11	'
files and file systems	
abbreviated path names, 24	0
ftp command	opening remote system connections, 20, 21

P	security issues, 23
passwords	specifying source and target, 24
authentication for remote logins	security
sftp command,20	copy operation issues, 23
path names	sftp command
scp command	command descriptions, 20
absolute or abbreviated, 24	opening remote system connections, 20
tilde (~) in, 24	overview, 19
permissions	sftp sessions
copying requirements, 24	copying files
proftpd daemon	from a remote system, 21
description, 11	to a remote system, 22
proftpd.conf file	opening remote system connections, 21
description, 11	shutmsg file
proftpd.scoreboard file	description, 11
description, 11	
put command (sftp)	
example, 22	т
	tilde (~)
n	abbreviated path names, 24
R	
remote file copying	
using scp command, 23	U
using sftp command, 20	/usr/bin/ftp command
remote logins	description, 10
opening sftp connection, 20	/usr/bin/ftpcount command
sftp commands, 20	description, 10
remote systems	/usr/bin/ftpdctl command
definition, 9	description, 10
remote file copying	/usr/bin/ftptop command
using scp command, 23	description, 11
using sftp command, 20	/usr/bin/ftpwho command
	description, 11
	/usr/lib/inet/proftpd daemon
S	description, 11
scp command, 23	/usr/sbin/ftprestart command
copying between local and remote systems, 24	description, 11
copying directories, 25	/usr/sbin/ftpscrub command
description, 23, 23	description, 11
path names	/usr/sbin/ftpshut command
absolute or abbreviated, 24	description, 11
,	1 ,

٧

/var/log/xferlog file
description, 11
/var/run/proftpd.scoreboard file
description, 11