

Core Entities
Oracle FLEXCUBE Universal Banking Europe Cluster
Release 11.3.81.02.0
[October] [2013]



Table of Contents

1.	ABOUT THIS MANUAL.....	1-1
1.1	INTRODUCTION.....	1-1
1.2	AUDIENCE.....	1-1
1.3	ORGANIZATION.....	1-1
1.4	RELATED DOCUMENTS.....	1-2
1.5	GLOSSARY OF ICONS.....	1-2
2.	MAINTAINING CUSTOMER INFORMATION FILES.....	2-1
2.1	INTRODUCTION.....	2-1
2.2	INVOKING CUSTOMER INFORMATION SCREEN.....	2-1
2.2.1	<i>Maintaining Customer Basic Record.....</i>	<i>2-1</i>
2.2.2	<i>Indicating Main Details.....</i>	<i>2-6</i>
2.2.3	<i>Postal Code and Locality Maintenance Screen.....</i>	<i>2-11</i>
2.2.4	<i>Postal Code and Locality Summary Screen.....</i>	<i>2-12</i>
2.2.5	<i>Maintaining Customer Address Details.....</i>	<i>2-14</i>
2.2.6	<i>Auxiliary Tab.....</i>	<i>2-23</i>
2.2.7	<i>Corporate Tab.....</i>	<i>2-30</i>
2.2.8	<i>Personal Tab.....</i>	<i>2-32</i>
2.2.9	<i>Check List Tab.....</i>	<i>2-36</i>
2.3	CUSTOMER DOCUMENT EXPIRY QUERY SCREEN.....	2-39
2.3.1	<i>Maintaining Domestic Details of Individual Customer.....</i>	<i>2-40</i>
2.3.2	<i>Maintaining Professional Details of Individual Customers.....</i>	<i>2-41</i>
2.3.3	<i>Capturing UDF Values for Customers.....</i>	<i>2-44</i>
2.3.4	<i>Special Customer Grouping.....</i>	<i>2-45</i>
2.3.5	<i>Dictionary Details.....</i>	<i>2-47</i>
2.3.6	<i>Specifying Analytical Parameters.....</i>	<i>2-48</i>
2.3.7	<i>Other Basic Customer Information.....</i>	<i>2-50</i>
2.3.8	<i>Viewing Debit Card Details.....</i>	<i>2-52</i>
2.3.9	<i>Viewing OFAC Check Response.....</i>	<i>2-53</i>
2.3.10	<i>Viewing KYC Details.....</i>	<i>2-54</i>
2.3.11	<i>Maintaining Joint Venture Details.....</i>	<i>2-62</i>
2.3.12	<i>Maintaining Tax Details.....</i>	<i>2-64</i>
2.4	FINANCIAL INSTITUTION EXEMPTION MAINTENANCE SCREEN.....	2-65
2.5	FINANCIAL INSTITUTION EXEMPTION SUMMARY SCREEN.....	2-67
2.5.2	<i>Maintaining Linked Account.....</i>	<i>2-71</i>
2.5.3	<i>Maintaining MiFID Classification.....</i>	<i>2-72</i>
2.5.4	<i>Maintaining Employer Details.....</i>	<i>2-74</i>
2.5.5	<i>Maintaining Province, City and Postal Code Details.....</i>	<i>2-75</i>
2.5.6	<i>Maintaining Province, City and Postal Code Summary Details.....</i>	<i>2-78</i>
2.5.7	<i>Maintaining Customer Sector Details.....</i>	<i>2-78</i>
2.5.8	<i>Maintaining CNAE/CNO Code.....</i>	<i>2-79</i>
2.5.9	<i>Maintaining CNAE, Sector Code and Customer Type.....</i>	<i>2-80</i>
2.5.10	<i>Maintaining Economic Group Code.....</i>	<i>2-81</i>
2.5.11	<i>Maintaining External Bank Details.....</i>	<i>2-82</i>
2.5.12	<i>Viewing External Bank Details.....</i>	<i>2-84</i>
2.5.13	<i>Maintaining Waiver for Customer Tax Group.....</i>	<i>2-84</i>
2.5.14	<i>Maintaining Tax Allowance Limit for Customers.....</i>	<i>2-87</i>
2.5.15	<i>Maintaining Church Tax Declaration for a Customer.....</i>	<i>2-93</i>
2.5.16	<i>Amendment Maintenance.....</i>	<i>2-96</i>
2.5.17	<i>Specifying Details for Generation of MT920.....</i>	<i>2-99</i>

2.5.18	<i>Invoking Customer Category Screen</i>	2-100
2.5.19	<i>Creating Customer Categories</i>	2-101
2.5.20	<i>Maintaining Customer Groups</i>	2-103
2.5.21	<i>Maintaining Limits for Customer Group</i>	2-104
2.5.22	<i>Associating Customer Account with Group</i>	2-104
2.5.23	<i>Maintaining Type of Relationships</i>	2-106
2.5.24	<i>Relationships for Customers</i>	2-107
2.5.25	<i>Maintaining Risk Category for Customers</i>	2-108
2.6	MAINTAINING CHEQUE NOT ALLOWED CUSTOMER DETAILS	2-109
2.7	MULTIPLE RELATIONSHIPS	2-110
2.7.1	<i>Maintaining Types of Relationships</i>	2-110
2.7.2	<i>Maintaining Relationships between Customers</i>	2-110
2.7.3	<i>Maintaining Customer Groups</i>	2-113
2.7.4	<i>Capturing Customer Prefixes</i>	2-115
2.7.5	<i>Storing Authorized Variations of Customer's Name</i>	2-116
2.7.6	<i>Maintaining Float Days for Outward Clearing Customer Transactions</i>	2-117
2.7.7	<i>Location Maintenance</i>	2-119
2.7.8	<i>Specifying the Dictionary Details</i>	2-119
2.8	MAINTAINING KYC TYPE	2-121
2.8.1	<i>Specifying KYC Value Details</i>	2-122
2.9	MAINTAINING CUSTOMER KYC DETAILS	2-127
2.10	CREATING A MESSAGE ADVICE FORMAT	2-140
2.11	VIEWING CUSTOMER DETAILS	2-142
3.	MAINTAINING MANDATORY INFORMATION	3-1
3.1	INTRODUCTION	3-1
3.2	MAINTAINING ACCOUNT CLASSES	3-1
3.2.1	<i>Invoking Account Class Maintenance Screen</i>	3-2
3.2.2	<i>Statement Parameters Tab</i>	3-8
3.2.3	<i>Maintaining Cheque Book Preferences</i>	3-11
3.2.4	<i>Capturing Details about Specially Designated Nationals</i>	3-12
3.2.5	<i>Specifying your Preferences for Account Class</i>	3-13
3.2.6	<i>Specifying Liquidation Preferences for Debit Interest and Charges</i>	3-19
3.2.7	<i>Maintaining Details for Free Banking</i>	3-20
3.2.8	<i>Specifying Initial Funding Preferences</i>	3-20
3.2.9	<i>Maintaining Provisioning Details</i>	3-21
3.2.10	<i>Maintaining Escrow Details</i>	3-21
3.2.11	<i>Maintaining Status Codes for Account Class</i>	3-22
3.2.12	<i>Specifying Reporting line Details</i>	3-23
3.2.13	<i>Maintaining Auto Deposits</i>	3-24
3.2.14	<i>Maintaining Rules for Automatic Status Change</i>	3-26
3.2.15	<i>Maintaining Sequence for Funds Allocation</i>	3-32
3.2.16	<i>Maintaining Transaction Restrictions for Account Class</i>	3-35
3.2.17	<i>Maintaining Details of Account Statements Generation</i>	3-35
3.2.18	<i>Specifying Regulation D Applicability for Account Class</i>	3-41
3.2.19	<i>Assigning Preferred Branches, Currencies and Customers</i>	3-41
3.2.20	<i>Maintaining Branch Preferences</i>	3-42
3.2.21	<i>Maintaining Currency Preferences</i>	3-43
3.2.22	<i>Maintaining Customer Preferences</i>	3-43
3.2.23	<i>Specifying Balance Account Codes</i>	3-45
3.2.24	<i>Maintaining Notice Preferences</i>	3-48
3.2.25	<i>Maintaining Account Class Transfer</i>	3-49
3.2.26	<i>Processing Account Class Transfer</i>	3-67
3.2.27	<i>Viewing Account Class Transfer</i>	3-68
3.2.28	<i>Maintaining Narratives</i>	3-69
3.2.29	<i>Maintaining Customer Instruction Details</i>	3-71

3.2.30	<i>Maintaining Lead Details</i>	3-74
3.2.31	<i>Maintaining Service Request Input Details</i>	3-77
3.2.32	<i>Viewing Service Request Details</i>	3-80
3.2.33	<i>Maintaining Location Details</i>	3-82
3.2.34	<i>Capturing Algorithm Details in Oracle FLEXCUBE</i>	3-84
3.2.35	<i>Maintaining Turnover Limits</i>	3-86
3.3	MAINTAINING DEPOSITS INSTRUCTIONS.....	3-88
4.	PROCESSING REFERRALS IN ORACLE FLEXCUBE	4-1
4.1	INTRODUCTION.....	4-1
4.1.1	<i>Maintenance Required for Referral Processing</i>	4-3
5.	PROVISIONING FOR CUSTOMER ACCOUNTS	5-1
5.1	INTRODUCTION.....	5-1
5.1.1	<i>Specifying Basis for Status Processing</i>	5-1
5.1.2	<i>Setting up Customer Groups for Provisioning</i>	5-2
5.1.3	<i>Setting up Customer Classifications for Status Processing</i>	5-3
5.1.4	<i>Setting up Exposure Categories</i>	5-4
5.1.5	<i>Maintaining Rules for Provisioning</i>	5-8
5.1.6	<i>Derivation Rules for Status Change</i>	5-9
5.2	MAINTAINING PROVISIONING COVERAGE DETAILS.....	5-10
5.3	VIEWING PROVISIONING COVERAGE DETAILS.....	5-12
5.4	MAINTAINING RISK LEVEL PROVISIONING RATE	5-13
5.5	VIEWING RISK LEVEL PROVISIONING RATE	5-15
5.6	MAINTAINING COUNTRY GROUP PROVISIONING RATES.....	5-16
5.7	VIEWING COUNTRY GROUP PROVISIONING RATES.....	5-17
5.8	VIEWING MANUAL PROVISIONING	5-18
5.8.1	<i>Viewing Contract Details</i>	5-20
5.9	PROVISIONING COMPUTATION BATCHES	5-20
5.9.1	<i>Provision Processing for Accounts</i>	5-21
6.	CUSTOMER INFORMATION QUERY	6-1
6.1	INTRODUCTION.....	6-1
6.2	INVOKING CUSTOMER POSITION SCREEN	6-1
6.2.1	<i>Viewing Account Details</i>	6-2
6.2.2	<i>Viewing Loans Details</i>	6-3
6.2.3	<i>Viewing Deposit Details</i>	6-5
6.2.4	<i>Viewing FX Details</i>	6-7
6.2.5	<i>Viewing FT Details</i>	6-8
6.2.6	<i>Viewing Collaterals Details</i>	6-9
6.2.7	<i>Viewing Assets/Liabilities Details</i>	6-10
6.2.8	<i>Viewing Limits Details</i>	6-12
6.2.9	<i>Viewing MIS Details</i>	6-12
6.2.10	<i>Viewing Projections</i>	6-13
6.2.11	<i>Viewing Accounting Entries</i>	6-14
6.2.12	<i>Overdrawn Accounts Query</i>	6-14
6.2.13	<i>Uncollected Funds Query</i>	6-16
6.2.14	<i>Customer Account Balance Query</i>	6-16
7.	360 DEGREE CUSTOMER VIEW	7-1
7.1	INTRODUCTION.....	7-1
7.2	INVOKING 360DEGREE CUSTOMER VIEW ENTRY SCREEN.....	7-1
7.3	VIEWING 360 DEGREE RETAIL CUSTOMER DETAILS	7-2
7.3.1	<i>Viewing Summary Details</i>	7-4
7.3.2	<i>Viewing Profile Details</i>	7-5
7.3.3	<i>Viewing Deposit Details</i>	7-16

7.3.4	Viewing Loan Details.....	7-30
7.3.5	Viewing Events Details.....	7-34
7.3.6	Viewing Schemes Details.....	7-34
7.3.7	Viewing Alerts.....	7-36
7.3.8	Viewing Limits Details.....	7-39
7.3.9	Viewing Payment Details.....	7-41
7.3.10	Viewing Islamic Deposits Details.....	7-42
7.3.11	Viewing Islamic Financing Details.....	7-44
7.3.12	Viewing External Details.....	7-46
7.4	VIEWING 360DEGREE CORPORATE CUSTOMER DETAILS.....	7-48
7.4.1	Viewing Summary Details.....	7-50
7.4.2	Viewing Profile Details.....	7-51
7.4.3	Viewing Deposits Details.....	7-57
7.4.4	Viewing Loan Details.....	7-64
7.4.5	Viewing Trade Details.....	7-67
7.4.6	Viewing Treasury Details.....	7-74
7.4.7	Viewing Events Details.....	7-77
7.4.8	Viewing Schemes Details.....	7-77
7.4.9	Viewing Alerts.....	7-79
7.4.10	Viewing Limits Details.....	7-79
7.4.11	Viewing Payment Details.....	7-80
7.4.12	Viewing Islamic Deposits.....	7-81
7.4.13	Viewing Is-Financing Details.....	7-86
7.4.14	Viewing Islamic Trade Details.....	7-88
7.4.15	Viewing Islamic Treasury Details.....	7-90
7.4.16	Viewing External Details.....	7-91
8.	GLOSSARY.....	8-1
8.1	IMPORTANT TERMS.....	8-1
9.	REPORTS.....	9-4
9.1	INTRODUCTION.....	9-4
9.2	IRA STATEMENT REPORTS.....	9-4
9.2.1	Selection Options.....	9-4
9.2.2	Contents of the Report.....	9-4
9.3	MINIMUM WITHDRAWAL ADVICE REPORTS.....	9-3
9.3.1	Contents of the Report.....	9-3
9.4	CHARGE ADVICE REPORTS.....	9-4
9.4.1	Contents of the Report.....	9-4
9.5	IRS FORM 5498.....	9-4
9.5.1	Generating Form 5498 as Part of Initial Filing.....	9-5
9.5.2	Generating Form 5498 after Tax Filing.....	9-5
9.5.3	Details printed on Form 5498.....	9-5
9.6	IRS FORM 1099-R.....	9-6
9.6.1	Generating Form 1099-R as Part of Initial Filing.....	9-6
9.6.2	Generating Form 1099-R after Tax Filing.....	9-6
9.6.3	Details printed on Form 1099-R.....	9-6
9.6.4	Filing IRS Forms Electronically.....	9-7
9.7	CUSTOMER ACCOUNT OPENING CONFIRMATION REPORT.....	9-7
9.8	NETTING REPORT.....	9-8
9.8.1	Contents of the Report.....	9-9
9.9	COMBINED STATEMENT REPORTS.....	9-9
9.9.1	Contents of the Report.....	9-10
9.10	MISSING SIGNATURE REPORT.....	9-11
9.10.1	Contents of the Report.....	9-13

10.	SCREEN GLOSSARY	10-1
10.1	FUNCTION ID LIST.....	10-1

1. About this Manual

1.1 Introduction

This manual is designed to explain the Core Entities module of Oracle FLEXCUBE. It provides an overview to the module, and provides information on using the Core Entities module of Oracle FLEXCUBE.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of day operators	Processing during end of day/ beginning of day
Financial Controller/Product Managers	Generation of reports

1.3 Organization

This manual is organized into the following chapters:

Chapter 1	<i>About this Manual</i> acquaints you quickly with the organization, audience, glossary of icons and related documents for this user manual
Chapter 2	<i>Maintaining Customer Information Files</i> explains the maintenance of various personal and business details of the customers of your bank
Chapter 3	<i>Maintaining Mandatory Information</i> explains how you can classify customer accounts into different groups known as account classes, and how to maintain specifications for account classes
Chapter 4	<i>Processing Referrals in Oracle FLEXCUBE</i> details the maintenance required and the processing done in Oracle FLEXCUBE when customer transactions force the accounts












	involved the transaction to exceed the overdraft limit
Chapter 5	<i>Provisioning for Customer Accounts</i> explains the process of provisioning for customer accounts in Oracle FLEXCUBE
Chapter 6	<i>360 Degree Customer View</i> explains how you can view and analyze personal and business details of the customers.
Chapter 7	<i>Customer Information Query</i> explains how queries to retrieve information on customer accounts can be made
Chapter 8	<i>Glossary</i> contains a list of important terms used in the manual.
Chapter 9	<i>Reports</i> provides a list of reports that can be generated in this module and also explains their contents.













1.4 Related Documents

- The Procedures User Manual
- The Settlements User Manual

1.5 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	New
	Copy
	Save
	Delete
	Unlock
	Print
	Close
	Re-open
	Reverse
	Template
	Roll-over

Icons	Function
	Hold
	Authorize
	Liquidate
	Exit
	Sign-off
	Help
	Add row
	Delete row
	Option List
	Confirm
	Enter Query
	Execute Query

Refer the Procedures User Manual for further details about the icons.

2. Maintaining Customer Information Files

2.1 Introduction

In the 'Customer Maintenance' screen, you maintain various personal and business details of the customers of your bank.

The CIF details are maintained at the branch level by the sign-on branch. These details can be accessed by all branches and therefore a duplicate customer record for a customer in two different branches need not be maintained.

2.2 Invoking Customer Information Screen

You can invoke the 'Customer Maintenance' screen by typing 'STDCIF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The four parameters listed on top are the four lines along which you maintain customer details. These details have been classified into the following broad heads:


Main	You maintain the main attributes of all customers, individuals and corporate houses
Auxiliary	This screen shows the other details pertaining to the customer
Personal	You maintain the attributes for individual customers
Corporate	You maintain the attributes for all corporate customers
Custom	You maintain any other corporate customer related information, which your bank would like to maintain in addition to the ones defined under Corporate
Analytical Parameters	You can capture certain parameters related to the customer which are used for validation purposes

2.2.1 Maintaining Customer Basic Record

To define the basic details of the customer click on the tab titled 'Main'. The details that you can specify for a customer depend on the type of customer whose details you are capturing.

If a particular field is disabled, it means that the field is not relevant to the type of customer that you are creating.

Select 'New' from the Actions menu in the Application toolbar. The system will display 'Transaction Branch' screen. Here you can select the transaction branch.



Here you are allowed to book other branch transactions from the logged in branch. Also, you can query other branch transactions from the logged in branch. Query operation would not be supported from the online screens for other branch transactions. Other branch transactions can be query from summary screen only. The system defaults the logged-in branch by default as the transaction branch. Option to authorize/modify/close other branch customer from the login branch is also provided.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This screen will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.



The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'Customer Maintenance' screen.

2.2.1.1 Specifying Details of Customer

Customer No

The customer code is the code you assign to identify a customer. It is referred to as the customer CIF Number. This code should be unique across branches. It can be 9-characters long.

Example

Assign a code using a maximum of 9 characters, alphanumeric. For example, assume your customer is DOW Corporation, US. You can assign him a code, which could either, be a number representing the customer's serial number or an alphabetic code like DowCorp or an alphanumeric code like Dow1000US or DowUS1000 / 1000DowUS, if he is the 1000th customer to approach your bank.

Short Name

Along with the Customer Code you have to capture the customer's abbreviated name. The description that you capture is unique for each customer. It helps in conducting a quick alpha-search or generating queries regarding the customer.

Enter the abbreviated name of the customer using a maximum of 20 characters, alphanumeric. Taking the same example, assume your customer is DOW Corporation. Its short name could be DOWCORP.

At the time of processing of transactions (and in any activity which requires entry of the customer identification), in addition to the customer code, the short name of the customer that you enter here will be available in the options list from which the customer is selected.

Branch Code

Specify the branch code from the adjoining option list.

Liability Number

The credit facility granted to any customer is tracked against this Liability Number of the customer.

The default liability number of a customer is the same as his customer code. However, you have the option of tracking the credit limit of this customer against an existing liability number (for another customer).

Thus if the liability number of the customer is the same as the customer's code, it implies that the liability granted to the customer is exclusive to the particular customer. Conversely, if the liability number of a customer is different from the customer code, it implies that the liability of the specific customer is tracked against a parent customer.

This parameter helps you to assign the same liability structure for a group of customers. This feature is useful when you have several subsidiary companies/divisions reporting to the same parent company.

Example

While assigning a liability number to Opel Motors, Germany a subsidiary of General Motors, US you can track the liability of Opel Motors against General Motors.

Full Name

You can specify the full name of the customer in this field.

Joint Venture

Check this box if the customer is a joint venture customer. For joint venture customers, the system will capture the parties in the joint venture and their ratios during joint venture maintenance.

Type

You have to indicate the Type to which the customer whose details you are capturing belongs. The options available are:

- Individual
- Corporate
- Bank

To recall, if a customer record is created from an external Siebel CRM application after a successful upload into Oracle FLEXCUBE, the 'CRM Customer' flag gets checked after the upload. You can however, uncheck the same when you unlock such a record and make changes. When you unlock such a record, system throws up an override stating that the customer is a CRM customer and asks whether you want to continue modifying the record. If you confirm the same, Oracle FLEXCUBE allows you to make changes. If you choose to ignore, the original record is saved.

Private Customer

Check this box to indicate that the customer type is private.

Customer Sub Type

Specify the customer sub-type. The adjoin option list displays the valid customer sub-types maintained in the system. Select the appropriate one.



It is mandatory to specify customer sub-type the customer type is 'Corporate'.

Description

System displays the description based on the selected 'Customer Sub-type'.

Document ID Type

Specify the type of document Id from the adjoining option list. It is not mandatory to maintain the document ID for the minor customers who are below 14 years.



The option list will display the following values for Spain:

- NIE
- NIF
- DNI

Document ID Number

Specify the document ID number.



For Spain, system validates based on the type of document selected with pre-defined algorithms.

2.2.2 Indicating Main Details

CLS Participant

Customers of your bank can settle their FX deals via the CLS (Continuous Linked Settlements) Bank to reduce the risks associated with such transactions. To allow the customers to do CLS trades, you have to mark the customer as a 'CLS Participant'. However, you have to ensure that the branch at which the customer operates is also qualified to process CLS deals i.e. the branch should also be marked as a CLS Participant before allowing the same for the customer.

Further, you can also capture currency restrictions for your customers by maintaining a list of allowed or disallowed currencies for CLS trading. Click the 'CLS Restrictions' button to maintain this list. Note that currency restrictions will be allowed only for customers who are CLS participants.

Refer the 'Continuous Linked Settlements' chapter of the Foreign Exchange User Manual for details on maintaining currency restrictions and other maintenances required for processing CLS deals in Oracle FLEXCUBE.

MT920

Check this option to indicate that the customer is eligible to request for MT920 messages.

MT920-Account Update Request-A request for an up-to-date statement from the bank where the referenced Account is held. The request may be for an Intra Day Update (MT942) or an End of Day Update (MT940) and is subject to the service agreed with that bank.

Issuer Customer

If the customer whose CIF you are maintaining is an issuer of securities, then check this box.

Relationship Pricing

Select this checkbox to indicate that the customer is eligible for relationship pricing. This checkbox will be unselected by default.

For more details on relationship pricing, refer Relationship Pricing user manual

Staff

Check this box whenever a customer record is created for a staff. By default this box is left unchecked.

ELCM Customer

Check this box to replicate the customer details to ELCM system. By default, system checks this box whenever the new customer is created. You can uncheck this box if required so that customer data will not get replicated to ELCM system.



Once you select the option 'ELCM customer', system will not allow you to unselect it.

ELCM Customer Number

You need to specify the ELCM customer number if the option 'Generate Customer Number' is not selected in 'ELCM Parameter Maintenance' screen. If the option 'Generate Customer Number' is selected in 'ELCM Parameter Maintenance' screen, then the system will replicate the customer number from ELCM system.

2.2.2.1 Specifying Geographical Details

As part of specifying the Geographical details of the Customer, you have to capture the following details:

Language

As part of maintaining customer accounts and transacting on behalf of your customer, you will need to send periodic updates to your customers in the form of advices, statement of accounts and so on.

You have to indicate the language in which your customer wants the statements and advices to be generated. English is defaulted as the language of correspondence; you have the option to change the default. The list positioned next to the language field contains all the language codes maintained in the SMS module. You can select the appropriate.

Country

This is the country as given in the address of correspondence of this customer. Click on the option list positioned next to this field, a list of countries maintained in the Country Codes screen is displayed. You can select the appropriate. Specify if the customers are resident/Non-resident for validation. The system checks the user entered country code with the branch country code and if both are equal then the user is allowed to select the resident status as resident else the user can only select the residential status as non resident.

Nationality

Specify the nationality of the customer. The list of country codes maintained in the Country Codes Maintenance screen are available in the option-list positioned next to this field. You can select the appropriate.

Exposure

This is the country of exposure of this customer. It is maintained for Central Liability tracking. For instance, for Toyota in the USA, the country of exposure is Japan.

Location

Each customer code should be associated with a location code. The location is indicative of the place of residence of your customer.

The option list positioned next to this field contains a list of all the location codes maintained in the Location Details maintenance screen. You can select the appropriate code to identify the place of residence of your customer.

Given below is an illustration of how a location code is associated with the CIF record of a customer

Example

You would like to maintain the CIF details of your customer Silas Marner. Although Silas Marner is Irish, he is a resident of London and lives in the northern part of London. Your entries in the respective fields of the CIF Maintenance screen should be as follows:

Fields in Oracle FLEXCUBE	Your entry
Customer Code	SILAS01
Nationality	IRS (Ireland)
Location Code	NL1 (North London)

2.2.2.2 Resident Status

Indicate the resident status of this customer. Whether the customer is a recognized resident of the country in which the particular branch of your bank operates. You can modify this field even after authorization.

For the customers classified as Residents, i.e. Country = 'PT', it is necessary to determine if the customer is resident of '01 Portugal Mainland', '02 Azores Islands' or '03 Madeira Island' based on the Region code maintained on the Customer Maintenance screen.

For the customers classified as Non-Resident, it is necessary to determine if the customer is resident in an ADT Country or in Other Country, based on the ADT identifier introduced on the Country Code Maintenance Screen.



Resident status gets validated based on a system logic, which checks the Customer Country Code and the Branch Country Code.

If Customer Country Code is same as Branch Country Code, then the Customer Resident Status is 'Resident'. If you specify the Resident Status as 'Non-Resident', then the system displays error message, hence enforcing the user to select the value as 'Resident'.

If Customer Country Code is different from Branch Country Code, then the Customer Resident Status is 'Non-Resident'. If you specify Resident Status as 'Resident', then the system displays error message, hence enforcing the user to select the value as 'Non-Resident'.

2.2.2.3 Document Expiry

If the customer is a Non-resident, residing in an 'ADT Country' or in 'Other Country', 'ADT Certificate' and 'Non Resident Proof', indicate the expiry status or availability of the documents.

ADT Certificate

If 'ADT Certificate' is checked, it indicates that the document 'Certificate for ADT (ADT – 21RFI)' is either expired or is not attached. System automatically updates it.

Non Resident Proof

If 'Non Resident Proof' is checked, it indicates that the document 'Proof of residence' is either expired or is not attached.. System automatically updates it. For a customer residing in Other Country, this flag is checked if the document 'Proof of Residence' is expired or is not attached. For all other cases this flag remains unchecked.



Flags 'ADT Certificate' & 'Non Resident Proof' are auto updated by the system & are not modifiable by the user.

2.2.2.4 Indicating Address for Correspondence

Name

In the lines that are provided you can enter the name of the customer. The customer will be addressed by this name in all correspondence sent from the bank. These characters should conform to SWIFT standards.



The number of characters that you can enter in this field is determined by the preference that you specified in the Bank Parameters screen. However, in the advices and statements that are sent to the customer only the first 35 characters of the name will be displayed.

Street Details

Specify the street details such as street name and number as a part of the customer address.

Province/Region Code

Specify the province or region of the customer. The adjoining option list displays the list of province or regions maintained in the 'Province City Maintenance' screen. Select the appropriate one.



If Ukraine is selected as the country, then it is mandatory to specify the region.

District Code

Specify the district code from the adjoining option list. The adjoining option list displays the list of districts maintained in the 'Province City Maintenance' screen. Select the appropriate one.

City

Specify the city of the customer. The adjoining option list displays the list of city names maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Postal Code

Specify the postal code. The adjoining option list displays the list of postal codes maintained in the 'Province City Maintenance' screen for a country and also in the 'Postal Code Maintenance' screen. The locality maintained in the 'Postal Code Maintenance' screen is a return field. Select the appropriate option..

Locality

If postal code maintained in 'Postal Code Maintenance Screen' is chosen from the adjoining option list, the locality corresponding to the Postal Code gets defaulted as per maintenance done in the 'Postal Code Maintenance Screen'. You can modify the defaulted locality.

If postal code maintained in 'Province City Maintenance' Screen is chosen from the adjoining option list, no value gets defaulted in the locality field.

Tax ID

Specify the tax identification number of the customer. The Tax ID number, in Portugal, is assigned by the Ministry of Finance and Public Administration to uniquely identify a tax entity or a contributor, for exclusive use in the treatment of tax information. When the bank user enters Tax ID number, system validates its check-digit, to assure that the ID number introduced is a valid Tax ID number.

System does not allow the same Tax ID number for different customers as Tax ID is unique identifier for each customer. Tax ID is applicable to Individual/Corporate/Bank clients, either resident or non residents in Portugal. System displays an error message and does not allow the user to save the record, if Tax ID number is not unique.



Tax ID specified is validated if branch level parameter 'Tax ID validation' flag is checked.

Financial Institution Type

Select the financial institution type from the adjoining option list. Adjoining option list displays the Financial Institution Types maintained in the Financial Institution Exemption Maintenance' screen.

Option for Aggregation

Check this box to indicate, if a non-resident individual customer opts for income aggregation.

Swift Code

You can choose to associate a SWIFT Code with the customer whose CIF details you are maintaining. This code will be used to send all SWIFT related messages to the customer. This is pertinent while creating CIF record for banks as customers.

Fax

You can specify the Fax Number of the Customer whose CIF details you are maintaining. This will be used for faxing the LC confirmation mail message copy to the Counterparty.

Credit Rating

Specify valid credit rating for a Customer number from the adjoining option list.

Credit rating basically indicates the credit worthiness of the customers linked to a particular credit line. It is used primarily for information only. The Limits Services Module also uses it in generation of reports.

Country

Specify the country code of the country to which the customer's correspondence address belongs. The adjoining option list displays all the country codes that are maintained in the system.

Building

Specify the building number of the customer's correspondence address.

Block

Specify the block number of the customer's correspondence address.

Apartment (Office) Number


Specify the apartment (office) number of the customer's correspondence address.

Zip Code

Specify the zip code of the customer's correspondence address.

Mobile Number

Specify the mobile number of the customer.

 Field 50F of outgoing MT103 message contains the customer address details. The first line of 50F has the customer's name and the second line of field 50F is populated with Address_Line1, which in turn contain the details of Street, Building, and Apartment No of the customer. Similarly, third line of 50F contains Address_Line2 i.e., 'Country, and Region', fourth line of 50F contains Address_Line3 i.e., Block, Locality and fifth line of 50F contains Address_Line4 i.e., District, Zip Code.

2.2.3 Postal Code and Locality Maintenance Screen

You can invoke the 'Postal Code and Locality Maintenance' screen by typing 'STDPLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. Postal Code and Locality Maintenance screen maintains the Postal Code and Locality information.

The screenshot shows a software window titled "Postal Code Maintenance". Inside, there is a section "Postal and Locality Details" with three required input fields: "Country Code *", "Postal Code *", and "Locality *". The "Country Code" field includes a dropdown arrow. Below this section, there are fields for "Maker", "Checker", and two "Date Time:" labels. A "Cancel" button is positioned in the bottom right corner of the window.

Postal Code and Locality Details

Country Code

Select the country code from the adjoining list of options.

Postal Code

Specify the postal code. Structure of postal code is NNNN-NNN. Postal codes are unique for the specified country.

Locality


Specify the locality corresponding to the postal code.

2.2.4 Postal Code and Locality Summary Screen

You can invoke the 'Postal Code and Locality Summary' screen by typing 'STSPLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. Postal Code and Locality Summary screen maintains the Postal Code and Locality summary information.

Navigation:

Core Entity > Postal Code and Locality View



Authorization Status

Select the authorization status from the adjoining drop down list. The options are:

- Authorized
- Unauthorized
- Rejected

Record Status

Select the record status from the adjoining drop down list. The options are:

- Open
- Closed

Country

Select the country from the adjoining option list.

Postal Code

Select the postal code from the adjoining option list. Value entered follows the 'Search and Fetch' mechanism.

Locality

Select the locality from adjoining option list. Value entered follows the 'Search and Fetch' mechanism.

2.2.5 Maintaining Customer Address Details

You can maintain the customer address details in 'Customer Address Maintenance' screen..You can invoke this screen by typing 'MSDCUSAD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Address Maintenance

Customer Address

Customer No *

Location *

Country

Answerback

Add Hold Mail Text

Name

Street Details *

City

Province

Postal Code

Media *

Language

Test Keyword

Delivery By

Send by Email

50F Party Details

Line 1

Line 2

Line 3

Line 4

Line 5

Message Type	Module	Branch	No of Copies	Format
<input checked="" type="checkbox"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>

Fields Change Log

Maker Date Time:

Checker Date Time:

Cancel

You can specify the following details in this screen:

Customer Number

It is the relevant customer account number in the current branch against which you are maintaining an address, based on a selected media and location. The branch code gets defaulted alongside.

A single customer can have any number of accounts. You can choose to link a specific location with an account number. Maintaining multiple locations for the customer facilitates the sending of interest and account statements to more than one address of the customer.

If an address is maintained at the Customer Account Definition level, all statements pertaining to the particular account will be sent only to the address specified at the account level, irrespective of the message and location maintenance for the Customer.

Location

As discussed earlier, a customer of your bank can have several addresses for the same media. To differentiate between one address of a customer account and another for a given media, it is mandatory for you to select a unique location for each address. The location that you specify for an address is used as a unique identifier for the customer account address.

The values made available against the option list here are maintained through the 'Account Address Location Maintenance' screen.

Refer to the section 'Location Maintenance' in the chapter titled 'Maintaining Customer Accounts' in the Core Entities (CE) User Manual for relevant information.

Country

Specify the country code of the country to which the customer's correspondence address belongs. The adjoining option list displays all the country codes that are maintained in the system.

Answer Back

Specify the answerback code for the customer. This field is applicable only if a message is transmitted through 'Telex'. It cannot be more than 20 characters in length. It is a free format text.

Add Hold Mail Text

If this box is checked, then all the mail advice generated for this customer and location would have the hold mail text displayed on top of the message. As a consequence, these mail advices would not be dispatched to the customer unless required. Check this box to indicate you want the hold mail text to be displayed on top of the message.

To recall, you maintain a hold mail text through the 'Messaging Branch Parameter Maintenance' screen.



This field is applicable only if the media is 'MAIL'.

Name

Specify the name of the customer for whom you are maintaining the address details. This address maintenance is for a particular customer account based on a unique media and location combination.

Street Details

Specify the street details such as street name and number as a part of the customer address.

City

Specify the city of the customer. The adjoining option list displays the list of city names maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Province

Specify the province of the customer. The adjoining option list displays the list of province maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Postal Code

Specify the postal code. The adjoining option list displays the list of postal codes maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Media

Select the media code for which you want to set-up addresses. Choose a code from the option-list of valid media codes maintained in the 'Media Maintenance' screen.

A customer of your bank can have several addresses for a particular media. The media supported include:

- Mail
- E-Mail
- Telex
- SWIFT
- FAX
- FILEACT(this is an interface to the TIPA network)

Each media type is identified by a 15 character Media Code.

Language

In this screen you can specify the language in which the messages sent to the address should be expressed. You can choose a language code from the factory shipped option list available for this field.

The language code that you specify is taken to be the default language in which all messages sent to the address will be expressed.



To send a message to a customer in a particular language you should have also maintained a message format for the language in the 'Advice File Maintenance' screen.

Test Keyword

Specify the test word allotted to a customer. This field is applicable only if the message is transmitted through Telex (ie. media is TELEX).

Delivery By

Select how statements sent to the customer by mail should be delivered from the adjoining option list.

All the values maintained through the 'Message Location Maintenance' screen will be displayed in the option list.

Send By Email

If your customer has an e-mail address, you can opt to capture it by clicking on the box adjacent to the 'Send by E-Mail' option. Enter the e-mail address for the selected customer account, media and location combination in the first line of the Address field. You can capture addresses such as fax, mail, etc, for different media and location combinations.

2.2.5.1 Specifying Unique Identifier Details

Each customer is required to provide certain identification details to your bank for establishing the customer's identity. For instance, the passport number or ration card of the customer may serve as the criteria to establish the customer's identity. In Oracle FLEXCUBE, this is known as Unique Identifier Name.

Name

Enter the identifier name in not more than 20 characters.

Value

You have to capture the serial number or any number of significance that is to be associated with the document, which can help in identifying the document. You can use a maximum of 20 alphanumeric characters, to capture the identifier value.

Identification Code

Specify the unique USREOU code of the customer. The value specified here cannot be less than 8 digits in length.

**A check digit is calculated for the last digit of the code and if this check digit is not equal to the last digit, then an error message gets displayed. **Check digit is not the last digit, it is 8th digit of 8 numeric identification code.



This is applicable only for 'Corporate' type of customers

Example 1:

A corporate customer has USREOU code **14903012**.

The check digit is the eighth digit of the code and equals to 2.

To check if the check digit "2" is correct for this code:

$$D_i = (1,4,9,0,3,0,1)$$

$$W_i = (1,2,3,4,5,6,7)$$

$$= 1*1 + 2*4 + 3*9 + 4*0 + 5*3 + 6*0 + 7*1 = 58,$$

$$|S/11|=|58/11| = 5 \text{ (remainder 2),}$$

$$CD = 58 - 11*5 = 3.$$

Hence, the check digit "3" in code 14903013 is correct



Note the following:

- Blank value of the code is permissible.
- If the value of the field is not "blank" and the length of the ID is less than 8 digits, the system will generate an error message.

For 'Individual' type of customers you need to specify the unique identification code, not less than 10 digits in length.

The value specified for 'Individual' type of customers needs to satisfy the following conditions:

- The first five digits of the identification code should be equal to the number of days from 31 December 31, 1899 to the customer's date of birth. The following override message will be displayed, if this condition is not met:

"Date of Birth is incorrect. Please check date of birth or Customer's Tax ID."

- If the customer is male, the next-to-last digit of identification code should be odd. If this validation fails, the system displays the following override message:

"The ninth digit of identification code should be odd."

- If the customer is female, the next-to-last digit of identification code should be even. If this validation fails, the system displays the following override message:

"The ninth digit of identification code should be even."

- If the value of the field is not "blank" and the length of ID is less than 10 digits, the system should generate an error message. The system must not save CIF. "Blank" value of the code is permissible



This is applicable only for Ukraine and if you have selected the country code of the current branch as 'UA'

2.2.5.2 Indicating Customer/Customer Account Status

As part of indicating the personal status of the customer or the customer's account, you have to specify whether the customer has:

- Deceased
- The customer's whereabouts are unknown
- Whenever Minor Customer attains Majority, and if he/she doesn't have a valid Document ID, then system will mark that Customer as Frozen during the EOD. After submitting the valid Document ID the user has to manually uncheck the 'Frozen' check box.

For each customer you will be allowed to mark one or more statuses. For example, if the customer has deceased then the customer account will be declared frozen. Therefore, for the particular customer both the statuses 'Deceased' and 'Frozen' will be applicable.

If none of the statuses is marked, it suggests that this customer's status is normal.

Customer Category

Each customer that you maintain can be categorized under any one of the categories that you have maintained in the Customer Category Maintenance screen. Select from the list and indicate the Category under which the particular customer is to be categorized.



You need to capture the basic details for each customer, regardless of the type of customer you are maintaining.

Black Listed

System checks this field to indicate that the customer is black listed. The system validates the customer against the Black Listed Customers Data file and throws an override message as follows.

Black Listed customer, Proceed?

In case the customer is not present in the Black Listed Customers Data file, this field remains unchecked

By default the field is unchecked.

2.2.5.3 Specifying Group to which Customer Belongs

When you maintain CIF details for customers, in the Customer Maintenance screen, you can specify the customer group, to which the customer belongs, for:

Economic Group Code

Specify the economic group code. The adjoining option list displays the list of all the valid economic group codes maintained in the 'Economic Group Codes Maintenance' screen. Select the appropriate one.



Note the following:

- You can select the same economic group code for more than one customer.
- It is mandatory to maintain the economic group code for the individual and Corporate customer type.

Group Code

You must specify a group code defined for a group type that is the same as the customer type, for instance, if the customer is a retail customer, you must specify a group defined for retail customers.

Charge Group

Specify the charge group of the customer from the option list provided. Only the Group codes maintained with type Charge will appear for selection.

Clearing Group

Categorize the customer for levying charges at a customer group level.

Tax Group

You need to specify the tax group of the customer from the option list provided. Only the Group Codes maintained with type Tax will appear for selection.



For tax group modification, the system displays an override message if there is an outstanding utilization for the current tax cycle.

Sector Code

Specify the sector code. The adjoining option list displays the list of all the valid sector codes maintained in the 'Customer Sector Maintenance' screen. Select the appropriate one. You can modify this field even after authorization.

Sector Description

System displays the brief description of the selected sector code.

Withholding Tax

This box is checked by default if the customer is resident. If non-resident, system checks If any of the following types of certificates expires, then the system checks this box and applies withholding tax during further interest liquidation:

- 'FISCAL' – for Fiscal Declaration Certificate
- 'CONSULAR' – for Councillor Certificate
- 'POLICE' – for Police Certificate

Also, system generates the mail message 'WHT_EXPIRY' – Withholding Tax Document Expiry to the customer before three months of the document expiry date advising them to re-submit the document to avoid withholding tax.

System checks this box based on the validity of the certificate; however, you will have to manually uncheck this box during initial customer creation or any further updating of certificate renewal. System will stop withholding tax from the time the box is unchecked and will pay the collected tax to the tax agency.



Irrespective of the customer status change from 'Resident' to 'Non-resident' or from 'Non-resident' to 'Resident', system will consider the check box 'Withholding Tax Applicable' to decide whether to apply withholding tax or not.

An SDE 'WHT_APPLICABLE' checks the box 'Withholding Tax Applicable' if the withholding tax is applicable.

A UDE 'WHT_RATE' is defined as per the different tax rate depending on the state in which the branch is located.

During BOD system triggers the batch 'STBWHTPR' – 'Withholding Tax Process Batch' to check if any of the above mentioned documents are expired. If any certificate is expired, then the system checks this box and the withholding tax will be applicable.

SSN

While maintaining the details of an individual type of customer you can capture the social security number (SSN) of the customer. While processing funds transfer on behalf of your customer the SS Number of the customer involved in the transaction will be defaulted from this screen to FT Contract Online screen.

If the value of debits (outgoing customer transfers) for a specific customer account exceeds USD 2500, with-in a seven-day working period the system displays an override message informing you of the same.

Example

Let us assume that on the 24th of September 2001, Mrs. Wendy Klien a customer of your bank initiates an outgoing FT for USD 2000. Since all weekends are considered as holidays at your bank, while processing the transfer all debits against her account for six working days preceding the 24th i.e., up to the 16th September will be tracked against her SS number.

Again, on the 1st of October 2001, she initiates another outgoing transfer, which necessitates a deduction of USD 700 on her account. While processing the transfer the system checks for all debits upto the 21st of September.

An amount of USD 2000 has already been tracked against her SS number on the 24th of September. However, since the current debit exceeds the maximum limit of USD 2500 for a running seven-day working period the transfer will be processed only if you confirm the override.

FX Nett. Customer

Oracle FLEXCUBE provides the facility of netting, currency wise or currency-pair wise and sending messages to the head office or a designated branch for a group of counterparties belonging to the same group.

All transactions meant to be settled on a particular day that are made before cut-off day are collated, netted and a single payment message is sent which called 'Netting days' in Oracle FLEXCUBE.

Here you specify the FX netting customer to whom the netted FX message shall be sent. For customers not belonging to any group, the FX netting customer will be the same as the customer of the maintenance.

Withholding Tax Pct

Specify the percentage of tax that should be withheld from the interest that is paid to the bank by the customer. This withholding tax percent is dictated by the country of the customer.



This is applicable for Bearing and Amortized loan contracts also.

KYC Reference Number

Specify the KYC Reference Number. The option list displays all valid KYC reference numbers generated. Choose the appropriate one. The system will link the KYC details of the selected reference number to the customer CIF.



KYC refers to Know Your Customer. KYC details for customers are maintained using KYC Details screen. The system generates a KYC Reference Number during this maintenance.

2.2.5.4 Specifying Exposure Category and Provisioning Details for Customers

When you maintain CIF details for customers, in the Customer Maintenance screen, you can specify the following exposure category details:

- Customer group to which the customer belongs, for provisioning and status processing. You must specify a group code defined for a group type that is the same as the customer type, for instance, if the customer is a retail customer, you must specify a group defined for retail customers
- Exposure category under which exposure due to loans issued to the CIF and the accounts of the CIF will be tracked. The exposure category is derived by the End of Day batch program and displayed, if the applicable logic has been maintained for the specified customer-provisioning group, in the Exposure Type Category Linkage maintenance. If no logic has been maintained for the group, you can specify the applicable exposure category
- Financial standing classification

Status for the CIF

If status processing for your branch is being done at Group/CIF level (as specified in the Branch Parameters), the current status assigned to all loans issued to the CIF as well as all overdraft accounts belonging to the CIF, is displayed in the CIF Status field in the Customer Maintenance screen. This status is the worst status of all loans contracts and overdraft accounts for a Group/CIF and is displayed both at the account as well as the loan level for all the accounts and loans a customer has in the current branch. The update applies only to the accounts and loans in the current branch not across branches.

The date since which the loans issued to the CIF (as well as the customer accounts belonging to the CIF with outstanding overdrafts) moved into the current status, is also displayed.



Note the following:

- The status change maintenance and movement change should be similarly set up for all loan products and accounts. If it is not the same across all loan products, then the worst status update will not happen for the dissimilar products.
- Status change update is done only for accounts where the movement type selected is either 'Auto' or 'Both' and is done by the status change batch which will be run after the CL batch. The status change batch uses the worst status derived by the CL batch for the update.

For details about loan status processing and provisioning, consult the Loans user manual. For details about account provisioning, refer to the chapter 'Provisioning for Customer Accounts' in this user manual.

External Ref No

To recall, if a customer record is created from an external Siebel CRM application after a successful upload into Oracle FLEXCUBE, the external reference number is defaulted in the 'External Ref No' field. You can amend the same when you unlock a record and make changes.

2.2.6 Auxiliary Tab

Click the Auxiliary tab to provide the auxiliary details pertaining to the customer.

AML Reporting

As a CIF level parameter, you can specify whether AML Reporting is required for the customer. You can check the box positioned next to this field to indicate that AML reporting should be done for the customer whose details you are maintaining.

Required

Check this box to indicate that AML Reporting is required. Acode assigned to the customer whose details you are maintaining is defaulted to the Customer Group field since the system recognizes each customer code as a customer group. You can choose to either categorize the customer under the same group or choose another customer group.



If you leave the box unchecked, the system will suppress the generation of AML reports for the customer.

Consolidated Certificate Required

Check this box to indicate whether a consolidated tax certificate is required for all transactions done for a given tax cycle. This option would work in conjunction with a similar option in the Tax Category screen and the Tax Details screen accessed from the Branch Parameters Detail screen.

Generating Consolidated Tax Certificate

Depending on the frequency maintained at the branch level, the system will generate the Consolidated Tax Certificate for a customer, provided the consolidated tax certificate generation is required at the customer level and the option is maintained at the Tax Category level. The Tax Certificate will be in a pre-shipped advice format and printed on a Year to Date basis

Maintaining Elements for Advice Generation

The following elements will be available for advice generation for consolidated tax certificates.

Element Name	Description	Data Type
CUSTOMERNO	The customer number for which the tax summary certificate is printed	Alphanumeric
CUSTOMERNAME	The customer name	Alphanumeric
FROMDATE	The from date for which the certificate is generated	Date
TODATE	The to date for which the certificate is generated	Date
TXNNUMBER	The contract reference number	Alphanumeric 16 characters
CALCDATE	The tax calculation date	Date
TAXCCY	The tax currency	Alphanumeric 3 characters
TAXAMTINTAXCCY	The tax amount in tax currency	Number
INTERESTAMT	The interest amount (basis amount on which the tax has been calculated)	Number

Individual Certificate Required

Check this box to indicate whether an individual tax certificate is required for each transaction. An individual tax certificate is a certificate (advice) which is generated for each individual event (in a transaction) resulting in computation/deduction of tax from the customer's account. The advice is linked to the product and is generated at the time of authorization of the contract/event.

Generating Individual Tax Certificate

For contracts that have tax defined on interest liquidation, an individual tax certificate will be generated by the system, provided the tax certificate is linked as an advice for the event and the individual transaction tax certificate is required to be generated for the customer.

For income other than through interest on customer accounts, the advice format for the tax certificate can be maintained depending on the requirement. This advice format can be linked to the products.

For income through interest on customer accounts, the advice format for the tax certificate is pre-shipped. The format of the advice can be modified except for the name of the advice format which is pre-shipped.

Maintaining Tags for Advice Generation

The following tags will be available for advice generation for individual transaction.

Tag Name	Description	Data Type
TXNNUMBER	The contract reference number	Alphanumeric 16 characters
CALCDATE	The tax calculation date	Date
COMPCCY	The interest component currency	Alphanumeric 3 characters
TAXCCY	The tax currency	Alphanumeric 3 characters
TAXAMTINTAXCCY	The tax amount in tax currency	Number
INTERESTAMT	The interest amount (basis amount on which the tax has been calculated)	Number

Utility Provider

Utility Providers are the recipients of the bill payment. Typical entities involved in a bill payment transaction are the consumer, your bank and the institutions (utility providers).

Utility Provider

Check this box if the customer whose details you are maintaining happens to be a Utility Provider

Utility Provider Id

Assign a unique ID to identify the utility provider.

Check Digit Validation Required

Check this box to indicate whether the check digit validation should be performed for the consumer number that is captured while making bill payment for the utility provider.

Algorithm ID

If the check digit validation should be performed you must also identify the Algorithm ID, which is used to perform the check digit validation on the consumer number.

Utility Provider Type

Indicate the type of utility provider. The option list adjoining 'Utility Provider Type' displays all valid utility provider types maintained in the system. You can select the appropriate one.

Head Office

Account Number

The Head Office Account Number is the customer's account number with the Head Office of your bank. You need to capture this value only if the Customer Type is a 'Bank'. It is used only for reference purposes.

Debtor Category

Specify the category of the Debtor from the adjoining option list.

Risk Profile

Specify the risk profile from the adjoining option list.

FT Accounting As of

For funds transfer contracts involving certain customers, you may need to generate messages on the booking date of the contract, while the actual accounting may be deferred to the debit value date.

This facility could be required in respect of future dated funds transfers involving specific customers for which the requisite messages need to be sent on booking the contract itself, whereas posting of accounting entries must be deferred to the debit value date.

You can indicate whether such a facility of allowing message generation before accounting is available for the customer, in the FT Accounting As Of field. You have the following options for accounting for FT contracts:

- Accounting as of message date (accounting entries will be posted on the date of message generation)
- Debit Value Date (accounting entries will be posted on the debit value date)

Trade Collateral Margin

Trade Collateral Margin value indicates the collateral percent which will be defaulted when the customer becomes a party to the LC. If Collateral margin is maintained at both product level and customer level, then the customer level Collateral percent gets precedence and gets defaulted to LC collateral subsystem.

Customer collateral margin will also be used in collection Bills not under LC. Collateral amount will be calculated using customer collateral margin and populated to field collateral amount under details tab, in bill online screen


Cheques

Specify the following details here:

Cheque Allowed


Specify that the customer is eligible to use the cheque. You can select one of the following options from the drop-down list:

- Yes – If you select yes, then the bank can issue the cheque book to that customer. Moreover, system will not allow you to maintain the 'Start Date' and the 'End Date'.
- No – If you select no, then you need to maintain the 'Start Date' and the 'End Date'. Customer can neither use any of the issued cheque books nor you can issue new cheques to that customer in the specified period.

 If you select 'No' for Cheque Allowed and if the cheque is already issued, then the system will display the following override message:

'Unused cheque for all customer accounts will be cancelled'

On authorization, the system will cancel all the unused cheques of the customer.

 If you amend the customer and select 'Yes' for Cheque Allowed, the status of the cancelled cheque will not change.

During BOD, the batch STCIFCHQ will change the value of this field to 'Yes' if the system date is greater than the end date.

Start Date

Specify the date from which the customer is not allowed to use the cheque. Alternatively, you can also select the date from the calendar button. The start date can be lesser than or equal to the application date.

End Date

Specify the date up to which the customer is not allowed to use the cheque. Alternatively, you can also select the date from the calendar button. The end date can be greater than or equal to the start date.

2.2.7 Corporate Tab

Click the 'Corporate Details' tab from the 'Customer Maintenance' screen to define the details of a Corporate or a Bank type of customer.

The screenshot shows the 'Customer Maintenance' window with the 'Corporate' tab selected. The window is divided into several sections:

- Customer Information:** Fields for Customer No, Full Name, Short Name, Branch Code, Type (radio buttons for Individual, Corporate, Bank, Private Customer, Joint Venture), Customer Sub Type, Description, Document ID Type, and Document ID Number.
- Registration Address:** Fields for Line 1, Line 2, Line 3, Region, Country, Name, National Id, and Issued By.
- Description of Business:** A large text area for describing the business.
- Incorporation:** Fields for Date, Capital, Constitution City, Constitution Province, Net Worth, Country, and Currency of Amounts.
- Navigation and Action:** A menu bar at the bottom with options like Group, MIS, Joint, Standing Instructions, Linked Entities, Text, Fields, Image, CLS Restrictions, MT920, Domestic, Professional, Issuer, Cards, Linked Account, KYC Details, Joint Venture, Dictionary, Tax, MIFID Classification, and Change Log. Below this are fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an 'Exit' button.

In this screen, you can maintain the following details for a corporate or bank type customer:

Name

Specify the full name of the main office of the Corporate/Bank customer.

National ID

Specify the corporate National Identification Number of this customer., in other words the registration number of your customer organization.

Country

Specify the country of the Corporate/Bank customer. You can also select the country from the adjoining option list.

Region

Specify the region of the Corporate/Bank customer. You can also select the region from the adjoining option list.



If Ukraine is selected as the country, then it is mandatory to specify the region.

Issued By

Specify the name of the authority that issued the National ID.

Incorporation

Date

Specify the date on which the customer's company was registered as an organization.

Capital

Enter the valid amount of total paid-up capital of this customer.

Constitution City

Specify the city name where the corporate customer is established.

Constitution Province

Specify the state name where the corporate customer is established.

Net Worth

This is the total net worth amount of this customer, you input in the customer code field. Enter the valid amount of total net worth amount of this customer.

Country

Specify the Country of registration of the office of the corporate.

Currency of Amounts

Specify the Currency in which you specify the particular customer's various financial details like the Net worth of the customer organization, the total Paid Up capital etc.

Description of Business

Specify the nature of the business and the business activities carried out by the customer organization.

Directors

Specify the list of the names of the Board of Directors of the organization.

2.2.8 Personal Tab

If your customer, for whom you have defined parameters in the 'CIF-basic' screen, is an 'individual, you also have to maintain the personal details in order to determine the credit line.

Click the 'Personal' tab from the CIF Maintenance screen to maintain these details.

The screenshot shows the 'Customer Maintenance' window with the 'Personal' tab selected. The form is divided into several sections:

- Customer Information:** Customer No (004986), Full Name, Short Name, Branch Code (000), Type (Individual selected), Customer Sub Type, Description, Document ID Type, and Document ID Number.
- Navigation:** Main, Auxiliary, Personal (selected), Corporate, Director, Check List, Analytical Parameter.
- Prefix:** Prefix 1, Prefix 2, Prefix 3.
- Name:** First, Middle, Last, Second Surname, Telephone, Fax, Email, Mobile Number, and Communication Mode (Mobile selected, Email Id unselected).
- Birth Details:** Date of Birth, Birth City, Birth State, Birth Country, Minor (Major selected, Incapable unselected), Submit Age Proof (Not Required), Guardian Document ID, and Guardian.
- Domicile Address:** City, Province, Postal Code, and Country.
- Passport Details:** Passport Number, Issue Date, and Expiry Date.
- Permanent Address:** Country, Line 1, Line 2, and Line 3.

At the bottom, there are buttons for 'Group', 'MIS', 'Joint', 'Standing Instructions', 'Linked Entities', 'Text', 'Fields', 'Image', 'CLS Restrictions', 'MT920', 'Domestic', 'Professional', 'Issuer', 'Cards', and 'Linked Account'. Below these are 'KYC Details', 'Joint Venture', 'Dictionary', 'Tax', 'MIFID Classification', and 'Change Log'. The footer contains fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with a 'Cancel' button.

In this screen, you can maintain generic personal details of a customer. In addition, you can also maintain the domestic and professional details of the 'individual' type customer. You can do this by invoking the relevant screens by clicking on the respective buttons.

The information that you capture in these screens forms more a part of a credit line questionnaire. Whenever you are deciding on a credit limit for an individual customer, you can use these details for verification.

You have to maintain the following parameters for every individual type of customer:

Prefix 1, 2 and 3

Specify the title prefixed to the name of the customer whose code is input against Customer Code in the Main section. The title could be Mr. /Mrs./ Ms./ Dr. / Prof. etc.

The academic titles (like Prof., Dr., etc) of the customer along with the salutations (like Consulate, Senator, Chancellor, etc.). You can either select the prefixes from the option list key-in a prefix of your choice.

Name

First

Specify the First of the customer.

Middle

Specify the Middle name of the customer.

Last

Specify the Last name of the customer.

Second Surname

Specify the second surname of the customer.

Telephone

Specify the telephone number of the customer.

Fax

Specify the fax number of the customer.

E-mail

Specify the E-mail address of the customer.

Mobile Number

Specify the mobile number of the customer.

Communication Mode

Indicate the mode of the communication to the customer to intimate about the beneficiary account credit. You can select one of the following options:

- Mobile
- Email ID

The above field is enabled only for the product that uses the NEFT clearing network, i.e., Network Qualifier of the Clearing network should be NEFT.

Legal Guardian

Date of Birth

Specify the customer's date of birth from the adjoining calendar.

Birth City

Specify the city name from the adjoining option list where the customer was born.

Birth State

Specify the state name from the adjoining option list where the customer was born.

Birth Country

Specify the country name from the adjoining option list where the customer was born.

Minor

Specify if the customer is major or minor from the adjoining drop-down list. If the customer's age is less than 18 years, then select 'Minor'. If the customer's age is more than 18 years, then select 'Major'. Select 'Emancipated Minor' if the customer is financially independent.

Incapable

Check this box to indicate that the customer is incapable to act i.e. minor or handicapped.

Submit Age Proof

Indicate the age proof submission status of the minor to major from the drop-down list. The available options are:

- Not required
- Pending
- Verified



Note the following:

- Any out flow or debit transaction is posted on a particular customer's account/s and the 'Submit Age Proof' chosen is 'Pending', then the system throws an error stating that:

'Necessary documents are not submitted for Major'

- Once the documents are submitted, the user has to manually set 'Submit Age Proof' as 'Verified'.
- After the field 'Submit Age Proof' is changed to 'Verified', then all the accounts created for the customer would be allowed for withdrawals.

Guardian Document ID

Specify the valid guardian document Id (NIF). The adjoining option list displays all the valid document Ids. Select the appropriate one.

Guardian

Specify the name of the guardian.

Sex

Indicate the gender of the customer.

National ID

Specify the national identification number or national social security number of this customer.

Domicile Address

City

Specify the city of the customer. The adjoining option list displays the list of city names maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Province

Specify the province of the customer. The adjoining option list displays the list of province maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Postal Code

Specify the postal code. The adjoining option list displays the list of postal codes maintained in the 'Province City Maintenance' screen. Select the appropriate one.

Country

Specify the country of the customer. A list of all country codes maintained in the 'Country Codes Maintenance' screen is available in the option list. You can select the appropriate code.

Passport Details

Passport Number

Specify the passport number of this customer.

Issue Date

Specify the date on which the passport was issued.

Expiry Date

Specify the date on which the passport is due to expire.

Permanent Address

Country

Specify the permanent address country of the customer. The adjoining option list displays all the valid country codes. Select the appropriate one.

Address Line 1 to 3

Specify the customer's permanent address.



You may or may not choose to maintain this information for specific individuals. This is entirely dependent on your requirement

2.2.9 Check List Tab

Click the 'Checklist' tab from the 'Customer Maintenance' screen to capture the details of document types that are to be maintained.



If Notification Date is a holiday, then system considers first working day prior to the Notification Date as the actual date for all calculation purposes.



On the notification date, a record is available in the Outgoing Message Browser Summary Screen which can be retrieved by the user and the 'Prior Notification' advice can be generated manually in the form of a letter to be sent to the customer, to inform the customer that the document proof(s) are going to expire.

Specify the following details:

Document Type

Specify the document type. The adjoining option list displays all the document types that are maintained in the system. You can select the appropriate one.

Along with the **Proof of Residence**, document **21-RFI** submission is needed for a Non-resident in an ADT Country

Name of the Document

System displays the name of the document based on the document type selected.

Reference Number

Specify the reference number for the selected document.

Issued By

Specify the name of the issuer of the document.

Date of Issuance

Specify the document issuance date from the adjoining calendar.



Note the Following:

- System validates that the document is not issued before two months of the received date.
- It is mandatory to specify the date of issuance for the 'Consular Certificate' document type.

Expiry Date

Specify the expiry date of the document from the adjoining calendar. Date should be a future date.

Prior Notification Days

Specify the prior notification days. Default value would be the 'Number of days' maintained on the Document Maintenance Screen for the document selected. The number of days entered should be less than the 'differential days between Expiry Date and Current System Date'

Notification Date

Notification date gets calculated in relation with the Expiry Date of the Document and the Prior Notification Days.

Country of Issuance

Specify the country where the document has been issued. The adjoining option list displays all the valid country code. Select the appropriate one.

Received Date

Specify the date from the adjoining calendar on which the document is received.



It is mandatory to specify the received date for the 'Consular Certificate' document type.

Unique ID

Check this box to indicate that the selected document type is unique.

Compilation Date

Specify the date from the adjoining calendar on which the documents are compiled.

Approval Date

Specify the date from the adjoining calendar on which the documents are verified and approved.

Person/Organization

Specify the name of the person or organization that has approved the document.

Name

Specify the name of the document.

Comment

You can specify any other information as a comment regarding the selected document type.

Document Series

Specify the serial number for the selected document.

Checked

Check this box to indicate that the received documents are acknowledged.

Remarks 1 to 10

Specify the additional information, if required.

2.3 Customer Document Expiry Query Screen

Customer Document Expiry Query Screen performs search on the basis of the Customer Number, Document Type, Document Expiry From Date and Document Expiry To Date. So, only those customers, who have the specified document type and within the expiry date gets returned as response. Also, user can search customers whose documents are getting expired in the provided date range in the search criteria.



Document Expiry To Date specified should be greater than or equal to Document Expiry From Date.

You can invoke the 'Customer Document Expiry Query' screen by typing 'STDDOCQU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Number

Specify the customer number from the adjoining option list.

Document Type

Specify the document type from the adjoining option list.

Document Expiry From Date

Specify the document expiry from date from the adjoining calendar based on which customer document search is to be performed.

Document Expiry To Date

Specify the document expiry to date from the adjoining calendar based on which customer document search is to be performed.

2.3.1 Maintaining Domestic Details of Individual Customer

As part of maintaining personal details of the customer, you can capture Domestic details about the customer like the customer's educational status, marital status, number of dependents etc. Click on 'Domestic' button. The Customer - Domestic Details screen will be displayed.

In this screen, you can capture the following details for each individual type of customer:

- The Marital status of the customer: A customer could be married, single, re-married, divorced, separated, widowed etc. You have to indicate the appropriate
- The name and employment status of the customer's spouse
- The educational status of a customer (Under Graduate, Graduate, Post Graduate and Non-student). If the customer has received no formal education, select Non-student
- The family members (children and others) who are dependent on the customer financially. You can indicate any number between 0 and 99
- The type of accommodation this customer is availing of. The types could be classified into - own accommodation, company provided and others. Others include all types other than self-owned and company provided. You can select the appropriate option.

2.3.2 Maintaining Professional Details of Individual Customers

After having captured the Domestic details of the individual customer you can capture the professional details about the customer.

These details include the customer's employment status, employer details or the annual expenses that the customer incurs and so on. Click on 'Professional' button. The Customer – Professional Details screen will be displayed.

The screenshot shows a software window titled "Professional Details" with a close button (X) in the top right corner. The window is divided into several sections:

- Employment:** Includes a dropdown menu for "Employment Status".
- Employment Details:** Includes text boxes for "Tenure", "Retirement Age", "Previous Designation", "Previous Employer", "Current Designation", "Current Employer" (with a selection icon), "Employer Description", "CNAE Code" (with a selection icon), "Description" (with a selection icon), "CNO Code" (with a selection icon), and "Description".
- Income:** Includes a dropdown for "Currency of amounts" (with a selection icon), and text boxes for "Salary" and "Other".
- Official Address:** Includes text boxes for "Line 1", "Line 2", "Line 3", and "Country" (with a selection icon).
- Contact:** Includes text boxes for "Telephone", "Telex", "Fax", and "Email".
- Expense:** Includes text boxes for "Rent", "Insurance", "Loan Payments", "Other", "House Value", and "No of Credit Cards".

At the bottom right of the window, there are "Ok" and "Cancel" buttons.

You can capture the following professional details of the individual/corporate type of customer through this screen:

Employment

Employment Status

Specify the employment status of the customer from the adjoining option list. The options are:

- Full time permanent
- Full time temporary
- Part-time
- Self-employed
- Retired pensioned
- Retired non-pensioned
- Unemployed

Employment Details

Tenure

Specify the number of years the customer has been in his/her current job.

Retirement Age

Specify the age at which the customer is due to retire from his/her current job or business.

Previous Destination

Specify the designation this customer held in his/her previous job or employment.

Previous Employer

Specify the name of the previous employer of this customer.

Current Designation

Specify the designation held by this customer in his present job.

Current Employer

Specify the current employer from the adjoining option list to map the current employer of the customer.

Employer Description

You can describe the current employer's full name here.

- The name, address, country, telephone, telex, fax and E-mail address of the customer's current employer. The name, address and country of the employer should conform to SWIFT standards

CNAE Code

Specify the National Activity Code. The adjoining option list displays the list of all the valid CNAE codes maintained in the 'CNAE/CNO Code maintenance' screen.



It is mandatory to specify CNAE code for the individual customer except self employed.

Description

System displays the description for the selected CNAE code.

CNO Code

Specify the National Occupational Code. The adjoining option list displays the list of all the valid CNO codes maintained in the 'CNAE/CNO Code maintenance' screen.

Description

System displays the description for the selected CNO code.



The 'Current Employer' field is used by the system to map the user to his current employer. Click the adjoining option list to display all the authorised and open employer codes maintained in the system.

Income

Currency of Amounts

Specify the currency in which the customer's financial details like, annual salary, annual rent expenses, annual loan repayment, etc is maintained.

Salary

The annual returns that your customer earns through salary and other sources of employment if any.

Others

If your customer earns revenue through other source apart from a monthly, salary you have to capture the customer's combined income from all other sources.

Expense

Specify the annual expenses that your customer incurs from sources other than the annual salary.

Rent

Specify the customer's annual expenditure on rent.

Insurance

Specify the customer's annual expenditure on premium on insurance.

Loan Payments

The customer's current annual expenditure incurred on re-payment of loans availed.

Other

The customer's current annual expenditure incurred on payment of expenses other than rent, insurance premium or loans

House Value

Specify the value in terms of money, of this customer's house (in case he owns one).

Number of Credit Cards

Specify the number of credit cards the customer has subscribed to.

Official Address

Specify the complete mailing address of the customer's employer (Line1, Line2, Line3 & Country).

Contact

Specify the telephone, telex, fax numbers and E-mail address of the customer's current employer or business partner

After having captured all the relevant details, you can save the record. You will be returned to the Personal Details section of the CIF Maintenance screen.

2.3.3 Capturing UDF Values for Customers

In order to know your customer better, you may need to capture certain additional information specific to a customer. This is in addition to the regular information that you would capture in the Customer Maintenance screen. To capture more details of the customer, you can define a set of UDFs and associate them with the function id 'STDCIF' (for Customer Maintenance screen). After you associate the UDFs, they will appear in the Customer Maintenance screen. You can then capture the values for these UDFs.

The UDFs that are displayed in the Customer Maintenance screen depend on your selections in the 'UDF in Base Table' screen. A maximum of five UDFs can be made to appear in Customer Maintenance screen.

Refer the manual on 'User Defined Fields' for details on defining a user-defined field and associating the UDF with the function id 'STDCIF'.

The values that you enter for the UDFs will be validated against the rules maintained for them. If the entries fail the validations, the system will display a suitable message to inform you that the entries made do not adhere to the rules maintained.

The UDFs will be displayed in the Customer Maintenance Summary screen as well. You will also be allowed to perform queries based on these fields.

2.3.4 Special Customer Grouping

While maintaining the customer information, you can place a customer under a special customer group for different rating purposes. Through the Special_Status user defined field (UDF) you can link the customer to a group and specify the rating for the group.

Whenever a contract is booked for such a customer, the system will display an alert message specifying the status of the customer thereby you can apply the new rates specified for such customers.

The steps involved for including the SPECIAL_STATUS UDF in customer maintenance are as follows:

1. Create a new user defined field SPECIAL_STATUS
2. Link it to the Function ID STDCIF
3. Specify the value of the user defined field at the time of creating a customer

The special status is also displayed in the information retrieval screen when you do a query for such a customer. You can do the query using the 'Customer Summary Query' screen.

You can invoke this screen by typing 'ACDCBIR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Customer Summary Query' application window. It features a top section for 'Information Retrieval' with fields for 'Customer Number', 'Special Status', 'Current Branch', 'Linked Customer', and 'Trade License Expiry Status'. A 'QUERY' button is positioned below the 'Linked Customer' checkbox. Below this are four data grids: 'Linked Customer' (with columns 'Customer No', 'Customer Name', 'Relation'), 'Account Class' (with columns 'Account Class', 'Description'), 'Products' (with columns 'Product Code', 'Description'), and 'Module' (with columns 'Module Code', 'Description'). There is also an 'External Account Types' grid (with columns 'Account Type', 'Description'). A 'Fetch' button is located to the right of the 'Linked Customer' grid. An 'EXIT' button is at the bottom right corner of the window.

STOP After having captured all the required details save the CIF record. It becomes valid only after a user other than you authorizes it.

Check the 'Linked Customer' check box.

Customer Number

You can select the customer number from the adjoining option list. The available options are:

- Customer Number
- Document ID Number
- Customer Name

Click 'Query' button to view all linked customers in Linked Customer Details. Select a customer from the details and click 'Fetch' button to perform a query operation on the selected customer. The displayed values are based on the query parameters provided.

2.3.5 Dictionary Details

An uploaded parameter value provided in the form of a dictionary needs to be assigned to a loan contract in the system for the purpose of statistical reporting.

A bank need to undergo statistical reporting to ensure it is following the directives as regulated by the central/governing bank which is the NBU. In order to abide by the regulations of the NBU and receive approval of rules for statistical reporting, the parameter values provided by the NBU are assigned to the customers in Oracle FLEXCUBE.

The DBF file provided by the NBU is uploaded through the 'Upload Analytical' screen, which is discussed under 'Core Services'. The customer is assigned to the parameter value K060,K016,K150 received during customer creation.

Dictionary	Field Name	Value	V
			V

Dictionary Name

Select the dictionary from the adjoining list for which the parameter value is to be assigned.

Field Name

Select the Field name from the adjoining List.

The adjoining option list displays all the field names in the dictionary that is selected.

Value

Select the appropriate value from the list provided after clicking 'V'. List displays the values of the field name.

If the wrong value is chosen or specified value is not present in LOV then an error message is displayed.

If the D_Open date is greater than application date , then the value will not be available in the LOV.

If D_Close date is less than the application date, then the value will not be available in the LOV.

2.3.6 Specifying Analytical Parameters

In the 'Analytical Parameters' tab, you can capture certain details related to the customer, which are used for validation purposes. The values that you can capture here are uploaded from various database tables available at the bank. Separate databases are available for the individual fields displayed in this screen and the values that you can specify are restricted to the options available in these tables.

For more details on upload of analytical parameters, refer the section titled 'Uploading Analytical Parameters' in this user manual.

The following screen is displayed when you click 'Analytical Parameters' tab in 'Customer Maintenance' screen.

The screenshot shows the 'Customer Maintenance' application window. At the top, there are input fields for 'Customer No *', 'Full Name', 'Short Name *', and 'Branch Code'. To the right, there are radio buttons for 'Type' (Individual, Corporate, Bank, Private Customer, Joint Venture) and text boxes for 'Customer Sub Type', 'Description', 'Document ID Type', and 'Document ID Number'. Below this is a tabbed interface with 'Analytical Parameter' selected. The main area is divided into 'Primary Parameters' and 'Secondary parameters', each with several alphanumeric codes and corresponding text input fields. At the bottom, there is a navigation bar with buttons for 'Group', 'MIS', 'Joint', 'Standing Instructions', 'Linked Entities', 'Text', 'Fields', 'Image', 'CLS Restrictions', 'MT920', 'Domestic', 'Professional', 'Issuer', 'Cards', and 'Linked Account'. Below the navigation bar are fields for 'KYC Details', 'Joint Venture', 'Dictionary', 'Tax', 'MIFID Classification', and 'Change Log'. The footer contains fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

You can capture primary and secondary parameters related to the customer, here. Once you specify the primary parameters, the system automatically populates the values for the secondary parameters from the corresponding linkage tables, which are also uploaded.

You can specify the following primary parameters for the customer:

Type of Economic Activity

Select the type of the economic activity the customer is involved in, from the option list provided. The option list displays the list of values uploaded from the internal database tables available at the bank.

Sector of Economy 1

Select the sector associated with the economic activity specified, from the option list provided. The option list displays the list of values uploaded from the internal database tables available at the bank.

Type of Ownership of the 1st Level

Select the ownership type of first level from the option list provided.

Section of Types of Economic Activity

Select the section related to the type of economic activity from the option list provided.

Secondary Parameters

The following secondary parameters related to the primary parameters specified are automatically displayed here.

- Type of Economic Activity
- Sector of Economy 1
- Sector of Economy 2
- Type of Ownership of the 1st Level
- Section of Types of Economic Activity

These details are picked up from the linkage tables that are uploaded to the system. You cannot modify any of these secondary parameter values.



This is applicable only for Ukraine and if you have selected the country code of the current branch as 'UA'..

2.3.6.1 Validations for Customer Parameters

Validations are performed on the primary and secondary parameter values specified, by cross checking these details with some other tables uploaded. These tables contain a combination of values, so that the details specified in this screen are validated for correct grouping.

The following validations are carried out by the system:

- For a new CIF if there are no accounts opened under the CIF, no validations are carried out.
- For a modified CIF, and accounts are already available under this, then all the parameters of CIF and accounts should form a set and this value should be verified in the combination database tables. Initially, the system checks if the 'Balance Account Code' corresponding to the customer account exists in these tables.
 - If it exists then the set of both CIF and account parameters are verified in the database table. If these parameters are not present in the tables, then an override message is displayed.
 - If the 'Balance Account Code' does not exist in the first table, then all the remaining tables are searched sequentially and if not found in any of the tables, the system displays the names of the tables where the balance account code was not present.
 - The system verifies the resident/non resident type (k030) and the balance code against the details maintained in the system. If the value specified here does not match, the system displays an override.
 - While opening a new account, the system verifies whether the values for R020 and K030 match with the corresponding values maintained.
















If there are multiple accounts for a CIF, these validations are done for each account related to the customer.

2.3.7 Other Basic Customer Information

You will notice the following buttons in the Customer Maintenance screen:


	Through this screen you can associate the customer code with a group
	Through this you can define the MIS details of a customer (for future use)
	Through this you can capture details of joint customers.
	Through this screen, you can view the details of all standing instructions associated with respective the customer code.
	<p>Through this screen, you can link different customers to the specific customer whose details you are capturing and specify the relation shared by the two customers.</p> <p><i>For details about linked entities, refer to the section Maintaining Customer Accounts under the heading 'Relationships for Customer' in this user manual.</i></p>

	<p>Through this screen, you can store free format text, scanned images etc about the customer whose details you are capturing.</p> <p>You can store this information either as text documents or as plain text.</p>
	<p>Through this you can capture user defined fields.</p>
	<p>Through this screen, you can capture the photograph of the customer whose details you are maintaining. You will be allowed to access this screen, only if you have the requisite access rights i.e., you may have rights to access the CIF screen but not view the photograph of the customer.</p>
	<p>Through this button you can view/modify/add (define) the liability details of a customer, provided you have been assigned the necessary rights.</p> <p> This button appears enabled only if the function Id LMTCURES has been added to your User Role</p> <p>If this Function Id has not been added to your User Role, the button will appear disabled.</p>
	<p>In case of a CLS participant, you can capture CLS currency restrictions.</p>
	<p>Through this screen, you can specify MT920 preferences.</p>
	<p>Through this screen, you can capture domestic details of the customer.</p>
	<p>Through this screen, you can capture professional details of the customer.</p>
	<p>In case of an issuer customer, you can capture issuer details.</p>
	<p>Through this screen, you can view cards details of the customer.</p>
	<p>Through this button you can call the OFAC service and view the response from the OFAC system.</p>
	<p>This button invokes the KYC Details screen where you can view the KYC details of the customer.</p>

Linked Account	You can capture linked account details through this screen.
Joint Venture	Through this screen, you can maintain the joint venture details.
Dictionary	Using this button, you can define the dictionary details for specific customers.
MIFD Classification	This button invokes the the MiFID classification screen to capture the MiFID classification details for a customer.
Tax	This button invokes the Tax Details screen for specific customers.

2.3.8 Viewing Debit Card Details

Click 'Cards' button to view details about debit cards issued to a customer.



Here, you can view the following details.

Branch Code

The branch code is displayed from the main 'Customer Information Maintenance' screen.

Customer No

The customer identification code (CIF) is displayed from the main 'Customer Information Maintenance' screen.

Account No

The system displays the account number against which you have maintained debit card details.

Authorisation Status

Indicate the authorisation status of the debit card by selecting one of the following values:

- Authorised
- Unauthorised

Record Status

Indicate the record status of the debit card by selecting one of the following values:

- Open
- Closed

Branch Code

The system displays the branch code where the debit card has been issued.

Request Reference Number

The system displays the request reference number of the card issuance record.

Card Number

The system displays the debit card number of the card holder.


Multiple cards can be issued to a customer.

2.3.9 Viewing OFAC Check Response

OFAC check enables the application to call an external web service to perform black list check for customer and customer accounts and give warnings appropriately while transacting with black listed customers. You can also capture your remarks before overriding the black list warning.

Click 'OFAC Check' button in 'Customer Account Creation' screen to view the OFAC check response in the 'External System Detail' screen. On clicking 'OFAC Check' button, system will build the request XML and call the web service. The 'External System details' screen displays the response is received from the external system; and you will be also allowed to enter your remarks in this screen. The response received will also be sent to Oracle FLEXCUBE Database layer for any further interpretations of the same.

This button can be made visible while carrying out the actual customization. Request building response interpretation in the database layer needs to be done as part of customization to enable this.



Here, you can view /capture the following details:

External System Response

The response from the external system regarding the black listed customer is displayed here.

User Remarks

Specify your remarks regarding the black listed customer here.

2.3.10 Viewing KYC Details

KYC refers to know your customer. You can view the KYC details maintained for a customer on 'KYC Maintenance' screen. Click 'KYC Details' button to invoke the screen.

The screenshot shows a window titled "KYC Maintenance". Inside the window, there are four labeled fields with asterisks indicating they are required:

- KYC Reference * 000ZKYC113650006
- Full Name of Customer * [text input field]
- KYC Customer Type * [dropdown menu]
- Risk Level * [dropdown menu]

Below these fields is a horizontal tab bar with four tabs: "Retail Customer", "Corporate Customer", "Financial Customer", and "Fields".

At the bottom of the window, there are two rows of labels: "Maker" and "Checker" on the left, and "Date Time:" on the right. A "Cancel" button is located in the bottom right corner.

The system displays the following details:

- KYC reference number
- Full name of the customer
- Type of customer
- Risk level of the customer

2.3.10.1 Viewing KYC Details of Retail Customers

You can view the KYC profile details for retail customers on 'KYC Retail Profile' screen. Click 'Retail Customer' button in the 'KYC Maintenance' screen.

The screenshot displays the 'KYC Retail Profile' window. It is divided into several sections:

- Beneficial Owner Information:** Includes fields for Declared (Resident, Politically Exposed Person), PEP Remarks, Local Address, Home Country Address, Birth Date, Birth Place, Nationality, Office Tel Number, Residence Tel No, Mobile Tel Number, Fax, Purpose Of Account Opening, Others, Account Type, Power Of Attorney, Passport Number, Passport Expiry Date, Visa Number, Visa Expiry Date, and KYC Amounts CCY (set to GBP).
- Beneficially Owned Company:** A table with columns: Company Name, Location, % Holding, Annual Income, and Line Of Business. It shows 1 of 1 records.
- Source of Income:** Includes checkboxes for Salary, Rental, Investment, Business Concern, and Professional Business.
- Related Companies Accounts with Bank:** A table with a column: Company Account Number. It shows 1 of 1 records.
- Personal Accounts with Bank:** A table with a column: Personal Accounts Number. It shows 1 of 1 records.

The window has 'Ok' and 'Exit' buttons at the bottom right.

The system displays the following details of the retail customer:

Beneficial Owner Information

- Whether the beneficial owner is declared as a resident
- Whether the beneficial owner is declared as politically exposed person
- Remarks on the politically exposed person
- Local address of the beneficial owner
- Home country address of the beneficial owner
- Birth date of the beneficial owner
- Place of birth of the beneficial owner
- Nationality of the beneficial owner
- Telephone number of the beneficial owner's office
- Residential telephone number of the beneficial owner
- Mobile phone number of the beneficial owner
- Fax number of the beneficial owner
- Purpose of opening the account
- Other details
- Type of account

- Whether power of attorney is given to beneficial owner
- Passport number of beneficial owner
- Expiry date of the passport
- Visa number of the beneficial owner
- Expiry date of visa
- Currency in which KYC amount is maintained

Beneficially Owned Company Details

- Name of the company
- Location of the company
- Percentage of the holding
- Annual income of the company
- Line of business of the company

Source of Income

- Whether salary is a source of income
- Whether rental is a source of income
- Whether investment is a source of income
- Whether business concern is a source of income
- Whether professional business is a source of income

2.3.10.2 Viewing KYC Details of Corporate Customers

'KYC Corporate Profile' screen gives an account of the KYC profile details for corporate customers. Click 'Corporate Customer' button in the 'KYC Maintenance' screen. The system displays 'KYC Corporate Profile' screen.

The screen is as shown below:

The screenshot shows the 'KYC Corporate Profile' window with the following sections:

- Customer and Sponsor(s) Information:** Includes fields for 'Main', 'Compliance/Aud', 'Parent Company Country of Incorporation', 'Type of Company', 'Others', and 'KYC Amounts Currency' (set to EUR).
- Reason of Account:** Includes 'Purpose of Account', 'Opening', and 'Others'.
- Nature of Business:** Includes 'Nature of Business', 'Product Traded', 'Main Source of Funds', 'Borrowing Account Group', and 'Annual Turnover'.
- Details of Key Person:** A table with columns: KYC Id, First Name, Middle Name, Last Name, Relationship, Nationality, Position Or Title. It contains one row with a checked 'KYC Id'.
- Company Details:** Includes 'Details of Company Branches', 'No of Person Employed', and 'Mode For Salary' (with 'Others' selected).
- Details of Suppliers:** A table with columns: Supplier Name, Country, Settlement Mode.
- Details of Clients:** A table with columns: Client Name, Country, Payment Mode.
- Transaction Type:** A table with columns: Transaction Type, Count, Total Amount, Max Single Amount, Purpose, Country, Fund Transfer Purpose Within Country.

Buttons for 'Ok' and 'Cancel' are located at the bottom right.

The system displays the following details:

Customer and Sponsors Information

- Name of the group
- Country of Parents Company
- Type of the company
- Other details
- Currency in which KYC amount is maintained

Reason of Account

- Reason for opening an account
- Other details

Specifying Nature of Business

- Nature of business
- Name and details of the product traded in the business
- Main source of funds
- Borrowing account group

- Annual turnover of the company

Details of Key Person

- Unique identification for the KYC
- First name of the key person
- Middle Name of the key person
- Last Name of the key person
- Relation ship of the key person with the corporate customer
- Nationality of the key person
- Position or title of the key person
- Percentage of share for the key person
- Document Id type to identify the key person
- Unique document Id number of the key person

Specifying Company Details

- Details of the company branches
- Number of person employed in the company
- Mode of salary in the company
- Other details

Specifying Details of Suppliers

- Name of the supplier
- Country of the supplier
- Mode of settlement

Specifying Details of Clients

- Name of the client
- Name of the country of the client
- Mode of payment

Specifying Transaction Types

- Type of transaction
- Count of the transaction
- Total amount of the transaction
- Maximum single amount for the transaction
- Purpose of the transaction
- Country of the transaction

- Purpose of fund transfer within a country
- Audit date
- Whether account should be solicited
- Date on which the account is solicited
- Details of the introducer
- Date of compliance clearance
- Date of business approval
- Trade licence number
- Next date of KYC review

Specifying Comments

- KYC comment about the corporate customer
- Comments on the corporate customer by the sales and service officers
- Name and comments of the approvers on the corporate customers

2.3.10.3 Viewing Corporate or Audit HO Details

Click 'Corporate or Audit HO Details' tab in the 'KYC Corporate Profile' screen.

The screenshot shows a software window titled 'KYC Corporate Profile'. The active tab is 'Compliance / Audit HO Details'. The form contains the following fields:

- CID Number: _____
- Name: _____
- STR Raised
- STR Date: _____
- STR Reference: _____
- CB Response
- CB Response Date: _____
- Activity: _____
- Activity Reason: _____
- Dairy Note: _____

At the bottom right of the window, there are 'Ok' and 'Exit' buttons.

The system displays the following details:

- Number of the corporate customer
- Name of the corporate customer
- Whether STR should be raised
- Date of STR using adjoining calendar
- Reference number of the STR
- Whether the CB should be responded

- Date of the CB Response
- Details of the activity
- Reason for the activity
- Dairy note

2.3.10.4 Viewing KYC Details of Financial Customers

'KYC Financial Profile' screen displays KYC profile details for financial customer. Click 'Corporate Customer' tab in the 'KYC Maintenance' screen.

The system displays the following details:

- Address of the bank
- Country of the financial customer
- Currency of the KYC amounts

Transaction Products

- Name of the transaction product
- Rating of the product
- Number of monthly transactions
- Monthly amount

Management Details


- Name of the manager
- Designation

Share Holders Details

- Name of the share holder
- Holding of the share holder
- Address of the share holder
- City of the share holder
- Country of the share holder

2.3.10.5 Viewing User Defined Fields

'User Defined Fields' screen displays the all UDFs defined using KYC Maintenance screen. You can invoke this screen by clicking 'Fields' tab in the 'KYC Maintenance' screen.




The system displays the following details:

- Name of the user defined field
- Value of the user defined field

2.3.11 Maintaining Joint Venture Details

You can maintain the joint venture details for a customer on 'Joint Venture Details' screen. Click 'Joint Venture' button to invoke the screen.

The screen is as shown below:



The screenshot shows a window titled "Joint Venture Details" with a close button (X) in the top right corner. Below the title bar is a navigation area with "1 of 1" and a "Go To Page" input field. The main content area is labeled "Details" and contains a table with three columns: "Party ID *", "Party Name *", and "Ratio *". Each column has a red asterisk indicating a required field. The table has three rows, each with a checkbox in the first column and a small icon in the second column. Below the table is a large yellow rectangular area. At the bottom right of the window are "Ok" and "Cancel" buttons.

Party ID *	Party Name *	Ratio *
<input type="checkbox"/>		
<input type="checkbox"/>		
<input type="checkbox"/>		

Party ID

Specify the party ID.

Party Name

The system displays the party name.

Ratio

Specify the ratio between the participants on share.

2.3.12 Maintaining Tax Details

Click on Tax button to invoke 'Tax Details' screen.

The screenshot shows a window titled "Tax Details" with a close button (X) in the top right corner. The window contains the following fields and controls:

- Customer No _____
- Exemption of VAT Reason Code _____
Reason _____
- Exemption of Income Tax Reason Code _____
Reason _____
- Exemption of Stamp Duty Reason Code _____
Reason _____

At the bottom right of the window, there are two buttons: "Ok" and "Exit".

You can specify the following details:

Customer No

The system displays the customer number here.

Exemption of VAT

System automatically updates 'Exemption of VAT'. This flag is auto updated as either checked or unchecked by the system based on the resident status of the customer and the expiry status or availability of the documents. You can modify this flag.

Reason Code

Exemption of VAT flag when checked, the adjoining option list for Reason Code gets default value only if one value is maintained in the limit types screen for VAT. If more than one value is maintained in the limit types screen for VAT, system defaults with null and you need to select from the adjoining option list. You can modify this field.

It is mandatory to specify the reason code if the tax is exempted. The system allows you to specify the reason code only if the checkbox 'Exemption of VAT' is checked..

Reason

Reason gets displayed based on the reason code.

Exemption of Income Tax

System automatically updates 'Exemption of Income Tax'. This flag is auto updated as either checked or unchecked by the system based on the resident status of the customer, Financial Institution Type selected and the expiry status or availability of the documents. You can modify this flag .

Reason Code

If 'Exemption of Income Tax' is checked, the adjoining option list for Reason Code gets default value based on the exemption codes maintained for the specific Financial Institution Type in the Financial Institution Exemption Maintenance screen. You can modify reason code.

It is mandatory to specify the reason code if the tax is exempted. The system allows you to specify the reason code only if the checkbox 'Exemption of Income Tax' is checked.

Reason

Reason gets displayed based on the reason code.

Exemption of Stamp Duty

System automatically updates the 'Exemption of Stamp Duty'. This flag is auto updated as either checked or unchecked by the system based on the Financial Institution Type selected. You can modify this flag.

Reason Code

Reason Code gets default value based on the exemption codes maintained for the specific Financial Institution Type in the Financial Institution Exemption Maintenance screen. You can modify Reason Code.

It is mandatory to specify the reason code if the tax is exempted. The system allows you to specify the reason code only if the checkbox 'Exemption of Stamp Duty' is checked.

Reason

Reason gets displayed based on the reason code.



System displays an error message, if any of the Exemption flags are checked and the Exemption Code is not selected

2.4 Financial Institution Exemption Maintenance Screen

You can invoke this screen by typing 'STDFIEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details:

Financial Institution Code

Select Financial Institution Code from the adjoining option list. Option list displays the Financial Institution Codes maintained in the limit types screen.

Financial Institution Name

Financial Institution Name gets displayed based on the Financial Institution code.

Stamp Duty Exemptions

Exemption

Check this checkbox if user wants to mark the Financial Institution Type as 'Eligible for Stamp Duty Exemption'

Exemption Code

Select the exemption code from the adjoining option list. Option list displays the exemption codes maintained in the limit types screen.

Exemption Reason

Exemption reason gets displayed based on the Exemption Code.

Income Tax Exemptions – Residents

Exemption

Check this box if you want to indicate the Financial Institution Type as 'Eligible for Income Tax Exemption' for resident customers.

Exemption Code

Select the exemption code from the adjoining option list. Option list displays the exemption codes maintained in the limit types screen.

Exemption Reason

Exemption reason gets displayed based on the exemption code.

Income Tax Exemptions – Non-Residents**Exemption**

Check this checkbox if you want to indicate the Financial Institution Type as 'Eligible for Income Tax Exemption' for non-resident customers.

Exemption Code


Select the exemption code from the adjoining option list. Option list displays the exemption codes maintained in the limit types screen.

Exemption Reason

Exemption reason gets defaulted based on the exemption code.

2.5 Financial Institution Exemption Summary Screen

You can invoke this screen by typing 'STSFIMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can specify the following details:

Authorization Status

Specify the authorization status from the adjoining drop down list. The options are:

- Authorized
- Unauthorized
- Rejected

Record Status

Specify the record status from the adjoining drop down list. The options are:

- Open
- Closed

Financial Institution Code

Specify the Financial Institution Code from the adjoining option list.

Financial Institution Name

Specify the Financial Institution Name from the adjoining option list.

2.5.1.1 Stamp Duty Exemption Indicator

Customer is exempted from Stamp Duty either on the basis of the Financial Institution Type associated to the customer (Automatic Exemption) or on the basis of manual exemption.

Information regarding Stamp Duty exemption is captured in below mentioned fields:

- Exemption of Stamp Duty
- Reason Code
- Reason

Automatic Exemption Process

Making a customer exempt from Stamp Duty on the basis of a Financial Institution Type is an automatic process. In this process, once the bank user selects the Financial Institution Type, the values in 'Exemption of Stamp Duty' and 'Reason' gets automatically filled on the basis of the exemption information maintained for the selected Financial Institution Type. Value in the exemption flags gets defaulted and can be manually changed by the user before saving.

Manual Exemption Process

You can manually check or uncheck the 'Exemption of Stamp Duty' checkbox and can manually change the 'Reason Code' and 'Reason'.

Apart from the customer level exemptions, there are some operations on the basis of which the bank can exempt or reduce the applicable tax. If overrides are done at the contract level and bank wants to tax the customer at a reduced rate, then changes will be made at each of the identified contract level screens. You can modify the rate as defaulted from the customer level on the contract screen. The reduced rate taxing is applicable only for stamp duty tax.

2.5.1.2 VAT Exemption Indicator

A customer is exempted from VAT either on the basis of the country associated to the customer and the expiry status or availability of the documents (automatic exemption) or on the basis of manual exemption.

Information regarding VAT exemption is captured in below mentioned fields:

- Exemption of VAT
- Reason Code
- Reason

Business Processing

System follows the system logic which checks the Customer Country Code and the Branch Country Code and the expiry status or availability of the documents. If the Customer Country Code is different from the Branch Country Code, then the Customer Status is to be 'Non-Resident'. Customer is considered to be a non-resident and exemption of VAT is checked if valid documents are attached.

The 'Exemption Code and Reason' in the Customer Maintenance Screen gets defaulted, if it has one value for VAT. If more than one value is maintained in for VAT, it gets defaulted with NULL and you need to select from the list of values.

Automatic Exemption Process

If you check 'Exemption of VAT' check box, then system checks the Customer Country Code and the Branch Country Code and the expiry status or availability of the documents. If the Customer Country Code is different from the Branch Country Code, then the Customer Status is to be 'Non-Resident'. Customer is considered to be a non-resident and exemption of VAT is checked if valid documents are attached.

The Exemption code and Reason option list in the Customer Maintenance Screen gets default value only if it has one value for VAT. If more than one value is maintained for VAT, it gets default with NULL and you need to select from the option list.

Value in the exemption flags gets defaulted and can be manually changed by the user before saving.

Manual Exemption-

User can manually check or uncheck the 'Exemption of VAT' checkbox and can manually change the 'Reason' and 'Reason Code'.

2.5.1.3 Income Tax Exemption Indicator

Customer is exempted from Income Tax either on the basis of the Financial Institution Type and Country associated to the customer and the expiry status or availability of the documents (automatic exemption) or on the basis of manual exemption.

Information regarding Income Tax exemption is be captured in below mentioned fields:

- Exemption of Income Tax
- Reason Code
- Reason

Business Processing

At the time of registration of a customer on the customer maintenance screen, user selects the Financial Institution Type and Country to which the customer belongs.

Customer is exempted from Income Tax either on the basis of the Financial Institution Type and Country associated to the customer and the expiry status or availability of the documents.

Automatic Exemption Process


Making a customer exempt from Income Tax on the basis of a Financial Institution Type, Country and the expiry status or availability of the document(s) is an automatic process. In this process, once the you select the Financial Institution Type, depending on whether the customer is resident or non-resident and depending on the expiry status or availability of the document(s) the values in the 'Exemption of Income Tax' and 'Reason' gets automatically filled on the basis of the exemption information maintained for the selected Financial Institution Type and Resident Status. Value in the exemption flags gets defaulted and can be manually changed by the user before saving.

Manual Exemption

You can manually check or uncheck the 'Exemption of Income Tax' checkbox and can manually change the 'Reason Code' and 'Reason'.

2.5.2 Maintaining Linked Account

Click on Linked Account button to invoke 'Linked Account' screen.



The screenshot shows a window titled "Linked Account" with a close button (X) in the top right corner. Below the title bar is a navigation bar with left and right arrows, a "10/1" indicator, and a "Go" button. To the right of the navigation bar are three icons: a plus sign, a minus sign, and a list icon. Below the navigation bar is a table with the following columns: "Verified" (with a checkbox), "Linked Account Number", "Linked Account IBAN", and "Linked Account BIC". The table is currently empty. At the bottom right of the window are "Ok" and "Exit" buttons.

You can specify the following details:

Verified

Check this box to verify and initiate a transaction.

Linked Account Number


Specify the Linked Account Number.

Linked Account IBAN

Specify the Linked Account IBAN.


Linked Account BIC

Specify the Linked Account BIC.

 If the country code of the processing branch is Spain then Linked Account Number and Linked Account IBAN is subjected to CCC format or IBAN account validation.

2.5.3 Maintaining MiFID Classification

Click 'MIFD Classification' button to invoke the 'MIFD Classification' screen.




You can specify the following details:

MiFID Classification

Classification

Specify the MiFID classification from the adjoining drop-down list based on the internal assessment for the customer. Default value of this field is 'None'. You can modify it by selecting one of the following:

- Retail
- Professional
- Counter Party

 Note the following:

- You can select 'Professional', 'Retail', or 'None' for the Individual or corporate customer types only.

- You can modify the classification from 'Counter Party' to 'Professional' and from 'Professional' to 'Counter Party' for the corporate type of customer only.
- The MiFID classification is not allowed for the 'Bank' type customer.
- You cannot change the MiFID classification If the initial MiFID classification is 'Retail'.
- You can select the classification to Professional / Counterparty from 'None'.

Expiry Date

Specify the date on which the MiFID will expire from the adjoining calendar.

MiFID Classification Status

Specify the MiFID classification status from the adjoining drop-down list. You can select one of the following:

- Approved
- Requested
- Pending
- None

Eligible Counter Party Type

Specify the eligibility counter party type. The adjoining option list displays the following options:

- Investment Firms
- Credit Institutions
- Insurance Companies
- UCITS and their Management Companies
- Regulated Financial Institutions
- Government Undertakings

Remarks

You can specify the reason to change the MIFD classification to another; change i=of eligibility conditions or change of eligible counter party type.

Eligibility Conditions

You can specify the eligibility conditions by selecting one or more options below:

Heritage (Portfolio Value) more than 500000

Check this box to indicate that the heritage portfolio value is more than 500000.

Quarterly Operations > 10

Check this box to indicate that the quarterly operations are more than 10.

Financial Experience > 1Year

Check this box to indicate that the financial experience is more than 1 year.

Corporate Equity >= 2 MM.E.

Check this box to indicate that the corporate equity is more than or equal to 2 MM.E.

Corporate Liabilities of Balance >=20 MM.E.

Check this box to indicate that the corporate liabilities of balance is more than or equal to 20 MM.E.

Corporate Turnover >= 40 MM.E.

Check this box to indicate that the corporate turnover is more than or equal to 40 MM.E.



Note the following:

- For 'Individual' type of customer with MiFID classification as 'Professional', you can select any two of the following options:
 - Heritage (Portfolio Value) more than 5000000
 - Quarterly Operations > 10
 - Financial Experience > 1Year
- For 'Corporate' type of customer with MiFID classification as 'Professional', you can select any two of the following options:
 - Heritage (Portfolio Value) more than 5000000
 - Quarterly Operations > 10
 - Financial Experience > 1Year
 - Corporate Equity >= 2 MM.E.
 - Corporate Liabilities of Balance >=20 MM.E.
 - Corporate Turnover >= 40 MM.E.

System will not allow selecting Eligibility conditions if the MiFID Classification is 'Counter Party' or 'Retail'.

2.5.4 Maintaining Employer Details

In Oracle FLEXCUBE, you can maintain details regarding the employer of a customer. You can maintain the employer details in the 'Employer Maintenance' screen. You can invoke this screen by typing 'SMDEMPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a window titled "Employer Maintenance". Inside the window, there are two input fields: "Employer Code *" and "Employer Description *". At the bottom of the window, there is a status bar with the following fields: "Maker", "Checker", "Date Time:", "Mod No", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner of the status bar.

You can maintain the following details here:

Employer Code

Specify a unique code for the employer. The employer code can be an alphanumeric character with a maximum length of nine characters.

Employer Description

Enter a small description for the employer code entered.

2.5.5 Maintaining Province, City and Postal Code Details

You can maintain the customer's province, city and postal code details using 'Province City Maintenance' screen. You can invoke this screen by typing 'STDPRCTY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software interface for maintaining province, city, and postal code data. The interface is organized into several sections:

- Country:** A text field for the country code and a dropdown arrow.
- Description:** A text field for a brief description of the country.
- Province/Region Details:** A table with columns for 'Province/Region code' and 'Province/Region Description'.
- District Details:** A table with columns for 'District' and 'District Description'.
- City Details:** A table with columns for 'City' and 'City Description'.
- Postal Code Details:** Fields for 'Maker', 'Checker', 'Date Time', and 'Mod No'.

An 'Exit' button is located in the bottom right corner of the window.

You can specify the following details:

Country

Specify the code of the country for which you want to maintain the province, city and postal codes. The adjoining option list displays all valid country codes maintained. Select the appropriate one.

Description

System displays the brief description about the selected country.

Province/Region Details

Province/Region Code

Specify the province/region of the selected country that you want to maintain in the system.

Province/Region Description

You can briefly describe the specified province/region.

District Details

District

Specify the district of the selected country and specified province/region that you want to maintain in the system.

District Description

Briefly describe the specified district.

City Details

City

Specify the city name of the selected country, specified province/region and specified district that you want to maintain in the system.

City Description

You can briefly describe the specified city.

Postal Code Details

Postal Code

Specify the postal code of the selected city that you want to maintain in the system.

2.5.6 Maintaining Province, City and Postal Code Summary Details

You can view summary details of the province/region, district, city and postal code using 'Province City Maintenance' screen. You can invoke this screen by typing 'STSPRCTY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

	Authorization Status	Record Status	Country
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			

You can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Record Status
- Country

2.5.7 Maintaining Customer Sector Details

You can maintain the sector details for the customer using 'Customer Sector Maintenance' screen. You can invoke this screen by typing 'STDCUSST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details:

Sector Code

Specify the unique code to identify the sector level. The length of this code can be used to determine till what level the sector is defined.

Sector Level 1 to 5

Specify the sector levels here.

Sector GL Node

Specify the sector GL node from the adjoining option list.

Sector Province Node

Specify the Sector Province Node from the adjoining option list.

Leaf Sector

Check this box to indicate that there is no next level sector for this sector code. This is the final level sector.

2.5.8 Maintaining CNAE/CNO Code

You can maintain the CNAE (National Activity Code) or CNO (National Occupational Code) using 'CNAE/CNO Code Maintenance' screen. You can invoke this screen by typing 'STDCNOCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

CNAE CNO Code maintenance

CNAE CNO Type *

Code *

Description *

Maker Date Time:

Checker Date Time:

Cancel

You can specify the following details:

CNAE/CNO Type

Specify whether you want to maintain CNAE/CNO code from the adjoining drop-down list.

Code

Specify the code for the selected CNAE/CNO type.

Description

You can describe the selected CNAE/CNO code.

2.5.9 Maintaining CNAE, Sector Code and Customer Type

You can maintain the CNAE (National Activity Code), sector code and customer type using 'CNAE Sector Customer Type Maintenance' screen. You can invoke this screen by typing 'STDCNSCT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details:

Unique Code

Specify the unique code here.

CNAE Code

Specify the CNAE (National Activity) code from the adjoining option list.

Sector Code

Specify the sector code from the adjoining option list.

Customer Type

Specify the type of customer. You can select any one of the following:

- Individual
- Corporate
- Bank

2.5.10 Maintaining Economic Group Code

You can generate the economic group code using 'Economic Group Code Maintenance' screen. You can invoke this screen by typing 'STDGCMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Economic Group Code

Click 'New' button to generate the economic group code. Four characters of bank code and eighteen characters of sequential code compose the twenty two characters of economic group code.

Group Description

Specify the economic group code description.



System will not allow you to close the economic group codes that are linked to the active customers.

2.5.11 Maintaining External Bank Details

You can maintain external financial institution details (External Bank Code & External branch code) using the 'External Bank Maintenance' screen. Invoke this screen by typing 'STDEXTBD' in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

External bank details' maintenance is done for the Spain banks. Based on this maintenance, system validates the external bank account during the transaction.

Bank Code

Specify the bank code.

Bank Description

Specify a brief description of the external bank here.

Branch Code

Specify the branch code of the above-mentioned external bank.



On CCC validation, the system checks if the branch code used in the account is an active branch code.

Branch Description

Specify a brief description on the branch.

Status

Select the status from the adjoining drop down list. The options are:

- Active – If the mentioned branch is active
- Closed– If the mentioned branch is closed, the same can be activated at any time.

Effective Date

The system defaults the current application date as effective date.

2.5.12 Viewing External Bank Details

You can view the external bank details in the external bank summary screen. You can invoke this screen by typing 'STSEXTBD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "External Bank Summary". At the top, there are two dropdown menus: "Authorization Status" and "Record Status". Below them is a "Bank Code" input field with a search icon. A search bar contains "Search" and "Advanced Search" buttons, followed by "Refresh" and "Reset" buttons. Below the search bar is a table with columns for "Authorization Status", "Record Status", and "Bank Code". The table is currently empty. The interface includes a "Records per page" dropdown set to 15, a "1 Of 1" indicator, and an "Exit" button at the bottom right.

You can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Record Status
- Bank Code

2.5.13 Maintaining Waiver for Customer Tax Group

You can maintain waiver related information for Customer Tax Group – Tax Category combination. Invoke this screen by typing 'STDTAXWV' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a window titled "Tax Waiver Maintenance". It contains the following fields:

- Customer Group * (with a description field below)
- Customer Number * (with a description field below)
- Tax Category * (with a description field below)
- Tax Currency * (with a description field below)
- Product Or Account Class * (with a description field below)
- From Date * (with a description field below)
- To Date (with a description field below)
- Waiver Percentage (with a description field below)

At the bottom, there is a "Fields" section with the following options:

- Input By
- Authorized By
- Date Time
- Date Time
- Modification Number
- Authorized
- Open
- Exit button

Customer Group

You need to specify the Customer Group for which you wish to maintain Tax waiver. Select a customer group from the option list provided.

Customer Number

All customers who have been maintained under the selected customer tax group will appear for selection. If the maintenance is applicable to all customers, select 'All' as customer number. If no maintenance is done, then there will be no tax waiver at the customer level.

Tax Category

You need to specify a tax category for which you wish to main tax waiver

Tax Currency

You need to specify the currency in which the tax waiver should be defined. Select 'All,' if you wish to define tax waiver for all currencies

Product Or Account Class

You need to specify the Product/Account Class for which the tax waiver is being defined. All account classes and all LD/MM products will be available for selection. You may also select 'ALL' in which case the tax waiver would be applicable to all products and account classes.

From Date and To Date

You need to specify the date from which the particular waiver rule is applicable. The To Date is the date up to which the waiver rule is effective.

The To Date should be greater than or equal to the From Date. The To Date field can also be left blank which would indicate that the maintenance is open-ended.



System updates To Date of all records having To Date NULL with new tax cycle's start date - 1 and inserts a new record with From Date as new tax cycle's start date and To Date as NULL at the time of tax cycle update.

Waiver %

Specify the tax waiver in terms of percentage, which should be made applicable for the period defined. The value you enter should be > 0 and < = 100.

2.5.13.1 Pick-up Order for Waiver Rule

The following table gives the waiver rule pick up order:

Customer Group	Customer No	Tax Category	Currency	Product/Account Class
Specific	Specific	Specific	Specific	Specific
Specific	Specific	Specific	Specific	ALL
Specific	Specific	Specific	ALL	Specific
Specific	Specific	Specific	ALL	ALL
Specific	ALL	Specific	Specific	Specific
Specific	ALL	Specific	Specific	ALL
Specific	ALL	Specific	ALL	Specific
Specific	ALL	Specific	ALL	ALL

Thus for a specific customer in the group, the rule is relaxed for the product first and then for the currency. If no rule is available for selection, then the same process will be repeated where customer number is 'ALL' for the customer group.

When you select the 'New' option the system disables To Date and arrives at To Date based on following conditions:

Case 1 - From Date is within current tax cycle:

While maintaining a new record, system checks if there are any record with From Date greater than or From Date less than From Date of the record being maintained. The system performs the following actions accordingly:

- If there are no such records, system will update To Date as NULL and disables it.
- If there is a record with From Date less than From Date of the record being maintained and it is within the current tax cycle, during authorization, system updates To Date for immediate previous record to From Date of the record being authorized -1.
- If there is a record with From Date greater than From Date of the record being maintained and it is within the current tax cycle, system defaults To Date as (From Date of the record found – 1) and disables it when you save the record.

Case 2 - From Date is a back date and less than current tax cycle start date:

While maintaining a new record, system checks if there are any record with From Date greater than or From Date less than From Date of the record being maintained. The system performs the following actions accordingly:

- If there are no such records, system will find out the tax cycle using From Date and default To Date of the record with end date of the tax cycle and also inserts a record with same limit amount for the current tax cycle.
- If there is a record with From Date greater than From Date of the record being maintained, system will default To Date (From Date of the record found – 1) and disables it when you save the record.
- If there is a record with From Date less than From Date of the record being maintained, during authorization, system will update To Date for immediate previous record to From Date of the record being authorized -1.
- If a new record is opened with backdated From Date, the system will check if From Date is within the current tax cycle and displays an override message if the same is not within the current tax cycle.



For the backdated modification or a new record opened, the From Date cannot be lesser than the current tax cycle start date. In such cases, system displays an override message if the From Date is less than the current tax cycle start date.

2.5.14 Maintaining Tax Allowance Limit for Customers

You can maintain tax-free allowance limit at the Customer level. Invoke this screen by typing 'STDCULMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Customer Tax Allowance Maintenance

Customer Tax Group * _____
Description _____
Customer Number * _____
Customer Name _____
Tax Category * _____
Description _____
From Date * _____
To Date _____
Limit Currency * _____
Limit Amount * _____
Remarks _____

Fields

Input By	Date Time	Modification Number	<input type="checkbox"/> Authorized
Authorized By	Date Time		<input type="checkbox"/> Open

Exit

Customer Group

You need to specify the tax group of the customer for whom you wish to define tax-free allowance limit. Select from the option list provided.

Customer Number


You need to specify the customer number for which you wish to define tax free allowance limit. Only customers belonging to the selected tax group will be available for selection. You may also select the 'All' option. This is indicative of all customers for the selected Tax Group.

Tax Category

You need to specify the tax category for which you wish to define tax free allowance limit. Select from the option list provided.

From and To Date

You need to specify the date from which the tax-free allowance limit is effective, as well as the date up to which this limit is applicable. The To Date should be greater than or equal to the From Date. The To Date field can also be left blank which would indicate that the maintenance is open-ended.

 System updates To Date of all records having To Date NULL with new tax cycle's start date - 1 and inserts a new record with From Date as new tax cycle's start date and To Date as NULL at the time of tax cycle update.

Limit Currency

You need to specify the currency in which the free allowance limit is being defined

Limit Amount

You need to specify the maximum waiver for the taxable amount (Basis Amount) for the customer for each tax cycle if the End Date overlaps tax cycles or for a particular tax cycle if the period falls within a specific tax cycle.

Remarks

You can specify any remarks you think necessary for the tax limit you have defined. This will be in free format text.



The system disallows the 'Close' and 'Re-open' operations for the maintenance.

When you use the 'Unlock' option for an existing tax-free allowance limit, system checks if the utilization for the tax cycle is more than the limit amount. It uses 'From Date' to get the tax cycle and then finds out the utilization amount for that tax cycle between 'From and To Dates'. If the utilization amount is more than limit amount of the record, then system displays an error message.

When you use the 'New' option, the system disables the date field and arrives at 'To Date' based on following conditions:

Case 1 - From Date is within current tax cycle

While maintaining a new record, system checks if there is any record with From Date greater than or less than the From Date record being maintained. The system performs the following actions accordingly:

- If there are no such records, system will update To Date as NULL and disables it.
- If there is a record with From Date less than From Date of the record being maintained and it is within the current tax cycle, then system will check the utilized amount for the current tax cycle and compare the same with the limit amount of the record being maintained. If the limit amount is less than the utilized amount, system displays an error message, if limit amount is greater than or equal to utilized amount, then it allows maintaining the record.
- If the utilized amount > limit amount for immediate previous record in the same tax cycle, then system displays an override message.
- During authorization, the system updates To Date for immediate previous record to From Date of the record being authorized -1.
- If there is a record with From Date greater than From Date of the record being maintained and it is within the current tax cycle, system will default the To Date (From Date of the record found – 1) and disables it when you save the record. It also checks if the limit amount is > than least limit amount for the records having From Date greater than From Date of the record being maintained for the same tax cycle. If yes, system displays an error message.

Case 2 - From Date is a back date and less than current tax cycle start date

While maintaining a new record, system checks if there is any record with From Date greater than or From Date less than the From Date of the record being maintained. The system performs the following actions accordingly:

- If there are no such records, system finds out the tax cycle using From Date and default To Date of the record with end date of the tax cycle and inserts a record with same limit amount for the current tax cycle.
- If there is a record with From Date greater than From Date of the record being maintained, system will default To Date as (From Date of the record found – 1) and disables it when you save the record. It also checks if the limit amount is > than least limit amount for the records having From Date greater than From Date of the record being maintained for the same tax cycle. If yes, system displays an error message.
- If there is a record with From Date less than From Date of the record being maintained, system will check the utilized amount for the tax cycle and compare the same with the limit amount of the record being maintained. If limit amount is less than utilized amount, system will display error message. If limit amount is greater than or equal to utilized amount, system will allow maintaining the record.
- If the utilized amount > limit amount for immediate previous record in the same tax cycle, then the system displays an override message.
- During authorization, system updates To Date for immediate previous record to From Date of the record being authorized -1.
- If a new record is opened with backdated From Date, system will check if From Date is within the current tax cycle and displays an override message if the same is not within the current tax cycle.



Note the following:

- From date cannot be back dated
- When a new record is created, system will check if already a church tax declaration record is present for the same customer with To Date as null. If such a previous record is present, previous record's to date will be updated as the new record's from date – 1.
- From date of the current record getting created should be greater than the end date of latest previous record (if available) for the same customer
- Church tax declaration record will be allowed for amendment. Only the end date will be allowed to be updated. End date can be updated only if the current value of end date is blank.
- For the backdated modification or a new record opened, the From Date cannot be lesser than the current year Start date. In such cases, system displays an override message if the From Date is less than the current year start date.

Example

Assume the following:

- Current Tax Cycle - TAXCY2
- Start date - 01/04/2010
- End date - 30/06/2010,
- Previous Tax Cycle - TAXCY1
- Start Date - 01/01/2010
- End Date - 31/03/2010

Case 1: From Date within the Current Cycle

- New Record
- From Date - 01/06/2010
- Limit Amount - 1500 USD

From Date Less than the New From Date

Existing Record

- From Date - 01/04/2010
- Limit amount - 3000 USD
- Utilized Amount(TAXCY2) - 2000 USD

Since Limit Amount < Utilized Amount i.e. 1500USD < 2000 USD, system displays an error message.

Existing Record

- From Date - 01/04/2010
- Limit amount - 3000 USD
- Utilized Amount(TAXCY2) - 1000 USD

Since Limit Amount > Utilized Amount i.e., 1500USD > 1000 USD, system creates a new record and updates the To Date of the previous record to 31/05/2010.

From Date Greater than the New From Date

Existing Record

- From Date - 15/06/2010
- Limit amount - 2000 USD

Since New Limit Amount < existing least Limit Amount i.e., 1500 USD < 2000 USD, system creates a new record and defaults the To Date as 'From Date' of existing record -1 i.e., 14/06/2010.

Existing Record

- From Date - 15/06/2010
- Limit amount - 1000 USD

Since the New Limit Amount > Least Limit Amount i.e., 1500 USD > 1000 USD, system displays error message.



If there is no record maintained greater than or less than 01/06/2010, system creates new record and defaults the 'To Date' as null.

Case 2: From Date backdated and less than the Current cycle Start Date

New Record

- From Date - 01/03/2010
- Limit Amount - 1500 USD

From Date Less than the New From Date

Existing Record

- From Date - 15/02/2010
- Limit Amount - 3000 USD
- Utilized Amount(TAXCY1) - 2000 USD

Since Limit Amount < Utilized Amount i.e., 1500USD < 2000 USD, system displays an error message.

Existing Record

- From Date - 15/02/2010
- Limit amount - 1000 USD
- Utilized Amount(TAXCY1) - 1500 USD

Since Limit Amount >= Utilized Amount i.e. 1500USD >= 1500 USD, system displays an override message and allow to create a record. It also updates the To Date of the previous record with 28/02/2010.

From Date Greater than New From Date

Existing Record


- From Date - 10/03/2010
- Limit amount - 2000 USD

Since New Limit Amount < existing Least Limit Amount i.e., 1500 USD < 2000 USD, system creates a new record and defaults the To Date as 'From Date' of existing record -1 i.e., 09/03/2010.

Existing Record

- From Date - 10/03/2010
- Limit amount - 1000 USD

Since the New Limit Amount > Least Limit Amount i.e., 1500 USD > 1000 USD, system displays an error message.

 If there is no record maintained greater than or less than 01/03/2010, system creates a new record and defaults the 'To Date' as 31/03/2010.

2.5.14.1 Deriving Tax Free Allowance Limit


The following table will be used to derive the tax-free allowance limit:

Customer Tax Group	Tax Category	Customer No
Specific	Specific	Specific
Specific	Specific	ALL

2.5.15 Maintaining Church Tax Declaration for a Customer

You can maintain the church tax for a customer in the 'Church Tax Declaration' screen. You can invoke this screen by typing 'STDCHTAX' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is given below:



Customer Church Tax Declaration

Customer Number * _____

Church Tax Start Date * _____

Church Tax End Date _____

Change Log

Maker	Date Time:	Mod No
Checker	Date Time:	Record Status
		Authorization Status

Exit

In this screen you can maintain the following details:

Customer Number

Specify the customer number for which the church tax has to be collected. Alternatively, you can also select the customer code from the adjoining option list.

Church Tax Start Date

Specify the date from which the church tax for a customer is applicable. Alternatively, you can also select the date from the calendar button.

When you create a new record, the system will check if a church tax declaration is already present for the same customer with To Date as null. If such a previous record is present, the previous record's To Date will be updated as the new record's From Date - 1. From date of the current record getting created should be greater than the end date of latest previous record (if available) for the same customer.

Church Tax End Date

Specify the date till when the church tax declaration is applicable. The Effective to date can also be left blank which indicates that the maintenance is open-ended.

2.5.15.1 Processing Church Tax

An SDE basis, 'Church tax' is used to derive the church tax percentage applicable for a customer. This SDE is used in the IC rule to calculate and apply the church tax.

For more details on SDEs, refer to 'Maintaining System Data Elements' section in the Interests and Charges User Manual.

An IC calculation is forced when one of the following happens:

When the customer's location is changed

When a new church tax declaration is created / existing church tax declaration modified for a customer

When IC calculation happens during EOD, system will first find out if there is a valid church tax declaration record for the current liquidation cycle. If there no such record, system will prepare a single SDE base record with date as liquidation cycle start date and basis amount as 0.

If church tax declaration record is present, SDE base records will be prepared based on the church tax declaration start date, end date and the church tax percentage maintained for the customer's location.

Change of customer's location within a liquidation cycle will not be tracked. Only the latest location of the customer in a liquidation cycle will be considered for the whole liquidation cycle

The following example illustrates how SDE base records are formed:

Example

Assume that the liquidation cycle is from 01-Jan-2008 to 31-Mar-2008.

Scenario 1

Church tax declaration record has Effective from date as 3rd Feb, 2008, with no Effective to date. The church tax percentage maintained for the customer's location is 8%.

In this scenario, the SDE record base is formed as follows:

Basis Date	Basis Figure
01-Jan-2008	0
03-Feb-2008	8

Scenario 2

On 15th Feb, 2008, the customer's location is changed and the tax percentage for the changed location is 9%.

During 15th Feb, 2008 EOD, the SDE record base is formed as follows:

Basis Date	Basis Figure
01-Jan-2008	0
03-Feb-2008	9

Scenario 3

On 14th March, 2008, customer gives a declaration to end the church tax. In this case, the 'Effective to date' in the 'Church tax declaration' screen will be updated as 14th March, 2008.

During 14th March, 2008 EOD, the SDE base record is formed as follows:

Basis Date	Basis Figure
01-Jan-2008	0
03-Feb-2008	9
14-Mar-2008	0

Scenario 4

Liquidation cycle becomes 1st Apr, 2008 to 30th June, 2008.

Customer does not give any further new church tax declaration. In this case, for this liquidation cycle, no church tax will be applied. The SDE base record is formed as follows:


Basis Date	Basis Figure
-------------------	---------------------

01-Apr-2008	0
-------------	---

2.5.15.2 Viewing Church Tax Declaration Details

You can view the details maintained for church tax declaration in the 'Church Tax Declaration Summary' screen. You can invoke this screen by typing 'STSCHTAX' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is given below:



2.5.16 Amendment Maintenance

To recall, you need to identify the fields that can be amended by an external system, say, a Siebel CRM application.

Every amendment request coming from such a system has the following data:

- Service Name: – This is a broad level grouping of similar operations within a module in Oracle FLEXCUBE. The service names are published by Oracle FLEXCUBE. As an example, you can consider FCUBSCustomerAccountService. This service is exposed by the FCUBS Interface Gateway to do a permissible operation on a customer account.

- **Operation Name:-** This is the name of the operation that the external system wishes to perform within the service. These operations names are published by Oracle FLEXCUBE. As an example, you can consider ModifyCustomer, which is for modification of a customer.
- **External Operation Name:-** This is the specific area of operation that an external system is performing on its side within the broad context of the Oracle FLEXCUBE's amendment. In an external system, if the personal details of a customer are changed, this has a unique name by which it is identified within Oracle FLEXCUBE. Similarly, if the limits related details of a customer are modified, it also has a unique name.

It is through the 'Amendment Maintenance' screen that you maintain a set of amendable fields, which can amend in Oracle FLEXCUBE whenever a request for the same will be send from an external system. Based on this maintenance, the amendment request is addressed by Oracle FLEXCUBE. Invoke this screen by typing 'STDAMDMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

External System

Select the relevant external system. Based on the maintenance here, only the fields that are selected as amendable can be modified if a request comes from the chosen external system.



The maintenance pertaining to external systems is factory shipped for your bank.

Source Operation

The free format text (without spaces) which identifies the amendment you are doing. This is mandatory

Service Name

The relevant service name, this is a broad level grouping of similar operations within a module in Oracle FLEXCUBE. The service names are published by Oracle FLEXCUBE.



The maintenance pertaining to service names is factory shipped for your bank

Operation Code

The relevant operation code. This is the operation that the external system wishes to perform within the selected service. The operation names are published by Oracle FLEXCUBE. As an example, you can take 'Modify Customer', which is for modification of a customer record. Each operation under different service names is identified by a unique code.



The maintenance pertaining to operation codes is factory shipped for your bank.

Element Name

The relevant field, that can be amended.

On choosing a field, its type gets defaulted in the 'Element Type' field. It can be one of the following:

Element - These ultimate leaf elements occur directly under the parent node of an amendment request. It is displayed as an 'F'.

Node - This is a child node of a main amendment request. It has its own child elements and nodes. It is displayed as an 'N'.

2.5.16.1 Processing for Element

If such a field is sent as part of an amendment request and is maintained in this screen, then a value for that field is expected when the request comes in from the external system. In case no value is passed, Oracle FLEXCUBE updates the field to a null value. If any value is passed, the same is taken as the new value for that field.

2.5.16.2 Processing for Node

If the field selected is of type 'Node', a check box called 'Full Amend' gets enabled. This pertains to only the 'Node' type elements and not for the 'Element' type. Checking against 'Full Amend' indicates that the external system always has to send the complete set of records for the subsystem whether amendment of that node is done or not. By default, the 'Full Amend' field is unchecked.

In case 'Full Amend' is checked, system overwrites the details during amendment even if all field values pertaining to a particular subsystem are not sent. In such a scenario, Oracle FLEXCUBE updates the fields with the available data sent by the external system during an amendment. If no records are passed for a subsystem during amendment, the complete subsystem is set to a NULL value.

In case the flag 'Full Amend' is not checked, system copies the details from the previous version and then makes changes to the existing records based on values sent by the external system. If any new record comes as part of an amendment record, the system inserts the same. If the upload table is empty during amendment, the system retains the data of the previous version.

The following points are noteworthy within the context of any amendment maintenance:

- Only subsystems of a contract or maintenance qualify for being a 'Node' type. The master record is never included as part of a 'Node' type and its fields alone are labeled as 'Elements'.
- This maintenance is required for supporting amendment requests from any external system. If no maintenance is done for a particular external system and source operation, the amendment fails.
- The list of fields (available in the LOV) that can be amended for a particular Service and Operation combination is factory shipped for your bank. You can add or remove fields based on your requirement.


To delete an element from the list of amendable fields, you can use Delete icon. To add an element to the same, you can use the Add icon.

2.5.17 Specifying Details for Generation of MT920

The SWIFT message MT920 is a transaction message requesting latest information available for the particular account. The request will be to transmit account customer statement message (MT940) or Balance report (MT941) or Interim statement (MT942) or a customer summary statement (MT950).

Check the MT920 checkbox only if the customer is eligible for requesting MT920 swift messages for transaction details. In the Customer Maintenance screen, you can indicate if a customer is eligible for requesting MT920 messages. To do this, you need to click MT920 button in the 'Customer Information Maintenance' screen and invoke the 'MT920' screen.

The screen is shown below:



Here you can enter the following details:

BIC Code

Enter or select valid BIC from the option list. This BIC Code information provided by you is crucial.

Account Number

Once you specify the BIC code, you can enter the relevant Account Number adjacent to it. Click 'Ok' to save the details entered here.

2.5.17.1 Defining Customer Category

You may wish to classify the customers of your bank into certain broad categories/groups. For instance, all financial institutions who are your bank's customer can be classified into a single common group head called Financial Institutions. Similarly, you can have a category called banks, individuals, etc.

The classification of customers into categories can be used for retrieving financial information by customer category; for generating reports on queries; and restricting access of a customer to a product in the front - end modules, for instance, Funds Transfer, Data Entry, etc. You may also retrieve financial information by customer category.

The categories are maintained in the 'Customer Categories' screen and are maintained at the bank level by your Head Office. The customers are allocated different categories maintained in this screen in the 'Customer Information Maintenance' screen.

2.5.18 Invoking Customer Category Screen

To invoke the 'Customer Category Maintenance' screen, type 'STDCSCAT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screen is shown below:

Customer Category Maintenance

Customer Category *

Category Id *

Description

Maintain Customer Log

Sub category

Description

Fields

Maker Date Time:

Checker Date Time:

Cancel

In this screen, you maintain the following:

- Name of the customer category
- Category ID
- Description of the category
- Customer log
- Sub Category
- Description of the Sub Category

2.5.19 Creating Customer Categories

To create customer categories the following parameters need to be maintained:

Customer Category

In this category, you can classify customers of your bank.

When you are creating a product – be it in a loan, a deposit, a placement, a swap foreign exchange deal, or a funds transfer, you may want to restrict access to the product to a set of customers.

For this, the customers are classified into broad categories, the code of which is input against this field. A category consists of a group of like customers. For instance, if you create a category called, Financial Institutions - all financial institutions who are customers of your bank will come under this category. Likewise, all customers of your bank belong to some category.

It should be noted that at the product level, specifications made for a customer overrides the specifications made for the category. For example, if all financial institutions are allowed access to a particular product; you have the option of restricting the access of one or a few individual financial institutions to his product.

Input the customer category you want to create using not more than 10 characters, alphanumeric. The category code should be unique. For Example, for Financial Institutions category, you can input the code as FinIn.

Description

This is the description of the customer category input above. Enter the description of the customer category input above in not more than 35 character, alphanumeric. Taking the above example, you can enter financial institutions

Category ID

Specify the category ID in not more than 3 numeric characters.

This is a unique identifier for each customer category. If you specify a Category ID that is already assigned to another customer category, then, on save the system displays the following error message:

'Category ID already used'



The SDE, 'CUST_CATEGORY', displays the customer category. You can also use this SDE for IC product maintenance.

Maintain Customer Log

Check this box to indicate that customer information has to be tracked.

Sub Category

Select the sub category for the category Id maintained, from the adjoining option list. This list contains all the valid subcategories maintained in the system as follows. Choose the appropriate one.

- Individual Persons
- Private Entrepreneurs
- Private Notaries and Lawyers
- Legal Entities
- Banks

- Legal Entities (Temporary Register)
- Legal Entities (For Statutory Fund Formation)
- Individuals Not Customers
- Private Entrepreneurs Not Customers
- Legal Entities Not Customers
- Banks-Counterparties
- Others

If the category you want to map is not available in the defined list, use 'Others' to map it.

The customer unique identifier validation is done on the basis of following parameters:

- The sub category
- The Identification Code
- The option selected for 'Resident/Non-Resident'.

The B3 certificate number will have to be captured as the unique identifier in Documents tab.

Description

Enter the description of the customer sub category input above.

After you have made the inputs, click the Save icon to save your record. A record is not used until a user other than you authorizes it.

To authorize, click 'Authorize' button in the toolbar. If any modifications were made, the old and the new values will be displayed. After which an alert box will indicate that the change will be authorized. You will be prompted to conform. To confirm, click 'OK' button. The change will be authorized. Your User ID, the date and time at which the authorization was made will be displayed in the Auth ID and date and time fields at the bottom of the screen. The status of the record will be updated to 'Authorized'. If you do not want to authorize the change then click Exit icon, you will be returned to the screen from where you invoked the authorization function. Remember that you cannot authorize an event that you have input. Only another user who has the requisite rights can authorize the event.

To exit, click Exit icon. You will return to the Application Browser.

2.5.20 Maintaining Customer Groups

To track your credit exposure to a group of customers you should:

- Create Customer Groups and assign credit limits to it
- Associate a customer with a group

2.5.21 Maintaining Limits for Customer Group

You can maintain Customer Groups and set up credit limits in the 'Customer Group Maintenance' screen. You can invoke this screen by typing 'STDGROUP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Group ID *	
Group Name	
Limit Currency	USD
Limit Amount	0

Input By: DOC4	Date Time	Modification Number	<input type="checkbox"/> Authorized
Authorized By	Date Time		<input checked="" type="checkbox"/> Open

Cancel

Group ID

You can assign a unique identification code to each customer group that you create. You can also enter the detailed name of the group. In the subsequent fields you can set up credit limits for the group.

While setting up a customer, you can indicate the group to which the customer is associated.

STOP It is important to note that in Oracle FLEXCUBE a customer group is different from a customer category. You create customer groups only to set up group limits and report credit utilization by the customers that belong to the group.

Limit Amount and Limit Currency

The limit amount indicates the maximum amount that customers under a group can utilize. You can indicate the currency in which the limit amount is expressed.

The outstanding of all customers associated with a group is aggregated to arrive at the credit utilization of the group. This includes issuer risk arising out of securities issued by your customers and held by the bank.

2.5.22 Associating Customer Account with Group

While maintaining details of a customer account, you can associate it with a customer group. A customer can be associated with several customer groups. Click 'Group' button from the 'Customer Maintenance' screen to associate the account with a customer group.

The screen is shown below:

The screenshot shows a software window titled "Customer Group". It is divided into two main sections. The top section, "Group Details", contains a table with two columns: "Group ID" and "Relation". The bottom section, "Partnership Details", contains a table with three columns: "Share Holder Id", "Shareholders Name", and "Holding Percentage". Both tables are currently empty. The interface includes navigation controls such as "Go to Page" and "1 of 1" in both sections. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

2.5.22.1 Specifying Group Details

To associate a customer account with a group, select Group ID from the option list. The option list will contain a list of all the customer groups that you maintained in the 'Customer Group Maintenance' screen. To add a group to the list, click Add icon and select a Group ID from the option list. To remove a group from the list, highlight the Group ID and click Delete icon.

For each group that you associate with a customer, you can specify the relationship that the customer shares with the group.

2.5.22.2 Specifying Shareholding Details

You can maintain percentages of shareholding of your individual customers in a corporate entity, which is also your customer. When maintaining customer details of the corporate entity, you can capture names and shareholding percentages of your individual customers who hold shares in the corporate entity.

When you query in Oracle FLEXCUBE, for limits utilizations for any such individual customer, your exposure to the corporate entities is also displayed.

Example

Silas Marner and Keith Butler are individual customers and they have contracts and accounts with your bank. Parivallal Express Limited, Gem Granites Limited and Assorted Chemicals Limited are your corporate customers.

Silas Marner has a shareholding in Parivallal Express Limited and Gem Granites Limited. Keith Butler has a shareholding in Gem Granites Limited and Assorted Chemicals Limited.

While querying limits for Silas Marner, your exposure to Parivallal Express Limited and Gem Granites Limited is displayed along with your exposure to Silas Marner.

You can choose to drill down any of the exposures to see the specific line details and contracts. However, if you query for exposure to Parivallal Express Limited or Gem Granites Limited your exposure to Silas Marner is not displayed.

Click 'Ok' button to save the details that you specified. Click the windows Close icon to exit the screen without saving the entries that you made.

2.5.23 Maintaining Type of Relationships

You can maintain the different types of relationships that can exist between customers of your bank in the 'Relation Maintenance' screen. Invoke this screen by typing 'CSDRELMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Relationship Maintenance". It features three input fields: "Relationship *", "Category *", and "Description". Below these fields is a "Fields" section containing a grid of fields: "Input By DOC4", "Date Time", "Modification Number", "Authorized" (checkbox), "Authorized By", "Date Time", "Open" (checkbox), and a "Cancel" button.

Specify the following details in this screen:

- **Relation** – Define the type of relationship in this field. You can use a maximum of 20 alphanumeric characters to define a relationship
- **Category** – Select the category from the drop down list to define the nature of the relationship with the customer. The available options are:
 - Customer to Customer
 - Customer to Account
 - Customer to Contract
- **Description** – Provide a brief description of the relationship being maintained. This will further help you in identifying the relationship. You can enter a maximum of 35 alphanumeric characters in this field.

The types of relationships defined in this screen will become available for linking two customers, only upon authorization of the details maintained.

2.5.24 Relationships for Customers

A customer of your bank can have relationships with any other customer of your bank. Also, a customer of your bank could be a joint account holder with another customer of your bank. You can capture these details when you set up the CIF or customer account.

For linking a customer account, you need to specify details of the relationship for the account. Click the 'Linked Entities' button in the 'Customer Maintenance' (CIF) screen. The 'Linked Entities' screen is displayed.

Customer *	Description	Relations *	Include Relationship
<input type="checkbox"/> 000000001	RELIANCE	FRIENDS	<input checked="" type="checkbox"/>
<input checked="" type="checkbox"/> 000000118	JPMorgan Chase Bank,	PRIMARY	<input checked="" type="checkbox"/>

You must specify a customer code, provide a description, and ID for the relationship.

Customer

Select the customer code from the option list. You can link any number of customers to the primary holder (the customer for whom you are capturing the CIF details) through this screen by establishing a relationship between the two customers.

Description

In this field, the system displays the name of customer that you have selected in the previous field. You cannot change this description.

Relationship

You have to choose a relationship code to establish a relationship between the customer being selected and the customer (primary holder) you are maintaining.

By default, the system will select the customer of the account as the Primary Holder. This is a pre-shipped relationship and you will not be allowed to change the relationship.

Include Relationship

When you specify the relationship of the customer you can also choose to default the same preference to the customer account maintenance for the specified customer by checking the 'Include Relationship' box.

Also, specifying this option at the customer maintenance level will inherit all the properties of the customer relationship to the counterparty of the loan/deposit during the contract input.

2.5.25 Maintaining Risk Category for Customers

In order to support risk-weighted risk tracking, you will have to maintain risk details for Customers.


You can maintain different Risk Categories for Customers in the 'Risk Category Maintenance' screen. You can invoke this screen by typing 'STDRKMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields	
Input By	DOC4
Date Time	
Modification Number	
Authorized	<input type="checkbox"/>
Authorized By	
Date Time	
Open	<input checked="" type="checkbox"/>

Specify the following details in this screen:


- Risk Category – Define the type of Risk Category in this field
- Description – Provide a brief description of the Risk Category being maintained

The types of Risk Categories defined in this screen will be available for Liability maintenance of customers and Risk percent maintenance, only upon authorization of the details maintained.

 Risk Category is not a mandatory input during Customer Maintenance. Risk Category is applicable to the Customer and not to the Customer's Liability ID.

2.6 Maintaining Cheque Not Allowed Customer Details

You can upload the file that contains the list of customers who are not eligible for writing cheques in the 'Cheque Not Allowed Customer Upload' screen. You can invoke this screen by typing 'STDCQCIF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Specify the following:

File Name

Specify the file name that contains the list of customers who are not eligible for writing cheques. You should input the file name along with the full file path.

The file consists of the following details, delimited by a semi-colon:

- Customer ID
- Effective Start Date
- Effective End Date

The date is in the following format:

DD-MON-YYYY

The system validates to ensure that the start date is less than or equal to the end date as well as the start date is less than or equal to the branch date.

When you click 'Upload' button, the Effective Start Date, Effective End Date and Cheque Allowed status is updated for the customer in the 'Customer Maintenance' screen. If the start date is less than or equal to the branch date for any unused cheques, including certified cheques, the status is updated to 'Cancelled'.

2.7 Multiple Relationships

The credit facility granted to any customer is tracked against the Liability Number of the customer. You can also track the liability of a customer (child) against a different customer (parent). Thus, the liability number emphasizes only one kind of relationship, that of the parent with the child.

However, a customer of your bank can have relationships with other customers of your bank i.e. there is a possibility of one to many relationships between customers.

Oracle FLEXCUBE allows you to define different types of relationships that can exist between two customers. For eg: Business, Husband, Wife, and Partners etc. You can link two customers by specifying the relationship that exists between them. The advantage being that, when you generate the exposure report for a customer, it will display the total exposure of the bank to every customer linked to the liability in question as well as the exposure of every customer who is related to any customer within the liability. The example given at the end of this section will further illustrate this concept.

2.7.1 Maintaining Types of Relationships

You can maintain the different types of relationships that can exist between customers of your bank in the 'Relation Maintenance' screen. You can invoke this screen by typing 'STDRELMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields	
Input By	DOC4
Date Time	
Modification Number	
Authorized	<input type="checkbox"/>
Authorized By	
Date Time	
Open	<input checked="" type="checkbox"/>

Specify the following details in this screen:

- Relation – Define the type of relationship in this field. You can use a maximum of 20 alphanumeric characters to define a relationship
- Description – Provide a brief description of the relationship being maintained. This will further help you in identifying the relationship

The types of relationships defined in this screen will become available for linking two customers, only upon authorization of the details maintained

2.7.2 Maintaining Relationships between Customers

The 'Customer Linkage Maintenance' screen is used to maintain relationships between customers. In this screen, you can link two customers and specify the relationship that exists between them. You can invoke this screen by typing 'STDCUREL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Customer Linkage Maintenance

Customer1 * [dropdown arrow]

Customer Name [text field]

Customer2 * [dropdown arrow]

Customer Name [text field]

Relation * [dropdown arrow]

Fields

<input type="checkbox"/> Input By DOC4	<input type="checkbox"/> Date Time	<input type="checkbox"/> Modification Number	<input type="checkbox"/> Authorized
<input type="checkbox"/> Authorized By	<input type="checkbox"/> Date Time	<input checked="" type="checkbox"/> Open	<input type="button" value="Cancel"/>

Customer 1 and 2

You can select the names of the customers between whom a relationship is to be established. All authorized customers of your bank will be available in the option-lists provided.

Relation

Specify the type of relationship that exists between the selected customers (1 & 2). All authorized relation types maintained through the 'Relation Maintenance' screen will be available in the option list provided. You can select the appropriate name from this list.

This linkage of customers will be used for taking exposure report for the customer. If you maintain a linkage between Customer1 and Customer2, the system will automatically establish a linkage of Customer2 with Customer1. After you maintain a linkage between two customers, you are not allowed to change the customers involved in the linkage. However, you can alter the relationship that exists between them. Only one type of relationship can exist between any two customers. The following example will illustrate the manner in which you can maintain relationship details between customers and the need for the same.

Example

John Doe is customer of you bank. He is running a business named 'John Doe Building Contractors'. He is married to Jane Doe but is separated. He now lives with Mary Bloggs. In addition, he also has a partnership with Jack Black and another partnership with Joe Green. In order to establish a relationship between the above individuals, you have to maintain each individual as a customer in Oracle FLEXCUBE.

In the Customer Information Maintenance screen, set up the details for:

- John Doe
- John Doe Building Contractor
- Jane Doe
- Mary Bloggs
- Jack Black Builders
- Joe Green Builders

Since you can link loans to a single customer only, the following pairs should also be maintained as customers:

- John and Jane Doe
- John Doe and Mary Bloggs
- John Doe and Jack Black, Builders
- John Doe and Joe Green, Builders

The linkage between the above individuals will be as follows:

Customer 1	Customer 2
John Doe	John Doe Building Contractor
John Doe	John and Jane Doe
Jane Doe	John and Jane Doe
John Doe	John Doe and Mary Bloggs
Mary Bloggs	John Doe and Mary Bloggs
John Doe	John Doe and Jack Black, Builders
Jack Black, Builders	John Doe and Jack Black, Builders
John doe	John Doe and Joe Green, Builders
Joe Green, Builders	John Doe and Joe Green, Builders

Depending on the type of loan availed and the 'Customer' involved in it, the exposure report will display the accounts of the individuals as depicted in the table below:

Customer	Account	John Doe OR John Doe Builder	Jane Doe	Jack Black	Mary Bloggs	Joe Green
John Doe	Personal Car Loan	Y				
John Doe Building Contractor	Commercial Loan Current Account Equipment Lease	Y Y Y				
John and Jane Doe	Home Loan	Y	Y			
John Doe and Mary Bloggs	Home Loan	Y			Y	

Customer	Account	John Doe OR John Doe Builder	Jane Doe	Jack Black	Mary Bloggs	Joe Green
John Doe and Jack Black, Builders	Commercial Loan	Y		Y		
John Doe and Joe Green, Builders	Current Account Commercial Loan Bridging Loan	Y				
Jane Doe	Car Loan		Y			
Mary Bloggs	Current Account Term Loan				Y Y	
Jack Black – Builder	Current Account Commercial Loan			Y Y		
Joe Green, Builders	Current Account					Y

2.7.3 Maintaining Customer Groups

You can maintain customer groups for any of the following reasons:

- Tracking Exposure for loans as well as outstanding overdrafts in accounts of customers involving the group; in which case, it would comprise of either Corporate or Retail customers.
- Defining Group specific rules – in which case it would either be a Clearing or a Charge Group. Clearing Groups are built in order to derive the Value Date of outward clearing check transactions. Charge Groups are created in order to levy specific charges on customers belonging to the group.

You can set up such groups through the 'Group Code Maintenance' screen. Invoke this screen by typing 'STDGRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Group Code Maintenance' window. It has a title bar with a diamond icon and the text 'Group Code Maintenance'. The main area contains the following fields and controls:

- Group Code * (text input)
- Description (text input)
- Exposure Category (text input with a dropdown arrow)
- Group Status (text input)
- Since (text input with a calendar icon)
- Group Type (radio buttons):
 - Corporate (selected)
 - Retail
 - Charge
 - Clearing
 - Tax

At the bottom, there is a 'Fields' section with the following items:

- Input By: DOC4
- Date Time
- Modification Number
- Authorized (checkbox)
- Authorized By
- Date Time
- Open (checkbox)
- Cancel button

Group Type

You could use this section to indicate whether the customer group you are defining is:

- Corporate
- Retail
- Charge
- Clearing
- Tax

You can select the appropriate option.

Creating Customer Groups for Tracking Exposure

You may wish to track exposure due to loans issued to a group of customers as a whole, and assign the status of all loans issued to the group as the status of the loan with the worst status, among those issued to the group.

You may similarly wish to include the exposure due to outstanding overdraft in respect of a group of customer accounts as a whole, and assign the status of all customer accounts belonging to the group as the status of the customer account with the worst status among the accounts and loans belonging to the group.

When you set up a group for tracking exposure due to loans and customer accounts, you will need to specify the applicable exposure category.

The exposure category for a group is either derived from the logic maintained in the Exposure Type Category Linkage maintenance for the group type, or explicitly specified. If it is derived, it is displayed in this screen, by the End of Day batch program. The type of the group indicates the type of customers that belong to the group – retail or corporate. If no logic has been maintained in the Exposure Type Category Linkage for the group type, you can indicate the applicable exposure category for the group.

Group Status

All loans and overdraft accounts issued to customers in the group will be assigned the same status, which will be the status of the loan / overdraft account with the worst status among those issued to customers in the group. The Group/CIF and the loan contracts and overdraft accounts are all updated with this worst status if they have been marked for automatic status processing. The individual status for the accounts and loan contracts (apart from assigning the worst status) is also captured and displayed. In the 'Group Code Maintenance' screen and the 'CIF Maintenance' screen, the status for the group is displayed, as well as the date since which the status came into effect.

For details about loan status processing and provisioning, consult the Loans user manual.

Customer Group

When you maintain CIF details for customers, in the 'Customer Information Maintenance' screen, you can specify the customer group to which the customer belongs, for:

- Provisioning and status processing (Group Code). You must specify a group code defined for a group type that is the same as the customer type, for instance, if the customer is a retail customer, you must specify a group defined for retail customers
- Classifying the customer as a Clearing customer
- Categorizing the customer for levying charges at a customer group level
- Classifying the customer as a taxpayer. If you select this option, the Exposure Category field will be disabled

2.7.4 Capturing Customer Prefixes

While maintaining the CIF details, of an Individual customer you can capture the academic titles (like Prof., Dr., etc) of the customer along with the salutations (like Consulate, Senator, Chancellor, etc.)

Therefore, you must maintain the list of possible options for each of these academic titles and salutations referred to as 'prefixes' through the 'Customer Prefix Maintenance' screen.

You can invoke this screen by typing 'STDCUSPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software interface for 'Customer Prefix Maintenance'. At the top, there are two input fields: 'Branch Code *' with a dropdown arrow and 'Branch Name' with a help icon. Below these is a table titled 'Customer Prefix Details' with three columns: 'Prefix1', 'Prefix2', and 'Prefix3'. At the bottom of the window, there is a 'Fields' section with several input fields: 'Input By' (with value 'DOC4'), 'Date Time', 'Modification Number', 'Authorized By', and 'Date Time'. There are also two checkboxes: 'Authorized' (unchecked) and 'Open' (checked). A 'Cancel' button is located on the right side of the 'Fields' section.

The following details need to be captured:

- Branch code - This is the code of the branch for which the list of prefixes will be made available. The description associated with the branch is displayed in the adjacent field
- Prefix1 - This is the first prefix to appear in the Customer Name
- Prefix2 - This is the second prefix to appear in the Customer Name
- Prefix3 - This is the third prefix to appear in the Customer Name

While specifying the prefix in the customer in the CIF screen, a list of all the values maintained in this screen is displayed. You will also be allowed to key-in a prefix of your choice.

These details will be printed along with the receiver name in all messages sent to the customer. If the global tags for prefixes have been maintained in the advice, the System substitutes the tags with the respective prefixes maintained in the customer personal details of the receiver.



This feature is applicable only for individual customers where the media type is Mail.

2.7.5 Storing Authorized Variations of Customer's Name

In Oracle FLEXCUBE, you can indicate whether incoming Funds Transfers, Payments and Collections should be processed only after the customer's Account Number and Name correspond to the authorized variations of the customer's name. If you have enabled this as a preference in the 'FT Product Preference', and 'PC Product Category' screens, you will need to maintain the authorized customer name variations through the 'Customer Names' screen.

Invoke this screen by typing 'STDCIFNM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Customer Name Maintenance". At the top, there is a "Customer Number *" field with a dropdown arrow and a "Customer Name" text field. Below this is a "Customer Name Detail" section with a "Customer Name *" field. At the bottom, there is a "Fields" section with labels: "Input By DOC4", "Date Time", "Modification Number", "Authorized" (checkbox), "Authorized By", "Date Time", "Open" (checkbox), and a "Cancel" button.

In this screen, you have to capture valid customer names, which have to be associated with Customer Numbers maintained in Oracle FLEXCUBE.

Because of this maintenance, each time an incoming FT or PC contact is processed, the System validates the account number and name involved in the transaction with the authorized customer name. If the validation is successful, the customer name is added to the existing list and the contract is marked as authorized.

If the validation fails the contract is marked as unauthorized. Even during manual authorization of such contracts, an override is displayed asking whether the customer name needs to be added to the existing list. It will be added to the existing list on confirming the override.

2.7.6 Maintaining Float Days for Outward Clearing Customer Transactions

Float days applicable for arriving at the Credit Value Date for outward clearing customer transactions are defined through the 'Float Days Detailed' screen.

Invoke this screen by typing 'STDFLTDS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can define the float days for transactions involving a specific Clearing Bank, Branch, Product, Sector and Currency combination for:

- All customer groups and all customers within the groups
- A specific customer group and all customers within the group
- A specific customer group and a specific customer within the group

The System resolves the float days in the following order:

Branch Code	Product Code	Sector Code	Currency	Customer Group	Customer Number
Specific	Specific	Specific	Specific	Specific	Specific
Specific	Specific	Specific	Specific	Specific	ALL
Specific	Specific	Specific	Specific	ALL	ALL



The float days will be considered as Working Days or Calendar Days depending on your specification in the 'ARC Maintenance' screen.

2.7.7 Location Maintenance

In Oracle FLEXCUBE, you have a provision wherein you can maintain location codes. You do this through the 'Account Address Location Maintenance' screen. Invoke this screen by typing 'STDACLOC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields			
Input By: DOC4	Date Time	Modification Number	<input type="checkbox"/> Authorized
Authorized By	Date Time		<input checked="" type="checkbox"/> Open

Location

The relevant location code. This pertains to a particular area in a country. It cannot be more than 15 characters

Description

A short description to the location code

Default

If the location code is to be maintained as a default location code, the same could be specified here by checking against this option. Only one location can be marked as a default location.

The following points are noteworthy:


- Once you save the above maintenance, Oracle FLEXCUBE checks for duplicate location codes. To recall, existing location codes are maintained through the 'Location Codes Maintenance' screen. If a match is found, system throws up an error.
- This maintenance is applicable only for account level address maintenances and not for address maintenances done at the customer level

2.7.8 Specifying the Dictionary Details

An uploaded parameter value provided in the form of a dictionary needs to be assigned to a customer ID (CIF) in the system for statistical reporting.


A bank need to undergo statistical reporting to ensure it is following the directives as regulated by the central/governing bank which is the NBU. In order to abide by the regulations of the NBU and receive approval of rules for statistical reporting, the parameter values provided by the NBU are assigned to the customer ID (CIF) in Oracle FLEXCUBE.

The DBF file provided by the NBU is uploaded through the 'Upload Analytical' screen. You can invoke this screen by typing 'CVDUPLAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



For details on 'Upload Analytical' screen, refer to the section 'Uploading Analytical Parameter Details' in this chapter.

Click on the 'Dictionary' button to invoke the 'Dictionary Details' Screen.



Dictionary

Specify the name of the dictionary. The option list displays all valid dictionaries maintained in the 'Dictionary Maintenance' screen.

Field Name

Select the name of the field assigned the parameter value from the uploaded dictionary. The option list displays all valid fields available for the dictionary selected in the above field.

If D_OPEN (dictionary open) is greater than the current system date for any record in the dictionary value then such a record of the dictionary will not be available in the option list. If the (dictionary close) D_CLOSE is smaller than the current system date for any record in the dictionary value then such record of the dictionary will not be available in the option list.

Value

Specify the value of the parameter to be assigned to the Oracle FLEXCUBE customer contract/account. You can also populate this value by clicking on the button 'V'. You can change the value of the parameter.

Click 'V' button and select the appropriate value from the list provided.

If the value specified is not present in system then the system displays the error 'Value mismatch in the dictionary'.


If a wrong value is chosen or specified for a particular field from the option list then an error message is displayed.

2.8 Maintaining KYC Type

Oracle FLEXCUBE maintains KYC details for all customers. For Individuals / Salaried employees, the KYC is fairly simple and straight forward. However, for Small and Medium Enterprises (SME) and corporate customers or Banks, the KYC for the company and its Directors should be done. The KYC for any share holder having the percentage of stock equal to or more than the defined percentage should be done. These share holders may not be the banks customers. The System maintains KYC for NON-CIF customers also.

Oracle FLEXCUBE tracks all the sources of funds/income of any person/company/banks undergoing KYC. The system also tracks approximate number of transactions they are expected to perform in their accounts.

You can specify the details of KYC type in the 'KYC Type Maintenance' screen. You can also invoke this screen by typing 'STDKYCTP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Here you can specify the following details:

KYC Type

Specify the type of KYC that should be maintained.

KYC Type Description

Specify the description that should be maintained for the specified KYC type.

2.8.1 Specifying KYC Value Details

You can specify the following KYC value details:

KYC Type Value

Specify the value of the KYC type.

KYC Type Value Description

Specify the description for the KYC type value.

The table below illustrates the KYC types and the possible values for each KYC types.

KYC Type	Possible Values
KYC_DECLARED	Ownership Shareholding
KYC_SRC_INCOME	Salary Rental Investment Business Concerns Professional Business Overseas Property Others
KYC_TYP_COMP	Sole Proprietor Partnership LLC PSC PJSC Free Zone Enterprise Government Entity Charity Orgn FZ Co. Offshore Company FZ LLC Others
KYC_PURPOSE	Commercial Individual
KYC_DET_PURPOSE_COMM	Commercial Banking Trade Services

KYC Type	Possible Values
	Private Banking Investments Loans Retail Banking Null (Provide Details)
KYC_DET_PURPOSE_IND	Salary Transfer Savings Investment Loan Repayment Transactional
KYC_SAL_TYPE	Cash Direct Deposit Company Cheque TT/SWIFT/CB Null (Provide Details)
KYC_SETTL_PAY	Cash Cheque Wire Transfer LC/Documentary Collection
KYC_TXN_DET	Monthly Withdrawals Deposits Remittances By Cash Remittances BY Cheque Local Remittance (Inward) Local Remittance (Outward) Foreign Remittance (Inward)

KYC Type	Possible Values
	Foreign Remittance (Outward) <i>For Salaried Individuals, this is required only for Risk level 2 & 3 customers</i>
KYC_TYPE_ACC	Sole/Joint
KYC_OCCUPATION	Own Business Employed
KYC_FI_STATUS	Ho Branch Central Office Subsidiary Rep Office Others
KYC_FI_TYPE	Commercial Bank Investment Bank Offshore Bank Leasing Company Exchange Company Others
KYC_AREA_OF_BUSINESS	Retail Corporate Investment Transfers Islamic Banking Trade Treasury Others

KYC Type	Possible Values
KYC_OWNERSHIP	Government Private Owned Public Held Partly Owned By Gov and part by private or public Investors/Partly Traded in Stock Exchange Shares Traded In Stock Exchange & Partly Held By Private And Public Investors Others
KYC_PRODUCTS	Incoming Transfer – MT103 Incoming Transfer – MT202 Outgoing Transfer – MT103 Outgoing Transfer – MT202 Clearing and Collections (Cheques and Drafts) LC Advising LC Reimbursements LC Confirmation LG Advising Bill Discounting Bankers Acceptances Risk Participation (Funded and Non-funded) per annum
KYC_BANK_STRUCTURE	Board of Directors Executive Committees
KYC_RATING	Satisfactory Unsatisfactory Fair
KYC_SHARE_HOLDER_TYPE	Legal Entity

KYC Type	Possible Values
	Individual

2.9 Maintaining Customer KYC Details

You can maintain the KYC details of the customer in the 'KYC Details' screen. You can invoke this screen by typing 'STDKYCMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Here you can specify the following details:

KYC Reference Number

The system displays the reference number. The KYC reference number will be generated and displayed while saving this screen.

Full Name of Customer

Specify the full name of the customer.

KYC Customer Type

Specify the type of KYC customer from the adjoining drop-down list. The list displays the following values:

- Retail Customer
- Corporate Customer
- Financial Customer

Risk Level

Select the risk level from the drop-down list. The list displays the following values:

- Level1
- Level2
- Level3

Retail Customer Tab

You can specify the KYC profile details for retail customer in the 'KYC Retail Profile' screen. Click 'Retail Customer' tab to invoke this screen.

The screenshot shows the 'KYC Retail Profile' window. It contains the following sections:

- Beneficial Owner Information:** Includes fields for Declared (Resident, Politically Exposed Person), Birth Date, Birth Place, Nationality, Office Tel Number, Residence Tel No, Mobile Tel Number, Fax, Purpose Of Account Opening, Others, Account Type (Power Of Attorney), Passport Number, Passport Expiry Date, Visa Number, Visa Expiry Date, and KYC Amounts CCY (GBP).
- Beneficially Owned Company:** A table with columns: Company Name, Location, % Holding, Annual Income, Line Of Business.
- Source of Income:** Includes checkboxes for Salary, Rental, Investment, Business Concern, and Professional Business.
- Related Companies Accounts with Bank:** A table with a column: Company Account Number.
- Personal Accounts with Bank:** A table with a column: Personal Accounts Number.

You can capture the following details on this screen:

Beneficial Owner Information

You can specify the following details pertaining to the beneficial owner:

Resident

Check this box to indicate that the beneficial owner is a resident. If you do not check this option, the system will not consider the owner as a resident.

Politically Exposed Person

Check this box to indicate that the beneficial owner is a politically exposed person.

PEP Remarks

Specify the remarks about the declaration of the beneficial owner as politically exposed person.

Local Address

Specify the local address of the beneficial owner.

Home Country Address

Specify the home country address of the beneficial owner.

Birth Date

Specify the birth date of the beneficial owner.

Birth Place

Specify the place of birth of the beneficial owner.

Nationality

Specify the nationality of the beneficial owner.

Office Tel Number

Specify the telephone number of the beneficial owner's office.

Residence Tel No

Specify the residential telephone number of the beneficial owner.

Mobile Tel Number

Specify the mobile telephone number of the beneficial owner.

Fax

Specify the Fax number of the beneficial owner.

Purpose of Account Opening

Specify the purpose of opening the account.

Others

If you wish to provide any additional information about the beneficial owner, use this field.

Account Type

Specify the type of the account.

Power of Attorney

Check this box to indicate that the beneficial owner holds a power of attorney.

Passport Number

Specify the passport number of beneficial owner.

Passport Expiry Date

Specify the expiry date of the passport.

Visa Number

Specify the visa number of the beneficial owner.

Visa Expiry Date

Specify the expiry date of visa.

KYC Amounts Ccy

Specify the currency in which KYC amount is maintained.

Beneficially Owned Company Details

You can specify the details of the beneficially owned company in the following fields:

Company Name

Specify the name of the company.

Location

Specify the location of the company.

% Holding

Specify the percentage of holding.

Annual Income

Specify the annual income of the company.

Line of Business

Specify the line of business of the company.

Source of Income

You can specify various sources of income in the following fields:

Salary

Check this box to indicate that salary is a source of income.

Rental

Check this box to indicate that rent is a source of income.

Investment

Check this box to indicate that investment is a source of income.

Business concern

Check this box to indicate that the business concern is a source of income.

Professional Business

Check this box to indicate that the professional business is a source of income.

2.9.1.1 Corporate Customer Tab

You can specify the KYC profile details for corporate customer in the 'KYC Corporate Profile' screen. You can invoke this screen by clicking 'Corporate Customer' tab in the 'KYC Maintenance' screen.

The screenshot displays the 'KYC Corporate Profile' window with the following sections:

- Customer and Sponsor(s) Information:** Includes fields for Groups Name, Parent Company's Country Of Inc, Type Of Company, Others, and KYC Amounts CCY (set to GBP).
- Reason of Account:** Includes Purpose Of Account Opening and Others.
- Nature of Business:** Includes Nature Of Business, Product Traded, Main Source Of Funds, Borrowing Account Group, and Annual Turnover.
- Details Of Key Person:** A table with columns: KYC ID, Name, Relationship, Nationality, Position Or Title, and Share Percentage.
- Company Details:** Includes Details Of Company Branches, Number Of Person Employed, and Mode For Salary (Others).
- Details Of Suppliers:** A table with columns: Supplier Name, Country, and Settlement Mode.
- Details Of Clients:** A table with columns: Client Name, Country, and Payment Mode.
- Transaction Type:** A table with columns: Transaction Type, Count, Total Amount, Max Single Amount, Purpose, Country, and Fund Transfer Purpose Within Country.

The interface includes navigation controls like 'Go to Page' and '1 of 1' for each table, and 'Ok' and 'Exit' buttons at the bottom right.

Here you can specify the following details:

Customer and Sponsors Information

You can specify the information of customers and sponsors in the following fields:

Groups Name

Specify the name of the group.

Parent Company's Country of Inc

Specify the country of Parents Company. The adjoining option list displays all valid countries maintained in the system.

Type of Company

Specify the type of the company. The adjoining option list displays all valid company types maintained in the system. You can choose the appropriate one.

Others

If you wish to provide additional information on customer and sponsors, use this field.

KYC Amounts Ccy

Specify the currency in which KYC amount is maintained.

Reason of Account

You can specify the reasons for opening the account in the following fields:

Purpose of Account Opening

Specify the reason for opening an account. The adjoining option list maintains all valid reasons maintained in the system. You can choose the appropriate one.

Others

If you wish to provide additional information and reasons, use this field.

Nature of Business

You can specify the nature of business in the following fields:

Nature of Business

Specify the nature of business. The adjoining option list displays all valid businesses maintained in the system. You can choose the appropriate one.

Product Traded

Specify the name and details of the product traded during the course of the business.

Main Source of Funds

Specify the main source of funds.

Borrowing Account Group

Specify the borrowing account group.

Annual Turnover

Specify the annual turnover of the company.

Details of Key Person

You can specify the details of the key person in the following fields:

KYC ID

Specify a unique identification for the KYC details of the key person.

Name

Specify the name of the key person.

Relationship

Specify the relationship between the key person and the corporate customer. The adjoining option list displays all valid relationships maintained in the system. You can choose the appropriate one.

Nationality

Specify the nationality of the key person. The adjoining option list displays all valid nationalities maintained in the system. You can choose the appropriate one.

Position or Title

Specify the position or title of the key person.

Share Percentage

Specify the percentage of share for the key person.

Company Details

You can specify the details of the company in the following fields:

Details of Company Branches

Specify the details of the company branches.

Number of Person Employed

Specify the number of person employed in the company.

Mode for Salary

Specify the mode of salary payment in the company. The adjoining option list displays all valid modes maintained in the system. You can choose the appropriate one.

Others

If you wish to provide additional information on the company, use this field.

Details of Suppliers

You can specify the details of suppliers in the following fields:

Supplier Name

Specify the name of the supplier.

Country

Specify the country to which the supplier belongs.

Settlement Mode

Specify the mode of settlement. The adjoining option list displays all valid modes maintained in the system. You can choose the appropriate one.

Details of Clients

You can specify the client's details in the following fields:

Client Name

Specify the name of the client.

Country

Specify the name of the country of the client.

Payment Mode

Specify the mode of payment. The adjoining option list displays all valid modes maintained in the system. You can choose the appropriate one.

Transaction Types

You can specify the details of the transaction types in the following fields:

Transaction Type

Specify the type of transaction.

Count

Specify the count of the transaction.

Total Amount

Specify the total amount of the transaction.

Max Single Amount

Specify the maximum single amount allowed for the transaction.

Purpose

Specify the purpose of the transaction,

Country

Specify the country in which the transaction takes place.

Fund Transfer Purpose within Country

Specify the purpose of funds transfer within the country.

Audit Date

Specify the audit date. Use the date button to choose a date from the calendar.

Account Solicited

Check this box to indicate that the account should be solicited.

Account Solicited Date

Specify the date on which the account should be solicited using adjoining calendar button.

Introducer Details

Specify the details of the introducer.

Compliance Clearance

Specify the date of compliance clearance using adjoining calendar.

Business Approval

Specify the date of business approval using adjoining calendar.

Trade Licence No

Specify the trade licence number. The adjoining option list displays all valid licence numbers maintained in the system. You can choose the appropriate one.

KYC Next Review Date

Specify the next date of KYC review.

Comments

KYC

Specify the comments on the KYC details of the corporate customer.

Sales and Service Officer


Specify the comments of sales and service officer on the corporate customer.

Approvers

Specify the name and comments of the approvers of the corporate customers.

2.9.1.2 Corporate or Audit HO Details Tab

Click 'Corporate or Audit HO Details' tab in the 'KYC Corporate Profile' screen.



The screenshot shows a window titled "KYC Corporate Profile" with a tab labeled "Compliance / Audit HO Details". The window contains several input fields and checkboxes:

- CID Number
- Name
- STR Raised
- STR Date
- STR Reference
- CB Response
- CB Response Date
- Activity
- Activity Reason
- Dairy Note

At the bottom right of the window, there are "Ok" and "Exit" buttons.

Here you can specify the following details:

CID Number

Specify the CID number of the corporate customer.

Name

Specify the name of the corporate customer.

STR Raised

Check this box to indicate that the STR should be raised.

STR Date

Specify the date of STR using adjoining calendar button.

STR Reference Number

Specify the reference number of the STR.

CB Response

Check this box to indicate that the CB should be responded.

CB Response Date

Specify the date of CB Response using the adjoining calendar button.

Activity

Specify the details of the activity.

Activity Reason

Specify the reason for the activity.

Dairy Note

Specify the dairy note.

2.9.1.3 Financial Customer Tab

You can specify the KYC details of financial customers using the 'KYC Financial Profile' screen. You can invoke this screen by clicking 'Corporate Customer' tab in the 'KYC Maintenance' screen.

The screen is as shown below:

The screenshot shows the 'KYC Financial Profile' application window. It features a header with a title bar and a close button. Below the header, there are input fields for 'Bank Address', 'Country', and 'KYC Amounts CCY' (set to 'GBP'). The main area is divided into three sections, each with a table and a 'Go to Page' button. The 'Transaction Products' table has columns for 'Transaction Products', 'Rating', and 'Monthly No Of Transactions'. The 'Management Details' table has columns for 'Name' and 'Designation'. The 'ShareHolders Details' table has columns for 'Name', 'Holding', 'Address', 'City', and 'Country'. At the bottom right, there are 'Ok' and 'Exit' buttons.

Here you can specify the following details:

Bank Address

Specify the address of the bank.

Country

Specify the country of the financial customer.

KYC Amounts CCY

Specify the currency of the KYC amounts.

Specifying Transaction Products

Specify the following details:

Transaction Products

Specify the name of the transaction product.

Rating

Specify the rating of the product.

Monthly No of Transactions

Specify the number of monthly transactions.

Monthly Amount

Specify the monthly amount.

Specifying Management Details

Specify the following details:

Name

Specify the name of the manager.

Designation

Specify the designation of the manager.

Specifying Share Holders Details

Specify the following details:

Name

Specify the name of the share holder.

Holding

Specify the holdings of the share holder.

Address

Specify the address of the share holder.

City


Specify the city of the share holder.

Country

Specify the country of the share holder.

2.9.1.4 Fields Tab

You can create user defined fields using the 'User Defined Fields' screen. To invoke this screen, click 'Fields' tab in the 'KYC Maintenance' screen.



Here you can specify the following details:

Field Name

Specify the name of the field.

Value

Specify the value of the field.

2.10 Creating a Message Advice Format

You need to create a message advice format through the 'Advice Format Maintenance' screen with the format named 'CUS_MIMJADV'. A batch function 'CASABAT' will perform status change from Minor to Major during EOD.

During EOD, batch (CASABAT) which would check for the current age of each minor customer, if the customer's current age is on or above the minor age limit maintained at branch parameters then you to do the following mentioned settings:

- The option 'Minor' at customer personal details will be unchecked in customer maintenance screen.
- The select 'Submit Age Proof' as 'Pending' in customer maintenance screen.



Note the following:

- In case of holiday the Minor to Major conversion would be done after the holiday.

- The Debit would be still allowed for the system initiated transactions (During EOD/BOD) even though the documents have not been submitted.

Customer Advice generation:

During EOD, batch (CASABAT) will generate the advice for the customers who are going to attain the Major status based on the number of days mentioned at Branch Parameters level for advice generation.

The customer will receive an advice in the following sample format:

```
#RH
  < Customer Minor Major Advice>
  -----
Date           : _BRANCHDATE_

Bank Name      : _BANK-NAME_

Branch Address : _BRANCH-ADDR_

Customer Name  : _CUST-NAME1_

Customer ID    : _CUSTOMER_
```

You are attaining the Major status on _DATE_ .Hence please submit the necessary documents on or before _DATE_.

#EH

#B

#SC

AUTHORIZED SIGNATORY.

#EC

#EB

- Branch Code
- Tax Id

After specifying the parameters for the query, click 'Search'. The system displays all the records matching the parameters specified.

- Authorization Status
- Record Status
- Customer No
- Type
- Name
- Short Name
- Customer Category
- Country
- Nationality
- Branch Code
- Language
- Address
- Frozen
- Deceased
- Exposure
- Location
- SSN
- Whereabouts Unknown
- Account Number
- Swift Code
- Value
- Document ID Type
- Document ID Number
- Tax ID

3. Maintaining Mandatory Information

3.1 Introduction

As part of capturing customer related information in Oracle FLEXCUBE you need to maintain Customer Information Files (CIF records) for each entity who is a customer of your bank. Apart from creating CIF records for each entity you need to maintain separate accounts for each customer. The features of these two screens have been discussed in detail in the preceding sections.

While defining CIF records and Customer Accounts, you would have noticed that many of the fields have option lists positioned next to them. While some option lists contain pre-defined values for some option lists to be populated you need to capture data through separate screens. For instance, while maintaining CIF records you need to associate each customer with a customer category. For this purpose you will need to maintain customer categories before you begin to maintain CIF records. Similarly, each customer account needs to be associated with an account class. Therefore, you will need to maintain account classes before you start defining customer accounts.

All such screens have been documented in the subsequent sections

3.2 Maintaining Account Classes

In the Oracle FLEXCUBE system, you can classify the customer accounts of your bank into different groups and assign each an identifying code. For instance, you may define a group called INDSB to represent savings accounts held by individuals, SB-INS to comprise institutional savings accounts, COR-CU for corporate current accounts.

Each group is referred to as an Account Class and is maintained in the 'Account Class' screen. For each class, you also define certain common attributes applicable to all accounts in this class, such as, the General Ledger lines to which the accounts in this class report to, facilities granted to the account holders (pass book, check book, ATM etc.).

In the 'Customer Accounts Maintenance' screen, where you open accounts for the customers of your bank, each customer account is linked to an account class, and the attributes defined for the account class are by default applicable to the customer account. For instance, if the frequency of account statement generation has been defined as daily for an account class CU-COR, the system generates statements for all accounts under this class on a daily basis. However, some of the parameters defined for the account class, can be revised at the account level for any of the accounts linked to the class. Account level parameters will supersede those defined for the account class.

While defining the account classes you should also keep in mind that the interest rate structure is also specified for an account class (in the Interest and Charges module).

The account class table is maintained at the Bank Level by the Head Office branch.

3.2.1 Invoking Account Class Maintenance Screen

You can invoke the 'Account Class Maintenance' screen by typing 'STDACCLS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Account Class Maintenance' window. At the top, there are input fields for 'Account Class', 'Description', 'Start Date', and 'End Date'. Below these are two tabs: 'Account Details' and 'Statement Parameters'. The 'Account Details' tab is selected and contains fields for 'Account Code', 'Dormancy Days', 'Account Statement Format', 'Natural GL' (with radio buttons for 'Debit' and 'Credit'), 'Dormancy Parameters', and 'Applicable Customer Status'. The 'Statement Parameters' tab is also visible and contains several sections: 'Provisioning Details' with fields for 'Provisioning Frequency', 'Provision Currency', 'Exposure Category', 'Event Class Code', and 'Provisioning Code'; 'Escrow Details' with 'Transaction Code' and 'Escrow Transfer Applicable'; 'Debit Interest / Charge Liquidation' with 'Liquidate Using Receivable', 'Verify Funds', and 'Debit Notice'; and 'Initial Funding' with 'Event Class Code' and 'Charge Role To Head Code'. At the bottom of the window, there are tabs for 'Restrictions', 'Branch/Currency Restriction', 'Customers/Categories', 'MIS', 'Preferences', 'Reg', 'Deposit', 'Auto Deposit', 'GL Lines', 'Status Rule', 'Amt Block', and 'Statement'. An 'Exit' button is located in the bottom right corner.

Defining an Account Class includes the maintenance of the following parameters:

1. Assigning a unique Code to the Account Class and associating an appropriate description with the class
2. Indicating the type of account for which account class is being maintained
3. Specifying the period after which accounts in this class should become dormant if no customer transaction is posted into the account.
4. Indicating the date from when new accounts can be created under the account class.
5. Indicating the end date after which the new accounts cannot be created for the account class.
6. Maintaining the different statuses applicable to the accounts for which the account class is being defined. This would be used for tracking NPA's on current and savings accounts.
7. Maintaining status-wise GLs for provisioning
8. Identifying the reporting lines (GL Line, Central Bank Lines and the Head Office Lines) for each status.

9. Maintaining account statement details like the type of statement that is to be generated, the frequency at which statements should be generated for all accounts under a class.
10. Indicating the preferences unique to an account class like the check book, passbook or ATM facilities to be given to account holders under this account class; whether overdraft facility should be allowed for accounts linked to this class; whether the credit limit should be checked for all accounts under the class; interest and charges to be computed for accounts under this class.
11. Specifying preferences regarding account holder facilities, interest computation etc.
12. Indicating whether status change for all accounts belonging to the account class should be automatic or manual.
13. Identifying and assigning preferred branches, currencies and customers to the account class.
14. Specifying whether receivables should be tracked for the account class. This specification will default to all accounts that are linked to this account class.
15. Specifying whether reordering of Cheque Books for all accounts linked to this account class should be triggered automatically or not. If yes, the parameters for the same.
16. Specifying liquidation preferences for debit interest and charges, to notify your customers through a Debit Interest Notification message (in the case of charges, a Charge Notification message) before debiting the customer's personal current account for debit interest or charges.
17. Maintaining initial funding details for new accounts
18. Indicating whether Escrow transfer is applicable or not for new accounts

Each of the parameters has been discussed in detail in the subsequent sections

Account Class and Description

The account class code is a unique 6-character code, which identifies the class. Along with the class code you need to assign an appropriate description to the account class.

For instance, let us assume you are defining a class for savings account of individuals. You could associate the code SB IND with it. Similarly, the description that you associate with it could be something like this – 'Savings accounts of individuals'.

Account Type

The six different types of accounts that you can maintain are:

- Nostro account - your bank's accounts with another bank

In the 'Customer Account Maintenance' screen, you will have to create new customer accounts with Account Class type as Line Account and ensure the following parameters for every new line associated with a liability

- The CIF of the account in the 'Customer Account Maintenance' screen will have to be the same as the liability to which the line will be linked in the 'Limits' screen.
- The currency of the account in the 'Customer Account Maintenance' screen will have to be the same as the currency of the line that will be attached in the 'Limits' screen.
- The interest calculation account maintained in the 'Interest and Special Conditions Maintenance' screen, will have to be the same as in the 'Limits' screen. However, the Interest Booking Account maintained in the 'Interest and Special Conditions Maintenance' screen can be some other account belonging to other account class types.

Since accounts can be of different types, you need to indicate the type of account for which you are defining an account class. It could belong to any one of the types mentioned above

Account Code

As per your bank's requirement you can choose to classify account classes into different account codes. The bank can decide the manner in which the account classes are to be assigned to different account codes. An account code can consist of a maximum of four characters.

Depending on the customer account mask maintained, the value in the account code field would be used during the generation of customer account numbers through the 'Customer Accounts Maintenance' screen.

If you have decided to include account code as part of the customer account number (in the account number mask), then at the time of creating a new customer account number, you will need to select the account class for the account number being generated. In the option-list provided, the account class is displayed along with the associated account code. When the account number gets populated, it is the account code that forms a part of the customer account number.

Start Date

Specify the date from which the account class should become active, using the adjoining calendar. You will be able to create accounts under this account class from this date.

End Date

You can also specify the life span of the account class by indicating the end date.

The end date for an account class refers to the termination date after which, creation of new account under the account class is disallowed.

Consequently, the option list for Account Class in all further transactions screen in Oracle FLEXCUBE, will not display the 'expired' account class as of the system date. However, the existing accounts for the account class will be active even after the end date.



If you do not specify an End Date for the account class, the account is taken to be an open-ended account class.

Project Account

Check this box to track the working capital of the project.

Dormancy Days

You have to indicate the period after which an account in an account class becomes inactive or dormant if customer transactions are not posted into the account.



However, while maintaining transaction codes, if you have checked the Consider for Account Activity field, all transactions posted to any account under this account class linked to the particular transaction code will become active from dormant irrespective of the dormancy period. If a customer-initiated transaction is posted into the account with the dormant status the account status will be updated to Active from Dormant since the Transaction Code associated with the account has the Consider for Account Activity option enabled.

Dormancy Parameters

As stated above, if Transaction Code associated with the account has the Consider for Account Activity option enabled, the dormant status of the account will be updated to Active. Apart from this, you can specify the parameter that is required for re activating the account. To indicate the re activation parameters for the dormant account choose any from the following options:

- Debit
- Credit
- Any
- Manual

In case of a transaction, the system will check for the parameter you have specified here and accordingly change the status of the account. However, the parameter maintained at the account level will super cede the parameter you have specified here.

Account Statement Format


Specify the format in which account statement should be generated. The adjoining option list displays all valid formats maintained in the system. You can select the appropriate one.

Display IBAN in Advices

For an account class you can indicate whether the IBAN number of the customers involving the accounts within the class should be printed on advices sent to the customer. If you would like to print the IBAN number of the customers on advices sent to the customers involving the account class, you can enable the Display IBAN in Advices option by checking it.

Specify the value other than 'None' for the fields ,inorder to check for IBAN availability for accounts belonging to particular class and printing it in the advices and statements.


Your specification will be made applicable to all customers linked to the account class. You will be allowed to change this option for a specific account.

 IBAN Account numbers for specific customers can be captured while defining a specific account through the IBAN Sub-screen of the 'Customer Account Maintenance' screen.

Display Nib in Statements and Advices

For an account class, you can indicate whether the NIB number of the customers involving the accounts within the class should be printed on advices sent to the customer or not.

Specify the value other than 'None' for the field ,inorder to check for NIB availability for accounts belonging to particular class and printing it in the advices and statements.


 Note the following:

- IBAN is displayed in blocks of four characters.(PT50 0002 0123 1234 5678 9015 4)
- NIB is displayed in blocks of four characters prefixed with 'NIB' (NIB 0002 0123 1234 5678 9015 4)

Dual Ccy Deposit

Check this box to enable the account class for Dual Currency Deposit (DCD) type.

Dual Currency Deposit (DCD) is a short-term currency-linked deposit that allows you to earn a higher interest rate than regular time deposits.

 You will be allowed to check this field only for 'Deposit' Account Type. If this box is checked for other Account types, system throws an error.

Natural GL

The reporting of all turnovers of the particular account class will be directed to the GL that you identify as the natural GL. Based on the characteristic of the account balance; you can specify whether the turnover is to be posted to the Debit GL or to the Credit GL. For instance, if the account class is for overdrafts, the balance is normally a debit whereas current accounts normally do not have a debit balance.

Applicable Customer Status

Specify the applicable customer status from the drop-down list. The available options are:

- Major
- Minor
- Both
- Not Applicable



Note the following:

- By default 'Not applicable' option would be selected when a new account class is created.
- If you select 'Minor' option at the CIF level and 'Applicable customer status' as 'Major' at the account class level then the system throws an error stating that:

The A/c class you selected is for major customer

- Similarly if you uncheck 'Minor' option at the CIF level and select 'Applicable customer status' as 'Minor' at the account class level then the system throws an error stating that:

The A/c class you selected is for minor customer

3.2.2 Statement Parameters Tab

For each account class that you maintain you have the option of generating account statement details, periodically, for all customer accounts associated with the account class.

If you need to generate account statements that would need to be sent across multiple media, generated at different frequencies, you can define up to three different frequencies at which the statements could be generated, with a primary, secondary and tertiary frequency.

Click 'Statement Parameters' tab to invoke the screen for maintaining these details. The screen is displayed below:

As part of specifying the account statement preferences you can indicate the following for each of the statements, whether primary, secondary or tertiary:

Type

The first preference that you specify for each account class is to indicate whether the periodic generation an account statement is required. If the generation of an account statement is necessary, you have to specify the format in which it is to be generated. The options available are:

- Detailed – indicating that the statement should be a detailed account of all the customer transactions within the account class.
- Summary - indicating that only a summary of the transaction details is enough.
- None – indicating that neither a summary nor a detailed account of transactions is required.

Cycle

The system generates the account statement details at a frequency that you specify. The frequency can be:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

If you indicate that the statement generation frequency is weekly, you should also indicate the day of the week on which the account statement is due. Similarly, for a monthly statement you should indicate the day of the month.

To specify the frequency for a monthly statement you can specify a number between 1 and 31 (corresponding to the system date). If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days.
- For months with 30 days on the 30th; if 30th is a holiday on the next working day.

If you set the statement date to 31, then account statements will be generated on:

- The 31st, for month with 31 days; if 31st is a holiday on the next working day.
- The last working day for months < 31 days.

For all other cycles, account statement would be generated on the last day of that cycle.

Offline Limit

This is the limiting amount till which transactions will be carried out between account(s) for the account class you are defining here, between branches when the database connectivity is not functional.

Enter the off-line limit here.



Note the following:

- If you are defining primary, secondary and tertiary statements, the frequency for each must be different and unique; for instance, if you define a monthly primary statement, you cannot define a secondary or tertiary statement with a monthly frequency.
- Offline limit is maintained only for primary level.

CSB 43 Statement

Type

Select the CSB Statement type from the adjoining drop down list. The options are:

- Type (1)
- Type (2)
- Type (3)
- The system displays an error message if Type 3 is selected.

Cycle

Select the CSB 43 Statement cycle from the adjoining drop down list. The options are:

- Semi Annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily
- Annually

CSB 43 Statement Generation batch (STBCSBGN) is configured to generate CSB 43 account statement.

Document Check List

Specify the following details:

Document Type

Specify the document type. The adjoining option list displays all the document types that are maintained in the system. You can select the appropriate one.

Customer Type

Specify the customer type. The adjoining option list displays all the customer types that are maintained in the system. You can select the appropriate one.

Mandatory

Check this box to indicate that the document specified here is mandatory.

3.2.3 Maintaining Cheque Book Preferences

Oracle FLEXCUBE provides you with the facility to automatically trigger the reorder of Cheque Books for all accounts reporting to a specific account class. However, you have the option of changing your preferences at the account level also.

To facilitate automatic reordering of Cheque Books, you have to maintain the following details:

Cheque Book

To indicate that automatic reordering of cheque books should be allowed and for specifying the details for the same, you have to check this option. If not selected, you will not be able to maintain the automatic reordering preferences for the account class.

Auto Reorder of Cheque Book

You have to select this option to specify that automatic reordering of Cheque Books is required for all accounts reporting to this account class. This field will be enabled only if you have checked the 'Cheque Book' option explained above.

Reorder Level

Here, you have to indicate the level at which the reordering of Cheque Book should happen. Automatic reordering will be set off by the system when the unused number of cheque leaves becomes equal to or less than the re-order level that you maintain here. This field will be enabled only if you have indicated that automatic reordering of Cheque Books is required i.e. the 'Auto Reorder of Cheque Book' option is checked.

Reorder No of Leaves

In this field you have to specify the number of leaves that should be ordered for the new Cheque Book. This field will be enabled only if you have checked the 'Auto Reorder of Cheque Book' option.

Max No. of Cheque Rejections

Specify the maximum number of cheque rejections that can be allowed for an account.

3.2.3.1 Processing Automatic Reordering of Cheque Books

The automatic reordering of Cheque Books is processed at EOD by executing a batch function.

The following conditions should be satisfied for initiation of automatic reordering:

- The 'Auto Reorder of Cheque Book' option is turned on at the account level
- The number of unused check leaves for the account is less than or equal to the reorder level maintained at the account level. The system will pick up the number of leaves to be reordered from the field 'Reorder Number of Leaves' maintained for the account.

The numbering of cheque leaves for the new Cheque Book will depend on the 'Cheque Number Unique for Branch' option in the 'Bank Parameters' screen. If this option is checked, the numbering will begin from the Last Number + 1 of the Cheque Book that was delivered last to any account. If you do not select this option, the number will start from the Last Number +1 of the Cheque Book delivered to the same account previously.

The value of 'Include for Cheque Book Printing' and 'Cheque Type' (specifications defined in the 'Cheque Book Details' screen) will be defaulted from the previous order of the Cheque Book.

3.2.4 Capturing Details about Specially Designated Nationals

Specially Designated Nationals (SDN) are those customers with whom you need to refrain from trading in any form. The US government publishes a list of such nationals and circulates this list among banks and other financial organizations. You can to maintain the details of SDNs in Oracle FLEXCUBE.

The details of Specially Designated Nationals are updated and published by the US government on a regular basis. You could download these details from their web site. You have two options to replicate the contents of this file into Oracle FLEXCUBE. They are:

1. Upload the file into Oracle FLEXCUBE through the SDN Upload screen.
2. Maintain the details of each SDN manually.

Both these options have been elaborated upon in the subsequent sections.

Maintaining SDN Details Manually

Through the 'Specially Designated Nationals' screen you can capture the details of SDN customers manually. Invoke this screen, by typing 'STDSDNMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a detailed form for Specially Designated Nationals. The form is titled "Specially Designated Nationals - Detailed". It contains the following fields and sections:

- Name ***: A text input field.
- Date Of Birth ***: A date picker field.
- Country of Origin ***: A dropdown menu.
- Remarks**: A text area with a speech bubble icon.
- Alias Names**: A table with columns "Sequence Number" and "Alias Name".
- Address**: A table with columns "Sequence Number", "Address Line 1", "Address Line 2", "Address Line 3", and "Address Line 4".
- Fields**: A section at the bottom with checkboxes for "Authorized" and "Open", and a "Cancel" button.

The following details have to be captured:

- Name of the Specially Designated National
- Date of Birth of the SDN: Specify the Date of Birth of the SDN in YYYYMMDD format
- Country of Origin: You can specify the SDN's country of origin by selecting the same from the option list provided
- Remarks: Any additional remarks, if required can be specified
- Alias Names of the SDN: You can specify a maximum of fifteen alias names
- Addresses of the SDN: You can specify a maximum of fifteen addresses (of address line 1 to address line 4) for a SDN

3.2.5 Specifying your Preferences for Account Class

Preferences are the options or attributes that uniquely distinguish an account class. You can specify the preferences of an account class in the 'Preference' screen. To invoke this screen, click 'Preferences' button in 'Account Class Maintenance' screen.

The screen is as shown below:

The following are the preferences that you can specify for an account class:

- Limit Check – you can check this box to indicate that a limit check for sufficient availability of funds in the account will be made for all accounts belonging to the account class
- Overdraft Facility – if checked indicates that all accounts belonging to this class would be allowed an overdraft facility (facility to draw a specified amount over and above the balance in the account)
- Interest Charges – if checked indicates that for interest and charges computation the Interest and Charges module will process accounts linked to this class.
- Track Accrued IC – if checked, indicates whether accrued interest in the Interest and Charges module on an account linked to this class, would be considered while computing credit utilization for the account.
- Passbook Facility – if checked, indicates that accounts linked to the account class are issued passbooks.
- ATM Facility – if checked, indicates that accounts linked to the class will avail the ATM facility
- Daylight Limit – if checked indicates that you can specify daylight overdraft limit for all the accounts belonging to this account class. While modifying the maintenance, if you uncheck this box, the daylight overdraft limit will be made zero for all the accounts belonging to this account class.

- Debit/Credit Advices – If checked, indicates that for all accounts belonging to this class, the system will generate a debit/credit advices on interest liquidation. The advices are generated during end of day processing in SWIFT or/and MAIL format. You can also specify this preference through the 'Special Conditions' screen.
- Track Receivable – if checked, you can choose to block the subsequent credit that happens to the settlement account (linked to this account class) of a loan contract or retail teller contract, if the system detects insufficient funds in the account, during liquidation. In other words, the system will track the account for receivables (credits). As and when a credit happens, the funds will be allocated to the loan or the retail teller contract for liquidation.
- Posting Allowed – This check box is checked by default. Uncheck this check box to setup Monetary Accounts for the selected Account Class.

This check box is provided to handle IRA Monetary Accounts. Using this facility, you can avoid posting into the IRA Monetary Accounts from Teller/Journal screens and ensure that the details are computed only through IRA subscriptions.



Uncheck this checkbox only for specific Inter-Branch Accounts.

- Referral Required - enabling this option indicates whether a referral check should be performed on accounts belonging to the account class. Consequently, the system checks the available balance (not the current balance) while performing the referral checks for all transactions involving the account. If a transaction involving the account results in the account moving to overdraft, the account and transaction details will be sent to the Referral Queue.
- Lodgement Book - If you wish to allow orders of lodgement books for all accounts that use an account class, you can indicate so, in the 'Account Class Maintenance' screen, by selecting the Lodgement Book option.
- Back Period Entry Allowed – if checked, indicates that back-valued entries can be posted to account belonging to the class as long as the account is open. You will be allowed to change this specification for a specific account.
- Uncollected Funds Group Tracking - This check box indicates that group level limit maintenance for uncollected funds is allowed for the account class. If you check this box, it indicates that uncollected fund limits can be maintained for each group separately in the accounts belonging to this account class. By default this box is left unchecked.
- Net IC Entries – This check box indicates that interest and charges for a customer account should be netted and posted into the customer account as one booking entry. This check box is enabled only if you have checked 'Interest Charges'.
- Exempt/Include Withholding Tax on Applicability Change – If this box is checked, then the system will deduct withholding tax for the document expired/Non-Submission period and not for the whole liquidation cycle. If this check box is not checked, then the withholding tax applicability depends on the check box 'Withholding Tax' at the customer level during liquidation cycle. Either tax will be applicable during the whole liquidation cycle or will not be applicable during that cycle. If the check box is checked, then then Withholding tax is applicable based on the below two methods:

- If the check box 'Withholding Tax' is checked at the customer level, then tax is applicable for entire liquidation cycle irrespective of whether the certificate is expired in the middle of the liquidation cycle.
- If the check box 'Withholding Tax' is unchecked at the customer level, then tax will be applicable only for those days for which certificate was expired,
- Integrated Liquidity Management - check to indicate that the accounts created under this account class would be part of an ILM Structure.

While posting back-valued transactions, the System verifies whether the Back Period Entry Allowed option has been enabled for the account class. If the option has not been enabled an error message is displayed. This check is also performed while uploading journal entry transactions.

Replicate Customer Signature

Check this box to indicate that customer signature should be replicated. On checking this option, the signature of the customer gets defaulted to account level.

No. of Days For Salary Block

Specify the number of days for salary block. At the time of salary credit in to a customer account, the system will place an amount block for the number of days specified here from the date of salary credit. The amount blocked will be equal to the loan instalments due during this period.

Example

For single loan installment:

No. Of Days for Salary Block	: 15 days.
Salary credit amount	: 10000 AED credited on 30-Oct-2009
Loan1 Installment Amt	: 5000 AED due on 05-Nov-2009

System will check for the Loan installments falling due till 14-NOV (salary credit on 30-Oct + 15). The system will put an amount block of 5000 AED with expiry date as due date i.e. 05-Nov-2009 and Effective date as Application date i.e. 30-Oct-2009. The created amount block will have amount block purpose code as '05' and Remarks field will be populated with Loan A/c Number.

Note: For a given loan account schedule, all the applicable component amounts are summed up and a consolidated amount block will be created.

These amount blocks created by system for hold on salary purpose cannot be amended by users and only can be closed if required for the purpose of doing a manual liquidation for loan prepayment.

For multiple Loan instalments:

No. Of Days for Salary Block	: 15 days
Salary credit amount	: 10000 AED credited on 30-Oct-2009
Loan1 Installment Amt	: 5000 AED due on 05-Nov-2009
Loan2 Installment Amt	: 3000 AED due on 10-Nov-2009

In this case, 2 block amount transactions will be placed by system on 30-oct-2009 (on Salary credit date) in the order of loan installment due date with block amounts.

No of days for Closing Unauthorized Accounts with No Activity

Specify the number of days after which the unauthorized accounts without any activity should be automatically closed.

No of days for Closing Authorized Accounts with No Activity

Specify the number of days after which the authorized accounts without any activity should be automatically closed.

Enabling Printing of Account Statistics

You can enable printing statistics in respect of accounts using an account class, either period code-wise or financial year-wise, for the following customer information:

- Low and High Balance for a period—The lowest and highest current balances for the period.
- Average credit and debit balance for a period—This is computed as the sum of credit/(debit) current balances in a period, divided by the number of days of credit/(debit) balance during the period.
- Credit and debit days—The number of days the account was in credit/(debit) balance in the period.
- Credit and Debit Turnover—The credit/(debit) turnover for the period.
- Excess days in debit balance—The number of days in a month when the account exceeded the overdraft limits.
- Overdraft Limit—This is computed by summing the temporary overdraft limit and the sub-limit of the account. For each month, this would represent the limit on the last date of the month.
- Credit grade of the Customer—This would be the prevalent rating on the last day of the period. For the current period, this information is provided up to the previous working day.

To enable printing of this information for all accounts using an account class, you must enable the Account Statistics option in the Account Class Maintenance.

For each account class for which account statistics has been enabled, an accounting End of Day (EOD) process updates the statistics table both period-wise and according to financial years. The book-dated balances are used for computation of statistics, and the balances are maintained according to accounting periods.

For information about viewing the period-wise account statistics, refer the section Querying on Account Statistics, found earlier in this chapter.

Status Change Automatic

If you check this option, the status of the account will be changed automatically by the system as per the conditions maintained in the 'Status Rule Definition' screen. If you do not select this option, you have to change the status manually through the 'Manual Status Change' screen. These screens are discussed in detail in the subsequent sections of this document. This specification will be defaulted to all the accounts reporting to this account class.

Exclude Same Day Reversal transaction from Statement

If you do not wish transactions booked and reversed on the same day to be reflected in the account statement, you can specify the preference here. This feature is applicable only for the customer account legs and not for the related GL legs. Also, reversals made through the DE module will not be considered for exclusion.

Your specification for this at the account class level defaults to all accounts involving the class. You can change it for a specific account.

For comparing transactions the System will look for similarity of reference number and date.

Consolidation for Inward Clearing

You need to indicate whether or not consolidation is required for inward clearing transactions in a batch at the Account Class level. The indication for this option is carried forward to the 'Customer Account Maintenance' screen. If this option is unchecked here, it cannot be checked in the 'Customer Account Maintenance screen'.

3.2.5.1 Processing for Consolidation of Inward Clearing

During the Inward Clearing process, the consolidated entry for clearing will be passed according to the following grouping:

- Remitter's Account
- Clearing Product
- Instrument Currency
- Remitter's branch
- End point

A consolidated clearing entry will be passed using a separate Transaction Code maintained in the 'Clearing Product Preferences' screen. This Transaction Code should be set with Cheque Mandatory option as No in the 'Transaction Code Maintenance' screen.

One consolidated clearing entry will be passed for each of the above groups. Entries will be passed against a common reference no. generated for each of the groups. After the consolidated entry has been passed, each individual instrument will be processed separately to pass charge entries (if applicable) at the transaction level.

Specifying Turnover Limit Preferences

You can specify turnover limits for an account class and thereby monitor the turnover in all accounts linked to the account class.

Turnover Limit Code

Specify a turnover limit code that should be linked to the account class. The adjoining option list displays all valid turnover limit codes maintained in the system using the 'Turnover Limit Maintenance' screen. You can choose the appropriate one.

3.2.6 Specifying Liquidation Preferences for Debit Interest and Charges

You must specify the liquidation preferences for debit interest and charges, for those accounts classes where interest/charge has to be debited from a Receivable GL before actually debiting the customer account. This feature is applicable only for the debit interest and any charges on the account calculated through the IC module. The preferences that you need to specify are:

- Liquidate Using Receivable - Indicates whether receivable tracking is required for IC Debit interest and IC charges
- Debit Notice – enabling this option indicates that a notification needs to be sent to customers before debiting the customer account for the interest / charge calculated for the period.
- Liquidation Days – specifies the number of working days from the actual liquidation date before the interest/charge can be liquidated into the customer account. Working days are calculated on the basis of the Local Holiday Calendar.
- Liquidation Mode – debit interest or charges can be liquidated either Manually or Automatically. If you choose the automatic mode of liquidation, debit interest or charges are liquidated automatically as part of the BOD process on the liquidation date. However, after having specified Auto as the mode of liquidation, if you wish to liquidate them manually for a specific account, the System intimates you with an override message. Manual interest liquidation can be triggered through the 'Debit Interest Liquidation' screen. Manual liquidation is recommended during Account Closure.
- Verify Funds –enabling this option indicates that an available balance check should be performed for receivable tracking. As a result, the System performs the available balance check before debiting the account. The available balance also includes the limit amount. Verification of funds is applicable only in the case of Auto-Liquidation. If you leave this option unchecked, the System performs a 'force-liquidation' regardless of whether the account has sufficient funds or not.



Note the following:

- You will not be allowed to change these preferences at the account level. However in the Amounts and Dates section of the 'Customer Accounts Maintenance' screen, both the total debit interest due as well as the charges due, are displayed.
- If there is any outstanding interest or charges on the account, the outstanding amount is displayed as an override while saving the transaction involving the account.

- While closing an account closure, the System verifies whether there is any outstanding debit interest or charges on the account. You will need to liquidate these before Account Closure.

An error log is created to store the error details of accounts for which liquidation could not be performed due to the following reasons:

- The Verify Funds option is enabled and partial liquidation is performed
- The Verify Funds option is enabled and the account has insufficient funds
- Accounting entries do not get passed successfully irrespective of whether the Verify Funds option is set or not.

Refer the End of Day processing for Debiting Receivable GLs section in the Daily Processing of IC chapter of the IC User Manual for details on end of day processes on Auto and Manual liquidation.

3.2.7 Maintaining Details for Free Banking

For account classes for which a free banking period is being provided, you can indicate the free banking parameters. These include:

- The number of days after the account opening date, for which no charges would be levied on the account. This is the free banking period. Charging for the account would commence when the free banking period has elapsed.
- Whether an advice (charge start advice) is to be sent to the customer, indicating the commencement of charging on the account
- The number of days before the charge start date, the charge start advice is to be sent to the customer, indicating the commencement of charging on the account.

3.2.8 Specifying Initial Funding Preferences

You need to specify the following details pertaining to initial funding for opening accounts under the account class.

Event Class Code

Specify the event class code maintained for initial funding process for the module code 'DE'. This adjoining option list displays all valid event class codes maintained in the system. You can choose the appropriate one.

Charge Role to Head Code

Specify the class code that you wish to use for posting charge-related accounting entries for initial funding. This adjoining option list displays all valid class codes maintained in the system. You can choose the appropriate one.

Refer the section 'Maintaining Event Class for Account Initial Funding' in the chapter titled 'Creating Classes' under Modularity User Manual for further details about the event class code.

3.2.9 Maintaining Provisioning Details

When you define an account class, you can specify whether provisioning is applicable for accounts using the class. You can make the following specifications in the Provisioning Details section in the 'Account Classes' screen:

- Auto Provisioning Required - Check this box if provisioning is applicable
- Provision Frequency - Frequency at which the provisioning would be done, either daily or monthly



The frequency you define here is only applicable if you have indicated individual account-wise status processing for accounts in the Branch Parameters. If you have indicated status processing at Group/CIF level, then the provisioning batch process executes at the frequency maintained in the 'Branch Parameters' screen for your branch, and not at the frequency maintained in the Account Classes screen.

- The currency in which the provisioning amount must be calculated – either account currency or local currency
- Default exposure category for accounts using the account class
- Event class for which the provisioning accounting entries would be defined

The specifications you make here are inherited by any account that uses the account class.

In addition to these preferences, you must also indicate:

- The accounting roles and heads representing the GLs to which the accounting entries for provisioning must be passed, for each account status
- Whether provisioning entries for an account must be rebooked when provisioning is done after an automatic status change for the account
- Specify the provision code to pick up the provision percentage for the calculation. The adjoining option list displays the provision code maintained in the 'Provision Coverage Maintenance' screen.

You can maintain these details for each account status in the 'Status Details' screen.

3.2.10 Maintaining Escrow Details

The following Escrow details can be maintained for the account class:

Escrow Transfer Applicable

Check this box to enable Escrow transfer for the accounts belonging to the selected account class.

Transaction Code

Select the Transaction Code to be used for Escrow transfer from the adjoining option list. The option list displays only those transaction codes which are not enabled for Escrow processing at the 'Transaction Code Maintenance' screen.



This is a mandatory input if Escrow transfer is enabled for the account class.

Transaction Code for Reversal

Select the transaction code to be used for Escrow Reversal transactions from the adjoining option-list. The option list displays only those transaction codes which are not enabled for Escrow processing at the 'Transaction Code Maintenance' screen.



During account class amendment, the system does not allow you to disable Escrow process for an account class if a Project account has been created using that account class.

Cash Deposit Limit on Trust Account

If you have checked the box 'Escrow Transfer Applicable', you will have to specify the maximum cash that can be deposited in the Trust accounts under this account class.

3.2.11 Maintaining Status Codes for Account Class

Current and Savings accounts that have not generated any interest over a specific period or have remained inactive with interest overdue may be identified as 'NPAs' (Non-Performing Asset). In Oracle FLEXCUBE, you can assign different status codes to an account class, which will be applicable to all the accounts under it. The accounts will move from one status to the other based on the number of days they have remained inactive in the system. The status of an account will determine whether the account should be marked as an NPA or not.

Further, you can also specify the reporting lines (for GL, Central Bank, and Head Office) to which accounting entries should be passed when an account moves from one status to the other. You can post all debit and credit balances of one account class to a single General Ledger account. Conversely, you also have the option of posting debits and credits to separate GLs.

The status codes and the reporting lines for each status may be defined in the 'Status Details' screen. Click the 'GL Lines' button in the 'Account Classes' screen to invoke it.

The screen is as shown below:

The screenshot shows the 'GL Lines' form in Oracle. It includes a search bar at the top with 'Account Class' and 'Description' fields. Below this are fields for 'Status' and 'Description', along with a checkbox for 'Rebook Provisioning on Status Change'. The form is divided into two main sections: 'Debit Reporting Lines' and 'Credit Reporting Lines'. Each section has a header field (Debit or Credit) and three empty rows for data entry. At the bottom, there is a 'Status Details' table with columns for 'Account Role', 'Role Description', 'Account Head', and 'GL Description'. The table is currently empty. The form also features navigation icons and 'Ok' and 'Cancel' buttons at the bottom right.

You can specify the following details in this screen:

Status

You can select the different status codes applicable to the account class, in this field. Use the Add icon to define each status and the attributes for the same. You can use the navigation icons to move from one status to the other.

Only status codes with status type 'Account' will be available in the option-list if the Status Processing Basis is defined as 'Contract/Account' for all branches, in the Branch Parameters. If the Status Processing Basis is defined as 'Group/CIF' level for any branch, then the statuses of type 'Both' are available. In this case, it is mandatory to link all the statuses defined.

On selection of the status, the associated description will be displayed alongside.

3.2.12 Specifying Reporting line Details

Dr and Cr GL Lines

Select the debit GL account, to which all debit balances within a specific account class will report to, when it moves to the status being defined. You can identify the debit GL from the list of existing GLs. Likewise, all credits within a particular account class will report to the GL account that you have identified to track credits.

Dr and Cr Central Bank Lines

Select the Central Bank Debit line to which all debit accounts belonging to an account class should report to when it moves to the selected status. You have maintained Central Bank Debit lines in the 'Reporting Lines Maintenance' screen. You can select the appropriate CB Debit Line from the available option-list.

Similarly, all accounts belonging to an account class, if in credit should report to a Central Bank Credit Line for the selected status. You can identify the CB Credit Line that should be associated with the status from the option-list available.

Dr and Cr Head Office Lines

This is the Debit Head Office GL maintained in the 'Reporting Lines Maintenance' screen to which all accounts belonging to this class will report, if they move to the status being defined.

Similarly, select the Credit Head Office GL maintained in the 'Reporting Lines Maintenance' screen to which all accounts belonging to this class will report to, when they move to the status being defined.



As a mandatory requirement, you have to associate the status 'NORM' (Normal) when maintaining status codes for an account class.

Accounting Roles and Heads for Provisioning

In addition to the provisioning preferences that you specify for an account class, you must also maintain the accounting roles and heads representing the GLs to which the accounting entries for provisioning must be passed, for each account status. You can maintain this information in the 'Status Details' screen, when you define each of the status codes.

Rebook Provisioning on Status Change

In the 'Status Details' screen, you can indicate whether provisioning entries for an account must be rebooked when provisioning is done after an automatic status change for the account. Rebooking essentially means that fresh provisioning is done, after writing back the previous provisioning amount.

The provisioning batch process, when executed, not only computes the provisioning amount; it also records the current status of the account and checks whether the current status is different from the status that was prevalent when the process was previously executed. If so, the old provisioning amount is reversed (*if* the Rebook Provision option has been set in the Status Details), and the entries for the new provisioning amount are booked into the provisioning and write back GLs maintained for the current status in the Status Details.

If the Rebook Provision has not been set, there is no reversal of the old provisioning amount, and the differential provisioning entries are passed, as usual, into the GLs maintained for the new status.

3.2.13 Maintaining Auto Deposits

Auto deposits are the linked deposit accounts to the savings accounts. These accounts are created once the threshold balance exceeds in the customer accounts. You can maintain these accounts using 'Auto Deposits' screen. Click the button 'Auto Deposit' in the 'Account Class Maintenance' screen to invoke it.

The screen is as shown below:

The screenshot shows the 'Auto Deposits' dialog box with the following fields and options:

- Account Class: [Text Input]
- Transaction Code: [Text Input]
- Currency: [Text Input]
- Minimum Required Balance: [Text Input]
- Cluster Identification: [Text Input]
- Def Rate Code: [Text Input]
- Def Rate Type: [Dropdown Menu: Mid]
- Sweep Mode: [Dropdown Menu: Automatic]
- Break Method: [Dropdown Menu: FIFO]
- Break Deposits First
- Provide Interest On Broken Deposit

You have to specify the following fields in this screen.

Account Class

Specify the deposit type of account class for the auto deposit account.

Transaction Code

Specify the transaction code (DPN - New deposit account) for the book event to trigger at the time of creation of auto deposit account.

Currency

Specify the currency in which the deposit account has to created.

Minimum Required Balance

Specify the balance that is required to be maintained at the linked savings account. If any balance exists beyond this balance in the account then the system creates an auto deposit account as part of batch process.

Cluster ID

The system displays the cluster ID linked with the deposit account class linked to the saving account class.

Def Rate Code

Select the code of the differential rate; whether 'Mid' or 'Standard'.

Def Rate Type

Select the type of differential rate code; whether 'Mid' or 'Buy' or 'Sell'

Sweep Mode

Select the mode of sweep from the following options.

- Automatic - For the deposit to be created as part of the batch

- Manual - For the deposit to be created manually

Break Method

Select the method in which the break of auto deposit should happen, from the following options.

- MAXB - The system breaks the maximum valued deposit account or the deposit account having the maximum balance in order of descending amount.
- MINB - The system breaks the deposit account having minimum balance in order of ascending amount.
- FIFO - The system breaks the deposit account in order of chronological account creation date.
- LIFO - The system breaks the deposit account in order of reverse chronological account creation date (the latest created deposit account breaks first).

Provide Interest On Broken Deposit

Check this field to indicate the system to calculate interest on the deposits. This is done when the attached account class is mapped to the IC product.

Break Deposits First

Check this field to indicate the system to break the deposit accounts created and transfer the proceedings to the savings account. The system breaks the deposits when the savings account does not have sufficient balance to withdraw the amount.

In this case the system breaks the auto deposit account and restores the savings account with balance to allow withdrawing the money.

Example

The customer has the total balance in the account for \$5675 including \$650 as auto deposit. He withdraws \$5500 from an ATM. As part of intraday batch (DESWPBAT), the system breaks the auto deposit account of \$650 and restores the balance amount to savings. So his current standings would be \$175 in his savings account and he does not hold any auto deposit account.

3.2.14 Maintaining Rules for Automatic Status Change

If you have opted for automatic status change for all accounts belonging to an account class, you have to maintain the criteria based on which the system will bring about the status change automatically.

You can define the different criteria in the 'Status Rule Definition' screen. Click the button 'Status Rule' in the 'Account Class Maintenance' screen to invoke it.

The screen is as shown below:

The screenshot shows a 'Status Rule Definition' dialog box. It includes fields for 'Account Class', 'Description', and 'Sequence Number'. A section titled '- Derivation Rule' contains five 'Status Rule' fields. On the right, there are dropdowns for 'Elements' and 'Logical Operators', a 'Status' field with 'P', a 'Status Reason Code' field, and a 'Status Reason Description' field. There are also 'Forward' and 'Reverse' checkboxes and 'Ok' and 'Cancel' buttons at the bottom.

In this screen, you can define five conditions for each status applicable to an account class. An account will be said to be in a specific status if any one of the five conditions associated with the status holds true for an account. Conversely, if all the conditions are false, the account will automatically move to the next available status for which the condition is true.

The following elements are available based on which you can build a condition for automatic status change. You can associate each of these elements with an account, in the 'Customer Accounts Maintenance' screen.

The set of elements are as follows:

- Frozen
- Dormant
- Nodebits
- Nocredits
- Stoppayment
- Current Status

In addition, the following elements will also be available for processing:

- OD (overdraft) Days
- Inactive Days
- Overline Days
- TOD (Temporary Overdraft) Days
- Customer Classification

For OD Accounts, you can maintain the following rules for CROF and 'SUSP'/'WOFF' statuses of 'Write-off' processing:

Status	Rule	Remarks
CROF	OD_DAYS>150 AND OD_DAYS<=1095	If the account is overdraft for more than 150 days, then you can change the account status as write-off
SUSP / WOFF	OD_DAYS>1095	If the account is overdraft for more than 1095 days, then you can change the account status as suspended

Logical Operators

Logical Operators are indicators of certain conditions that you specify while building a rule. These operators are used in combination with the elements discussed earlier. The following is a list of logical operators that you would require to build a status rule:

AND	The conjunction 'and'
OR	The conjunction 'or'
>	Greater than
>=	Greater than or equal to (please note that there is no space between the two symbols)
<	Less than
<=	Less than or equal to (please note that there is no space between the two symbols)
< >	Not equal to (please note that there is no space between the two symbols)
=	Equal to

Status Reason Code

Specify the reason code for the status movement from the adjoin option list.

Status Reason Description

System displays the reason description based on the reason code selected.

Forward

Check this box to indicate that the forward status movement is automatic. If this box is unchecked, then the status movement will be manual.

Reverse

Check this box to indicate that the reverse status movement is automatic. If this box is unchecked, then the status movement will be manual.

Oracle FLEXCUBE allows data store for tracking of SOD debit interest due. During Interest liquidation for debit interest, the system populates the SOD Debit Interest Due Data Store with the Amount Due as debit interest for the SOD utilized amount and the due date of payment for the interest amount.

The debit interest due amount is adjusted in the SOD utilized amount and the system checks for any credit entries for the SOD corresponding to the debit interest. During EOD, if any credit entry exists for the account, then the system does adjustments on the amount due for the SOD debit interest due data store. The system also adjusts the debit interest payment against the oldest available debit interest due amount, and so on.

Oracle FLEXCUBE provides SDEs for 'SOD Due Count' and 'SOD Overdue Days' for status rule generation. During EOD while running the status update batch, the system calculates SDE 'SOD Due Count' value as the count of the records having due amount not equal to zero from the SOD debit interest due data store. The system updates the 'SOD Overdue Days' with the number of days since the last debit interest payment done for the account.

Oracle FLEXCUBE provides an account status called 'DIDF' for an SOD account, which is available as part of 'Status Rule Screen'. If the 'SOD Due Count' or 'SOD Overdue Days' satisfies the condition specified in the status change rule, then the system changes the status for the account to 'DIDF'.

While running the status change batch, the system updates the 'No Debit' flag as 'Y' for 'DIDF' status account. If payment for the debit interest happens on the SOD account against the utilized amount, and if on recalculation the value of SDE 'SOD Due Count', or 'SOD Overdue Days' is not met, the status batch changes the status of the OD account from 'DIDF' to the previous account status and updates the 'No Debit' flag as 'N'.




Note the following:

- Amount block is not considered because of the possibilities of simultaneous utilizations of the SOD.
- Any credit transaction towards the SOD account is tracked under interest due for the SOD.
- Any impact on account status after the execution of account status change batch for the day, gets reflected in the next EOD execution.

3.2.14.1 Modifying Account Status Manually

For status movements that have to be performed manually on a customer account, you can use the 'Manual Status Change' screen. Invoke this screen, by typing 'STDSTMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Select 'New' from the Actions menu in the Application toolbar. The system will display 'Transaction Branch' screen. Here you can select the transaction branch.



Here you are allowed to book other branch transactions from the logged in branch. Also, you can query other branch transactions from the logged in branch. The system defaults the logged-in branch by default as the transaction branch.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This screen will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.



The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'Manual Status Change' screen.

The screenshot shows a software window titled "Manual Status Change Input". The window contains the following fields and options:

- Branch * 000
- Customer Account Number * (dropdown menu)
- Account Status
- Since * 2012-01-02 (calendar icon)
- New Status (dropdown menu)
- Status Code (dropdown menu)
- Status Reason Description (text input)
- P
- No Debit
- No Credit
- Frozen
- Posting Allowed
- Status Change Automatic
- Dormant

At the bottom, there is a "Fields" section with the following labels:

- Maker
- Checker
- Date Time:
- Mod No
- Record Status
- Authorization Status
- Exit button

Provide the following details in this screen to facilitate a manual status change:

Account No

Select the customer account for which you are marking a manual status change, from the option-list provided.

On selection of the account, the system will display the current status of the account as well as the date on which the account moved to the current status.

New Status

Specify the new status of the account. You can select the appropriate status from this list.

If Status Processing Basis specified in the Branch Parameters for all the branches is 'Contract/Account', only status codes maintained with status type 'Account' (in the 'Status Codes Maintenance' screen) will be available in the option-list. If Status Processing Basis for even one of the branches is specified as 'Group/CIF' level, then the only statuses available will be of type 'Both'.

Status Code

Specify the status code for the status movement from the adjoint option list.

Status Reason Description

System displays the status reason description based on the status code selected.

Account Statuses

In addition to the new status, you can also mark the account with any one of the following statuses, if required:

- No Credit – if checked, no credit movement will be allowed on the account
- No Debit – the system will not allow debit movements on the account if you select this option
- Frozen – if selected, no activity will be allowed on the account
- Posting Allowed – if checked, posting of accounting entries will be allowed in the account

Status Change Automatic

You can select this option if you want the subsequent status change for the account to be performed automatically by the system. After the account moves to the new status specified here, all subsequent status movements will be triggered automatically, during the EOD run for the branch. However, the changes will come into effect only upon authorization of the details maintained here. At a later date, you can switch back to the manual mode by unchecking this option and having the same authorized.

The manual status movement that you specify in this screen has to be authorized for the new status of the account to come into effect.

3.2.14.2 Maintaining Status Change Processing

For accounts marked with automatic status change, you can execute a batch process at EOD to trigger the status movement and other associated changes. Use the 'Account Status Update Processing' screen available in the Application Browser to begin the batch process.


If the Status Processing Basis defined for the branch is 'Group/CIF' level, the worst status for all loans and overdrafts accounts is calculated for a Group/CIF level. This status is displayed in the respective Group/CIF screens as well as at the respective account and contract screens. The individual status of each account and contract is also displayed in the accounts screen as 'Account Derived Status'.

Refer the 'Products' chapter of the Interest and Charges user manual for more details.

3.2.15 Maintaining Sequence for Funds Allocation

The allocation of funds will occur as per the product sequence you maintain in the 'Product Maintenance' screen invoked from the 'Account Class Maintenance' screen. Click the 'Amt Block' button to access this screen.

The screen is as shown below:



In this screen, you will specify the sequence of products based on which funds will be made available when a credit is posted to an account with a track receivable option. The sequence number is automatically generated by the system. All authorized products of your bank will be available in the option-list. On selection of the product, the product description will appear alongside.

Whenever a credit happens to an account with a track receivable option, the system will check if the account has any receivable being tracked against it. If yes, the amount is blocked as a receivable and this process continues until the amount needed for liquidation becomes fully available.

The batch process run as part of EOD/BOD will liquidate the loan contract or retail teller contracts.

If the amount received is not sufficient for full liquidation, then depending on the minimum amount required for liquidation, the system would initiate a partial liquidation for loans but for retail teller contracts liquidation will be initiated only when full amount is available.

The following example illustrates the manner in which the system will use the sequence for allocation of funds:

Assume that you have maintained the following product sequence for funds allocation:


Sequence No.	Product
1	ADBN
2	LDBD
3	ABCD

The liquidation schedule dates for the various loan contracts are as follows:

Contract	Liq. Schedule Dt.	Liqd. Amt. (in USD)
LDBD001	1 st January 2002	1000
LDBD002	1 st January 2002	500
ADBN001	2 nd January 2002	1000
ABCD001	2 nd January 2002	500

Further, all contracts are marked for auto liquidation and the settlement account for all contracts is A1. The balance in account A1 as on 1st January 2002 is 500 USD.


Batch liquidation run as part of BOD/EOD on 1st Jan.	Liquidation does not occur as the system detects insufficient funds in A1 (only 400 USD). The account is marked for receivable tracking and a block is placed on 400 USD.
A credit of 500 USD to A1 on 2nd Jan.	<p>The total amount blocked gets updated to 1000 USD. Since we have two contracts involving the same product (LDBD) maturing on the same date, funds will be allocated to the first contract, LDBD001 (based on the Contract Reference Number). Subsequent credits to the account will be used towards loan LDBD002.</p> <p>Since contracts with LDBD have earlier schedule dates, funds will be allocated to them though, as per the product sequence, contracts with ADBN should receive the funds first. The liquidation schedule date takes precedence in this case.</p> <p>Further credits to account, A1 will be allocated against the contract ADBN001 followed by the contract ABCD001. This will be based on the product sequence number since both contracts have the same schedule dates.</p> <p>Within a contract, allocation of funds towards the various components like interest, penalty interest etc. will be determined by the 'Liquidation Order' maintained for the loan product.</p> <p>To sum up, the schedule date of the loan contract takes precedence followed by the product sequence and finally the liquidation order.</p>

 If insufficient funds are detected in an account with a receivable tracking, the system will trigger the event 'LBLK' indicating that enough funds are not available and that subsequent credits made to the account will be blocked as a receivable.

3.2.16 Maintaining Transaction Restrictions for Account Class

You can place restrictions on transactions involving customer accounts, at the account class level. As discussed earlier (for customer account), these restrictions get defaulted to all accounts that are linked to the account class. But you are allowed to change these restrictions for individual accounts as well.

To maintain the restrictions click the 'Restriction' button in the 'Account Classes' screen. The 'Product and Transaction Codes Restriction' screen is displayed.



The restrictions can be based on:

- Products
- Transaction Codes

Validation of Restrictions

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account class used by the specified account is restricted for the product that has been selected, or the debit/credit transaction type. If so, an override is sought when such contracts are saved.

3.2.17 Maintaining Details of Account Statements Generation

To receive the details of account balances you need to capture the relevant information in the MT 941/MT942 message. The account balance details can be linked to the message by employing the statement screen. To invoke this screen click on the 'Statement' button, in the 'Account Class Maintenance' screen. You need to specify the details for an MT 941/MT942 message.

The screen is as shown below:

The screenshot shows a software dialog box titled "Interim Transactions and Balance Report". It is divided into two main sections: "Interim Transactions Report" and "Balance Report".

Interim Transactions Report Section:

- Two checkboxes: "Generate Message" and "Generate Message only on Movement".
- Two dropdown menus: "Report Transactions Since" and "Interim Report Type".
- Two data grids side-by-side:
 - Left grid: "Minimum Debit Amount". Header: "Currency *", "Amount". Includes "Go to Page" control.
 - Right grid: "Minimum Credit Amount". Header: "Currency *", "Amount". Includes "Go to Page" control.

Balance Report Section:

- Checkbox: "Generate Balance Report".
- Dropdown menu: "Report Transactions Since".
- Dropdown menu: "Of".

At the bottom, there are two tabs: "Times - Interim Transactions Report" and "Times - Balance Report". "Ok" and "Cancel" buttons are located in the bottom right corner.

This screen contains the details necessary for the account generation parameters. The message details the balance of an account or group of accounts under a particular account class. The account balances indicate the condition of the account for an identified time period.

3.2.17.1 Specifying Interim Transactions Report

Generate Message

Check this box to indicate that the accounts belonging to the account class are to be considered for periodic interim statement generation i.e., MT942.

Generate Message Only On Movement

Check this box to indicate that the interim statement needs to be generated only if additional entries have been posted subsequent to the previous interim statement generation.

Report Transaction Since

This is a list of all the transactions the accounts under a class have undergone, on basis of which the transactions would be reported in the interim account statement. You can choose the appropriate values applicable:

- Previous MT942: This indicates that all transactions posted and authorized since previous MT942 would be sent in the current interim statement
- Previous MT940/MT950: This indicates that all transactions posted and authorized since previous MT940/MT950 would be sent in the current interim statement. If this option is selected, user will have to specify the cycle of account statement to be considered.

Minimum Debit Amount and Currency

Specify the minimum transaction amount for the debit transaction, which is eligible for reporting in the interim statement. This amount should be qualified by a currency. The amount for the corresponding account currency will be defaulted from here while opening the account.

Minimum Credit Amount and Currency

Specify the minimum transaction amount for the credit transaction, which is eligible for reporting in the interim statement. This amount should be qualified by a currency. The amount for the corresponding account currency will be defaulted from here while opening the account.

Generate Balance

To indicate that accounts under certain account classes are to be considered for generation of their balance messages, check this box. The valid values for this action are Y and N.

Of


Select the mode of message for balance generation from the option list

Report Transaction Since

This is a list of all the transactions the accounts under a class have undergone, in the interval of balance messages generated for the accounts under the respective classes. You can choose the appropriate values applicable:

- Previous MT940: This indicates all transactions posted and authorized since the issue of a previous MT 940 in the current balance report.
- Previous MT941: This indicates all transactions posted and authorized since the issue of a previous MT 941 in the current balance report.
- Previous MT950: This indicates all transactions posted and authorized since the issue of a previous MT 950 in the current balance report.

You can synchronize the time instance by hours for generation of balance messages by clicking the 'Times' button.



This screen is employed to indicate the the time instance in hours for the generation of the balance reports.

Message Generation Time

Specify the timing for generation of the MT 941/MT942 messages. You can specify the time interval in hours only.

A new message type is created for the balance report process which can be run as part of a scheduled task. This message type is ACST_BALANCE and ACST_INT_DTL.

3.2.17.2 Balance Statement Handoff

The balance statement can be handed off as part of scheduled task under Oracle. You need to assign its frequency in hours. This process is initiated for all accounts requiring a balance account statement. As discussed previously the time for generation of the statement is determined and specified. In case of no subsequent transactions reports, the statement is not generated.


3.2.17.3 Assigning Balance Statement as Job

The balance statement can be facilitated to run as part of a scheduled job as part of the Oracle jobs initiated during processing.

The 'Jobs Browser' screen of the application provides you the facility to run the balance statement as a synchronized task, subject to specified time intervals in hours.

Invoke the 'Jobs Browser' screen from the application typing 'CSSJOBBER' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screen is as shown below:




Select the option 'Generate Balance Report' from the Process option list. All associated accounts of the particular branch that have been marked for generation of balance statements are procured by Oracle FLEXCUBE.

The debit and credit accounts considered since the previous issue of an MT 941 are picked for the current processing. The previous messages are based on the parameters maintained for each account. This processing produces details of the statement generation.

3.2.17.4 Generation of Ad hoc Reports

Balance reports for each account under an account class can be generated on an ad hoc basis. The Ad Hoc report generation screen is used for capturing details of a balance report sent ad hoc. You can invoke this screen by typing 'ACDADCRP' in the upper right corner of the application toolbar, and clicking the arrow adjacent it.



Branch Code

The branch to which the account marked for balance report generation belongs is displayed; you cannot change or modify this value.

Account

Select the account which has been identified for generation of a balance statement, from the option list. The account balance of this account is generated as an outgoing statement.

Swift Message Type

Select the type of message required to be sent. As the message is a balance statement, select MT941/MT942.

Click on the 'Generate Statement' button to initiate the generation of balance statement for the account you have selected. This process would pick up the entire debit and credit component accounts created since the issue of a previous MT941, MT942, MT950 or MT940 are included in the generated statement.

You can examine the details of the generated message, to ensure that all details entered are correct. Click on the 'View' button, to observe the outgoing message.

The screenshot shows a window titled "Message Details" with a blue header and a white body. At the top right of the window are standard window controls (minimize, maximize, close). Below the header, there are three navigation buttons: a left arrow, a right arrow, and a plus sign. The main area contains several input fields and labels: "Reference Number" with a text input field, "DCN*" with a text input field, "Version Number" with a text input field, and "Swift Message Type" with a dropdown menu. At the bottom of the window, there are three labels: "Remarks", "Reject Reason", and "Message Trailer", each followed by a horizontal line representing a text area. In the bottom right corner, there is an "Exit" button.

You can examine the message for ensuring the information entered is complete. You can only view the details of the message; no input of additional information is supported at this stage.

3.2.18 Specifying Regulation D Applicability for Account Class

For an account class, you can define whether the Regulation D limits are applicable, and the period over which the limits would be applicable. In the 'Account Class Maintenance' screen, click the 'REG' button to invoke the 'Reg Details' screen. You can specify the Regulation D applicability details in this screen.



The screenshot shows a dialog box titled "REG Details". It contains a checkbox labeled "Applicable" which is unchecked. Below it, under the heading "Periodicity", there are three radio buttons: "Monthly", "Statement Cycle", and "None". The "None" radio button is selected. At the bottom right of the dialog, there are two buttons: "Ok" and "Cancel".

If you indicate the periodicity of Regulation D applicability as 'Statement Cycle', the restricted transactions would be counted over the primary statement cycle defined for the account class.

The Regulation D applicability details specified for an account class would default to all accounts using the class. However, you can make changes to these details when you set up a customer account that uses the account class.

3.2.19 Assigning Preferred Branches, Currencies and Customers

In addition to what you have specified in the 'Account Class Maintenance' screen you have the option of specifying the following for an accounts class:

- List of allowed or disallowed branches and allowed or disallowed currencies
- List of allowed and disallowed customer categories and allowed and disallowed customers

You can specify the branch and currency preferences through the 'Account Class – Branch and Currency Preferences' screen.

Click 'Branches/Currencies' in the 'Account Class Maintenance' screen. The 'Account Class – Branch and Currency Preferences' screen will be displayed.

The screen is as shown below:

Branch Currency

Account Class

Branch Details | Currency Details

Branch Restrictions Allowed Disallowed

Available Branches

Branch Code

Currency Preferences

Ok Cancel

In this screen you can specify the following for an account class:

- Those branches to which all parameters defined for this account class should be available
- Those currencies in which all customer accounts linked to this account class can operate


3.2.20 Maintaining Branch Preferences

Customer accounts maintained in any branch can be linked to any account class. However, you have the option of restricting the linkage of customer accounts in a particular branch or branches to an account class.

Example

Your bank has a total of 25 branches. Branch 001 and 004 handles only Corporate Customers. For an account class, say, SAV-IND (savings accounts of individuals) you would like to disallow linkage of all customer accounts of branch 001 and 004.

To specify this, click on disallowed since the disallowed branch list is smaller than the allowed branch list. From the list of Available Branches select 001 and click the adjoining arrow. Repeat the procedure for 004. 001 and 004 will be listed under disallowed branches.

 For specifying the allowed list of branches, first click on allowed. You will notice that the list title changes accordingly to allowed and vice versa. You should select allowed or disallowed depending upon the length of the list.

3.2.21 Maintaining Currency Preferences

For all accounts under this account class you have the option of specifying currencies in which transactions are allowed/disallowed.

Example

You want to restrict all account level transactions under the account class Corporations for corporate type accounts to four important currencies only, say - USD, GBP, JPY, and DEM. You can specify the same. But currency preference needs to be accompanied by specifications regarding the minimum balance limit in each currency.

To do this, click the 'Currency Preference' button. The 'Account Class - Currency Preferences' screen will be displayed.

<input type="checkbox"/>	Currency Code *	Minimum Balance	ATM Cash Limit	ATM Transaction Limit	Cash Deposit Limit on Trust Account
--------------------------	-----------------	-----------------	----------------	-----------------------	-------------------------------------

All the allowed currencies you have defined for this account class will be displayed in the option list adjoining the 'Currency Code' field. You can enter the minimum balance that should be maintained against each currency. You can also specify the minimum amount that should be deposited at account opening. This value should not be less than the minimum balance for the currency. Additionally, you can specify charges that should be levied against each currency for opening a customer account. You can also maintain the maximum number of ATM transactions that can be carried out on every currency. Similarly, you can maintain the maximum cash that can be withdrawn from an ATM for every currency. If the box 'Escrow Transfer Applicable' is checked for the account class, you can capture currency-wise cash deposit limit for the Trust accounts linked to the account class.

3.2.22 Maintaining Customer Preferences

Instead of linking each customer account to an account class, a customer category is linked to the class.

For an account class you should specify the category that should be linked to it and also specify if all customers under each of the categories are to be linked to the account class. In the 'Account Class - Customer List' screen you have the option of specifying the categories that should be linked to this account class and within a category you can also restrict individual customers to be linked to the class.

To indicate allowed customer categories click the 'Customer/Categories' button. The 'Account Class - Customer List' screen will be invoked.

The screenshot shows the 'Account Class - Customer List' interface. At the top, there are two text boxes for 'Account Class' and 'Description'. Below them are two tabs: 'Category' and 'Customer'. Under the 'Customer' tab, there is a 'Selection Indicator' section with two radio buttons: 'Allowed' (selected) and 'Disallowed'. Below this is a table titled 'Customer Categories' with one row containing a checkbox and the text 'Customer Catageory *'. The table is currently empty. At the bottom right, there are 'Ok' and 'Cancel' buttons.

In this screen you define the following:

- A list of allowed or disallowed customer categories
- A list of disallowed customers (if any) under the allowed category

For an account class you need to specify the customer categories that should be linked to it and also customers within a category who should not be allowed to be linked to this account class.

Example

Requirement

You are capturing the features of a Nostro account class called NostroLCY, you would like to:

- Associate the customer category called Banks with NostroLCY
- Disallow a customer called Midas-Bank associated with the customer category called Banks from using the features of this class
- Grant your customer Morgan Stanley linked to the customer category called Financial Institutions all rights associated with NostroLCY

Procedure

In the Selection Indicator field click on Allowed (since your allowed list is smaller and therefore easier to indicate).

1. Highlight and select the Customer Categories called Banks and Financial Institutions in the Available Categories list and click the adjoining arrow.
2. Next, highlight Financial Institutions and click adjoining arrow against Customers. It will display the entire list of customer accounts maintained under the customer category Financial Institutions
3. Select Morgan Stanley. It will be listed in the first row. To allow this customer the parameters assigned to this account class check the small square box alongside
4. To add a row, click the Add icon. To delete an extra row, click the Delete icon
5. To disallow Midas Bank, click on Banks under available categories. Click the adjoining arrow against Customers, to display a list of all the customers under this category. Select Midas Bank. Since you would like to disallow this customer do not check the square box against it




Check the square box to allow a customer the parameters assigned to this account class. Leave the box unchecked to disallow a customer from being assigned to this account class.

3.2.23 Specifying Balance Account Codes

To generate account numbers as per the requirements of NBU (National Bank of Ukraine), special numbers called balance account codes are maintained. Every account class will be linked to a set of balance account codes. The account numbers of all accounts belonging to an account class should start with any of the balance account codes linked to that account class.

You can indicate the list of balance account codes to be linked to an account class in the 'Balance Account Code' screen. Click Balance Account Codes in 'Account Class Maintenance' screen to invoke this screen.



The account class and its description get defaulted in this screen. You can specify the following details here:

Balance Account Code

Specify the balance account code to be linked to the account class or select the same from the option list provided. All balance account codes maintained in 'Balance Account Code Maintenance' screen are displayed here.

The following table indicates the account codes to be maintained for different types of account classes:

Account class	Balance accounts according to NBU chart of accounts
Current accounts of legal entities	2600,2601,2602,2603,2604,2605,2606
Current accounts of individual persons	2620, 2622, 2625
Budgetary current accounts	2520, 2523, 2526, 2530, 2531, 2541, 2542, 2544, 2545,

Account class	Balance accounts according to NBU chart of accounts
	2553, 2555, 2560, 2561, 2562, 2565, 2570, 2571, 2572
Savings Account	2620, 2625
Current accounts of election funds , non banking financial organizations	2640, 2641, 2642, 2643, 2650, 2655
Deposits of legal entities	2610, 2611, 2615
Deposits of individual persons	2630, 2635
Budgetary deposits	2525, 2546
Deposits of non banking financial organizations	2651, 2652

3.2.23.1 Maintaining Balance Account Codes

You need to maintain balance account codes to be used for generating account number according as per the requirements of NBU (National Bank of Ukraine), You can maintain balance account codes in 'Balance Account Code Maintenance' screen.

You can invoke this screen by typing 'STDBALAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details in this screen:

Balance Account Code

Specify the balance account code to be used to indicate the type of an account class.

The balance account code should not start with zero (0). If you specify an account code that starts with the digit '0', then the system displays the following error message

The First Number Cannot be 0

The balance account code is applicable only if the country of the current branch is Ukraine. However, the balance account code can be maintained even in other countries.


Description

Specify a suitable description for the account class.

3.2.24 Maintaining Notice Preferences

You can specify the notice preferences for the withdrawal of amount through the 'Notice Preferences' screen. Click 'Notice' in the 'Account Class Maintenance' screen.

The 'Notice Preferences' screen is displayed as follows:



The screenshot shows a window titled "Notice Details" with a blue header bar. Inside the window, there are several input fields and a checkbox. The fields are labeled "Account Class", "Account Description", "Monthly Free Amount", "Notice Days", and "Validity Period". There is a checkbox labeled "Advance Interest" which is currently unchecked. At the bottom right of the window, there are two buttons: "Ok" and "Cancel".

The following fields are displayed in this screen:

- Account Class – The unique code assigned to the account class is displayed
- Description – A short description of the account class is displayed

The following are the notice preferences that you can specify for an account class:

Advance Interest

Check this field to levy the advance interest on the account class.



Note the following:

- The customer of the account class is liable to pay this interest in case he/she fails to provide the required notice to the bank.
- The system deducts the advance interest from the credit Interest earned by the customer of the account class on his/her credit balance in the account.

Monthly Free Amount

Specify the amount that a customer of the account class can withdraw per calendar month from his/her savings account without being liable to pay advance interest.

Notice Days

Specify the number of days before which a customer of the account class should notify the bank if he/she wants to withdraw an amount more than the 'Free Amount' from his/her account.

Validity Period

Specify the notice validity period in number of days. During this period, a customer of the account class can do the withdrawal of the amount for which he/she notified the bank.

3.2.25 Maintaining Account Class Transfer

Oracle FLEXCUBE facilitates the change of account class at the customer account level without changing the customer account number. Depending on the destination account class, system defaults the reporting GL lines and IC related values. The account class transfer can be initiated through the 'Account Class Transfer Maintenance' screen.

You can invoke the 'Account Class Transfer' screen by typing 'STDACTFR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Account Class Transfer' application window. At the top, there are input fields for 'Branch Code' (set to 000), 'Account *', 'Old Account Class', 'Account Class *', and 'Currency'. Below these fields are two tabs: 'Main' and 'Auxiliary'. The 'Main' tab is selected and contains three main sections: 'Effective Date' with a 'Next Liquidation Cycle' checkbox and an 'Effective Date' field; 'GL Details' with 'Status', 'Credit', and 'Debit' fields; and 'Preferences' with checkboxes for 'Cheque Book', 'Passbook', 'ATM', and 'Status Change Automatic'. At the bottom of the window, there are several tabs: 'Interest', 'Charges', 'Consolidated Charges', 'Statement', 'MIS', and 'Account Status'. The 'Account Status' tab is active, showing fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with a 'Cancel' button.

The following details are maintained here:

Branch Code

The current branch is defaulted here.

Account

Select the account number which requires an account class transfer, from the adjoining option list. This adjoining option list displays all valid accounts maintained at the account class level.

Old Account Class

The account class to which the selected customer account belongs is defaulted here.

Currency

The currency of the selected customer account is defaulted here.

Account Class

Select the new account class to which the customer account has to be transferred, from the adjoining option list. This adjoining option list displays all valid account class. When the account class is selected, the system checks whether the new account class is a valid one or not.

Click the 'Default' button to generate default parameters.

If the old and new account class are of different type, then the system will display the following Error Message on Save:

Old and new A/c class belongs to different a/c class types

Failed to Process the Request

Click 'Ok' to reset Account Class parameters.

If the old and new account class are of same type, then the system will display the following Override Message:

Provisioning details should be manually modified, if required

Click 'Accept' if you wish to continue. The system will display the following Information Message:

Request Successfully Processed

Click 'Ok' to continue. The following GL details are defaulted based on the values maintained at the Account Class level:

- Status

- Credit
- Debit

Effective Date

The effective date of account class transfer can be based on either next liquidation cycle or effective value date.

Next Liquidation Cycle

Check this box to indicate that the account class transfer should be effective from the earliest liquidation date of the products mapped to the account.

Effective Date

Select the effective date for account class transfer from the adjoining calendar.



System displays an error message in the following conditions:

- If the specified date coincides with a holiday
- If the effective date is not provided and the transfer is based on actual date
- If the selected customer account has an unprocessed record

GL Details

The reporting GL details of the account selected is defaulted here when you click 'Default' button.

Preferences

You can specify preferences for your account here.

Cheque Book

Check this box if you need a cheque book to be issued for your account.

Passbook

Check this box if you need a passbook to be issued for your account.

ATM

Check this box if you need to avail an ATM facility for your account.

Status Change Automatic

Check this box if you need automatic status change for your account.'

3.2.25.1 Auxiliary' Tab

Specify the auxiliary details by clicking 'Auxiliary' tab in the 'Account Class Transfer' screen.

The screenshot shows the 'Account Class Transfer' window with the 'Auxiliary' tab selected. The top section contains input fields for 'Branch Code', 'Account *', 'Currency', 'Old Account Class', and 'Account Class *'. Below this, the 'Main' and 'Auxiliary' tabs are visible, with 'Auxiliary' being the active tab. The 'Cheque Book Preferences' section includes a checkbox for 'Auto Re-order Cheque Required', a text field for 'Reorder Cheque Level', a text field for 'Reorder Number Of Leaves', and two text fields for 'Check Book Name 1' and 'Check Book Name 2'. The 'ATM Preference' section has three text fields: 'Atm Account No', 'Daily Amount Limit', and 'Daily Amount Count'. The 'Options' section contains five checkboxes: 'Lodgment Book', 'Consolidated Cert. Reqd', 'Back Period Entry Allowed', 'Referral Required', and 'Track Receivable'. A 'Remarks' field is present with a 'Processed Status' dropdown menu set to 'Un-Processed'. At the bottom of the window, there are tabs for 'Interest', 'Charges', 'Consolidated Charges', 'Statement', 'MIS', and 'Account Status'. Below these tabs are fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

Cheque Book Preferences

Maintain the following cheque book preferences if you have opted for a cheque book for your account in the 'Main' tab.

Auto Re-order Cheque Required

Check this box to automatically reorder cheque books for all accounts belonging to this account class.

Reorder Cheque Level

Specify the level at which you need a cheque book for the account.

Reorder Number Of Leaves

Specify the number of cheque leaves you need in the reordered cheque book.

Cheque Book Name 1

Specify the name used for opening savings account A1. This name will be printed on the cheque book and will be used for all cheque transactions.

Cheque Book Name 2

Specify the name if you need to enter the name of the joint account holder on the cheque book, if the customer account is joint operations account.

ATM Preference

You can maintain the following parameter if the ATM box is checked in the Main screen.

Atm Account No

Specify the valid ATM account number that should be linked to the new account class.

Daily Amount Limit

Specify the daily limit for the amount that can be withdrawn from the ATM.

Daily Amount Count

Specify the daily count for the amount that can be withdrawn from the ATM.

Options

You can maintain the following parameters for your account here.

Lodgement Book

Check this box if you need a lodgement book to be issued for the account.

Consolidated Cert. Reqd

Check this box if you need a consolidated certificate to be issued for the account.

Back Period Entry Allowed

Check this box if you need back period entries for the account.

Referral Required

Check this box if you need a referral check for your account.

Track Receivable

Check this box if you prefer to track the receivables for the account.

Remarks

Specify the reason for the account class change.

Processed Status

System displays the status of account class transfer here. The drop-down list displays the following options:

- Unprocessed–This status is defaulted till the account class transfer is effective.
- Processed–This status is defaulted when the account class transfer is effective.

3.2.25.2 Maintaining IC Special Conditions

You can maintain the interest and consolidated charges of the account class in the 'IC Special Conditions Maintenance' screen. The system would generate the details by default. You can manually maintain the products if IC special condition is applicable for this account-account class combination.

Click 'Interest' button in the 'Account Class Transfer' screen to invoke 'IC Special Conditions Maintenance' screen.

The screenshot shows the 'IC Special Conditions Maintenance' window. It features a top section with various input fields for account and date information. Below this is a 'Product Details' section with fields for Product and UDE Currency. The main area contains two data tables, each with a '1 of 1' indicator and navigation controls. The first table has columns for 'UDE Effective Date' and 'UDE Currency'. The second table has columns for 'User Defined Element ID', 'User Defined Element Value', and 'Rel'. At the bottom right, there are 'Ok' and 'Cancel' buttons.

The following details are captured here:

Branch Code

The current branch code is defaulted here.

Calculation Account

Select the valid customer account number for calculation from the adjoining option list.

Interest Booking Account

Select the valid customer account number from the adjoining option list.

Interest Start Date

Select to indicate the effective date to generate interest from the adjoining calendar.

Interest Booking Branch

Select to indicate valid Branch for calculating the interest from the adjoining option list.

Interest Statement

Check this box to generate the interest statement.

Charge Booking Account

Select the valid customer account number for booking the charge from the adjoining option list.

Charge Start Date

Specify to indicate the effective date to generate charges from the adjoining calendar.

Charge Booking Branch

Select to indicate the valid Branch from the option list, for calculating the charge.

Dr Cr Advices

Check this box to generate debit and credit related advices.

Consolidated Account

Select the valid account number from the adjoining option list.

Consolidated charge bank

Select the valid bank from the adjoining option list.

Product Details

You can specify product details for your account here.

Product Code

Select the valid product code from the adjoining option list.

UDE Currency

The system generates the user defined currency type maintained at 'Interest Product Preference' level.

Waive

Check this box if you need to waive of interest or charges defined for the selected interest product at the Interest Product Preference level.

Generate UDE Change Advice

Check this box if you need to generate advice for change in values of the User Data elements for the account.

Open

Check this box if you need to apply the selected interest product for the account.

3.2.25.3 Maintaining Account Level Charges Conditions

Click 'Charges' button in the 'Account Class Transfer' screen to invoke 'Account level charges conditions' screen.

The screenshot shows a software window titled "Account level charges conditions". It is divided into several sections:

- Account Details:** Includes text boxes for "Branch Code" (containing "000") and "Account" (containing "00000007501").
- Product Detail:** Includes text boxes for "Product Code" and "UDE Currency". To the right, there are input fields for "Minimum", "Maximum", and "Free Items". Below these are two checkboxes: "Waive Charges" and "Open".
- Slab Amount Table:** A table with columns "Slab Amount", "Charge Amount", and "Rate". The first row is checked with a green box. Below the table is a large empty area.
- Navigation and Controls:** At the top right of the Product Detail section, there is a "1 of 1" indicator with navigation arrows. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

The following details are captured here:

Account Details

You can maintain the account details here.

Branch Code

The current branch code is defaulted here.

Account

The system generates the account number maintained in the 'Main' screen of 'Account Class Transfer'.

Product Detail

You can specify the parameters related to product here.

Product Code

Select a valid product code from the adjoining option list.

UDE Currency

The system generates the user defined currency type defined for the selected charges product.

Minimum

Specify the minimum charge that can be applied for the account.

Maximum

Specify the maximum charge that can be applied for the account.

Free Items

Specify to indicate the number of items on which the charges are not levied.

Waive Charges

Check this box if you need to waive the charges defined for the selected charges product at the account level.

Open

Check this box if you need to apply the selected charges product for the account.

Slab Amount

You can specify the parameters related to slab amount here. You can add additional rows by clicking the '+' button and delete rows by clicking '-' button.

Slab Amount

Specify an amount slab for the charges maintained at the account level. Rate will be applied for the amounts less than or equal to the amount slab.

Charge Amount

Specify the charge amount applied for the selected product at the account.

Rate

Specify the rate to be applied for the charges maintained at the account level.

3.2.25.4 Maintaining Account Level Consolidated Charges Conditions

Click 'Consolidated Charges' button in the 'Account Class Transfer' screen to invoke 'Account Level Consolidated Charges Conditions' screen.

The screenshot shows a window titled "Account Level Consolidated Charges Conditions". It contains the following fields and controls:

- Account Details:**
 - Branch Code: 000
 - Account: 00000007501
- Product Details:**
 - Product: [Dropdown menu]
 - Currency: [Text box]
 - Minimum: [Text box]
 - Maximum: [Text box]
 - Open:
 - Waive:
- Discount:**
 - Discount Percentage: [Text box]
 - Discount Amount: [Text box]

At the bottom right, there are "Ok" and "Cancel" buttons.

The following details are captured here:

Account Details

You can maintain the account details for an account here.

Branch Code

The current branch code is defaulted here.

Account

The system generates the account number maintained in the 'Main' screen of 'Account Class Transfer'.

Product Details

You can specify product details for your account here.

Product Code

Select a valid product code from the adjoining option list.

Currency

The system generates the user defined currency type defined for the selected consolidated charges product.

Minimum

Specify the minimum consolidated charges that can be applied for the account.

Maximum

Specify the maximum consolidated charges that can be applied for the account.

Open

Check this box if you need to apply the selected consolidated charges product for the account.

Waive Charges

Check this box if you need to waive the consolidated charges defined for the selected consolidated charges product.

Discount

You can specify discount details for the consolidated charges applied for the account.

Discount Percentage

Specify percentage of the amount to be discounted from the computed consolidated charges.

Discount Amount

Specify a flat amount to be discounted from the computed consolidated charges.

3.2.25.5 Specifying Statement Details

Click 'Statement' button in the 'Account Class Transfer' screen to invoke 'Statement' screen.

The screenshot shows a dialog box titled "Statement" with three sections for configuring statement details for different account types:

- Primary A/c Statement:** Type (radio buttons: None selected, Summary, Detailed), Cycle (dropdown), On (dropdown).
- Secondary A/c Statement:** Type (radio buttons: None, Summary, Detailed), Cycle (dropdown), On (dropdown).
- Tertiary A/c Statement:** Type (radio buttons: None selected, Summary, Detailed), Cycle (dropdown), On (dropdown), and a checkbox for "Exclude Same Day Reversal trns from stmt".

Buttons for "Ok" and "Cancel" are located at the bottom right of the dialog.

Specify the following parameters for each of the valid account type.

Primary A/c Statement

You can generate account statement periodically for primary account type.

Type

Select the statement type to be generated from the options. The following values are available for selection:

- None—Select this option if you do not need an account statement.
- Summary—Select this option if you need a brief account statement.
- Detailed—Select this option if you need a detailed account statement.

Cycle

Select the frequency to generate statement, from the adjoining drop-down list. This list displays the following values:

- Annual—Select this option if you need to generate the statement annually.
- Semi Annual—Select this option if you need to generate the statement half yearly.
- Quarterly—Select this option if you need to generate the statement quarterly.
- Monthly—Select this option if you need to generate the statement monthly.
- Fortnightly—Select this option if you need to generate the statement fortnightly.
- Weekly—Select this option if you need to generate the statement weekly.
- Daily—Select this option if you need to generate the statement daily.

On

Select a month, a date or a day to generate statement from the adjoining drop-down list. The drop-down list displays following values:

- Displays names of the months when Annual, Semi Annual, and Quarterly are selected at the 'Cycle' level
- Displays numbers from 1 to 31 when Monthly is selected at the 'Cycle' level
- Displays names of the week days when Fortnightly and Weekly are selected at the 'Cycle' level
- Displays a blank list when Daily is selected at the 'Cycle' level

Secondary A/c Statement

You can generate account statement periodically for secondary account type.

Type

Select the statement type to be generated from the options. The following values are available for selection:

- None—Select this option if you do not need an account statement.
- Summary—Select this option if you need a brief account statement.
- Detailed—Select this option if you need a detailed account statement.

Cycle

Select the frequency to generate statement, from the adjoining drop-down list. This list displays the following values:

- Annual—Select this option if you need to generate the statement annually.
- Semi Annual—Select this option if you need to generate the statement half yearly.
- Quarterly—Select this option if you need to generate the statement quarterly.
- Monthly—Select this option if you need to generate the statement monthly.
- Fortnightly—Select this option if you need to generate the statement fortnightly.
- Weekly—Select this option if you need to generate the statement weekly.
- Daily—Select this option if you need to generate the statement daily.

On

Select a month, a date or a day to generate statement from the adjoining drop-down list. The drop-down list displays following values:

- Displays names of the months when Annual, Semi Annual, and Quarterly are selected at the 'Cycle' level
- Displays numbers from 1 to 31 when Monthly is selected at the 'Cycle' level
- Displays names of the week days when Fortnightly and Weekly are selected at the 'Cycle' level
- Displays a blank list when Daily is selected at the 'Cycle' level

Tertiary A/c Statement

You can generate account statement periodically for tertiary account type.

Type

Select the statement type to be generated from the options. The following values are available for selection:

- None—Select this option if you do not need an account statement.
- Summary—Select this option if you need a brief account statement.

- Detailed–Select this option if you need a detailed account statement.

Cycle

Select the frequency to generate statement, from the adjoining drop-down list. This list displays the following values:

- Annual–Select this option if you need to generate the statement annually.
- Semi Annual–Select this option if you need to generate the statement half yearly.
- Quarterly–Select this option if you need to generate the statement quarterly.
- Monthly–Select this option if you need to generate the statement monthly.
- Fortnightly–Select this option if you need to generate the statement fortnightly.
- Weekly–Select this option if you need to generate the statement weekly.
- Daily–Select this option if you need to generate the statement daily.

On

Select a month, a date or a day to generate statement from the adjoining drop-down list. The drop-down list displays following values:

- Displays names of the months when Annual, Semi Annual, and Quarterly are selected at the 'Cycle' level
- Displays numbers from 1 to 31 when Monthly is selected at the 'Cycle' level
- Displays names of the week days when Fortnightly and Weekly are selected at the 'Cycle' level
- Displays a blank list when Daily is selected at the 'Cycle' level

Exclude Same Day Reversal trns from stmt

Check this box to exclude details of the transactions reversed on the same day from the generated statement.

3.2.25.6 Maintaining MIS Details

Click 'MIS' button in the 'Account Class Transfer' screen to invoke 'Management Information System' screen.

The screen is as shown below:

Management Information System

Branch Code: 000

Account No: 00000014001

MIS Group: [Empty]

Link to Group

Ref Rate Code: [Empty]

Calculation Method: 30(Euro)/360

Ref Rate Code: Fixed

Ref Spread: [Empty]

Rate Flag: Pool Code
 Contract Level

Pool Code: [Empty]

Reference Rate: [Empty]

Transaction MIS Code:

- COS_CENTR
- LOAN_TYPE
- LOAN_TERM
- A_OFFICER
- [Empty]
- [Empty]
- [Empty]
- [Empty]
- [Empty]

Composite MIS Codes:

- ACC_OFFCR
- [Empty]
- [Empty]
- [Empty]
- [Empty]
- [Empty]
- [Empty]
- [Empty]
- [Empty]

MATHEW

Cost Codes:

- [Empty]
- [Empty]
- [Empty]
- [Empty]

Ok Cancel

All the parameters are defaulted here. You can change the values if needed. The following parameters are maintained:

Branch Code

The current branch code is defaulted here.

Account No

The system generates the account number maintained in the 'Main' screen of 'Account Class Transfer'.

MIS Group

Select a valid MIS group from the adjoining option list.

Link to Group

Check this box if you need to link MIS group to the account. Any changes to the MIS group would be automatically applied to the linked account.

Ref Rate Code

Specify a valid reference rate code for the account.

Calculation Method

Select a method to calculate the rate from the adjoining drop-down list. This list displays the following values:

- 30(Euro)/360
- 30(US)/360
- Actual/360
- LBL_30_EURO_363
- 30(US)/365
- Actual/365

Ref Rate Code

Select a valid reference type from the adjoining drop-down list. This list displays the following values:

- Fixed—Select this option if you need a fixed reference rate for the account.
- Floating Automatic—Select this option if you need to apply the reference rate maintained at the account level.

Ref Spread

Specify the reference spread for the account.

Rate Flag

Select a valid rate flag from the options. The following values are available for selection:

- Pool Code—Select this option if you need to apply the rate maintained for the pool to which the account belongs.
- Contract Level— Select this option if you need to apply the rate maintained at contract level.

Pool Code

Select a valid pool code to which the account class belongs, from the adjoining option list.

Reference Rate

Select a valid reference rate from the adjoining option list.

Transaction MIS Code

The system generates transaction type of MIS code from the Account Class level. You can select a valid MIS code from the adjoining option list, if needed.

Composite MIS Codes

The system generates composite type of MIS code from the Customer Maintenance level. You can select a valid MIS code from the adjoining option list, if needed.

Cost Codes

The system generates cost codes from the Account Class level. You can select a valid cost code from the adjoining option list, if needed.

3.2.25.7 Maintaining Account Status

Click 'Account Status' button in the 'Account Class Transfer' screen to invoke 'Account Status' screen.

Account	
Branch Code	000
Account	00000014001
Account Status	
Status	ASD
Description	Normal Status
GL Lines	
Credit	111100004
Debit	131120002
HO Lines	
Credit	HO0000000
Debit	HO0000001
CB Lines	
Credit	CB0000001
Debit	CB0000001

All the parameters are defaulted here. You can change the values, if needed. The following parameters are maintained

Account

You can maintain account details for your account here.

Branch Code

The current branch code is defaulted here.

Account

The system generates the account number maintained in the 'Main' screen of 'Account Class Transfer'.

Account Status

You can maintain account status details for your account here.

Status

The current account status is defaulted here. You can select a valid account status from the adjoining option list, if needed.



Account class transfer is processed only if the account status is 'NORM'.

Description

The description of the account status is defaulted here.

GL Lines

You can maintain the credit and debit details of the general ledger reporting lines for your account here.

Credit

The GL code related to credit is defaulted here. You can select a valid GL code from the adjoining option list, if needed.

Debit

The GL code related to debit is defaulted here. You can select a valid GL code from the adjoining option list, if needed.

HO Lines

You can maintain the credit and debit details of the Head Office reporting lines for your account here.

Credit

The line code related to credit is defaulted here. You can select a valid line code from the adjoining option list, if needed.

Debit

The line code related to debit is defaulted here. You can select a valid line code from the adjoining option list, if needed.

CB Lines

You can maintain the credit and debit details of the Central Bank reporting lines for your account here.

Credit

The line code related to credit is defaulted here. You can select a valid line code from the adjoining option list, if needed.

Debit

The line code related to debit is defaulted here. You can select a valid line code from the adjoining option list, if needed.

3.2.26 Processing Account Class Transfer

Oracle FLEXCUBE facilitates the change of account class at the customer level without changing the customer account number. Depending on the destination account class, system defaults reports the reporting GL lines and IC related values.

3.2.26.1 Processing EOD Batch

During IC EOD process, system considers interest accrual for the back value dated transactions carried out prior to account class transfer, and computes the interest from the effective date of transfer based on new account class values. If the value date of the back value transaction is before the effective date of transfer, then the system does not compute interest for the period between value date and effective date.



System does not process IC calculation of back valued UDE change, back value dated transaction, CIF type change and bulk change of the old account class.

3.2.26.2 Processing BOD Batch

During BOD process, system initiates the IC online liquidation of interest accrued on various products for all the customer accounts in the account class, till the effective date of account class transfer. Using gateway infrastructure, system authorizes and changes the account class based on the parameters maintained at the account class transfer level. However, GL balance of the accounts processed for account class transfer would be considered for the next day EOC.



Note the following:

- Transfer of the account class would be effective only after the liquidation of customer accounts.
- Error log is written for the customer account which has failed in the account class transfer.

When account class transfer maintenance is saved, the system will enforce restriction and display an error message in following conditions:

- If one of the mask components of the customer account is Account class
- If dual-currency is enabled for the old account class

- If the account is already linked in ILM structure
- If the old account class is deposit type
- If the new account class has customer or currency restriction on the selected customer and account currency respectively

3.2.27 Viewing Account Class Transfer

You can view a summary of Account Class Transfer maintained at the 'Account Class Transfer' level using 'Account Class Transfer' summary screen. You can invoke the 'Account Class Transfer' summary screen by typing 'STSACTFR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

	Authorization Status	Record Status	Branch Code	Account Class	Old Account Class	Account	Next Liquidation
<input type="checkbox"/>	Authorized	Open	005	CACIN	CACCS	1111111124	NO
<input type="checkbox"/>	Authorized	Open	001	SAVIN	SAVST	00100008601	NO
<input type="checkbox"/>	Authorized	Open	005	SAIR	SAVIN	1111111121	YES
<input type="checkbox"/>	Unauthorized	Open	001	SAVST	SAVIN	00100010502	
<input type="checkbox"/>	Authorized	Open	005	SAVRY	SAVIN	1111111120	YES
<input type="checkbox"/>	Authorized	Open	005	SAIR	SAVHN	1111111126	YES
<input type="checkbox"/>	Authorized	Open	001	SAVNR	SAVIN	00100026402	YES
<input type="checkbox"/>	Authorized	Open	001	SALA2	SAVIN	00100008607	NO
<input type="checkbox"/>	Authorized	Open	001	SAVHN	SAVIN	00100042902	YES

You can view records based on any or all of the following criteria:

Authorization Status

You can view records based on the authorization status of the account class transfer by selecting an option from the adjoining drop-down list. This list provides the following options:

- Authorised–Select this option if the account class transfer is authorised.
- Unauthorised–Select this option if the account class transfer is unauthorised.

Branch Code

Select a valid branch code if you need to view records based on the branch code of the account.

Old Account Class

Select a valid account class if you need to view records based on the account class from which the account was transferred, from the adjoining option list.

Next Liquidation Cycle

Check this box if you need to view records based on status of liquidation cycle.

Record Status

You can view records based on the record status of the account class transfer by selecting an option from the adjoining drop-down list. This list provides the following options:

- Open—Select this option if the account class transfer is not effective.
- Closed—Select this option if the account class transfer is effective.

Account Class

Select a valid account class if you need to view records based on the account class to which the account is transferred, from the adjoining option list.

Account

Select a valid account number if you need to view records based on the account class for which the account class transfer is applied from the adjoining option list.

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Account Class
- Old Account Class
- Account
- Next Liquidation Cycle
- Effective Date

3.2.28 Maintaining Narratives

The 'Narrative Maintenance' screen allows you to define the format of a Detailed Account Statement.

Invoke the 'Narrative Maintenance' screen, by typing 'CSDSTNAR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

If you are defining the details of a new record, choose new from the Actions Menu, or click new icon from the toolbar. The 'Narrative Maintenance' screen is displayed without any details.

The screenshot shows the 'Statement Narratives Maintenance' application window. At the top, there is a 'Module *' field. Below it, the 'Narrative Details *' section contains a table with columns 'Order' and 'Narratives *'. The 'Language Details' section contains a table with columns 'Language' and 'Description'. To the right, the 'Narrative Type *' section has radio buttons for 'Narrative', 'Tax', 'Event', 'Charge', 'Interest', 'Commission', and 'Transaction'. At the bottom, the 'Fields' section includes input fields for 'Input By DOC4', 'Date Time', 'Modification Number', 'Authorized By', and 'Date Time', along with checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

After you have entered all the details of a record, save the record using one of the following methods:

- Click Save icon in the toolbar
- Select Save from the Actions Menu

While maintaining narratives, if you choose the narrative type for a module the prompt codes maintained for this module are displayed. You can choose the relevant prompt code from the option list.

For the FT module, the prompt codes can be the following:

- FT-EVENTDESC
- FT-USERREFNO

For the above prompt codes you have to enter the descriptions in the desired language. For instance the description for FT-EVENTDESC can be maintained as EVENT DESCRIPTION in the English language.

The Account statement for the above maintenance will look like EVENT DESCRIPTION – REVERSAL, where reversal is the actual event happening. The word REVERSAL itself is picked up from the same screen for Event type of narratives.



The same logic applies to the other type of narratives

3.2.29 Maintaining Customer Instruction Details

Instructions Maintenance screen allows users to maintain instructions for customers with the current branch as the local branch.

Invoke this screen, by typing 'CSDINSTR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Instructions Maintenance' application window. At the top, it displays 'Customer Number * E03000115' and 'Customer Name SAIDEEP1'. Below this is a table titled 'Instructions Details' with the following data:

<input type="checkbox"/>	Institution Id	Instruction Description	Instruction Date	Instruction Expiry Date
<input checked="" type="checkbox"/>	1	Testing Instructions	2007-11-27	
<input type="checkbox"/>	2	Testing Instructions 2	2007-11-27	2007-11-30

At the bottom of the window, there is a status bar with the following information: 'Maker A27208M01', 'Date Time: 2007-11-30 12:32:55', 'Mod No 4', 'Checker A27208A01', 'Date Time: 2007-11-30 12:34:11', 'Record Status Open', and 'Authorization Status Authorized'. An 'Exit' button is located in the bottom right corner.

Customer Number

Specify the required Customer Number from the list of values maintained.

Customer Name

The name of the customer is displayed here.

Instruction Id

Unique ID for the instruction is displayed here.

Instruction Date

Specify the date on which the instruction is added. You can select the date from the adjoining calendar.

Instruction Expiry Date

Specify the date on which the instruction will expire. You can select the date from the adjoining calendar.


Instruction Description

Specify the description of the Actual Instruction.

3.2.29.1 Viewing Customer Instructions

All the instructions maintained in the Instructions Maintenance screen can be viewed in the Customer Instructions View screen. To invoke this screen, specify the Customer number, Contract reference number or Account number and press the hotkey F6.

If F6 is pressed from customer account number field, system fetches all the instructions of customer of the selected customer account. If F6 is pressed from a contract reference number field, system fetches all the instructions of the counterparty of the contract. If F6 is pressed from customer field, system fetches all the instructions of customer of the selected customer.



The Customer Instruction View screen will be launched with all the instructions maintained for the customer.

The following fields can be viewed in this screen:

- Customer Number
- Customer Name
- Instruction Id
- Instruction Date
- Instruction Expiry Date

- Instruction Description

3.2.29.2 Viewing the Instructions Summary

You can view the summary of instructions in the 'Instructions Summary' screen. It displays the status of the records maintained, whether it is authorized, unauthorized or rejected.

You can invoke this screen by typing 'CSSINSTR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

	Authorization Status	Record Status	Customer Number
<input type="checkbox"/>	Authorized	Open	E01100040
<input type="checkbox"/>	Authorized	Open	E03000115
<input type="checkbox"/>	Authorized	Open	E03000118
<input type="checkbox"/>	Authorized	Open	E03000120
<input type="checkbox"/>	Authorized	Open	E03000121
<input type="checkbox"/>	Authorized	Open	E03000234
<input type="checkbox"/>	Authorized	Open	001000130
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			

To view the summary of instructions, you can perform a search based on any of the following.

Authorisation Status

Select the authorisation status of the instruction as:

- Authorised
- Unauthorised

Record Status

Select the record status of the instruction as:

- Open

- Closed

Customer number

Select a Customer number from the list to view the instructions maintained for that customer. The following details of the record get displayed.

- Authorization Status
- Record Status
- Instruction Details



This facility is generic for all the screens, but you can make modifications for these instructions.

3.2.30 Maintaining Lead Details

You can capture details of products and offers that are rendered to a customer and the response of the customer to the same in the 'Lead Input' screen. To invoke this screen, type 'STDLEDMT', in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Specify the following details:

Lead Id

The system displays the lead identification number.

Customer No

Specify the customer identification number whose request is being maintained. The adjoining option displays all the customer numbers that are maintained in the system. You can choose the appropriate one.

E-mail

The system will display the customer's email address based on the customer number selected.

Telephone

The system will display the customer's contact number based on the customer number selected.

First Name

The system will display the customer's first name based on the customer number selected.

Last Name

The system will display the customer's last name based on the customer number selected.

Address 1, 2, 3, and 4

Specify the address line 1, 2, 3, and 4.

Areas of Interest

Specify the area in which the customer is having interest.

Remarks

Specify any additional information, if any.

3.2.30.1 Product Tab

Specify the product details:

Product Code

Specify the product code which is to be associated to the customer. The adjoining option list displays all the product code that are maintained in the system. You can select the appropriate one.

Product Description

The system displays a brief description of the product.

Interested Flag

Check this box to indicate that the product that is selected should be included in the lead creation.

3.2.30.2 Offer Tab

The screenshot shows a web application window titled "Lead Maintenance". The interface is divided into several sections:

- Form Fields:** On the left, there are input fields for "Lead Id", "Customer No" (with a "Search" button), "E-mail", "Telephone", "First Name", and "Last Name". On the right, there are input fields for "Address1", "Address2", "Address3", "Address4", "Area of Interest", and "Remarks".
- Navigation:** Below the form fields, there are tabs for "Product Code" and "Offer Details".
- Table:** A table is displayed below the tabs. The table has a header row with columns: "Offer Code", "Offer Description", and "Response". The table body is currently empty. Above the table, there are navigation controls including "1 of 1" and a "Go to Page" field.
- Footer:** At the bottom of the window, there are input fields for "Maker", "Checker", "Date Time" (two instances), "Mod No", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner.

Specify the offer details:

Offer Code

Specify the offer code that is rendered to the customer. The adjoining option list displays all the offer code that are maintained in the system. You can select the appropriate one.

Offer Description

The system displays a brief description of the offers that are offered to the customer.

Response

Choose the offer response from the drop-down. The options available are:

- Accepted
- Rejected
- Interested
- Not interested
- Tell a friend

3.2.31 Maintaining Service Request Input Details

You can maintain the customer and non-customer's request/complaints in the 'Service Request Input' screen. To invoke this screen, type 'STDSRQST' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Service Request Input' window. It has a title bar with a diamond icon and a close button. The main area is split into two columns. The left column is titled 'Customer Details' and contains the following fields: Requester Type (dropdown menu with 'Customer' selected), Customer No, Short Name, Full Name, Telephone, Mobile Number, E-mail, Subject, and Description. The right column is titled 'Service Details' and contains: Service Request Type (dropdown menu with 'Transactional' selected), Service No., Branch Code, Account No., Priority (dropdown menu with 'High' selected), Status (dropdown menu with 'Open' selected), Nature, Criteria (dropdown menu), Contact date, Target Date, and Activation Date. Below these sections is a 'Lead' section with a blue header. It contains fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, and an 'Exit' button.

You need to maintain the following details:

Customer Details

Specify the following details:

Requestor Type

Select the type of requestor from the adjoining drop-down list. This list displays the following values:

- Customer
- Non- Customer

Customer No

Specify the customer identification number whose request is being maintained. The adjoining option displays all the customer numbers that are maintained in the system. You can choose the appropriate one. This field will be enabled only if the requestor type is selected as 'Customer'.

Short Name

The system will display the customer's short name based on the customer number selected.

Full Name

The system will display the customer's full name based on the customer number selected.

Telephone

The system will display the customer's contact number based on the customer number selected.

Mobile Number

The system will display the customer's mobile number based on the customer number selected.

E-mail

The system will display the customer's email address based on the customer number selected.

Subject

Specify the subject matter of the request\complaint.

Description

Specify the brief description of the request\complaint.

Service Details

Specify the following details:

Service Request Type

Select the service request type from the adjoining drop-down list. This list displays the following values:

- Transactional
- Non Transactional
- Complaint

Service No

The system generates the service request number.

Branch Code

The system displays the branch

Account No

The system will display the customer's account number based on the customer number selected.

Priority

Select the priority of the request\complaint from the drop-down list. This list displays the following values:

- High
- Medium
- Low

Status

Select the status of the request\complaint from the drop-down list. This list displays the following values:

- Open
- Pending
- Closed
- Escalated

Nature

Select the nature of the request\complaint from the drop-down list. This list displays the following values:

- Service
- Sales

Criteria

Select the criteria of the request\complaint from the drop-down list. This list displays the following values:

- Enquiry
- Channel
- Product
- Application
- Maintenance

Contact Date

Specify the date on when the request or complaint is made.

Target date

Specify the date on when the request or complaint is to be closed.

Activation Date

Specify the date on when the request or compliant is activated.

3.2.31.1 Specifying Lead Details

You can maintain both the customers and non –customer details in the ‘Lead Input’ screen by clicking ‘Lead’ button in the ‘Service Request Input’ screen. The following screen will be displayed.

The screenshot shows the 'Lead Maintenance' application window. It features a search section with fields for Lead Id, Customer No (with a 'Search' button), E-mail, Telephone, First Name, and Last Name. To the right are fields for Address1 through Address4, Area of Interest, and Remarks. Below this is a tabbed interface with 'Product Code' and 'Offer Details' tabs. The 'Product Code' tab displays a table with columns: Product Code, Product Description, Interested Flag, and a checkbox. The table is currently empty. At the bottom of the window, there are fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an 'Exit' button.

For more details on the Lead Input screen, refer the ‘Maintaining Lead Details’ section of this user manual.

3.2.32 Viewing Service Request Details

You can view the summary of service request details in the ‘Service Request’ screen. To invoke this screen, type ‘STSSRQST’ in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

- Record Status
- Service No
- Service Request Type
- Customer No
- Account No
- Branch Code
- Requestor Type
- Status
- Contact date
- Target Date
- Telephone

3.2.33 Maintaining Location Details

While maintaining Customer Information details through the CIF Maintenance screen, in addition to indicating the name of the country in which your customer resides you can also choose to specify the name of the region or locality where your customer stays. For instance, Silas Marner, a customer of your bank is a Londoner, Great Britain is his country of residence. He lives in the northern part of London; therefore North London becomes the location where he resides.

Location codes, along with a brief description of the locality can be maintained through the 'Location Details' maintenance screen.

Invoke the 'Location Maintenance' screen, by typing 'STDCULOC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Maker	Date Time:	Mod No
Checker	Date Time:	Record Status
		Authorization Status

Location Code

You can capture a unique three-character code to identify the locality where the customer resides.

STOP While maintaining customer information details and associating a location code with a Customer and Country Code combination, a list of all the valid location codes you have maintained in this screen will be available in the option list for the Location Code field. You can select the appropriate code.

Description

You can also associate a brief description with the location code. This description is for information purposes only and will not be printed on any customer correspondence.

STOP While maintaining the Customer Short Name in the 'CIF Details' screen the system automatically appends the Location code to the customer short name when you associate the appropriate Location Code with the Customer Code.

Church Tax percentage

Specify the church tax percentage to be charged for customers belonging to the specified location..

STOP The church tax percentage will vary for each state in Germany.


3.2.34 Capturing Algorithm Details in Oracle FLEXCUBE

In Oracle FLEXCUBE, you can choose to generate check-digits for Customer Accounts based on the algorithm of your choice. You can define algorithms of your choice through the 'Algorithm Maintenance' screen. Invoke this screen by typing 'CSDALGMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields	
Input By	DOC4
Date Time	
Modification Number	
Authorized	<input type="checkbox"/>
Authorized By	
Date Time	
Open	<input checked="" type="checkbox"/>

In this screen, you should specify the following details:

- The Name of the Algorithm. This will uniquely identify the algorithm in Oracle FLEXCUBE
- A brief description of the algorithm

 After you capture the details of a new algorithm you must 'write' the algorithm through the 'Algorithm Procedure Generation' screen

3.2.34.1 Generating Procedure for Algorithm

For every algorithm that you define through the 'Algorithm Maintenance' screen must write the algorithm generation rule through the 'Algorithm Generation Input' screen.

Invoke this screen by typing 'CSDALGGN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows a web-based form titled "Algorithm Generation Input". The form includes the following elements:

- Algorithm Name ***: A text input field with a dropdown arrow on the right.
- Function Type ***: A dropdown menu currently showing "Check Digit Generation".
- Algorithm Rule**: A large text area for entering code, with a small speech bubble icon on the right.
- Buttons**: "Execute", "Errors", and "Clear" buttons are stacked vertically. Below the "Clear" button, the word "Errors" is displayed.
- Fields Section**: A dark blue bar at the bottom contains labels for "Input By DOC4", "Authorized By", "Date Time", "Date Time", "Modification Number", "Authorized" (checkbox), "Open" (checkbox), and a "Cancel" button.

Since the access to this screen is restricted to only a few authorized users at your branch level, you will be allowed to invoke the screen only if you have the requisite rights.

In this screen, you can specify:

- The name of the algorithm for which you are writing the algorithm generation rule. A list of all the algorithms you have maintained through the 'Algorithm Maintenance' screen is displayed. You can select the appropriate
- The Function Type, which specifies the type of the function using the algorithm. The options available are:
 - Validation - indicates that the function is using the algorithm to validate the 'input' string. For all such functions, the input string is validated as being True or False depending upon whether the validation was a success or a failure
 - Check Digit Generation - indicates that the function is used for the generation of check digit using the algorithm. Such functions will take the input string without the check digit and return the check digit

You must enter the algorithm rule in the form of PL/SQL code. After writing the PL/SQL code, click 'Execute' button to compile the code. The algorithm rule is validated by the system and the success or failure message is shown in the Error editor. Click 'Errors' button to view the errors.

If any checks fail, you must alter the statement so that the validation can be made successfully. The algorithm is generated on Authorization of the rule.

Click the 'Clear' button, the Algorithm Rule editor and the Error editor will be cleared for you to enter a new rule in the field.



The System provides two pre-defined key elements both for Check Digit Generation and Validation type of algorithms. They are:

- I_branch_code
- I_customer_no

You will not be allowed to enter the following keywords in an Algorithm Rule:

- ROLLBACK
- COMMIT
- DECLARE
- DELETE
- UPDATE
- INSERT

Once defined, you will not be allowed to unlock and amend the following fields:

- Algorithm Rule
- Algorithm Description
- Function Type

You can refer the Clearing user manual for more information

3.2.35 Maintaining Turnover Limits

You can maintain turnover limits for a given period of time using the 'Turnover Limit Maintenance' screen. You can attach these limits to an account class and thereby track the turnover on all accounts under the account class.

You can invoke the 'Turnover Limit Maintenance' screen by typing 'STDTOLMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

The screenshot shows a software window titled "Turnover Limit Maintenance". At the top, there are two input fields: "Limit Code *" and "Description". Below these are two data grids. The first grid, "Limit Period Details", has columns for "Period Code", "Start Date", and "End Date". The second grid, "Limit Amount Details", has columns for "Currency" and "Amount". At the bottom of the window, there are several status fields: "Maker", "Checker", "Date Time", "Mod No", "Record Status", and "Authorization Status", along with an "Exit" button.

Here, you need to specify the following details.

Limit Code

Specify a unique code used to identify turnover limit.

Description

Specify a brief description associated with the turnover limit.

Period Details

You can specify the following details pertaining to the period for limit application.

Period Code

Specify a unique code to identify the financial period for which you wish to maintain turnover limits.

Start Date

Specify the start date of the financial period, using the adjoining calendar.

End Date

Specify the end date of the financial period, using the adjoining calendar.

You can maintain multiple period codes. However, the periods cannot overlap.

Limit Amount Details

You can specify the following details pertaining limits applicable on the period code.

Limit Currency

Specify the currency of the limit amount. This adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

Limit Amount

Specify the limit amount applicable of the financial period.



Note the following:

- You can increase or decrease the maximum turnover limit as part of record modification. The modified limits will be applicable only for subsequent transactions.
- Unutilized limit amount does not get carried forward to the next period.

3.3 Maintaining Deposits Instructions

You can maintain deposits instructions for auto created deposits. The values you specify here will override the parameters you have maintained in the Account Class maintenance. Invoke the 'Deposits Instruction' screen from the Application Browser to maintain the deposits instructions specifically for the auto created deposits. To invoke this screen type 'ICCINSTR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screen is as shown below:

The screenshot shows a window titled "Deposit Instructions" with a list of fields for data entry:

- Branch Code
- Account *
- Account Class
- Customer
- Currency
- Sweep Branch
- Deposit Currency
- Sweep To Account
- Sweep Amount
- Seq No
- Tenor
- Sweep Multiple Of
- Minimum Required Balance
- SCode
- External Reference Number
- Retry Till Date
- Start Date

Buttons for "Ok" and "Exit" are visible at the bottom right of the window.

You can set the terms and a condition for a deposit as follows:

- Account Number – This is the account number of the deposit
- Account Class – This is the account class to which the account is linked
- Customer Number – The customer for whom you are maintaining the deposit instructions.
- Sweep to Account – Indicate the account to which the sweep is carried out
- Amount – This is the deposit amount
- Minimum Required Balance – The minimum balance indicates that only the amounts above this limit will be used for auto creating deposits
- Source Code – The code assigned for the sweep
- External Reference Number
- Start Date – The instructions will be valid from this date
- Branch Code – The branch code of the branch which is to be associated with the account
- Sequence Number – The system generated sequence number for the instruction you are maintaining
- Currency Code - The Currency of the particular account
- Deposit Currency – The currency in which the deposit is made
- Tenor – The tenor for the deposits that are opened under an account class
- Sweep Multiple of – The sweep can only be in multiples of the sweep specified
- Retry Till Date – The instructions specified will be invalid after this date. Any failed sweeps after this date will not be picked up for processing the next day.
-

Financial Institution Type Maintenance Screen

You can invoke the 'Static Type Maintenance' screen by typing 'CODSTTYP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Field Value	Code
-------------	------

You can specify the following:

Type

Select the 'Financial Institution Types' from the adjoining option list.

Description

Specify the description as 'List of Financial Institution Type'.

Field Value

Specify the financial institution type name.

Code

Specify the financial institution type code.

Exemption Code Maintenance Screen

You can invoke the 'Static Type Maintenance' screen by typing 'CODSTTYP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following:

Type

Select the 'Exemption Codes' from the adjoining option list.

Description

Specify the description as 'List of Exemption Codes'.

Field Value

Specify the exemption name.

Code

Specify the exemption code.

4. Processing Referrals in Oracle FLEXCUBE

4.1 Introduction

Referral refers to the process of handling customer transactions, which force the accounts involved in such a transaction to exceed the overdraft limit. Examples of typical transactions, which force an account to move into overdraft, are Payment and Collections, Funds Transfers, Standing Instructions or Clearing transactions. In Oracle FLEXCUBE, if an account involved in a transaction moves into overdraft, it is sent to the Referral Queue.

You can invoke this screen by typing 'STSREFQU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch Code	Account Number	Customer Name	Current Balance	Available Balance	Overdraft Limit	Credit Rating
-------------	----------------	---------------	-----------------	-------------------	-----------------	---------------

In this screen the following details of the account are displayed:

- The account Branch and Branch code
- The Account Number
- The Name of the customer who holds the account
- The Current Balance in the account. This includes the aggregate of debit, credit, uncollected, unauthorized, authorized and unposted transactions
- The amount available for withdraw
- The overdraft limit of the account. This is inclusive of the sub-limit
- The Credit Rating or the credit worthiness of the account holder



A charge, fee or interest debited to the customer account will not be referred to the Referral Queue

Using the Referral Queue, you can view details of all transactions processed during the day due to which the account has moved into overdraft. For example, Silas Marner's savings account has a balance of 1000 Euro (with no O/D facility). There are five checks of 300 Euro each drawn on the account on the same day. On double clicking on Silas Marner's account number in the Referral Queue, the details of all five checks will be displayed for your perusal in the Referral screen.

You can invoke this screen by typing 'STDREFQU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Posting Date	Contract Reference Number	Referral Description	Dr Amount	Pay Flag	Unpay Flag	Waive Charges	Reason
--------------	---------------------------	----------------------	-----------	----------	------------	---------------	--------

You will be able to view the following details about the entries which have been posted and those that are not to post:

- The Posting Date
- The Contract Ref No/DD Reference Number
- A brief description about the Referral
- The amount, which is to be debited from the customer account
- Pay
- Un pay

The default option is to approve (Pay) the check/DD amount. On occasion you may want to 'unpay' or reject a check/DD. You will be allowed to levy charges both for approving as well as recalling/rejecting checks. There are no limits on the charges for recalling a check but you can levy approval charges for a maximum of three transactions only. The charges for each accept/reject are computed on the basis of the IC Charge Rule linked to the customer account.



You will not be allowed to recall or unpay future dated transactions (typically future dated fund transfers or standing orders). The transaction will be initiated and entries posted passed only if the referral decision is to pay.

Each time you choose to reject a transaction you will have to indicate the reason for rejecting the transaction. A list of Reason Codes is available in the option list. You can select the appropriate.

A transaction is considered for charging only if the Waive Charge option has not been enabled for a particular Reject Code. You can enable the option if the charge is to be waived.

4.1.1 Maintenance Required for Referral Processing

For the successful processing of referrals in Oracle FLEXCUBE, you will need to maintain the following details.

4.1.1.1 Enabling Referral Required Option

You will need to enable the Referral Required option in the following maintenance screens:

- **Customer Account Class Maintenance** - Enabling this option would indicate whether a referral check should be performed on accounts belonging to the account class. Consequently, the system checks the available balance (not the current balance) while performing the referral checks for all transactions involving the account.
- **Customer Accounts Maintenance** - The Referral Required option is defaulted from the account class linked to the account. However, you can change it for a specific account. If an account is marked for referral, the details of transactions resulting in the account moving into Overdraft will be referred to the Referral Queue.
- **Product Preferences** screens of the Funds Transfer, Standing Instructions, Payment and Collections modules and the **Product Definition** screen of the Clearing module. While maintaining the details of an FT, SI, PC or CG product you can indicate whether transactions involving the product need to be considered for referral checks. Enabling this option indicates whether the product needs to be considered for referral. If a product is marked for referral, the details of transactions resulting in the account (involved in the transaction) moving into Overdraft will be sent to the Referral Queue.

4.1.1.2 Specifying Referral Cut-off Time

In branch parameter, you have to specify the referral cut-off time for accepting / rejecting transactions in the referral queue.

In case a transaction is rejected from the referral queue after the cut-off time then system displays the following override message:

'Rejected after cut off time`



Transactions are accepted into the Referral Queue even after cut-off time if account goes into overdraft.

4.1.1.3 Processing the Referral Batch

While marking EOTI, the system checks if any unprocessed referral transactions exist in the referral queue. If so, the system will display an error message. However, if you check the 'Auto Approval of Referral Transaction' box in the 'Branch Parameters Preferences' screen, system will not perform the referral queue check.

During the referral batch process, all the unprocessed transactions are fetched from the referral queue. The batch will then reject or pay transactions based on the 'pay' or 'un-pay' checks in the referral queue.

If you run the referral batch during EOD and if the 'Auto Approval of Referral Transaction' box is checked in the 'Branch Parameters Preferences' screen, then the referral batch will fetch any unprocessed transactions for which the 'pay' and 'un-pay' options are unchecked in the referral queue. For such transactions, the system will check if the accounting entries are passed for the contract or not.

- If the entries are not passed, then the system liquidates the contracts.
- If the entries are passed, then the system accepts the contracts and updates the IC charge counter.



Note the following:

- The referral batch should run only during the EOTI stage and not during the End Of Financial Input (EOFI) stage.
- It is possible for the referral batch to update the run status in the pending programs list.

4.1.1.4 Enabling Netting Required Option

If linked accounts are marked for referral you can choose to consolidate the balances in all the linked accounts before performing the referral check. To process linked accounts which are marked for referral you will need to enable the Netting Required option in the following screens:

4.1.1.5 Enabling Limit Maintenance Screen

Enabling this option indicates that the netting of balances is allowed for accounts linked to the credit line. To pool balances across accounts you may need to link a common Credit Line across accounts where balances are to be pooled. Therefore, you will need to indicate whether balances for the credit line and the respective accounts should be netted. As a result, while performing the limits check for accounting the system will take into consideration the collective balance across all accounts linked to the line.

EXAMPLE

Let us assume that Silas Marner holds three accounts with your bank

- SA0000121
- SA0000122
- SA0000123

All three are linked to the credit line SA_Pool. The credit utilization limit you have offered him is USD 10,000.

The Available Balance in each of the account is as follows:

	SA0000121	SA0000122	SA0000123
Available Balance	USD 1000	USD 2500	EUR 3000
Debits due to transactions processed today	- 9000	NA	NA
Sum of debits for today	- 8000	+ 2500	+ 3200 (in USD)

Total Debit across accounts = - USD 2500 (8000 – 5700)

After pooling Mr. Marner still has a credit utilization limit of USD 7, 700 (10000 – 2300)

If you have defined temporary overdraft limits for the accounts, and the temporary OD limit forms a part of the netting, the temporary OD limit will not be considered for netting.

Rules for Set off for principal in referrals

When customer accounts are linked for principal set-off, the Available Balance (summed for all accounts in the arrangement) plus the Overdraft Limit (for the main account) and the Sub limit (for the main account) minus the Total transactions received (on all accounts) is less than zero.

All transactions received are 'referred' even if a transaction is on an account, which has sufficient credit balance to pay the transaction.

If an account is set for principal, it means that it is automatically set for interest pooling too. However, if an account is marked only for interest set off the system does not perform the principal set off for referral.

Account Limits sub-screen of the Customer Account Maintenance screen

The Netting Allowed option is defaulted from the Credit Line associated with the customer account. If you change the default option the system displays an override message.

Liability Maintenance sub-screen of the Customer Information screen

The netting option is defaulted to the Liability Maintenance sub-screen of the Customer Maintenance screen. This option is defaulted from the Liability Code (which is linked to the Credit Line) that you associate with the CIF ID. If you change the default, the system displays an override message.

4.1.1.6 Future-dated Funds Transfers (FT)

Entries are not passed for future dated FTs and SIs in case of insufficient funds. Such transactions are moved to the Referral Queue for Approval (pay) / Rejection (un-pay). The pool balance defined in the LM Structure Maintenance is the balance, which is considered for OD.

Status

If accounting entries have not been passed

Resulting Action

Accept – the accounting entries are passed and the IC Charge counter is updated.

Reject – No resulting action.

If you have not performed any action on the contract, the transaction is resubmitted for processing the next day.

4.1.1.7 Standing Instructions (SI)

Standing instructions are sent to Queue when sufficient funds are not available in the customer's account

Status

If accounting entries have not been passed

Resulting Action

Accept - the accounting entries are passed and the IC Charge counter is updated

Reject – No resulting action

4.1.1.8 Payments and Collections (PC)

If you have enabled the Override Overdraft option as a preference while defining Outgoing Payments or Incoming Collection products the transactions involving the products will be processed regardless of the overdraft status. Else, such transactions will be sent to the Credit Exception queue and to the Referral queue as well. Upon Accepting or Rejecting a transaction in the Referral Queue, these transactions are processed in the same manner as any other transaction in the Credit Exception queue.

For further details refer to the processing transactions in the Credit Exception Queue refer to the Processing Credit Exceptions section in the Processing a Payment or Collection Transaction chapter of the Payment and Collections manual.

4.1.1.9 Clearing (CG) Transactions

If the fund available in the customer account are insufficient, the clearing transaction is processed (i.e., the relevant accounting entries are passed) and the transaction is sent to the Referral Queue.


If the transaction is rejected, the entries are reversed. The status of the transaction is updated to 'Dishonored' in the clearing log. In case the transaction is accepted, no processing is required apart from updating the charge counter.

If the account goes into overdraft, all processed transactions for the day with transaction code marked for referral are moved to the Referral Queue. However, transactions which have already been accepted will not be marked for referral again.

If a transaction is to be marked for referral, the transaction details are stored in a separate table. The details in the referral screen are displayed from this table.

Note that transactions from Savings module will appear in the 'Posted' tab.

You can get accounting entries reversed or confirm for the overdrawn account using the 'Intra Day Batch Start' screen. You can invoke this screen by typing 'BADIDBAT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Specify the following information.

Function

Specify 'CSREFQPR' or choose this value from the adjoining option list.

Click 'OK' button to run the batch.

5. Provisioning for Customer Accounts

5.1 Introduction

Your bank may wish to set up certain guidelines according to which provision must be made for outstanding overdrafts on customer accounts.

For instance, it may be necessary to set the provisioning amount for an account in respect of which there is an outstanding overdraft, based on the status of the account, as well as the financial standing of the customers.

You might also wish to include exposure due to loans issued to a customer, as well as total outstanding overdraft in all accounts of a customer, or a group of customers as a whole, and assign the status of all loans issued to the group as well as all accounts under a group, as the worst status among all loans and accounts, belonging to the group.

This chapter explains how you can use the system to perform the processes related to provisioning for customer accounts.

In order to maintain provisioning guidelines, you must

- Specify whether you wish to track the status of customer accounts and loan contracts at a customer group/CIF level, or at the level of individual contracts or accounts, for your branch.
- Set up the categories under which you wish track exposure and specify the provisioning percentages for each exposure category type
- Maintain the logic according to which the exposure category would be arrived at, based on the customer type, and the amount limits applicable for each customer type.
- Set up classifications for considering the financial standing of customers, for the purpose of status processing
- Set up the customer groups for which you wish to track exposure as a whole
- Set up rules for deriving the status of accounts for a group or CIF
- Set up rules for deriving the provisioning amount, for accounts using an account class
- Set up the frequency at which the provisioning batch would be executed, if the status processing is done at group/CIF level

5.1.1 Specifying Basis for Status Processing

In the Branch Parameters, you can indicate the basis upon which status processing must be done at the branch, for customer accounts as well as loan contracts.

Status processing can be done either at the level of individual contracts and accounts, or at a customer group or CIF level.

5.1.1.1 Status Processing at Group/CIF Level

If you opt for group or CIF-level processing, it is done in two stages:

- The worst status among all loan contracts and accounts under a specific customer group or CIF is arrived at
- All accounts and contracts involving the customer group or CIF are then moved to the worst status that was arrived at. The individual status of the account and contract, apart from the worst status being assigned, is also captured and displayed in the respective account and contract screens.

5.1.1.2 Processing at Individual Contract/Account Level

If you opt for status processing at individual contract/account level, the status of each contract or account would be assigned according to the status processing parameters that are operative for the contract or account.

For details about the Branch Parameters screen, refer the Core Services user manual.

5.1.2 Setting up Customer Groups for Provisioning

You may wish to track exposure due to loans issued to a group of customers as a whole, and assign the status of all loans issued to the group as the status of the loan with the worst status, among those issued to the group.

You may similarly wish to include the exposure due to outstanding overdraft in respect of a group of customer accounts as a whole, and assign the status of all customer accounts belonging to the group as the status of the customer account with the worst status among the accounts and loans belonging to the group.

You can set up such customer groups, for tracking exposure due to loans as well as overdraft customer accounts, in the 'Group Code Maintenance' screen. Invoke this screen by typing 'STDGRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Group Code Maintenance' window. It features a header bar with the title 'Group Code Maintenance'. Below the header, there are several input fields: 'Group Code *', 'Description', 'Exposure Category', 'Group Status', and 'Since'. To the right of these fields is a 'Group Type' section with radio buttons for 'Corporate', 'Retail', 'Charge', 'Clearing', and 'Tax'. At the bottom of the window, there is a 'Fields' section with checkboxes for 'Input By DOC4', 'Authorized By', 'Date Time', 'Modification Number', 'Authorized', and 'Open'. A 'Cancel' button is located in the bottom right corner.

Each group code that you define is associated with an appropriate exposure category that must be used to track exposure due to loans issued to customers in the group, as well as customer accounts with outstanding overdrafts.

The exposure category for a group is either derived from the logic maintained in the Exposure Type Category Linkage maintenance for the group type, or explicitly specified. If it is derived, it is displayed in this screen, by the End of Day batch program. The type of the group indicates the type of customers that belong to the group – retail, corporate, Charge Clearing or Tax. If no logic has been maintained in the Exposure Type Category Linkage for the group type, you can indicate the applicable exposure category for the group.

Group Code

When you maintain CIF details for customers, in the Customer Information Maintenance screen, you can specify the customer group to which the customer belongs, for provisioning and status processing. You must specify a group code defined for a group type that is the same as the customer type, for instance, if the customer is a retail customer, you must specify a group defined for retail customers.

Group Status

All loans and overdraft accounts issued to customers in the group will be assigned the same status, which will be the status of the loan/overdraft account with the worst status among those issued to customers in the group. The Group/CIF and the loan contracts and overdraft accounts are all updated with this worst status if they have been marked for automatic status processing. The individual status for the accounts and loan contracts (apart from assigning the worst status) is also captured and displayed. In the Group Code Maintenance screen and the CIF Maintenance screen, the status for the group is displayed, as well as the date since which the current status came into effect.

For details about loan status processing and provisioning, consult the Loans user manual.

5.1.3 Setting up Customer Classifications for Status Processing

You can set up the different classifications under which the financial standing of the customer would be considered, for status processing. You can set up these classifications in the 'Customer Classification Details' screen. You must specify an appropriate classification code and description.

You can invoke this screen, by typing 'STDCCMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields			
<input type="checkbox"/> Input By DOC4	<input type="checkbox"/> Date Time	<input type="checkbox"/> Modification Number	<input type="checkbox"/> Authorized
<input type="checkbox"/> Authorized By	<input type="checkbox"/> Date Time	<input checked="" type="checkbox"/> Open	<input type="button" value="Cancel"/>

For instance, you could set up the following classifications:

- Good – for customers with no bad loans and no accounts with outstanding overdrafts
- Unstable – for customers with a few bad loans and accounts with outstanding overdrafts
- Not Good – for customers with many bad loans and accounts with outstanding overdrafts

- Deteriorate – for customers with mostly bad loans and accounts with outstanding overdrafts
- Bad – for customers with only bad loans and accounts with outstanding overdrafts

Customer Classification

When you specify CIF details for a customer in the Customer Information Maintenance screen, you can also specify the appropriate classification for the customer.

Description

Enter a description for the classification.

5.1.4 Setting up Exposure Categories

You can maintain the different categories under which you wish to track total exposure due to loans issued to customers in customer groups or CIF's, as well as due to total overdraft in accounts belonging to customer groups or CIFs, for the purpose of ascertaining the amount of provisioning required.

You can maintain such exposure categories in the 'Exposure Category Maintenance' screen, by specifying the name of the exposure category, and a short description.

Invoke this screen by typing 'LDDECMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can view the summary of the exposure categories in the 'Exposure Category Maintenance Summary' screen.

5.1.4.1 Specifying Status-wise Provisioning Percentages for Each Exposure Category

After you have maintained exposure categories, you must maintain the appropriate provisioning percentages to apply to each exposure category, for contracts as well as accounts in each of the statuses. You must also maintain the applicable discount percentages. You can do this in the 'Exposure Category Provisioning Percent Maintenance' screen, where you can specify the applicable provisioning percentage and discount percentage for each status.

Invoke this screen by typing 'LDDPRVMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can view the summary of the provisioning details in the 'Exposure Category Provisioning Percent Maintenance' Summary screen.

Invoke this screen by typing 'LDSPRVMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

For contracts and accounts involving a customer whose exposure is being tracked under the exposure category, the applicable provisioning percentage (as well as the discount percentage) is picked up from this maintenance, if not specified at contract input (or in the case of accounts, in the Customer Account Maintenance).

5.1.4.2 Specifying Logic for Deriving Exposure Category

After you have maintained exposure categories, you must also specify how the system would derive the exposure category under which contracts and accounts must be tracked. The exposure category can be derived from the following parameters:

Category Type

You may wish to track the exposure in respect of customers from different categories such as retail or corporate, under different exposure categories.

Amount Limits

You may wish to specify an amount range within which the total exposure would be tracked, for the customer or group.

In the 'Exposure Category - Category Type Linkage' screen, you can link the exposure category to be used for tracking different customer category types and total exposure in respect of a customer group.

Invoke this screen by typing 'LDDTMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Serial Number	Basis Amount From	Basis Amount To	Exposure Category
---------------	-------------------	-----------------	-------------------

You can view the summary of the exposure category linkages in the 'Exposure Category - Category Type Linkage Summary' screen.

Invoke this screen by typing 'LDSETMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Corporate Deposits Category Type Summary

Authorization Status Record Status
Category Type Basis Amount Currency

Search Advanced Search Reset Export Records per page 15 1 of 1 Go to Page

<input type="checkbox"/>	Authorization Status	Record Status	Category Type	Basis Amount Currency
--------------------------	----------------------	---------------	---------------	-----------------------

Authorization Status: A - Authorized, U - Unauthorized
Record Status: C - Closed, O - Open

Exit

Category Type

You must specify the customer category type, for which you wish to link the appropriate exposure category type.

Basis Amount

You must specify the basis amount range, within which the total exposure will be tracked, using the exposure category that you have associated, for the customer category type.

For all slabs except the first one, the To Amount of the previous slab must also be equal to the From Amount of the slab.

The To Amount of a slab must be equal to or greater than the From Amount of the same slab.

Exposure Category

You can specify the exposure category that is to be used to track the total exposure, within the basis amount range, for the customer category type you have specified.

STOP When the exposure category for a CIF or customer group is derived according to the logic maintained in the Exposure Category Type Linkage screen, the outstanding overdraft in all accounts belonging to the group/CIF, as well as the exposure due to loans issued to the group / CIF is summed, to compute the total exposure.

5.1.4.3 Specifying Exposure Category for Customer

When you maintain CIF details for customers, in the Customer Information Maintenance screen, you can specify the exposure category under which exposure due to loans issued to the CIF will be tracked. The exposure category is derived by the End of Day batch program and displayed, if the applicable logic has been maintained for the specified customer provisioning group, in the Exposure Type Category Linkage maintenance. If no logic has been maintained for the group, you can specify the applicable exposure category.

5.1.5 Maintaining Rules for Provisioning

For each account class for which you have defined account provisioning to be applicable, you can define the rules according to which the provisioning amount would be computed, when applied to an account using the class. You can define the provision rules in the Account Class Provisioning Rule Maintenance screen.

Invoke this screen by typing 'LDDPRULE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows the 'Corporate Deposits Provisioning Rule Maintenance' application window. At the top, there is a 'Product Code *' field with a search icon. Below this, the screen is divided into three main sections: 'Rule', 'Case', and 'Result'. Each section contains a table with five rows and one column. Below these sections, there are three dropdown menus labeled 'Elements', 'Functions', and 'Operators'. There is also a 'Logical Operators' dropdown and a 'Reset' button. At the bottom, there is a 'Fields' section with a grid of fields: 'Input By DOC2', 'Date Time', 'Modification Number', 'Authorized', 'Authorized By', 'Date Time', 'Open', and a 'Cancel' button.

To define rules, you can use the following elements, for the account for which provision is being made:

- **Outstanding Balance ACY** – This is the book-dated debit balance, in account currency, in the account for which provision is being made
- **Outstanding Balance LCY** – This is the book-dated debit balance, in local currency, in the account for which provision is being made
- **Receivable Interest** – This is the interest receivable on the account for which provision is being made

- **Accrued Interest** – This is the interest that has been accrued but not liquidated as yet in the account for which provision is being made; typically, the interest that has accrued during the current liquidation cycle
- **Receivable Interest LCY** – This is the interest receivable, in local currency, on the account for which provision is being made
- **Accrued Interest LCY** – This is the interest that has been accrued but not liquidated as yet, in local currency, on the account for which provision is being made
- **Account Status** – This is the user-defined status for the account for which provision is being made
- **Exposure Category**– This is the exposure category of the account for which provision is being made. It is picked up from the account details; if it has not been specified in the account details, it is picked up from the maintenance for the CIF or customer group to which the account belongs.
- **Risk-Free Exposure Amount** – This indicates the risk-free amount (collateral) specified in the details of the account for which provisioning is being made.
- **Provisioning Percentage** – The provisioning percentage is generally picked up from the account details. If not specified in the account details, it is picked up from the Exposure Category Provisioning Percentage maintenance, for the exposure category of the customer of the account and the account status.
- **Discount Percentage** – The discount or loss percentage is used to compute the recoverable value of the account for which provision is being made. It is picked up from the account (if specified in the account details) or from the Exposure Category Provisioning Percentage maintenance, for the exposure category and status of the account for which provision is being made.
- **Status Seq** – This indicates the sequence number that represents the status, as defined in the Status Definition. It can be used with arithmetic operators for ease of status rule definition.

5.1.6 Derivation Rules for Status Change

For accounts, the basis for processing of status changes is governed by an attribute that you set in the Branch Parameters. You could opt for status processing at a group or CIF level, or at contract-level.

If processing is done at a customer group or CIF level, it is done in two stages:

- The worst status among all accounts and loan contracts belonging to the customer group or CIF is arrived at
- All accounts and contracts belonging to the customer group or CIF are then moved to the worst status that was arrived at

In the Status Rule Derivation screen, in the Derivation Rule field, you can define the conditions according to which the status of all accounts using an account class (the aging analysis) could be tracked. For each account class, you can maintain a derivation rule, which would be used during status processing to arrive at the status of each account (if status processing is at a contract level) or the worst status among all accounts and loans belonging to groups or CIF level (if status processing is at a Group/CIF level)

To define the derivation rule, you could use a combination of multiple elements, and arithmetic and logical operators. The following elements may be used:

- Frozen
- Dormant
- Nodebits
- Nocredits
- Stoppayment
- Current Status
- Customer Classification

In addition, the following elements will also be available for processing:

- OD (overdraft) Days
- Inactive Days
- Overline Days
- TOD (Temporary Overdraft) Days

For details regarding the maintenance of other status control parameters in the Status Rule Definition screen, refer the chapter Maintaining Mandatory Information in this user manual.

5.2 Maintaining Provisioning Coverage Details

You can maintain the provisioning coverage details for the individual contracts to pick up the provisioning percentage using 'Provisioning Coverage Details' screen. Provisioning is required for Loan, Leasing, Guarantee, and Over Draft Accounts types of products.

To invoke this screen, type 'CSDPROVN' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Status	Sequence Number	From	To	Unit	Provisioning Percentage
<input checked="" type="checkbox"/>					

You can specify the following details here:

Provisioning Code

Specify the unique provisioning code for which you want to maintain the coverage details.

Description

You can describe the provisioning code.

Provisioning Coverage Details

Status

Specify the status for which you want to maintain the provisioning coverage from the adjoining option list.

Sequence Number

System generates the sequence number while saving the record. You cannot amend this number.

From

Specify the number of days, months or years from which the provision percentage should be applicable.

To

Specify the number of days, months or years till which the provision percentage should be applicable.

Unit

Specify the unit for the provisioning coverage. The adjoining drop-down list has the following options:


- Days
- Months
- Years

Provisioning Percentage

Specify the provisioning percentage to be applied for the specified period.

5.3 Viewing Provisioning Coverage Details

You can view provisioning coverage details for the individual contracts using 'Provisioning Coverage Summary' screen. To invoke this screen, type 'CSSPROVN' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.



In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Provisioning Code
- Record Status
- Description

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Authorization Status
- Record Status
- Provisioning Code
- Description

5.4 Maintaining Risk Level Provisioning Rate

You can maintain the alpha and the beta provisioning rates for each risk level using 'Risk Provisioning Rate Maintenance' screen. This maintenance will be done at the head-office and will apply to all the branches. To invoke this screen, type 'CSDAPBTR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows a window titled "Risk Provisioning Rate Maintenance". It has a blue header bar with a diamond icon and the title. The main area contains several input fields: "Risk Level *" (a dropdown menu), "Alpha Rate" (a text box), "Beta Rate" (a text box), and "Transaction Code" (a text box with a search icon). On the right side, there are two sections for General Ledger (GL) entries: "Provision Expense GL" and "Provision Liability GL", each with a text box and a "GL Description" field. At the bottom, there are fields for "Maker" and "Checker" (each with a "Date Time" field) and a "Cancel" button.

You can specify the following details here:

Risk Level

Specify the risk level from the adjoining drop-down list. You can select any one of the following:

- Negligible risk
- Low risk
- Medium-low risk
- Medium risk
- Medium-high risk
- High risk

Alpha Rate

Specify the alpha rate percentage for the selected risk.

Beta Rate

Specify the beta rate percentage for the selected risk.

Transaction Code

Specify the transaction code that will be used for the accounting entries from the adjoining option list.

Provision Expense GL

Specify the GL for accounting entries at risk level. The adjoining option list displays all the GL belong to expense category. Select the appropriate one.

GL Description

System displays the description for the provision expense GL.

Provision Liability GL

Specify the GL for accounting entries at risk level. The adjoining option list displays all the GL belong to liability category. Select the appropriate one.

GL Description

System displays the description for the provision liability GL.



Note the following:

Provisioning will be based on the following parameters:

- If the status of contract is doubtful, then the system calculates the provision amount separately for each contract.
- If the status of the contract is not doubtful, then Grouping needs to be done at Risk Level and Country Group Level separately at the bank level for all the customers.

- If the Risk Level is changed, then during next provisioning process, provisioning amount will be recalculated and accounting will be updated accordingly.

5.5 Viewing Risk Level Provisioning Rate

You can view the alpha and the beta provisioning rates for each risk level using 'Risk Provisioning Rate Summary' screen. To invoke this screen, type 'CSSAPBTR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Record Status
- Risk Level

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Authorization Status
- Record Status
- Risk Level

5.6 Maintaining Country Group Provisioning Rates

You can maintain the country group provisioning rates for country groups using 'Country Group Provisioning Rates Maintenance' screen. This maintenance will be done at the head-office and will apply to all the branches. To invoke this screen, type 'CSDCGRPR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows a window titled "Country Group Provisioning Rates Maintenance". It contains the following fields and controls:

- Country Group Code * (dropdown menu)
- Group Code Description (list icon)
- Group Rate (text input)
- Transaction Code (dropdown menu)
- Provision Expense GL (dropdown menu)
- GL Description (list icon)
- Provision Liability GL (dropdown menu)
- GL Description (list icon)
- Maker (text input)
- Checker (text input)
- Date Time: (text input)
- Date Time: (text input)
- Cancel (button)

You can specify the following details here:

Country Group Code

Specify the country group code. The adjoining option list displays the list of country group codes maintained in the system. Select the appropriate one.

Group Code Description

System displays the group code description for the selected country group code.

Group Rate

Specify the group rate percentage for each country.

Transaction Code

Specify the transaction code that will be used for the accounting entries from the adjoining option list.

Provision Expense GL

Specify the GL for accounting entries at country group level. The adjoining option list displays all the GLs belonging to provision category. Select the appropriate one.

GL Description

System displays the description for the provision expense GL.

Provision Liability GL

Specify the GL for accounting entries at country group level. The adjoining option list displays all the GLs belonging to liability category. Select the appropriate one.

GL Description

System displays the description for the provision liability GL.

5.7 Viewing Country Group Provisioning Rates

You can view the country group provisioning rates for country groups using 'Country Group Provisioning Rates Maintenance' screen. To invoke this screen, type 'CSSCGRPR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Country Group Provisioning Rates Summary' window. At the top, there are several input fields: 'Authorization Status' (dropdown), 'Country Group Code' (text with a search icon), 'Provision Expense GL' (text with a search icon), 'Transaction Code' (text with a search icon), 'Record Status' (dropdown), 'Group Rate' (text with a search icon), and 'Provision Liability GL' (text with a search icon). Below these fields are 'Search' and 'Advanced Search' buttons, followed by 'Refresh' and 'Reset' buttons. A 'Records per page' dropdown is set to '15', and a 'Go' button is next to it. The main area is a table with the following columns: 'Authorization Status', 'Record Status', 'Country Group Code', 'Group Rate', 'Provision Expense GL', and 'Provision Liability GL'. The table is currently empty. At the bottom right, there is an 'Exit' button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Country Group Code
- Provision Expense GL

- Transaction Code
- Record Status
- Group Rate
- Provision Liability GL

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Authorization Status
- Record Status
- Country Group Code
- Group Rate
- Provision Expense GL
- Provision Liability GL
- Transaction Code

5.8 Viewing Manual Provisioning

You can view manual provisioning amount computed for risk and country group using 'Manual Provisioning' screen. To invoke this screen, type 'CSDMPROV' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Manual Provisioning' application window. The window title is 'Manual Provisioning'. It contains several sections:

- Provision Details:** Includes fields for 'Processed as on', 'Bank Code', 'Processed By', and 'Order of Process', along with a 'Process Accounting' button.
- Risk Level Alpha Details:** A table with columns: Risk Level, Provision Amount, Alpha Rate, Alpha Amount, Accounting Status.
- Risk Level Beta Details:** A table with columns: Risk Level, Provision Amount, Beta Rate, Beta Amount, Accounting Status.
- Country Group Details:** A table with columns: Group Level, Provision Amount, Group Rate, Group Amount, Accounting Status.
- Events / Contract Details:** A section at the bottom with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', and an 'Exit' button.

Processed as on

Specify the date on which the group provision was computed from the adjoining calendar.

Processed By

System displays the value to indicate whether the group provisioning has been running during EOD or manually through intraday batch. It can be one of the following:

- Automatic
- Manual

Bank Code

System displays the bank code here.

Order of Process

You can view the order of processing here if the group provisioning has run multiple times a day.

You can click on the 'Process Accounting' button to manually initiate the accounting.

System will display the accounting entries for the following:


- Risk Level Alpha
- Risk Level Beta
- Country Group Provision



You can select the specific records for 'Risk Level Alpha'; 'Risk Level Beta'; and 'Country Group Level' for accounting.

5.8.1 Viewing Contract Details

You can view contract details using 'Contract Details' screen. Click on the 'Contract Details' button to invoke this screen.



5.9 Provisioning Computation batches

CSBGRPRV

This batch is configured and run at the head office level.

This computes the provision amount at risk level and country group level for all contracts across branches for group provisioning. System will not pass accounting during batch. It only logs provision amount.

System selects the contracts with:

- The status 'Active'
- The check box 'Group Provisioning Required' is checked
- The Coverage maintenance doesn't exist.

Risk Provisioning

Contracts will be grouped based on the risk level. Total debt amount will be computed based on the risk components maintained at product level and the outstanding amounts for these components maintained with the same risk level.

Contracts picked for the risk provisioning in every batch will be stored in data store along with the total debt for each contract.

Country Group Level

Contracts will be grouped based on the country group level. Total debt amount will be computed based on country group components maintained at the product level; outstanding amounts for these components maintained for the same country group; provisioning rate maintained at the country group level.

Contracts picked for the country group provisioning in every batch will be stored in data store along with the total debt for each contract.

CSBPROVN

EOD Batch will be triggered post EOTI batch to compute provisioning for Leasing, Loans, Guarantee, and Overdraft accounts.

5.9.1 Provision Processing for Accounts

Provision processing for customer accounts is only done if indicated in the account details. Provision processing depends upon the status processing for accounts.

The Provisioning Batch

For accounts for which provisioning has been indicated, a batch process is run subsequent to the following processes, to perform provisioning:

- Status processing for accounts
- Interest and Charges (IC) batch process
- The Automatic Daily Contract Update process in the Loans module

To trigger the provisioning batch, you can use the Provisioning Batch screen. When the batch is triggered, the provisioning events SPRO (provision) and SPWB (write back) are executed.

5.9.1.1 Specifying Frequency at which Provisioning Batch is Executed


To recall, provision processing depends upon status processing for accounts and contracts. The provisioning batch executes after the status processing batch, as explained in the previous section. If status processing is indicated to be processed at group/CIF level, you can indicate the frequency at which the provisioning batch is to be executed for your branch.


You can specify the provisioning frequency in the Branch Parameters Preferences screen. The frequency options available are daily and monthly.

To view the Branch Parameters Preferences screen, refer the Core Services user manual.

The Provisioning Process

If status processing for your branch is done at customer group/CIF level, (as specified in the Branch Parameters), the provisioning process executes according to the frequency defined in the Branch Parameters. The process executes as described below:

1. The exposure categories for the customer group or CIF are first derived, either from the specification for the same in the contract and account details, or depending upon the total exposure of the group or CIF, according to the logic maintained for deriving the exposure category, in the Exposure Type – Category Linkage maintenance
 When the exposure category for a CIF or customer group is derived according to the logic maintained in the Exposure Category Type Linkage screen, the outstanding overdraft in all accounts belonging to the group/CIF, as well as the exposure due to loans issued to the group/CIF is summed, to compute the total exposure
2. The provisioning percentage applicable is then derived, either from the contract and account details, or using the exposure category of the CIF and the status of all accounts and contracts involving the CIF, according to the linkage maintained in the Exposure Category Provisioning Percentage maintenance
3. Having obtained the provisioning percentage applicable, the system then computes the provision amount, based on the rule defined in the Loans Provisioning Rule maintenance (for loans) and the Account Provisioning Rule Maintenance (for accounts).
4. The computed provision amount would then be stored for the accounts and contracts, and appropriate accounting entries passed. The computed provision amount is stored and displayed in the Amount Tab in the Customer Account Maintenance. The current status and exposure category of the account is also stored along with the balances.

 In case of contracts, the provision amount is not re-computed when a contract amendment, value-dated amendment, or automatic or manual payment is done, but only as part of the provisioning batch. On maturity of the contract, the provision amount is reversed. Similarly in the case of accounts, the provision amount is written back when the account is closed.

5.9.1.2 Computation of Provision Amount

When status processing is done at a group or CIF level,

- The worst status among all contracts and accounts under a specific customer group or CIF is arrived at
- All accounts and contracts with automatic status processing involving the customer group or CIF are then moved to the worst status that was arrived at.
- The total exposure of customers in a group or CIF is considered as the sum of all outstanding overdrafts in respect of accounts belonging to the group/ CIF, as well as the loans issued to the group or CIF. This total exposure is considered for deriving the provision percentage, and computation of the provision amount.

- The computed provision amount is stored and displayed in the Amount Tab in the Customer Account Maintenance. The current status and exposure category of the account is also stored along with the balances.

The provision amount is computed for each account using the provision rule defined for the account class that the account uses. Typically, the computation could be done according to the following guidelines:

Status of the Accounts

For instance, let us suppose the statuses for accounts belonging to a CIF are derived according to the following guidelines:

	Delay Period				
Debtor Financial Standing	Up to 30 days	Between 31 and 60 days	Between 61 and 90 days	Between 91 and 180 days	Beyond 180 days
Good	Regular	Watch	Substandard	Doubtful	Loss
Unstable	Watch	Substandard	Doubtful	Loss	Loss
Not Good	Substandard	Doubtful	Loss	Loss	Loss
Deteriorate	Doubtful	Loss	Loss	Loss	Loss
Bad	Loss	Loss	Loss	Loss	Loss

Provision for General Credit Risk

General Credit Risk includes all contracts and accounts in 'Regular' status. The provision amount computation could be done as follows, according to the following categories:

Exposure to Corporate Customers

The expression used for this category could be:

$$PA = (OD - RFC) \times PP, \text{ where,}$$

PA = Provisioning Amount,

OD = Outstanding Overdraft Amount = Principal + Overdue Interest,

RFC = Risk-free Collateral,

PP = Provisioning Percentage

The provisioning percentage could be computed as shown:

Loan Type	Categorization	Provision
Corporate Small – (CS)	Exposure <= BGN 50,000	1.5%
Corporate Intermediate – (CI)	Exposure > BGN 50,000 and <= BGN 500,000	2.0%
Corporate Large – (CL)	Exposure > BGN 500,000 and < L-Sig	3.0%
Corporate Big – (CB)	Exposure >= L-Sig	0.0%

Here, L-Sig could correspond to one percent of bank's capital base rounded to nearest lower amount divisible by 50,000. Typically, the bank sets this figure.



In arriving at the total exposure figure (as shown in the table above), the outstanding overdraft in the account as well as the outstanding amounts on all loans issued to the group/CIF that the account belongs to, are summed.

Example

Customer	Exposure	Amount (BGN)	Type
Account 1	Loan 1	20,000	CI
	Loan 2	15,000	CI
	Account Overdraft	12,000	CI
Account 2	Loan 3	5,000	CI
	Loan 4	5,000	CI
	Account 1 Overdraft	26,000	CI
	Account 2 Overdraft	15,000	CI
	Sum of total exposure amounts	98,000	

Exposure to Retail Customers

The expression used for this category could be:

$$PA = (OD - RFC) \times PP, \text{ where}$$

PA = Provisioning Amount

OD = Outstanding Overdraft Amount = Principal + Overdue Interest

RFC = Risk-free Collateral

PP = Provisioning Percentage

The provisioning percentage could be computed as shown:

Loan Type	Categorization	Percentage
Retail OD – (RO)	Retail Overdrafts	1.5%
Retail Mortgages – (RM)	Retail Loans that has mortgages as collateral	2.0%
Retail Consumer (RC)	Other than the above	1.5%

Provisioning for Impairment Losses

Impairment losses include loans that are not in the 'Regular' status. The provision amount computation could be done as follows, according to the following categories:

All Corporate customers regardless of exposure and Retail customers with exposure exceeding BGN 5000

The expression used for this category could be:

$$PA = (BVE - RV - RFC) \times PP$$

Where

PA = Provisioning Amount

BVE = Balance Value of Risk Exposure = Outstanding Overdraft amount (which is, Principal + Balance Overdue Interest)

RFC = Risk-free Collateral

RV = Recoverable Value

PP = Provisioning Percentage

The recoverable value could be computed by applying the discount percentage to the balance expected cash flow, as shown:

Status	Minimum Limit	Accepted discount
Watch	10%	25%
Substandard	30%	50%

Doubtful	50%	75%
Loss	100%	100%

The resultant amount could be discounted using the overdraft interest rate. For loans in status 'LOSS', the recoverable value is zero.

An example for the provision amount calculation for accounts in impairment loss

For an account in respect of which the balance value of exposure is BGN 700 and the balance overdue interest is BGN 100, the outstanding overdraft amount = 700 + 100 = BGN 800.

If the account is in 'WATCH' status, the applicable discount (or loss) percentage for the account is 25 %

Therefore, the recoverable value of the exposure = 800 – (800 * 25%) = BGN 600

If the risk free collateral is BGN 100, the provision amount = 800 – 600 – 100 = 100

Retail Customers with Exposure Less than BGN 5000

The expression used for this category could be:

$$PA = (OD - RFC) \times PP, \text{ where}$$

PA = Provisioning Amount

OD = Outstanding Overdraft Amount = Principal + Overdue Interest

RFC = Risk-free Collateral

PP = Provisioning Percentage

The provisioning percentage could be computed as shown:

Status	Provisioning Percentage
Watch	10%
Substandard	30%
Doubtful	50%
Loss	100%

The provisioning would be done for individual accounts as shown above.

5.9.1.3 Specifying Rebooking Provision Entries

In the Status Details function, you can indicate whether provisioning entries for an account must be rebooked when provisioning is done after an automatic status change for the account. Rebooking essentially means that fresh provisioning is done, after reversing the previous provisioning amount.

The provisioning batch process, when executed, not only computes the provisioning amount; it also records the current status of the account and checks whether the current status is different from the status that was prevalent when the process was previously executed. If so, the old provisioning amount is written back into the write back GL of the old status (*if* the Rebook Provision option has been set in the Status Details), and the entries for the new provisioning amount are booked into the provisioning GLs maintained for the current status in the Status Details.

If the Rebook Provision has not been set, there is no reversal of the old provisioning amount, and the differential provisioning entries are passed, as usual, into the GLs maintained for the current status. When there is a status change between two provisioning cycles, the Rebook Provision option is set for the status with the higher sequence number. For instance, while moving from status NORM (Normal) to PDO1 (Past Due Obligation), the Rebook Provision option is set for the status PDO1 and while moving from PDO1 to NORM, the Rebook Provision option is set for the status PDO1 again.



If manual provisioning has been done, the entries for the differential amount are passed or written back into the GLs associated with the NORM (normal) status.

5.9.1.4 Maintaining Accounting Entries for Provisioning

The computed provision amount is stored and displayed in the Amount Tab in the Customer Account Maintenance. The current status and exposure category of the account is also stored along with the balances.

For account provisioning, accounting entries are passed for the following:

- Changes in provisioning amount without status change
- Reversal of provisioning amount as a result of status change

Accounting Entries for Changes in Provision Amount without Change in Status

The entries passed for new provisions or increase of provision amount:

Dr: Expense GL

Cr: Provisioning GL

Entries for decrease in provision amount:

Dr: Provisioning GL

Cr: Reintegration GL

Accounting entries for change in status with/without changes in provision Amount and with the Rebook Provision option applicable

In this case, the existing entries are reversed into a reintegration GL and new provisioning entries are booked, provided the 'Rebook Provision on Status Change' option has been set for the new status of the account. In this case, the following entries would be passed

For reversal of provision amount

Dr: Provisioning GL

Cr: Reintegration GL

For booking of new provision amount

Dr: Expense GL

Cr: Provisioning GL

6. Customer Information Query

6.1 Introduction

You can access the following information through the Customer Information Query screen:

- Customer Limits, specifically relating to Overdraft Limits on Current Accounts and Foreign Exchange Exposure Limits
- Details relating to a Customer Account
- Facility to query for Account statement
- Facility to view future settlement balance/contracts
- Facility to view Asset and Liability Balances of the customer
- Facility to view summary of Collaterals and Account Details

6.2 Invoking Customer Position Screen

Invoke the 'Customer Information Query' screen, by typing 'ACDSCPQR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Information Query

Customer Information

Customer*

Address

Linked Customer

Current Branch Only

Relationship

Query

Customer Relation

Customer ID	Name
-------------	------

Fetch

Accounts: Loans Deposits FX FT

Account Details

Branch	Customer Account	Customer	Description	Currency	Current Balance	Related Customer	Relationship	Debit/Credit Indicator
--------	------------------	----------	-------------	----------	-----------------	------------------	--------------	------------------------

Collateral Asset/Liab MIS Limits Projection Accounting

From Date

To Date

Transaction Date

Value Date

Exit

The screen displays all the accounts linked to the selected customer for the specified date range, and grouped by Branch, Customer Account, and Currency.

If you check the 'Linked Customer' check box and provide the Customer Number and click 'Query' button, all linked customers of the customer number entered will be displayed.

To query on any linked customer displayed, select the customer and click 'Fetch' button. A query operation is performed on the selected customer and the details are displayed. The displayed values are based on the query parameters provided.

6.2.1 Viewing Account Details

You can view details of all the accounts linked to the selected customer through the Customer Position screen. Click the Accounts tab. The screen appears as shown below:

The screenshot shows the 'Customer Information Query' window. It features a search section with 'Customer *' and 'Address' fields, and checkboxes for 'Linked Customer', 'Current Branch Only', and 'Relationship'. A 'Query' button is located below these fields. Below the search section is a 'Customer Relation' table with columns 'Customer Id' and 'Name'. A 'Fetch' button is positioned to the right of this table. At the bottom of the window, there is an 'Accounts' tab with sub-tabs for 'Loans', 'Deposits', 'FX', and 'FT'. Below the 'Accounts' tab is an 'Account Details' table with columns: 'Branch', 'Customer Account', 'Customer', 'Description', 'Currency', 'Current Balance', 'Related Customer', 'Relationship', 'Debit/Credit Indicator', and 'Joint Holder Ret'. At the very bottom, there are several buttons: 'Collateral', 'Asset/Liability', 'MIS', 'Limits', 'Projection', and 'Accounting'. There are also 'From Date' and 'To Date' input fields, and radio buttons for 'Transaction Date' and 'Value Date'. An 'Exit' button is located in the bottom right corner.

You can run the query based on following parameters:

Customer

Select the customer number from the adjoining option list. The available options are:

- Customer Number
- Document ID Number

- Customer Name

Address

Specify the customer address.

Linked Customer

Check Linked Customer and provide Customer Number then click Query button to view all the Account Numbers of the customer and its linked customers.

Branch

You can indicate whether only customer accounts in the current branch should be displayed or customer accounts across branches should be displayed. Check this box to view customer accounts pertaining to the current branch.

Indicating whether to include Relationship

While querying for the customer position, you can choose to include all the accounts, loans or deposits where the customer is not the primary holder. To indicate this, choose the check box Include Relationship. The summary screen displays the customer number or primary holder of the account, the customer's name, and the relationship that the customer has with the account.

If you leave this box unchecked, system will display the account details of primary account holder only.

If you are allowed to query customer information, then system displays the following details pertaining to the fetched records:

- Customer
- Description
- Currency
- Current Balance
- Related Customer
- Relationship
- Debit Credit Indicator
- Joint Holder Relationship

6.2.2 Viewing Loans Details

You can view details of all loan contracts for the selected customer through the Customer Position screen. Click the Loans tab. The loan amount that appears is the consolidated amount grouped by Branch, Product, and Currency.

The screen appears as shown below:

Customer Information Query

Customer Information

Customer*

Address

Linked Customer

Current Branch Only

Relationship

Query

Customer Relation

Customer ID	Name
-------------	------

Fetch

Accounts | Loans | Deposits | FX | FT

Contract Details

Branch	Product	Description	Currency	Balance	Debit/Credit Indicator
--------	---------	-------------	----------	---------	------------------------

Collateral
Asset/Liab

MIS
Limits

Projection
Accounting

From Date

To Date

Transaction Date

Value Date

Exit

Double clicking a record displays the Loan Contracts Summary screen comprising a summary of transactions contributing to the balance displayed in the Customer Position screen. The balance displayed is the outstanding principal amount for the Loan product. This screen also displays MM contracts, that is, MM borrowings are displayed under the Deposits tab and MM Placements are displayed under Loans. Double clicking a record in the Loans Contract Summary screen displays the corresponding Loan Contract screen comprising transaction details.



The summary screen will not be shown for contracts that do not belong to the current branch

For more details on the LD Contract Online screen, please refer the Loans User Manual

6.2.3 Viewing Deposit Details

You can view details of all Deposit contracts for the selected customer through the Customer Position screen. Click the Deposits tab. The deposit amount that appears is the consolidated amount grouped by Branch, Product and Currency.

The screen appears as shown below:

Customer Information Query

Customer Information

Customer*

Address

Linked Customer

Current Branch Only

Relationship

Query

Fetch

Customer Relation

Customer ID	Name
-------------	------

Accounts | Loans | Deposits | FX | FT

Deposits Details

Branch	Product	Description	Currency	Balance	Debit/Credit Indicator
--------	---------	-------------	----------	---------	------------------------

Collateral | Asset/Liab | MIS | Limits | Projection | Accounting

From Date

To Date

Transaction Date

Value Date

Exit

Double clicking a record displays the Deposits Contracts Summary screen comprising a summary of transactions contributing to the balance displayed in the Customer Position screen (MM borrowings + Deposits). The Balance is the principal balance for the selected Deposit product. Double clicking a record in the Loans and Deposits Contract Summary screen displays the corresponding Deposit Contract screen comprising transaction details.




The summary screen will not be displayed if the deposit does not belong to the current branch

For more details on the Contract Online screen, please refer the user manual for Deposits.

6.2.4 Viewing FX Details

You can view details of all FX contracts for the selected customer through the Customer Position screen. The entries are the consolidated amounts for contracts grouped by product, branch and currency. Double clicking a record displays the summary screen for that record and double clicking further, displays the contract details screen for that record. Click the FX tab.

The screen appears as shown below:



Here, the FX bought amount is displayed as Debit Balance and the FX sold amount is displayed as Credit Account.

Double clicking a record in the Customer Position screen displays the corresponding FX Contract Summary screen. Double clicking a record in the FX Contract Summary screen displays the corresponding FX Contract Detail screen comprising the transaction details.

6.2.5 Viewing FT Details

You can view details of all FT contracts for the selected customer through the Customer Position screen. Click the FT tab.

The screen appears as shown below:

The screenshot shows the 'Customer Information Query' application window. It features a 'Customer Information' section with a 'Customer*' field, an 'Address' field, and checkboxes for 'Linked Customer', 'Current Branch Only', and 'Relationship'. A 'Query' button is located below these fields. Below the 'Query' button is a 'Customer Relation' table with columns 'Customer ID' and 'Name'. To the right of this table is a 'Fetch' button. Below the 'Customer Relation' table is a navigation bar with tabs for 'Accounts', 'Loans', 'Deposits', 'FX', and 'FT'. Below the navigation bar is a 'Funds Transfer Details' table with columns 'Branch', 'Product', 'Description', 'Currency', 'Balance', and 'Debit/Credit Indicator'. Below the 'Funds Transfer Details' table are several buttons: 'Collateral', 'Asset/Liab', 'MIS', 'Limits', 'Projection', and 'Accounting'. Below these buttons are 'From Date' and 'To Date' fields, and radio buttons for 'Transaction Date' and 'Value Date'. An 'Exit' button is located in the bottom right corner of the window.

The Balance amount displayed here is the incoming cash flow amount or credit balance for the FT product.

Double clicking a record in the Customer Position screen displays the corresponding FT Contract Summary screen. Double clicking a record in the FT Contract Summary screen displays the corresponding FT Contract Detail screen comprising the transaction details.

6.2.6 Viewing Collaterals Details

You can view the collateral details for the selected customer through the Customer Position screen. Click the 'Collateral' button. The Collateral Summary View screen appears for all collaterals linked to the customer liability.

Double clicking a record in the Collaterals Summary screen displays the details of the selected collateral.


6.2.7 Viewing Assets/Liabilities Details

You can view the total asset and total liability for the selected customer through the Customer Position screen. Click the 'Asset/Liab' button. The Assets/Liabilities Summary screen appears. All Assets and Liabilities transactions are displayed in Asset and Liabilities transaction blocks along with the local currency equivalent for each transaction. The total for Assets and the total for Liabilities are also displayed at the end of each block.

STOP Asset = Sum of Current balance of All the account having –ve balance + Sum of all the Loans outstanding balance Linked to a given customer + Sum of all MM placements of the customers

Liability = Sum of Current balance of all the account having +ve balance + Sum of all the Deposits Linked to a given customer + Sum of all MM borrowings of the customer.

Invoke the 'Customer Asset & Liability Query screen, by typing 'ACDSQASL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Customer Liability

The following customer liability details are displayed based on the query parameters provided:

- Authorized Status
- Contract Status
- Branch
- Reference Number
- Customer
- Currency
- Debit/Credit
- Amount
- Local Currency Amount
- Value Date

The following account status details are displayed based on the query parameters provided:

- Status Dormant

- No Debit
- No Credit
- Frozen

6.2.8 Viewing Limits Details

Check Linked Customer and provide Customer Number and click Query button to view all linked customers in Linked Customer Details. To query on any linked customer displayed, select the customer and click 'Fetch' button. A query operation is performed on the selected customer and the details are displayed. The displayed values are based on the query parameters provided.

You can view details of limits maintained for the selected customer through the Customer Position screen. Click the 'Limits' button. The Liability Summary screen appears. Double clicking on a record displays the Limits Line Summary screen which provides a summary view of all the lines linked to the liability of the customer. Double clicking on a record in the Limits Line Summary screen, displays the utilization summary screen.

6.2.9 Viewing MIS Details

You can view MIS information about the selected customer through the Customer Position screen. Click MIS tab.

The screenshot shows a software window titled "MIS". At the top, there is a "MIS Group" field and a checked "Link to Group" checkbox. To the right, the "Customer Code" is set to "001003094". Below this is a table with two columns: "Customer MIS Code" and "Composite MIS Code". The table contains several rows, with the first two labeled "BUS_SEGMT" and "CU_REGION". At the bottom of the window, there are "Change Log" and "Transfer Log" buttons, and "Ok" and "Exit" buttons in the bottom right corner.

For more details on the MIS screen, refer the MIS User Manual

6.2.10 Viewing Projections

You can view future settlement balances and outstanding FX and FT contracts for the selected customer account through the Customer Position screen. Click 'Projection' button.

Invoke the 'Customer Projections Query' screen, by typing 'ACDSQPRO' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Customer Projections Query' window. It features a title bar with a diamond icon and the text 'Customer Projections Query'. The main area contains several input fields: 'Customer *' (with a red asterisk), 'Customer Name', 'Customer Account Number', 'Description', and 'Date'. There is a 'Query' button below the 'Description' field and a 'Fetch' button to the right of the 'Date' field. A 'Linked Customer' checkbox is located below the 'Description' field. Below these fields are two data grids. The first grid is titled 'Linked Customer' and has columns 'Account Number' and 'Customer Id'. The second grid is titled 'Customer Cash Flow' and has columns 'Due Date', 'User Reference', 'Component', 'Contract Reference', 'Module', 'Transaction Date', 'Currency', and 'Debit/Credit'. An 'Exit' button is located at the bottom right of the window.

To view the settlement balance for the selected customer for a particular future date, enter a date in the date field and click the 'Q' button. The system displays details of all the unsettled transactions, which have occurred until the date indicated in the "Date" field. "Total" indicates the sum total of all unsettled transactions in local currency for the selected customer number.

Check Linked Customer and provide Customer Number and click Query button to view all linked customers in Linked Customer Details. To query on any linked customer displayed, select the customer and click 'Fetch' button. A query operation is performed on the selected customer and the details are displayed. The displayed values are based on the query parameters provided.

Double clicking a record in this screen invokes the contract summary screen for the selected contract. The current balance of the selected customer is displayed at the bottom of this screen. The current balance denotes the sum total of balances in all the accounts of the selected customer.

6.2.11 Viewing Accounting Entries

You can view all the accounting entries passed for a selected Customer Account in the Accounting Entry Retrieval screen. To invoke this screen, select a customer account and a date range in the Customer Position screen and then click 'Accounting' button.

The Accounting Entry Retrieval screen is displayed with all the accounting entries passed for the selected customer account and date range:

The screenshot shows the 'Accounting Entry Retrieval' window. It is divided into three main sections: Query Criteria, Account Details, and Transaction Details.

Query Criteria: Includes fields for Contract Reference, Transaction Code, Event Code, Value Date, Related Reference, From Date (2012-02-27), Debit/Credit (dropdown), Currency, Module Code, Transaction Date, Related Account, and To Date (2012-03-05). A 'Query' button is located below the From Date field.

Account Details: Includes fields for Branch Code (001), Starting Balance (0), Currency (GBP), Debit Credit Balance (C), and Account Number (00100309401).

Transaction Details: A table with columns: Contract Reference, Entry Serial No, Module Code, Transaction Code, Event Code, and Transaction Date. The table contains six rows of data.

Contract Reference	Entry Serial No	Module Code	Transaction Code	Event Code	Transaction Date
001IC01120620005	591656	BC	ACH	INIT	2012-03-02
001ILCL120620007	591560	LC	IBC	BISS	2012-03-02
001IC01120620005	591658	BC	TAX	INIT	2012-03-02
001IC01120620005	591648	BC	MSC	INIT	2012-03-02
001IC01120620005	592580	BC	BST	LIQD	2012-03-02
001IC01120620005	592579	BC	BST	LIQD	2012-03-02

Buttons for '+', '-', and a list icon are located above the table. An 'Exit' button is at the bottom right of the window.

Double clicking on an accounting entry in this screen displays the corresponding contract input screen.

Click 'Query' button if you wish to query for any particular accounting entry

6.2.12 Overdrawn Accounts Query

Invoke the 'Overdrawn Accounts Query' screen, by typing 'ACDCODQS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Overdrawn Accounts Query

Customer Number

Currency

Liability Number

Account No

Facility Identifier

Linked Customer

Linked Account

Query

Result

<input type="checkbox"/>	Customer Number	Branch Code	Account No	Currency	Facility Identifier	Liability Number	Payable Balance	Uncoll. Funds
--------------------------	-----------------	-------------	------------	----------	---------------------	------------------	-----------------	---------------

Exit

You can view the following information in this screen:

- Customer Number
- Account Branch
- Account Number
- Account Currency
- Facility Identifier
- Liability Number
- Payable Balance

Linked Customer

Check Linked Customer and provide Customer Number and click Query button to view all the Overdrawn Account Numbers of the customer and its linked customers.

Linked Account

Check Linked Account and provide Account Number and click Query to view all Overdrawn Account Numbers of the customer of the account. The displayed values are based on the query fields provided.

6.2.13 Uncollected Funds Query

Invoke the 'Uncollected Funds Query' screen, by typing 'ACDFUNCO' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Available Date	Transfer Reference	Bank Code	Amount	Account Number
----------------	--------------------	-----------	--------	----------------

You can view the following information in this screen

- Available Date
- Transfer Reference Number
- Bank Code
- Amount
- Amount Number

Linked Account

Check Linked Account and provide Account Number and click Query to view all Uncollected Fund Account Numbers of the customer and its linked customers. When Linked Account is not checked the existing query operation takes place. The displayed values are based on the query fields provided.

6.2.14 Customer Account Balance Query

You can use the Balance Enquiry screen to view the account balance details of any particular account of the selected customer.

Invoke the 'Customer Account Balance Query' screen, by typing 'ACDCBIRD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software interface titled "Customer Account Balance Query". At the top, there are input fields for "Account Number", "Customer Number", "Currency", and "Account Class". Below these are two checkboxes: "Linked Customer" and "Linked Account", and a "QUERY" button. A table with the following columns is visible: Account Number, Status Dormant, No Debit, No Credit, Frozen, Currency, Current Balance, Available Balance, and Utilized. At the bottom of the window, there are buttons for "Account Statistics", "Account Details", and "Exit".

Linked Customer

Check Linked Customer and provide Customer Number then click Query button to view all the Account Numbers of the customer and its linked customers.

Linked Account

Check Linked Account and provide Account Number then click Query to view all account numbers of the customer of the account. The displayed values are based on the query fields provided.

The following account balance details are displayed based on the query parameters provided:

- Account Number
- Currency
- Current Balance
- Available Balance
- Utilized Line Amount
- Total Available Balance
- Uncollected Funds
- Amount Blocked

- Tod Limit
- Sublimit
- Uncollected Funds Limit
- Accrued Interest Debit
- Accrued Interest Credit
-

The following account status details are displayed based on the query parameters provided:

- Status Dormant
- No Debit
- No Credit
- Frozen

The account status details can also be viewed by placing the cursor in the 'Account Number' field and pressing the hot key F11.

7. 360 Degree Customer View

7.1 Introduction

Oracle FLEXCUBE allows you to view and analyze personal and business details of the customers. You can query customer limits, account statements, view settlement balances contracts, view assets and liability balances of the customer. You can also view summary of collateral and account details. The 360 degree customer view facilitates easy and total view of the customer details and reduces customer service complexities.

7.2 Invoking 360Degree Customer View Entry Screen

Invoke the '360Degree Customer View Entry Point' screen, by typing 'STSCUSVW' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the '360Degree Customer View Entry Point' application window. The window title is '360Degree Customer View Entry Point'. The interface includes a search form with the following fields: Customer Number, Short Name, Unique Identifier Name, National ID, External Reference, Full Name, and Unique Identifier Value. Below the search form are buttons for Search, Advanced Search, Refresh, and Reset. A table below the form shows a list of records with columns: Customer Number, External Reference, Short Name, Full Name, Unique Identifier Name, Unique Identifier Value, Passport Number, and Telephone. The table is currently empty. At the bottom right, there is an Exit button.


Here you can query on the basis of any one of the following details:

- Customer No
- Short Name
- Unique identifier Name
- National ID
- External Reference

- Full Name
- Unique Identifier value

On entering any one of the following details and clicking 'Search', the system displays the following details:

- Customer Number
- External Reference
- Short Name
- Full name
- Unique Identifier Name
- Unique Identifier Value
- Passport Number
- Telephone
- Mobile Number

 When you double click on the customer record, the system will launch either Retail view screen or corporate view screen depending on the type of customer.

7.3 Viewing 360 Degree Retail Customer Details

You can invoke '360 Degree Retail Customer View' screen if the customer is Retail by double clicking on the customer record in the '360Degree Customer View Entry Point' screen or by typing 'STDRETVW' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Customer Number: Branch: Short Name: Reporting Currency: Full Name: Reports

Summary | Profile | Deposits | Loans | Events | Schemes | Alerts | Limits | Payments | Is-Deposits | Is-Financing | External Products

Prefix:
 Address For Correspondence:
 Name:
 Address:
 Telephone:
 Fax:
 E-mail:

Status:
 Frozen
 Deceased
 Whereabouts Unknown
 KYC Status:
 CIF Status:
 Since:
 Credit Rating:
 Customer Category:
 Charge Group:
 Tax Group:

Balance Sheet Asset And Liabilities

Asset	Ccy	Value	Liability	Ccy	Value
<input type="checkbox"/> Corporate Loans		0.00	Current Accounts		0.00
<input type="checkbox"/> Leasing		0.00	Saving Accounts		0.00
<input type="checkbox"/> Mortgages		0.00	Term Deposits		0.00
<input type="checkbox"/> Syndicated Loans		0.00	Islamic Current Accounts		0.00
<input type="checkbox"/> Islamic Financing		0.00	Islamic Saving Accounts		0.00

Off Balance Sheet Asset And Liabilities


Asset	Ccy	Value	Liability	Ccy	Value
<input type="checkbox"/> Forward Buy Contracts		0.00	Forward Buy Contracts		0.00
<input type="checkbox"/> Forward Sale Contracts		0.00	Forward Sale Contracts		0.00
<input type="checkbox"/> Islamic Derivatives Buy		0.00	Islamic Derivatives Buy		0.00
<input type="checkbox"/> Derivatives Buy		0.00	Derivatives Buy		0.00
<input type="checkbox"/> Islamic Derivatives Sale		0.00	Islamic Derivatives Buy		0.00

Cancel

The system displays the following details:

- Customer Number
- Short Name
- Reporting Currency
- Branch
- Full Name

Click the 'Reports' button to view the '360 Degree Customer Report' screen.



The details that can be viewed in the '360 Degree Retail Customer View' screen is classified into 12 broad heads.

Summary	You can view the address, status. Balance sheet asset and liabilities and off balance sheet asset and liabilities under the summary tab.
Profile	You can view the details of the customer's profile.
Deposits	You can view the details of the customer deposits.
Loans	You can view the details of the customer's loan.
Events	You can view the details of the upcoming events.
Schemes	You can to view the details of the relationship schemes.
Alerts	You can view the alerts for overdue loans, matured deposits but not renewed or liquidated, Locker Charges Overdue Details, Cheques Returned, Amount Block Details and Stop

	Payment Details.
Limits	You can view the limits and collaterals of the customer.
Payments	You can view the FT and PC contracts of the customer which is not liquidated.
Is-Deposits	You can view details about active CASA account and Term Deposit.
Is-Financing	You can view details about Islamic Account and Islamic Term Deposit..
External Products	You can view external details about products like credit cards, insurance, and mutual fund.

7.3.1 Viewing Summary Details

You can view the address, status, Balance sheet asset and liabilities and off balance sheet asset and liabilities under the summary tab. The following details are displayed here:

Address For Correspondence

Here you can view the following details:

- Name
- Address
- Telephone
- Fax
- E-mail

Status

Here you can view the following details:

- Frozen
- Deceased
- Whereabouts Unknown
- KYC Status
- CIF Status
- Since
- Credit Rating

- Customer Category
- Charge Group
- Tax Group

Balance Sheet Asset and Liabilities

Here you can view the following details:

- Asset
- Ccy
- Value
- Liability
- Ccy
- Value

Off Balance Sheet Asset and Liabilities

Here you can view the following details:

- Asset
- Ccy
- Value
- Liability
- Ccy
- Value

7.3.2 Viewing Profile Details

Click 'Profile' tab in the '360 Degree Retail Customer View' screen to view the details of the customer's profile.

The screenshot shows the '360 Degree Retail Customer View' application window. The 'Profile' tab is selected, displaying the following sections:

- Customer Information:** Customer Number, Branch, Short Name, Full Name, Reporting Currency, and Reports button.
- Navigation Tabs:** Summary, Profile (selected), Deposits, Loans, Events, Schemes, Alerts, Limits, Payments, Is-Deposits, Is-Financing, External Products.
- Name Section:** First, Middle, Last, Unique Identifier (Name, Value), Geographic (Country, Nationality, Language, National Id).
- Personal Details:** Sex (Male, Female), Resident Status (Resident, Non Resident), Joint Customer checkbox, Passport Details (Passport Number, Issue Date, Expiry Date), Legal Guardian (Date of Birth, Nominee Minor checkbox, Guardian, Submit Age Proof dropdown).
- Address Section:** Domicile Address (Line 1, Line 2, Line 3, Country, Mobile Number) and Permanent Address (Line 1, Line 2, Line 3, Country).
- Additional Tabs:** Image, Linked Customers, Locker Details, Professional, Domestic, Joint, Linked Entity, KYC Details, Fields, MIS.
- Footer:** Cancel button.


Here you can view the following details:

- Name
 - First
 - Middle
 - Last
- Sex
 - Male
 - Female
- Resident Status
 - Resident
 - Non Resident
 - Joint Customer
- Domicile address
 - Line 1 to 3
 - Country
 - Mobile Number
- Unique Identifier
 - Name
 - Value

- Passport Details
 - Passport Number
 - Issue Date
 - Expiry date
- Permanent Address
 - Line 1 to 3
 - Country
- Geographic
 - Country
 - Nationality
 - Language
 - National Id
- Legal Guardian
 - Date of Birth
 - Guardian
 - Submit age Proof

7.3.2.1 Viewing Signature Image and Photograph of the customer

Click on the 'Image' button to invoke 'Customer Signatory Details' screen. Here you can view the signature image and photograph of the customer.




Here you can view the following details:

- Signature Id

- Signature Title
- Signature
- Image

7.3.2.2 Viewing Related Customer Details

Click on the 'Linked Customers' button to invoke 'Linked Entities' screen. Here you can view other related customer details.




Here you can view the following details:

- Customer
- Description
- Relations

7.3.2.3 Viewing Locker Details

Click on the 'Locker Details' button to invoke 'Safe Deposit Locker Details' screen. Here you can view the locker details of the customer.

The screen is as shown below:



Here, you can view the following details:

- Contract Reference
- SD Vault Code
- SD Box Code
- Box Type
- Box Dimension
- Box Description
- Contract Currency
- Deposit Amount
- Tenor
- Issue Date
- Closure date
- Expiry Date

7.3.2.4 Viewing Professional Details of the Customer

Click on the 'Professional' button to invoke 'Customer Professional Details' screen. Here you can view the professional details of the customer.

The screen is as shown below:

Customer Professional Details

Employment: Employment

Employment Details:

- Tenure _____
- Retirement Age _____
- Previous Designation _____
- Previous Employer _____
- Current Designation _____
- Current Employer _____

Income:

- Salary _____
- Other _____
- Currency of Amounts _____

Official Address:

- Line 1 _____
- Line 2 _____
- Line 3 _____
- Country _____

Contact:

- Telex _____

Expense:

- Rent _____
- Insurance _____
- Loan Payments _____
- Other _____
- House Value _____
- Number of Credit Cards _____

Cancel

7.3.2.5 Viewing Domestic Details of the Customer

Click on the 'Domestic' button to invoke 'Customer Domestic Details' screen. Here you can view the domestic details of the customer.

Customer Domestic Details

Marital Status:

Spouse Employment Status:

Accommodation: _____

Spouse Name: _____

Educational Status:

Dependents:

- Children _____
- Others _____

Cancel

Here you can view the following details:

- Marital status
- Spouse Employment Status
- Accommodation
- Spouse Name

- Dependents
- Children
- Others

7.3.2.6 Viewing Customer information

Click on the 'Joint' button to invoke 'Customer Information Maintenance' screen. Here you can view information about the customer.


Here you can view the following details:

- Customer No
- Sex
 - Male
 - Female
- Prefix
- First name
- Last Name
- Middle
- Address line 1 to 3
- Passport Details
- Passport Number
- Issue Date

- Expiry Date
- Date of Birth
- Resident status
 - Resident
 - Non Resident
- Deceased
 - Deceased
 - Non Deceased
- Telephone
- E-mail
- SSN

7.3.2.7 Viewing Customer Entities

Click on the 'Linked Entity' button to invoke 'Linked Entity' screen. Here you can view details about customers who are linked to this customer, accounts for which this customer is linked, and loans which are guaranteed by this customer.



CASA Details of Linked Customers

Here you can view the following details:

- Branch Code
- Account No
- Account Description
- Current Balance
- Available Balance
- Blocked
- Uncollected
- Debit Interest Accrued Amount
- Credit Interest Accrued Amount
- Limit Currency
- Temp. OD limit
- Temp. OD Start
- Temp. OD End
- Account Status
- Since
- Related Customer
- Account Class

Retail Deposits of linked Customers

Here you can view the following details:

- Branch Code
- Account No
- Account Description
- term Deposit amount
- Maturity Date
- Interest Start Date
- tenor in Days
- Interest Rate
- Last Interest Effective Date
- Interest Accrued

- Account Status
- Since
- account Class
- Recurring Deposit

Corporate Deposits of Linked Customers

Here you can view the following details:

- Branch
- Contract Reference
- Product Description
- Currency
- Booking Date
- Value Date
- maturity date
- Interest Rate
- Contract Status
- Product
- No of Times Rollover
- Related Customer

Loan Details of linked Customers

Here you can view the following details:

- Branch Code
- Account Number
- Product description
- currency
- Amount financed
- Amount Disbursed
- outstanding Amount
- Booking Dated
- Value Date
- Maturity Date

7.3.2.8 Viewing KYC Details

Click on the 'KYC Details' button to invoke 'KYC Maintenance' screen. Here you can view KYC details of the customer.

KYC Maintenance

KYC Reference *

Full Name of Customer *

KYC Customer Type *

Risk Level *

Retail Customer Corporate Customer Financial Customer Fields

Maker Date Time: Mod No
Checker Date Time: Record Status
Authorization Status

Exit

Refer Core Entities for more information about the 'KYC Maintenance' screen.

7.3.2.9 Viewing User Defined Fields

Click on the 'Fields' button to invoke 'User Defined Fields' screen. Here you can view the UDF details of the customer.

The screen is as shown below:

User Defined Fields

Go to Page 1 of 1


UDF Details

Field Name *	Value

Cancel

7.3.2.10 Viewing MIS Details

Click on the 'MIS' button to invoke 'MIS' screen. Here you can view the MIS details of the customer.



The screenshot shows a software window titled 'MIS'. At the top, there are input fields for 'Customer *', 'MIS Group', and 'Branch Code'. Below these is a 'Default From MIS Group' button and a 'Link to Group' checkbox. The main area has two tabs: 'Customer MIS' (selected) and 'Composite MIS'. Below the tabs is a table titled 'Customer MIS Classes' with columns 'MIS Class' and 'MIS Code'. The table contains three rows, each with a checkbox in the first column. At the bottom of the window, there are 'Change Log' and 'Transfer Log' buttons, and 'Ok' and 'Exit' buttons in the bottom right corner.

7.3.3 Viewing Deposit Details

Click 'Deposits' tab in the '360 Degree Retail Customer View' screen to view the details of the customer deposits.

The screen is as shown below:

360 Degree Retail Customer View

Customer Number * _____ Short Name _____ Reporting Currency _____
Branch _____ Full Name _____ Reports

Summary Profile **Deposits** Loans Events Schemes Alerts Limits Payments Is-Deposits Is-Financing External Products

CASA Deposits

<input type="checkbox"/>	Branch Code	Account	Description	Currency	Current Balance	Available Balance	Uncollected Amount	Blocked Amount
<input type="checkbox"/>								

Summary of CASA Deposit _____ To enter Period _____
Total Credit Amount _____ From Date _____
Total Debit Amount _____ To Date _____

Account Signatory Standing Instruction Periodic Instructions Transactions Cheques Statement Generation Cards Others Joint Holders

Retail Deposit Details

<input type="checkbox"/>	Branch Code	Account	Description	Currency	Term Deposit Amount	Maturity Date	Interest Start Date	Tenor in Days	Last Interest Effective Date	Interest Accrued
<input type="checkbox"/>										


Cancel

CASA Deposits

Here, you can view the following details for an active CASA account:

- Branch code
- Account
- Description
- Account Class
- Related Customer
- Account Status
- Status Since
- Currency
- Current Balance
- Available Balance
- Uncollected amount
- Blocked amount
- Debit Interest Accrued Amount
- Credit Interest Accrued Amount
- Limit Currency

- TOD Limit
- TOD Limit Start Date
- TOD Limit End Date
- Account Type(Single or Joint)
- Relationship

 Closed accounts will not be displayed.

Retail Deposit Details

You can view the following details about the retail deposit:

- Account Number
- Branch Code
- Description
- Account Class
- Related Customer
- Status
- Since
- Currency
- Term Deposit Amount
- Maturity date
- Interest Start Date
- Account type(Joint or single)
- Tenor – Tenor will be displayed in terms of days.
- Interest rate – Interest Rate of a deposit. System will pick up the current interest rate of a deposit during query.
- Latest Interest Effective Date – System will pick up latest interest effective date of a deposit during query.
- Interest Accrued – Interest accrued till date for an account. This will be derived by the system during query.
- Recurring Deposit- This check box will be checked if it is Recurring Deposit
- Relationship

Corporate Deposit Details

You can view the following Corporate Deposit details:

- Contract Reference Number
- Customer No
- Product
- Product Description
- Currency
- Amount
- Maturity Date
- Booking Date
- Value Date
- Contract Status
- No of times Rollover – the system displays the number of times roll over has been done for deposit. This is arrived during query.
- Interest Rate – the system displays the current interest rate of a deposit. This is arrived during query.

7.3.3.1 Viewing Account Signatory

Click 'Account Signatory' button to view the 'Signatory Details' screen. In this screen, you can view the signatory details of the selected account.

The screenshot shows a window titled "Signatory Details" with the following fields:

- Branch Code *
- Account *
- Account Description
- Customer No
- Minimum No of Signatories
- Customer Name
- Account Message

Below the fields is a table with the following columns:


Signature Id *	Signature Name	Signatory Type	Approval Limit	Signatory Message
<input checked="" type="checkbox"/>				

At the bottom right of the window are "Ok" and "Exit" buttons.

Refer the section 'Specifying Account Signatory Details' under the 'Current and Savings Account' module for more information.

7.3.3.2 Viewing Standing Instruction

Click 'Standing Instruction' button to view the 'Standing Instruction Details' screen. In this screen you can view the standing instructions which have debit account as account selected from multiple block.




Here you can view the following details:

- Instruction Number
- SI Type
- First Execution date
- Next Execution Date
- SI Expiry Date
- Processing Time
- Credit Account
- Credit Account Branch
- SI Amount Currency
- SI Amount
- Product Code

7.3.3.3 Viewing Periodic Instructions

Click 'Periodic Instructions' button to view the 'Periodic Instructions' screen. In this screen, you can view the period instructions which have debit account as account selected from multiple block



Here you can view the following details:

- Instruction Reference Number
- Product Code
- Product Category
- Customer account Branch
- Counter Party Account Number
- Counter Party Name
- Transaction Currency
- Transaction Amount
- Next Generation date
- Execution days
- Execution Months
- Execution Years
- End date

7.3.3.4 Viewing Transactions

Click 'Transactions' button to view the 'Customer Account Transaction Query' screen. In this screen, you can query the transactions of an account during a given period.

Customer Account Transaction Query

Query Criteria

Contract Reference

Transaction Code

Event Code

Value Date

Related Reference

From Date 2012-03-22

Debit/Credit

Currency

Module Code

Transaction Date

Related Account

To Date 2012-03-14

Account Details

Branch Code 000

Starting Balance

Currency GBP

Debit Credit Balance

Account Number 00000210501

Transaction Details


<input type="checkbox"/>	Contract Reference	Entry Serial No	Module Code	Transaction Code	Event Code	Transaction Date	Value Date	Debit/Credit
--------------------------	--------------------	-----------------	-------------	------------------	------------	------------------	------------	--------------

Refer the section 'Querying Accounting Entries' under 'Core Services' module for more information.

7.3.3.5 Viewing Cheques

Click 'Cheques' button to view the 'Cheque Details' screen. In this screen, you can view the details of the cheques which are issued for a given period.

The screen is as shown below:



Here you can view the following details:

- Cheque Book Number
- Cheque Number
- Status
- Presentation Date

7.3.3.6 Viewing Statement Generation

Click 'Statement Generation' button to view the 'Account Statement Report' screen. In this screen, you can generate adhoc statement for an account.

The screen is as shown below:

The screenshot shows a dialog box titled "Account Statement Report". It has several sections:

- Account Selection Type:** Radio buttons for "One Account", "Multiple Account", and "Range".
- Statement Type:** Radio buttons for "Brief" and "Detailed".
- Date Range:** "From Date" and "To Date" text boxes with calendar icons.
- Single Account:** "Account Number" text box, "Charge" dropdown menu, and a checkbox for "Show linked Account Details".
- Account Currency:** Text box and radio buttons for "Booking Dated" (selected) and "Value Dated".
- Print Options:** Radio buttons for "View" (selected) and "Server Spool".
- Select Multiple Accounts:** A list box with a header "Select Multiple Accounts" and a sub-header "Account Number".
- From Account Number and To Account Number:** Text boxes with search icons.
- From Account Currency and To Account Currency:** Text boxes with search icons.
- Buttons:** "Ok" and "Exit" buttons at the bottom right.

Refer the section 'Account Statement Report' under 'Current and Savings Account' module for more information.

7.3.3.7 Viewing Cards Details

Click 'Cards' button to view the 'Debit Card Details' screen. In this screen, you can view details about active debit cards which are issued during given period for an account.

The screenshot shows a window titled "Debit Card Details". It features a table with the following columns:

<input type="checkbox"/>	Branch Code	Card Number	Primary Card	Name On Card	Card Expiry Date	Dispatch Status	Pin Mailed Status	Card Status

At the top right, there are navigation icons and "1 of 1" text. At the bottom right, there is a "Cancel" button.

Here, you can view the following details:

- Branch Code
- Card Number
- Primary card
- Name On Card
- Card Expiry Date
- Dispatch Status
- Pin Mailed Status
- Card Status
- ATM Limit Unit
- ATM Count Unit
- ATM Amount Limit
- POS Limit unit
- POS Count Limit
- POS Amount Limit

7.3.3.8 Viewing Other Details

Click 'Others' button to view the 'Other Details Of Account' screen. In this screen, you can view additional details about interest, limit, statement, account and nominees.

The screenshot shows a window titled "Other Details Of Account" with a close button (X) in the top right corner. The window is divided into several sections:

- Interest Details:** Credit Interest Accrued Amount (text input), Debit Interest Accrued Amount (text input).
- Limit Details:** Temp. OD Start (text input), Temp. OD End (text input), Limit Currency (text input, value: GBP), Temp. OD Limit (text input), Line Identification (text input).
- Statement Details:** Last Statement Date (text input), Last Statement Balance (text input), Last Statement Number (text input).
- Account Status:** A list of checkboxes: No Debit, No Credit, Stop Payment, Dormant, Frozen.
- Nominees:** Nominee1 (text input), Nominee2 (text input).

A "Cancel" button is located in the bottom right corner of the window.


Here, you can view the following details:

- Credit Interest Accrued Amount – the system displays the credit interest accrued. This value is arrived during query.

- Debit Interest Accrued Amount – the system displays the debit interest accrued till date for an account. This value is arrived during query.
- TOD Limit Start Date.
- TOD Limit End Date.
- Limit Currency
- TOD Limit
- Lind Id
- Last Statement Date
- Last Statement Balance
- Last Statement Number
- No Debit
- No Credit
- Stop Payment
- Dormant
- Frozen.
- Nominees

7.3.3.9 Viewing Joint Holder Details

Click 'Joint Holders' button to view the 'Joint Holders' screen. In this screen, you can view the joint holders details.



Here you can view the following details:

- Joint Holder Code

- Description
- Joint Holder Type
- Start Date
- End Date

7.3.3.10 Viewing Recurring Deposits Details

Click 'Recurring Deposits Details' button to view the 'RD Details' screen. In this screen, you can view recurring deposits if the deposit is recurring.

The screen is as shown below:


The screenshot shows a window titled "RD Details" with a blue header bar. The main content area contains two columns of input fields. The left column includes "Frequency Days", "Frequency Months", "Frequency Years", and "Installment Amount", each followed by a horizontal line for text entry. The right column includes "Payment Branch", "Payment Account", "Payment Currency", and "Payment Date", each followed by a horizontal line. In the bottom right corner of the window, there is a small rectangular button labeled "Exit".

Here you can view the following details:

- Frequency Days
- Frequency Months
- Frequency Years
- Installment amount
- Payment Branch
- Payment Currency
- Payment Date

7.3.3.11 Viewing Redemption Details

Click 'Redemption Details' button to view the 'Redemption Details' screen. In this screen, you can view redemption deposits of a deposit account.




Here you can view the following details:

- Redemption Date
- Redemption Amount
- Principal Amount
- Interest Amount
- Penal Interest Amount

7.3.3.12 Viewing Joint holder Details

Click 'Joint Holders' button to view the 'Joint Holders' screen. In this screen, you can view the joint holders details.




Here you can view the following:

- Joint Holder Code
- Description
- Joint Holder Type
- Start Date
- End Date

7.3.3.13 Viewing Schedule Details

Click 'Schedules' button to view the 'Schedule Details' screen. In this screen, you can view the schedule details of all components attached to the corporate deposit contract.

The screen is as shown below:



Here you can view the following details:

- Component
- Component Description
- Schedule Type
- Frequency
- Unit
- No of schedules
- Start date
- Amount

7.3.4 Viewing Loan Details

Click 'Loans' tab in the '360 Degree Retail Customer View' screen to view the details of the customer's loan.

The screen is as shown below:

360 Degree Retail Customer View

Customer Number * _____ Short Name _____ Reporting Currency _____
Branch _____ Full Name _____ Reports

Summary Profile Deposits **Loans** Events Schemes Alerts Limits Payments IS-Deposits IS-Financing External Products

Commitment Details

<input type="checkbox"/>	Branch Code	Account Number	Description	Currency	Amount Financed	Amount Disbursed	Outstanding Amount	Book Date	Value Date	Maturity Date	Product
--------------------------	-------------	----------------	-------------	----------	-----------------	------------------	--------------------	-----------	------------	---------------	---------

Component Details

Loan Details

<input type="checkbox"/>	Branch Code	Account Number	Description	Currency	Amount Financed	Amount Disbursed	Outstanding Amount	Book Date	Value Date	Maturity Date	Product
--------------------------	-------------	----------------	-------------	----------	-----------------	------------------	--------------------	-----------	------------	---------------	---------

Cancel

The loans details are classified as follows:

- Commitment Details
- Loan Details
- Mortgage
- Leasing
- Syndicate Loans details


Under each of the loan details, the system displays the following:

- Branch Code
- Account Number
- Description
- Currency
- Amount Financed
- Amount Disbursed
- Outstanding Amount
- Book Date
- Value date
- Maturity Date

- Product Code
- Account Status
- User Defined Status

7.3.4.1 Viewing Component Details

You can view details about the components linked to an account in the 'Component Details' screen. You can invoke this screen by clicking the 'Component Details' button in the '360 Degree Retail Customer View' screen.



You can view the following component details:

- Component Name
- Component Currency
- Expected – the system displays the amount which is not due for the present date. This amount is arrived during querying.
- Overdue – – the system displays the amount which is not overdue for the present date. This amount is arrived during querying
- Outstanding – the system displays the amount which is due for the present date. This amount is arrived during querying.
- Advance – the system displays the amount pre paid for a component as on the present date. This amount is arrived during querying.
- Latest Interest rate – the system display the current interest rate only for main interest component.

- Number of Days Overdue.


Component Schedule details

Here you can view the following:

- Component Name
- Schedule Due Date
- Due amount
- Settled Amount
- EMI Amount
- Accrued Amount

7.3.4.2 Viewing Collection Details

You can view the collection details of a loan in the 'Collection Details of Default Loan' screen. You can invoke this screen by clicking the 'Collection Details' button in the '360 Degree Retail Customer View' screen.



The screenshot shows a window titled "Collection Details of Default Loan" with a blue header bar. The window contains two columns of input fields. The left column includes "Collection Reference Number", "Asset Reference Number", "Collection Agent", and "Collection Creation Date". The right column includes "Queue Id", "State", and "Product". Each field is represented by a text label followed by a horizontal line. An "Exit" button is located in the bottom right corner of the window.

Here, you can view the following details:


- Collection reference Number
- Asset Reference Number
- Collection Agent
- Collection Creation Date
- Queue ID
- State

- Product

7.3.5 Viewing Events Details

Click 'Events' tab in the '360 Degree Retail Customer View' screen to view the details of the upcoming events.

The screen is as shown below:



Here you can view the following details:

- Event
- Branch
- Reference Number
- Currency
- Amount
- Event date

7.3.6 Viewing Schemes Details

Click 'Schemes' tab in the '360 Degree Retail Customer View' screen to view the details of the relationship schemes.

The screen is as shown below:

The screenshot shows a software window titled "360 Degree Retail Customer View". At the top, it displays customer information: Customer Number * 000002105, Branch 000, Short Name ROHIT VERMA, Full Name ROHIT VERMA, and Reporting Currency GBP. Below this is a navigation bar with tabs for Summary, Profile, Deposits, Loans, Events, Schemes (selected), Alerts, Limits, Payments, Is-Deposits, Is-Financing, and External Products. The main area is titled "Non Linked RP scheme details" and contains a table with the following data:

<input type="checkbox"/>	Pricing Scheme Id	Pricing Scheme ID Description	Scheme Start Date	Scheme End Date	Eligibility Plan Code
<input checked="" type="checkbox"/>	PS1EMP01	Pricing Scheme for Free T	2011-09-02	2015-11-30	EMP01ELIG
<input type="checkbox"/>	PS2EMP01	Bnefit of ADHOC statemer	2011-09-02	2015-09-02	EMP01ELIG
<input type="checkbox"/>	PS3T	Pricing scheme for Specif	2011-09-02	2014-09-03	EMP01ELIG
<input type="checkbox"/>	RPC1_S	CL SCHEME	2010-11-27	2015-11-27	EG_NEW_2
<input type="checkbox"/>	RPC2_S	CL SCHEME	2010-11-27	2015-11-27	EG_NEW_2
<input type="checkbox"/>	RPC1_S	CL SCHEME	2010-11-27	2015-11-27	EG_NEW_2

Below the table is a button labeled "RP Scheme Linkage Details". At the bottom right of the window is a "Cancel" button.


Here, you can view the relationship schemes which are not linked to the customer. The following fields are displayed:

- Pricing scheme Id
- Pricing scheme Id description
- Scheme Start Date
- Scheme End Date
- Eligibility Plan code

7.3.6.1 Viewing Relationship pricing schemes linked to the customer

Click 'RP Scheme Linkage Details' to view relation ship pricing schemes linked to the customer.


The screen is as shown below:



Refer 'Relationship Pricing' module for more information about this screen.

7.3.7 Viewing Alerts

Click 'Alerts' tab in the '360 Degree Retail Customer View' screen to view the alerts for overdue loans, matured deposits and so on.



Following alerts can be viewed in this screen:

Overdue Loans

Here you can view the Loan accounts which have overdue component as on today. The following details can be viewed here:

- Branch Code
- Account number
- Due Date
- Currency
- Overdue Amount

Deposits Matured but not renewed or liquidated

Here you can view the deposit accounts or contracts which are matured but not yet liquidated or renewed. The following details can be viewed here:

- Branch code
- Deposit reference number
- Currency
- Amount
- Maturity Date

Locker Charges Overdue Details

Here you can view the Locker charge components of the customer which fall on overdue. The following details can be viewed here:

- Contract Reference Number
- Component
- Description
- Currency
- Amount
- Due date

Cheques Returned

Here you can view the cheques returned to the customer. The following details can be viewed here:

- Branch
- Account
- Cheque Book Number
- Cheque Number
- Presentation Date

Amount Block Details

Here you can view all active amount blocks related to a customer. The following details can be viewed here

- Branch
- Account
- Amount Block Number
- Amount
- Effective Date
- Expiry date
- Block Type

Stop Payments Details

Here you can view active stop payments created for the customer. The following details can be viewed here

- Branch
- Account
- Stoppayment Number
- Stoppayment Type
- Start Cheque Number
- End Cheque Number
- Effective date
- Expiry Date
- Amount
- Confirmed flag

7.3.8 Viewing Limits Details

Click 'Limits' tab in the '360 Degree Retail Customer View' screen to view the limits and collaterals of the customer.

The screen is as shown below:

360 Degree Retail Customer View

Customer Number * _____ Short Name _____ Reporting Currency _____
Branch _____ Full Name _____ Reports

Summary Profile Deposits Loans Events Schemes Alerts **Limits** Payments Is-Deposits Is-Financing External Products

Limit Details

Customer/Group Id _____ Utilisation Amount _____
Limit Currency _____ Available _____
Limit Amount _____ Revision Date _____

Line Details 1 of 1

<input type="checkbox"/>	Line Identification	Main Line	Limit Currency	Limit Amount	Available Amount	Revolving Line	Line Start Date	Line Expiry Date
--------------------------	---------------------	-----------	----------------	--------------	------------------	----------------	-----------------	------------------

Collateral Details 1 of 1

<input type="checkbox"/>	Collateral Code	Collateral Description	Collateral Currency	Collateral Value	Lendable Margin	Limit Contribution	Start Date	End Date
--------------------------	-----------------	------------------------	---------------------	------------------	-----------------	--------------------	------------	----------

Cancel

Limits Details

Here the system displays the following limits details:

- Customer/Group ID
- Limit Currency
- Limit Amount
- Utilization Amount
- Available
- Revision Date

Line Details

Here the system displays the following line details:

- Line Identification
- Main Line
- Limit Currency
- Limit Amount
- Available Amount
- Revolving Line
- Line Start Date

- Line Expiry Date


Collateral Details

Here the system displays the following collateral details:

- Collateral Code
- Collateral Description
- Collateral Currency
- Collateral Value
- Lendable Margin
- Limit Contribution
- Start Date
- End date

7.3.9 Viewing Payment Details

Click 'Payments' tab in the '360 Degree Retail Customer View' screen to view the FT and PC contracts of the customer which is not liquidated.



Funds Transfer Details

Here you can view the following Funds Transfer details:

- Contract Reference Number

- Product Description
- Credit Account Branch
- Credit Account
- Credit Currency
- Credit Amount
- Credit value date
- Debit Account Branch
- Debit Account
- Debit currency
- Debit amount
- Debit Value Date
- By order of
- Ultimate Beneficiary
- Product Code

Payments and Collection Details

Here you can view the following payments and collection details:

- Contract Reference Number
- Product Description
- Account No
- Customer Account Branch
- Counterparty Bank code
- Cpty account number
- Cpty Name
- Transaction currency
- Transaction Amount
- Booking Date
- Customer Entry Value Date
- Counterparty Entry Value date
- Network
- Product Code

7.3.10 Viewing Islamic Deposits Details

Click 'Is-Deposits' tab in the '360 Degree Retail Customer View' screen to view details about active CASA account and Term deposit.

360 Degree Retail Customer View

Customer Number * Short Name Reporting Currency
Branch Full Name Reports

Summary Profile Deposits Loans Events Schemes Alerts Limits Payments **Is-Deposits** Is-Financing External Products

Islamic Accounts

<input type="checkbox"/>	Branch Code	Account	Description	Currency	Current Balance	Available	Uncollected	Blocked	Limit Currency	Temp. OD Limit	Temp. OD Limit Start	Temp. OD
--------------------------	-------------	---------	-------------	----------	-----------------	-----------	-------------	---------	----------------	----------------	----------------------	----------

Summary of Islamic Accounts To enter Period

Total Credit Balance 0.00 From Date

Total Debit Balance 0.00 To Date

Account Signatory Standing Instruction Periodic Instructions Transactions Cheques Statement Generation Cards Others Joint Holders

Islamic Term Deposits

<input type="checkbox"/>	Branch Code	Account No	Account Description	Currency	Term Deposit Amount	Maturity Date	Profit rate	Profit Start Date	Tenor in Days	Latest Profit Effective D
--------------------------	-------------	------------	---------------------	----------	---------------------	---------------	-------------	-------------------	---------------	---------------------------


Cancel

Islamic Accounts

Here, you can view the following details for an active CASA account:

- Branch code
- Account
- Description
- Account Class
- Related Customer
- Account Status
- Status Since
- Currency
- Current Balance
- Available Balance
- Uncollected amount
- Blocked amount
- Debit Interest Accrued Amount
- Credit Interest Accrued Amount
- Limit Currency

- TOD Limit
- TOD Limit Start Date
- TOD Limit End Date
- Account Type(Single or Joint)

 Closed accounts will not be displayed.

Islamic Term Deposit

The following details about Islamic term deposit will be displayed:

- Account Number
- Branch Code
- Description
- Account Class
- Related Customer
- Status
- Since
- Currency
- Term Deposit Amount
- Maturity date
- Interest Start Date
- Account type(Joint or single)
- Tenor – Tenor will be displayed in terms of days.
- Profit rate – the system displays the Profit Rate of a deposit. System will pick up the latest profit rate of a deposit during query.
- Latest Profit Effective Date – the system will pick up latest profit effective date of a deposit during query.
- Profit Accrued – Interest accrued till date for an account. This will be derived by the system during query.
- Recurring Deposit- this check box will be checked if it is Recurring Deposit.

7.3.11 Viewing Islamic Financing Details

Click 'Is-Financing' tab in the '360 Degree Retail Customer View' screen to view details about Islamic Finance.

360 Degree Retail Customer View

Customer Number * Short Name Reporting Currency
Branch Full Name Reports

Summary Profile Deposits Loans Events Schemes Alerts Limits Payments Is-Deposits **Is-Financing** External Products

1 of 1

<input type="checkbox"/>	Branch Code	Account Number	Product Description	Currency	Amount Financed	Amount Disbursed	Outstanding Amount	Book Date	Value Date	Maturity Date
--------------------------	-------------	----------------	---------------------	----------	-----------------	------------------	--------------------	-----------	------------	---------------


Islamic Financing Total 0.00

Here you can view the following details:

- Branch code
- Account Number
- Customer ID
- Product Code
- Product Type
- Description
- Currency
- Amount financed
- Amount Disbursed
- Amount outstanding
- Book Date
- Value date
- Maturity Date
- Account Status
- User defined Status

7.3.11.1 Viewing Component Details

You can view details about the components linked to an account in the 'Component Details' screen. You can invoke this screen by clicking the 'Component Details' button in the '360 Degree Retail Customer View' screen.



Refer the section titled 'Viewing Components Details' under 'Viewing Loan Details' for further details.

7.3.12 Viewing External Details

Click 'External products' tab in the '360 Degree Retail Customer View' screen to view external details about products like credit cards, insurance, and mutual fund.

The screen is as shown below:

The screenshot displays the '360 Degree Retail Customer View' window. At the top, there are input fields for 'Customer Number *', 'Branch', 'Short Name', 'Full Name', and 'Reporting Currency', along with a 'Reports' button. Below this is a navigation bar with tabs for 'Summary', 'Profile', 'Deposits', 'Loans', 'Events', 'Schemes', 'Alerts', 'Limits', 'Payments', 'Is-Deposits', 'Is-Financing', and 'External Products'. The 'External Products' tab is active, showing two sections: 'Credit Card' and 'Insurance'. Each section has a table with columns and a 'Go to Page' button. The 'Credit Card' table has columns: Card Number, Card Type, Credit Limit, Billed Amount, Min Amount Due, Available Limit, Due date, Delinquent, and Processing Date. The 'Insurance' table has columns: Product Name, Policy number, Number of units, NAV, Insured amount, Premium amount, Purchase Date, TERM, Maturity Date, Next Premium date, and Processing Date. A 'Cancel' button is located at the bottom right of the window.

Credit Card

Here you can view the following credit card details:

- Card Number
- Card Type
- Credit Limit
- Billed Amount
- Min Amount Due
- Available Limit
- Due Date
- Delinquent(Y/N)
- Processing Date

Insurance

Here you can view the following insurance details:

- Product name
- Policy Number
- Number of units

- NAV
- Insured Amount
- Premium Amount
- Purchase date
- Term
- Maturity date
- Next Premium Date
- Processing Date

Mutual Fund

Here you can view the following mutual fund details:

- Name of Fund
- Number of units
- Purchase NAV
- Billed Amount
- Min amount Due
- Processing Date

7.4 Viewing 360Degree Corporate Customer Details

You can invoke '360 Degree Corporate Customer View' screen if the customer is Corporate by double clicking on the customer record in the '360Degree Customer View Entry Point' screen or by typing 'STDCUSVW' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Customer Number * _____ Short Name _____ Reporting Currency _____
Branch _____ Full Name _____ Reports

Summary Profile Deposits Loans Trade Treasury Events Schemes Alerts Limits Payments Is-Deposits Is-Financing Is-Trade Is-Treasury External Products

Prefix _____

Address For Correspondence
Name _____
Address _____
Telephone _____
Fax _____
E-mail _____

Status
 Frozen
 Deceased
 Whereabouts Unknown
KYC Status: Verified
CIF Status _____
Since _____
Credit Rating _____
Customer Category _____
Charge Group _____
Tax Group _____

Balance Sheet Asset And Liabilities
Asset Ccy Value Liability Ccy Value

Off Balance Sheet Asset And Liabilities
Asset Ccy Value Liability Ccy Value

Exit

The system displays the following details:

- Customer Number
- Short Name
- Reporting Currency
- Branch
- Full Name

Click the 'Reports' button to view the '360 Degree Customer Report' screen.

360 Degree Customer Report

Customer Details

Customer Number * _____
Customer Name _____

Ok Exit

The details that can be viewed in the '360 Degree Corporate Customer View' screen is classified into 16 broad heads.

Summary	You can view the address, status. Balance sheet asset and liabilities and off balance sheet asset and liabilities under the summary tab.
Profile	You can view the details of the customer's profile.
Deposits	You can view the details of the customer deposits.
Loans	You can view the details of the customer's loan.
Trade	You can view trade details
Treasury	You can view the details of Treasury.
Events	You can view the details of the upcoming events.
Schemes	You can to view the details of the relationship schemes.
Alerts	You can view the alerts for overdue loans, matured deposits but not renewed or liquidated, Locker Charges Overdue Details, cheques returned, amount block details and stop payment details.
Limits	You can view the limits and collaterals of the customer.
Payments	You can view the FT and PC contracts of the customer which is not liquidated.
Is-Deposits	You can view details about active CASA Account and Islamic Term Deposit.
Is-Financing	You can view details about Islamic Finance.
Is-Trade	You can view Islamic trade details.
Is-Treasury	You can the details of Islamic Treasury.
External Products	You can view external details about products like credit cards, insurance, and mutual fund.

7.4.1 Viewing Summary Details

You can view the address, status, Balance sheet asset and liabilities and off balance sheet asset and liabilities under the summary tab.

Refer the section titled 'Viewing Summary Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.2 Viewing Profile Details

Click 'Profile' tab in the '360 Degree Corporate Customer View' screen to view the details of the customer's profile.

The screenshot displays the '360 Degree Corporate Customer View' application window. The title bar reads '360 Degree Corporate Customer View'. The interface includes a top navigation bar with tabs for Summary, Profile (selected), Deposits, Loans, Trade, Treasury, Events, Schemes, Alerts, Limits, Payments, Is-Deposits, Is-Financing, Is-Trade, Is-Treasury, and External Products. Below the tabs, there are several sections of input fields:

- Customer Information:** Customer Number * (with a red asterisk), Branch, Short Name, Full Name, and Reporting Currency.
- Registration Address:** Name, Country, National Id, Line 1, Line 2, Line 3, First, Middle, and Last.
- Geographic:** Country, Language, Exposure, Location, and SWIFT Code.
- Head Office:** Account Number, Debtor Category, Risk Profile, and FT Accounting as of (with a dropdown menu).
- Description of Business:** A large text area for business description.
- Incorporation:** Date, Capital, Net Worth, Country, and Currency Of Amounts.

At the bottom of the window, there is a row of buttons: Image, Linked Customers, Locker Details, Directors, Linked Entity, KYC Details, Fields, and MIS. An Exit button is located in the bottom right corner.

Registration Address

Here you can view the following details:

- Name
- Country
- National Id
- Address Line 1 to 3
- First Name
- Middle Name
- Last name

Geographic

Here you can view the following details:

- Country
- Language
- Exposure
- Location
- SWIFT Code

Incorporation

Here you can view the following details:

- Date
- Capital
- Net Worth
- Country
- Currency of Amount


Head Office

Here you can view the following details:

- Account Number
- Debtor Category
- Risk profile
- FT Accounting as of
- Description of Business

7.4.2.1 Viewing Signature Image and Photograph of the customer

Click on the 'Image' button to invoke 'Customer Signatory Details' screen. Here you can view the signature image and photograph of the customer.




Refer the section titled 'Viewing Signature Image and Photograph of the customer' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.2.2 Viewing Related Customer Details

Click on the 'Linked Customers' button to invoke 'Linked Entities' screen. Here you can view other related customer details.


The screen is as shown below:



Refer the section titled 'Viewing Related Customer Details' under 'Viewing 360 Degree Retail Customer Details' for further details

7.4.2.3 Viewing Locker Details


Click on the 'Locker Details' button to invoke 'Safe Deposit Locker Details' screen. Here you can view the locker details of the customer.



Refer the section titled 'Viewing Locker Details' under 'Viewing 360 Degree Retail Customer Details' for further details

7.4.2.4 Viewing Director Details

Click on the 'Directors' button to invoke 'Directors' screen. Here you can view the director details of the customer.



Here you can view the following details:


- Director Name
- Customer No
- Tax ID
- Mobile Number

- E-mail
- Mailing Address 1 to 4
- Permanent Address 1 to 3

7.4.2.5 Viewing Customer Entities

Click the 'Linked Entity' button to invoke 'Linked Entity' screen. Here you can view details about customers who are linked to this customer, accounts for which this customer is linked, and loans which are guaranteed by this customer.

The screen is as shown below:



Refer the section titled 'Viewing Customer Entities' under 'Viewing 360 Degree Retail Customer Details' for further details

7.4.2.6 Viewing KYC Details

Click the 'KYC Details' button to invoke 'KYC Maintenance' screen. Here you can view KYC details of the customer.

The screen is as shown below:

KYC Reference *

Full Name of Customer *

KYC Customer Type *

Risk Level *

Retail Customer Corporate Customer Financial Customer Fields

Maker Date Time: Mod No
Checker Date Time: Record Status
Authorization Status

Exit

Refer Core Entities for more information about the 'KYC Maintenance' screen.

7.4.2.7 Viewing User Defined Fields

Click on the 'Fields' button to invoke 'User Defined Fields' screen. Here you can view the UDF details of the customer.

User Defined Fields

1 of 1 Go to Page

UDF Details

<input type="checkbox"/>	Field Name *	Value
<input type="checkbox"/>		
<input type="checkbox"/>		


Cancel

Refer the section titled 'Viewing User Defined Fields' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.2.8 Viewing MIS Details

Click on the 'MIS' button to invoke 'MIS' screen. Here you can view the MIS details of the customer.

The screen is as shown below:



Refer the section titled 'Viewing MIS Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3 Viewing Deposits Details

Click 'Deposits' tab in the '360 Degree Corporate Customer View' screen to view the details of the customer deposits.

The screen is as shown below:

Refer the section titled 'Viewing Deposit Details' under 'Viewing 360 Degree Retail Customer Details' for further details


7.4.3.1 Viewing Account Signatory

Click 'Account Signatory' button to view the 'Signatory Details' screen. In this screen, you can view the signatory details of the selected account.

Refer the section 'Specifying Account Signatory Details' under the 'Current and Savings Account' module for more information.

7.4.3.2 Viewing Standing Instruction


Click 'Standing Instruction' button to view the 'Standing Instruction Details' screen. In this screen you can view the standing instructions.



Refer the section titled 'Viewing Standing Instruction' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.3 Viewing Periodic Instructions

Click 'Periodic Instructions' button to view the 'Periodic Instructions' screen. In this screen, you can view the period instructions.



Refer the section titled 'Viewing Periodic Instructions' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.4 Viewing Transactions

Click 'Transactions' button to view the 'Customer Account Transaction Query' screen. In this screen, you can query the transactions of an account during a given period.

Customer Account Transaction Query

Query Criteria

Contract Reference

Transaction Code

Event Code

Value Date

Related Reference

From Date 2012-03-22

To Date 2012-03-14

Debit/Credit

Currency

Module Code

Transaction Date

Related Account

Account Details

Branch Code 000

Starting Balance

Currency GBP

Debit Credit Balance

Account Number 00000210501

Transaction Details


<input type="checkbox"/>	Contract Reference	Entry Serial No	Module Code	Transaction Code	Event Code	Transaction Date	Value Date	Debit/Credit
--------------------------	--------------------	-----------------	-------------	------------------	------------	------------------	------------	--------------

Refer the section 'Querying Accounting Entries' under 'Core Services' module for more information.

7.4.3.5 Viewing Cheques

Click 'Cheques' button to view the 'Cheque Details' screen. In this screen, you can view the details of the cheques which are issued for a given period.


The screen is as shown below:



Refer the section titled 'Viewing Cheques' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.6 Viewing Statement Generation

Click 'Statement Generation' button to view the 'Account Statement Report' screen. In this screen, you can generate adhoc statement for an account.



Refer the section 'Account Statement Report' under 'Current and Savings Account' module for more information.

7.4.3.7 Viewing Card Details

Click 'Cards' button to view the 'Debit Card Details' screen. In this screen, you can view details about active debit cards which are issued during given period for an account.

<input type="checkbox"/>	Branch Code	Card Number	Primary Card	Name On Card	Card Expiry Date	Dispatch Status	Pin Mailed Status	Card Status
--------------------------	-------------	-------------	--------------	--------------	------------------	-----------------	-------------------	-------------

Refer the section titled 'Viewing Card Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.8 Viewing Other Details

Click 'Others' button to view the 'Other Details Of Account' screen. In this screen, you can view additional details about interest, limit, statement, account and nominees.

Interest Details		Limit Details	
Credit Interest Accrued Amount	_____	Temp. OD Start	_____
Debit Interest Accrued Amount	_____	Temp. OD End	_____
		Limit Currency	GBP
		Temp. OD Limit	_____
		Line Identification	_____

Statement Details		Account Status	
Last Statement Date	_____	<input type="checkbox"/> No Debit	
Last Statement Balance	_____	<input type="checkbox"/> No Credit	
Last Statement Number	_____	<input type="checkbox"/> Stop Payment	
		<input type="checkbox"/> Dormant	
		<input type="checkbox"/> Frozen	

Nominees	
Nominee1	_____
Nominee2	_____

Refer the section titled 'Viewing Other Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.9 Viewing Customer Signatory

Click 'Account Signatory' button to view the 'Customer Signatory Details' screen. In this screen, you can view the signature image and photograph of the customer.

The screenshot shows a window titled "Signatory Details". It contains several input fields for account information:

- Branch Code *
- Account *
- Account Description
- Customer No
- Minimum No of Signatories
- Customer Name
- Account Message

Below the input fields is a table with the following columns:

Signature Id	Signatory Name	Signatory Type	Approval Limit	Signatory Message

At the bottom right of the window is an "Exit" button.

7.4.3.10 Viewing Recurring Deposits Details

Click 'Recurring Deposits Details' button to view the 'RD Details' screen. In this screen, you can view recurring deposits if the deposit is recurring.

The screenshot shows a window titled "RD Details". It contains two columns of input fields:

Frequency Days	_____	Payment Branch	_____
Frequency Months	_____	Payment Account	_____
Frequency Years	_____	Payment Currency	_____
Installment Amount	_____	Payment Date	_____


At the bottom right of the window is an "Exit" button.

Refer the section titled 'Viewing Recurring Deposits Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.11 Viewing Redemption Details

Click 'Redemption Details' button to view the 'Redemption Details' screen. In this screen, you can view redemption deposits of a deposit account.


The screen is as shown below:



Refer the section titled 'Viewing Redemption Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.3.12 Viewing Schedule Details

Click 'Schedules' button to view the 'Schedule Details' screen. In this screen, you can view the schedule details of all components attached to the corporate deposit contract.




Refer the section titled 'Viewing Schedule Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.4 Viewing Loan Details

Click 'Loans' tab in the '360 Degree Corporate Customer View' screen to view the details of the customer's loan.

The screen is as shown below:




Refer the section titled 'Viewing Loans Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.4.1 **Viewing Component Details**

You can view details about the components linked to an account in the 'Component Details' screen. You can invoke this screen by clicking the 'Component Details' button in the '360 Degree Corporate Customer View' screen.


The screen is as shown below:



Refer the section titled 'Viewing Component Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.4.2 Viewing Collection Details

You can view the collection details of a loan in the 'Collection Details of Default Loan' screen. You can invoke this screen by clicking the 'Collection Details' button in the '360 Degree Corporate Customer View' screen.



Refer the section titled 'Viewing Collection Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.5 Viewing Trade Details

Click 'Trade' tab in the '360 Degree Corporate Customer View' screen to view the details of trade.

The screenshot shows the '360 Degree Corporate Customer View' application window. The 'Trade' tab is selected in the navigation menu. The main area displays two sections: 'Bills Detail' and 'LC Details'. The 'Bills Detail' section has a table with columns: Branch Code, Contract Reference, Product Description, Counter Party, Bill Currency, Bill Amount, Maturity Date, Outstanding Amount, and Our Letter of Credit Reference. The 'LC Details' section has a table with columns: Branch Code, Contract Reference, Product Description, Currency, Contract Amount with Tolerance, Current Available Amount, Liability, Beneficiary, and Contract Status. Both sections are currently empty. The window title is '360 Degree Corporate Customer View' and includes fields for Customer Number, Branch, Short Name, Full Name, and Reporting Currency.

Bills Detail

Here you can view the following bills details:

- Branch Code
- Contract Reference Number
- Counter party
- Product
- Product Type
- Product Description
- Beneficiary
- Bill Currency
- Bill Amount
- Maturity date
- Outstanding Amount
- Discrepancy Flag – System will derive this flag based on the availability of discrepancies of bill.

- Exception Flag – System will derive this flag based on exception data.
- LC Reference Number
- Contract Status

LC Details

Here you can view the following details relating to Letters of credits:

- Branch Code
- Contract reference number
- Product Code
- Product Type
- Product description
- Currency
- Contract Amount
- Customer
- Beneficiary
- Current Available Amount
- Liability
- Contract Status
- Expiry date

Guarantee Details

Here you can view the following details relating to guarantees:

- Branch Code
- Contract reference number
- Product Code
- Product Type
- Product description
- Currency
- Contract Amount
- Customer
- Beneficiary
- Current Available Amount

- Liability
- Contract Status
- Expiry date
- Guarantee Type

7.4.5.1 Viewing Additional Bills Details

You can view additional details about the bill from the 'Bills Other Details' screen. You can invoke this screen by clicking on 'Other Bill Details' button.

The screen is as shown below:

The screenshot shows a window titled "Bills Other Details". It contains the following fields:

- Base Date _____
- Value Date _____
- Liquidation Date _____
- Tenor _____
- Operation _____
- Reimbursement days _____
- Loan Linkage Flag
- Interest Rate _____
- Interest Accrued _____

Below these fields are two tables:

Discrepancy Details

Description	Resolved
	<input type="checkbox"/>

Loan Details

Account	Currency	Amount	Down Payment

An "Exit" button is located at the bottom right of the window.

Here you can view the following details:

- Base date
- Value Date
- Liquidation Date
- Tenor
- Operation

- Reimbursement Days
- Loan Linkage Flag – System will derive this flag based on the loan details of a bill.
- Interest Rate – Current Interest Rate of a bill. System picks up during query.
- Interest Accrued – Interest accrued till date. System will derive this value during query.

Discrepancy Details

Here you can view the following details:

- Discrepancy Description
- Resolved

Loan Details

The loans which are related to Bills will be displayed here. The following fields will be displayed:

- Account
- Currency
- Amount
- Down Payment

7.4.5.2 Viewing Additional LC Details

You can view additional details about LC in the 'LC Additional Details' screen. You can invoke this screen by clicking on 'LC Other Details' button.

The screen is as shown below:

The screenshot shows a window titled "LC Additional Details" with the following fields and sections:

- Operation Code _____
- Issue Date _____
- Closing Date _____
- Effective Date _____

Commission Details

Component Description	Component	Currency	Amount	Good Until Date

Bill Linkage Details

BC Reference	Currency	Amount

Loan Details

Account	Currency	Amount	Down Payment

Exit

Here you can view the following details:

- Operation Code
- Issue date
- Closing Date
- Effective date

Commission Details

Here you can view the following details:

- Component

- Currency
- Amount
- Good Until Date
- Event Sequence Number

Bill Linkage details

Here you can view the following details:

- BC Reference Number
- Currency
- Amount

Loan Details

Here you can view the Loans details which are related to LC. The following fields are displayed:

- Account
- Currency
- Amount
- Down Payment

7.4.5.3 Viewing Additional Guarantee Details

You can view additional details about guarantee in the 'Guarantee Additional Details' screen. You can invoke this screen by clicking on 'Guarantee Other Details' button

Guarantee Additional Details

Operation Code _____ Issue Date _____
Guarantee Type _____ Closing Date _____
Effective Date _____

Commision Details

10f1

Component Description	Component	Currency	Amount	Good Until Date
-----------------------	-----------	----------	--------	-----------------

Loan Details

10f1

Account	Currency	Amount	Down Payment
---------	----------	--------	--------------

Exit

Here you can view the following details:

- Operation Code
- Issue date
- Closing Date
- Effective date
- Guarantee Type

Commission Details

Here you can view the following details:

- Component
- Component Description
- Currency

- Amount
- Good Until Date
- Event Sequence Number


Loan Details

Here you can view the Loans details which are related to guarantee. The following fields are displayed:

- Account
- Currency
- Amount
- Down Payment

7.4.6 Viewing Treasury Details

Click 'Treasury' tab in the '360 Degree Corporate Customer View' screen to view the details of Treasury.



Foreign Exchange Details

Here you can view the following details:

- Contract Reference
- Buy/sell

- Book Date
- Bought Currency
- Bought Amount
- Bought Value date
- Sold Currency
- Sold Amount
- Sold Value date
- Deal Rate

Money Markets Details

Here you can view the following details:

- Branch Code
- Contract Reference Number
- Related Customer
- Currency
- Amount
- Tenor
- Book Date
- Value Date
- Maturity Date
- Type(Borrowing or Placement)

Security Portfolio

Here you can view the following details:

- Portfolio reference
- Portfolio Description
- Currency
- Auto Liquidate for corporate Actions
- Corpus Account
- Short Position Allowed
- Accrue Withholding Tax for Coupons
- Bankers Acceptance

Derivatives

Here you can view the following details:

- Contract Reference number
- Buy or Sell
- In Leg Currency
- Out Leg Currency
- In Principal Amount
- Out Principal Amount
- Book Date
- Value Date
- Maturity Date
- Type

OTC Options

Here you can view the following details:

- Contract Reference Number
- Related Customer
- Currency
- Contract Amount
- Strike Price
- Premium Currency
- Option Premium
- Premium Pay date
- Buy or sell
- Tenor
- Book Date
- Value date
- Maturity date
- Type


ETD Portfolio Details

Here you can view the following details:

- Portfolio Reference Number
- Portfolio Description
- Fund Id

7.4.7 **Viewing Events Details**

Click 'Events' tab in the '360 Degree Corporate Customer View' screen to view the details of the upcoming events.




Refer the section titled 'Viewing Events Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.8 **Viewing Schemes Details**

Click 'Schemes' tab in the '360 Degree Corporate Customer View' screen to view the details of the relationship schemes.


The screen is as shown below:



Refer the section titled 'Viewing Schemes Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.8.1 Viewing Relationship pricing schemes linked to the customer

Click 'RP Scheme Linkage Details' to view relation ship pricing schemes linked to the customer.



Refer 'Relationship Pricing' module for more information about this screen.

7.4.9 Viewing Alerts

Click 'Alerts' tab in the '360 Degree Corporate Customer View' screen to view the alerts for overdue loans, matured deposits and so on.

The screenshot shows the '360 Degree Corporate Customer View' application. At the top, there are input fields for 'Customer Number *', 'Branch', 'Short Name', 'Full Name', and 'Reporting Currency'. Below these is a 'Reports' button and a navigation bar with tabs for 'Summary', 'Profile', 'Deposits', 'Loans', 'Trade', 'Treasury', 'Events', 'Schemes', 'Alerts', 'Limits', 'Payments', 'Is-Deposits', 'Is-Financing', 'Is-Trade', 'Is-Treasury', and 'External Products'. The 'Alerts' tab is selected. The main content area is divided into two sections. The first section is titled 'Overdue Loans' and contains a table with columns: Branch Code, Account Number, Due Date, Currency, and Overdue Amount. The second section is titled 'Deposits Matured but not renewed or liquidated' and contains a table with columns: Branch Code, Deposit Reference Number, Currency, Term Deposit Amount, and Maturity Date. Both tables are currently empty. At the bottom right of the application window, there is an 'Exit' button.

Refer the section titled 'Viewing Alerts Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.10 Viewing Limits Details

Click 'Limits' tab in the '360 Degree Corporate Customer View' screen to view the limits and collaterals of the customer.

The screen is as shown below:


The screenshot displays the '360 Degree Corporate Customer View' application window. At the top, there are input fields for 'Customer Number *', 'Branch', 'Short Name', 'Full Name', and 'Reporting Currency'. A 'Reports' button is located to the right of the 'Reporting Currency' field. Below these fields is a horizontal menu with tabs for 'Summary', 'Profile', 'Deposits', 'Loans', 'Trade', 'Treasury', 'Events', 'Schemes', 'Alerts', 'Limits' (which is currently selected), 'Payments', 'Is-Deposits', 'Is-Financing', 'Is-Trade', 'Is-Treasury', and 'External Products'.

The 'Limits' section contains several input fields: 'Customer/Group Id', 'Limit Currency', 'Limit Amount', 'Utilisation Amount', 'Available', and 'Revision Date'. Below this is a 'Line Details' table with a header row containing columns: 'Line Identification', 'Main Line', 'Limit Currency', 'Limit Amount', 'Available Amount', 'Revolving Line', 'Line Start Date', and 'Line Expiry Date'. The table body is currently empty. Below the table is a 'Collateral Details' table with a header row containing columns: 'Collateral Code', 'Collateral Description', 'Collateral Currency', 'Collateral Value', 'Lendable Margin', 'Limit Contribution', 'Start Date', and 'End Date'. This table body is also empty. The application has a standard Windows-style interface with a title bar, scroll bars, and an 'Exit' button at the bottom right.

Refer the section titled 'Viewing Limits Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.11 Viewing Payment Details

Click 'Payments' tab in the '360 Degree Corporate Customer View' screen to view the FT and PC contracts of the customer which is not liquidated.



Refer the section titled 'Viewing Payments Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.12 Viewing Islamic Deposits

Click 'Is-Deposits' tab in the '360 Degree Corporate Customer View' screen to view details about active CASA account and term deposit.

The screenshot displays the '360 Degree Corporate Customer View' application window. At the top, there are input fields for 'Customer Number *', 'Branch', 'Short Name', 'Full Name', and 'Reporting Currency'. A 'Reports' button is located to the right of the 'Full Name' field. Below these fields is a horizontal menu with tabs: 'Summary', 'Profile', 'Deposits', 'Loans', 'Trade', 'Treasury', 'Events', 'Schemes', 'Alerts', 'Limits', 'Payments', 'Is-Deposits' (which is highlighted), 'Is-Financing', 'Is-Trade', 'Is-Treasury', and 'External Products'. The main content area is divided into two sections. The first section is titled 'Islamic Accounts' and contains a table with the following columns: Branch Code, Account, Description, Currency, Current Balance, Available, Uncollected, Blocked, Limit Currency, Temp.OD.Limit, Temp.OD.Limit Start, and Temp.OD. Below the table is a 'Summary of Islamic Accounts' section with fields for 'Total Credit Balance', 'Total Debit Balance', 'From Date', and 'To Date'. The second section is titled 'Islamic Term Deposits' and contains a table with columns: Branch Code, Account No, Account Description, Currency, Term Deposit Amount, Maturity Date, Profit rate, Profit Start Date, Tenor in Days, and Latest Profit Effective D. At the bottom right of the window is an 'Exit' button.

7.4.12.1 Viewing Additional Islamic Bill Details

You can view additional details about the bill from the 'Bills Other Details' screen. You can invoke this screen by clicking on 'Other Bill Details' button.

The screen is as shown below:

The screenshot shows a software window titled "Bills Other Details". The window contains the following elements:

- Input fields for: Base Date, Value Date, Liquidation Date, Tenor, Operation, Reimbursement days, Interest Rate, Interest Accrued, and a checkbox for Loan Linkage Flag.
- A section titled "Discrepancy Details" containing a table with columns "Description" and "Resolved".
- A section titled "Loan Details" containing a table with columns "Account", "Currency", "Amount", and "Down Payment".
- An "Exit" button at the bottom right.

Refer the section titled 'Viewing Additional Bill Details' under 'Viewing 360 Degree Corporate Customer Details' for further details.

7.4.12.2 Viewing Additional Islamic LC Details

You can view additional details about LC in the 'LC Additional Details' screen. You can invoke this screen by clicking on 'LC Other Details' button.

The screenshot shows a software window titled "LC Additional Details". At the top, there are four input fields: "Operation Code", "Issue Date", "Closing Date", and "Effective Date". Below these are three data tables, each with a search icon and a refresh icon. The first table is "Commision Details" with columns: Component Description, Component, Currency, Amount, and Good Until Date. The second table is "Bill Linkage Details" with columns: BC Reference, Currency, and Amount. The third table is "Loan Details" with columns: Account, Currency, Amount, and Down Payment. An "Exit" button is located at the bottom right of the window.

Refer the section titled 'Viewing Additional LC Details' under 'Viewing 360 Degree Corporate Customer Details' for further details.

7.4.12.3 Viewing Additional Islamic Bank Guarantee Details

You can view additional details about guarantee in the 'Guarantee Additional Details' screen. You can invoke this screen by clicking on 'Guarantee Other Details' button.

The screen is as shown below:

The screenshot displays a software window titled "Guarantee Additional Details". At the top, there are five input fields: "Operation Code", "Guarantee Type", "Issue Date", "Closing Date", and "Effective Date". Below these fields are two data tables. The first table, "Commision Details", has a header row with columns: "Component Description", "Component", "Currency", "Amount", and "Good Until Date". The second table, "Loan Details", has a header row with columns: "Account", "Currency", "Amount", and "Down Payment". Both tables are currently empty. At the bottom right of the window is an "Exit" button.

Refer the section titled 'Viewing Additional Islamic Bank Guarantee' under 'Viewing 360 Degree Corporate Customer Details' for further details.

7.4.13 Viewing Is-Financing Details

Click 'Is-Financing' tab in the '360 Degree Corporate Customer View' screen to view details of Islamic finance.

360 Degree Corporate Customer View

Customer Number * 001001745 Short Name ACE BANK LIMITED Reporting Currency GBP
Branch 001 Full Name ACE BANK LIMITED Reports

Summary Profile Deposits Loans Trade Treasury Events Schemes Alerts Limits Payments Is-Deposits **Is-Financing** Is-Trade Is-Treasury External Products

1 of 1 Go to Page

<input type="checkbox"/>	Branch Code	Account Number	Product Description	Currency	Amount Financed	Amount Disbursed	Outstanding Amount	Book Date	Value Date	Maturity Date
--------------------------	-------------	----------------	---------------------	----------	-----------------	------------------	--------------------	-----------	------------	---------------

Islamic Financing Total 0.00 Component Details


Cancel

Refer the section titled 'Viewing Islamic Financing Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

7.4.13.1 Viewing Component Details

You can view details about the components linked to an account in the 'Component Details' screen. You can invoke this screen by clicking the 'Component Details' button in the '360 Degree Corporate Customer View' screen.

The screen is as shown below:



Refer the section titled 'Viewing Components Details' under 'Viewing Loan Details' for further details.

7.4.14 Viewing Islamic Trade Details

Click 'Is-Trade' tab in the '360 Degree Corporate Customer View' screen to view details of Islamic trade.

The screen is as shown below:

The screenshot shows the '360 Degree Corporate Customer View' window. At the top, it displays customer information: Customer Number * 001001745, Branch 001, Short Name ACE BANK LIMITED, Full Name ACE BANK LIMITED, and Reporting Currency GBP. Below this is a navigation bar with tabs: Summary, Profile, Deposits, Loans, Trade, Treasury, Events, Schemes, Alerts, Limits, Payments, Is-Deposits, Is-Financing, Is-Trade (selected), Is-Treasury, and External Products. A 'Reports' button is also visible. The main content area is divided into two sections. The first section is titled 'Islamic Bills' and contains a table with the following columns: Branch Code, Contract Reference, Product Description, Bill Currency, Bill Amount, Maturity Date, Outstanding Amount, Our Letter of Credit Reference, and Contract Status. The table is currently empty. Below the table is a 'Bills Other Details' button. The second section is titled 'Islamic Letter of Credits' and contains a table with the following columns: Branch Code, Contract Reference, Product Description, Currency, Contract Amount, Current Available Amount, Liability, Beneficiary, Contract Status, and Expiry Date. This table is also empty. The window has a 'Cancel' button at the bottom right.

Islamic Bills Detail

Here you can view the following bills details:

- Branch Code
- Contract Reference Number
- Counter party
- Product
- Product Type
- Product Description
- Beneficiary
- Bill Currency
- Bill Amount
- Maturity date
- Outstanding Amount

- Discrepancy Flag – System will derive this flag based on the availability of discrepancies of bill.
- Exception Flag – System will derive this flag based on exception data.
- Our LC Reference Number
- Contract Status

Islamic Letter of Credit Details

Here you can view the following details relating to Letters of credits:

- Branch Code
- Contract reference number
- Product Code
- Product Type
- Product description
- Currency
- Contract Amount
- Customer
- Beneficiary
- Current Available Amount
- Liability
- Contract Status
- Expiry date

Islamic Bank Guarantee Details

Here you can view the following details relating to guarantees:

- Branch Code
- Contract reference number
- Product Code
- Product Type
- Product description
- Currency
- Contract Amount
- Customer
- Beneficiary

- Current Available Amount
- Liability
- Contract Status
- Expiry date
- Guarantee Type

7.4.15 Viewing Islamic Treasury Details

Click 'Is-Treasury' tab in the '360 Degree Corporate Customer View' screen to view the details of Islamic Treasury.

The screen is as shown below:

The screenshot shows the '360 Degree Corporate Customer View' window. At the top, it displays customer information: Customer Number * 001001745, Branch 001, Short Name ACE BANK LIMITED, Full Name ACE BANK LIMITED, and Reporting Currency GBP. A 'Reports' button is visible. Below this is a navigation menu with tabs for Summary, Profile, Deposits, Loans, Trade, Treasury, Events, Schemes, Alerts, Limits, Payments, Is-Deposits, Is-Financing, Is-Trade, Is-Treasury (selected), and External Products. The main content area is divided into two sections: 'Islamic Money Market Details' and 'Islamic Derivatives'. Each section has a table with a search icon and a 'Go to Page' button. The 'Islamic Money Market Details' table has columns: Branch Code, Contract Reference, Currency, Amount, Book Date, Maturity Date, Value Date, Tenor, and Type. The 'Islamic Derivatives' table has columns: Contract Reference, Buy, In Leg Currency, In Principal Amount, Out Leg Currency, Out Principal Amount, Book Date, Value date, Maturity, and Type. A 'Cancel' button is located at the bottom right of the window.

Islamic Money Market Details

Here you can view the following details:

- Branch Code
- Contract Reference
- Currency
- Amount
- Book Date
- Maturity Date

- Value Date
- Tenor
- Type


Islamic Derivatives

Here you can view the following details:

- Contract Reference
- Buy
- In Leg Currency
- In Principal Amount
- Out Leg Currency
- Out Principal Amount
- Book Date
- Value date
- Maturity
- Type

7.4.16 Viewing External Details

Click 'External products' tab in the '360 Degree Corporate Customer View' screen to view external details about products like credit cards, insurance, and mutual fund.



Refer the section titled 'Viewing External Details' under 'Viewing 360 Degree Retail Customer Details' for further details.

8. Glossary

8.1 Important Terms

Account Class

A group of customer accounts with similar characteristics and attributes

Account Statement Cycle

The periodicity for the generation of account statements

Account Statement Type

An indicator of the kind of account statement required to be generated periodically; this could be either a summary statement or a detailed one.

Alternate Account Number

An unique identifier for a customer account, other than the main Account Number. This provision is made to enable tracking of accounts existing in the bank before the installation of FLEXCUBE. For such accounts, you can capture the old account numbers as the Alternate Account Numbers.

Available

The amount available in a customer's account, which can be drawn

Blocked

The amount that is blocked for other transactions, which the customer has entered into and not executed. At any point of time, the account balance cannot be less than the blocked amount.

Corporate Parameters

Information captured under customized parameters for corporate customers

Customer Category

A group of customers with logically similar features or attributes

Dormancy Days

The period following which customer accounts under a class are made inactive

Exposure Country

This is the country of exposure of a customer. This information is maintained for Central Liability tracking

Identifier Name

The name of the identification document furnished by the customer to the bank as proof of identity

Identifier Value

The serial number, document number or any identification number by which the identifier name document can be uniquely identified.

Joint Holder Code

The account identifier codes given to joint holders of any customer account

Legal Guardian

If the account holder is a minor, this is the legal guardian of the customer

Liability Number

A code used to keep track of the credit limit facility granted to a customer

Limit Check

A validation maintained for all accounts in an account class to see if there are adequate funds in the account.

Loan Repayment

The amount paid towards loan repayment

MTD (Month to Date)

Indicates the turnover on an account for the current month and up to the current date. It is specified for both Credit and Debit turnovers

Narratives

Specifications that help achieve a desired format for account statements

Natural GL

The code of the GL to which the turnovers of all accounts in the account class will be reported.

Regulation D

This is a regulation of the U.S. Securities and Exchange Commission. Regulation D, also known as "Reg D," exempts certain offerings of equity from many of the regulatory requirements that impose costs upon standard public offerings. A Reg D offering is intended to make access to the capital markets possible for small companies that could not otherwise bear those costs.

Reporting Lines

The general ledger codes to which balances (debit or credit) of all accounts in an account class will be reported.

Sub-limit

The maximum credit amount that can be used by a customer account without requiring an override. The sub-limit is specified for accounts for which the credit amount is limited to a part of the available line amount.

Temporary OD End

The date on which the temporary overdraft limit ceases to be effective

Temporary OD Limit

The maximum overdraft allowed on an account, for a specified period of time

Temporary OD Start

The date on and following which the temporary overdraft limit comes into effect

Tenure

The duration for which a customer has been in professional employment. This information is captured as part of the professional details for a customer.

Uncollected Funds Limit

On any given business day, the credit transaction amounts that have not been collected.

Unposted Credits

In a multi-branch or online activity (such as tele-banking or Internet banking) transactions that are posted into an account when the system is either not available or during End of Day run, are stored, to be posted into the system when the system is available. Credit transactions of this nature are classified as unposted credits.

Unposted Debits

In a multi-branch or online activity (such as tele-banking or Internet banking) transactions that are posted into an account when the system is either not available or during End of Day run, are stored, to be posted into the system when the system is available. Debit transactions of this nature are classified as unposted debits.

W-8BEN Form

The W-8BEN form (entitled Certificate of Foreign Status of Beneficial Owner for United States Tax Withholding) is used in the United States taxation system by foreign persons (including corporations) to certify their non-American status. The form, issued by the Internal Revenue Service, establishes that one is a foreign, non-resident alien or foreign national performing work outside the United States, in order to claim tax treaty benefits such as a lower amount of tax withholding from dividends paid by U.S. corporations.

9. Reports

9.1 Introduction

Every action that results in a debit or credit to the customer's monetary account is recorded. The advices are generated and sent to the customer depending on the advice generation frequency that you have specified.

You can generate the following reports:

- IRA Statement
- Minimum Withdrawal Advice
- Charge Advice
- IRS Form 5498
- IRS Form 1099-R
- Customer Account Opening Confirmation
- Netting
- Combined Statement Reports
- Missing Signature Report

9.2 IRA Statement Reports

An IRA statement is a statement of accounts for an IRA plan. You will be able to generate statements for a list of all the transactions carried out in an IRA plan for the statement generation frequency specified for the plan. You also have the option of generation on an ad-hoc basis.

9.2.1 Selection Options

You can choose to generate the account statements for transactions involving all plans within your branch or for transaction within a single plan or for a range of plans.

You will also have to indicate the date range for the generation of the report.

9.2.2 Contents of the Report

The options that you specified while generating the report are printed at the beginning of the report. The contents of the IRA Statement have been discussed under the following heads:

Header

The Header carries the title of the Report, information on the branch code, the date and time at which the report was generated and the page number of the report.

Body of the Report

Customer Information	The CIF Number, full Name and mailing address of the customer as recorded in the CIF Maintenance screen
Plan Number	The reference number of the plan involving the transaction
Plan Type	The plan type involving the plan
Period of the statement	The period for which you are generating the statement
Statement Number	The statement number of the statement
Plan Balances	<p>The balances in the plan at the beginning and end of statement period (Current and Previous Years)</p> <p>Note:</p> <p>The current balance is reflected for the current year and the year ending balance (after considering contributions and distributions done during the current year for the previous year) for the previous year.</p> <p>Total Contributions</p> <p>Excess Contributions</p> <p>Total Distributions</p> <p>Total Employer Contributions (where applicable)</p> <p>Excess Employer Contributions</p>
Transaction Information	<p>Transaction type (Contributions, Distributions, Monetary Account Interest).</p> <p>Transaction Reference Number</p> <p>Amount and Currency</p> <p>Transaction Year</p> <p>Monetary Account Breakup</p>

Customer Information	The CIF Number, full Name and mailing address of the customer as recorded in the CIF Maintenance screen
	Account (Branch, Account, Currency) Amount and Currency Withholding Tax information (where applicable) Tax Withheld (Amount and Currency) Transaction Remark (if any) Plan Balance after the transaction (current and previous year balances) Transactions are sequenced in the manner in which they were processed in the system.

9.3 **Minimum Withdrawal Advice Reports**

This advice is sent to all customers approaching the minimum distribution age. The advice contains information about all the plans held by the customer under the plan type.

Since it is not generated automatically, you have to invoke the advice generation screen and identify the Plan Type and the Reference Number of the plan involving the plan type for which the minimum distribution age advice is to be generated.

9.3.1 **Contents of the Report**

Apart from the header the following details are printed for the report:

Body of the Report

Customer Information	The CIF Number, full Name and mailing address of the customer as recorded in the CIF Maintenance screen.
Plan Type	The plan type involving the plan.
Plans Held	This information includes: Plan Number. Plan Balances (current year only) Plan Balance Total Contributions Excess Contributions Total Distributions

	Total Employer Contributions (where applicable) Excess Employer Contributions Plan Remarks (if any)
--	---

9.4 **Charge Advice Reports**

This advice is sent to all customers on whom you are levying a charge as a result of the IRA Charge set-up. The system generates this advice automatically as part of the EOD processes on the day the charge liquidation takes place.

9.4.1 **Contents of the Report**

Apart from the header the following details are printed for the report:

Body of the Report

Customer Information	The CIF Number, full Name and mailing address of the customer as recorded in the CIF Maintenance screen.
Charge Code	The Code associated with the Charge for which you are charging the customer.
Charge Level	Indicates the level at which charging is being done: CIF Level or Plan level
Plan Type	The plan type involving the plan.
Charge Amount and Currency	The charge is always charged in the local currency of your branch.
Liquidation Date	The date on which the charge amount was liquidated.
Debit Account Information	The Branch, Account Number and Currency of the account involved in the transaction.

9.5 **IRS Form 5498**

Oracle FLEXCUBE allows you to generate Form 5498 for reporting contributions to IRA plans for any year to the Internal Revenue Service (IRS). You can generate this report for:

- Filing with IRS authorities;
- Providing a copy to your customer;
- Keeping an internal copy for you.

You can generate Form 5498 either as part of initial filing with the IRS or after you have filed tax returns for that particular year.

9.5.1 Generating Form 5498 as Part of Initial Filing

During normal generation of Form 5498 as part of your initial filing with the IRS, the system will include all transactions entered in the previous year for the previous year. For example, during normal generation of Form 5498 on, say, January 20, 2003, all transactions entered during 2002 and pertaining to the financial year 2002 will be reported.

9.5.2 Generating Form 5498 after Tax Filing

During corrected generation post the date of tax filing, the system will include, apart from all the transactions included in normal generation, such transactions which are entered in the current year for the previous year. The report shows the total contributions for the year.


9.5.3 Details printed on Form 5498

Oracle FLEXCUBE generates Form 5498 customer-wise and plan-wise – that is, for each customer for each type of plan held by the customer. The type of plan can be Traditional IRA, Roth IRA, SEP, SIMPLE, etc.

The form contains the following details:

- Your bank's name and address;
- The customer's name, social security number and address;
- The plan/product type for which the form is being generated;
- The year for which the report is being generated;
- Total rollover contributions – this is the total of all contributions into plans of the selected type with 'Rollover' as the contribution code;
- Roth IRA conversion amount – while usually applicable for Roth IRAs, this, in the general case, is the total contribution into plans of the selected type with 'Conversion' as the contribution code;
- Total re-characterized contributions – this is the total of all contributions into plans of the selected type with 'Re-characterization' as the contribution code;
- New contributions – this is the total of all contributions into plans of the selected type with 'New' as the contribution code;

- Other contributions – this is the total of all contributions into plans of the selected type with contribution codes different from any of those mentioned above;
- Fair Market Value – this is the total year-end balance of all the plans of the selected type.

 IRA codes that you have marked for not reporting to the IRS will be left out of all of the above summations.

9.6 **IRS Form 1099-R**

Oracle FLEXCUBE allows you to generate Form 1099-R for reporting distributions from a selected type of IRA plan for any year to the Internal Revenue Service (IRS). You can generate this report for:

- Filing with IRS authorities;
- Providing a copy to your customer;
- Keeping an internal copy for you.

You can generate Form 1099-R either as part of initial filing with the IRS or after you have filed tax returns for that particular year.

9.6.1 **Generating Form 1099-R as Part of Initial Filing**


During normal generation of Form 1099-R as part of your initial filing with the IRS, the system will include all transactions entered in the previous year for the previous year. For example, during normal generation of Form 1099-R on, say, January 20, 2003, all transactions entered during 2002 and pertaining to the financial year 2002 will be reported.

9.6.2 **Generating Form 1099-R after Tax Filing**

During corrected generation post the date of tax filing, the system will include, apart from all the transactions included in normal generation, such transactions, which are entered in the current year for the previous year. The report shows the total contributions for the year.

9.6.3 **Details printed on Form 1099-R**

Oracle FLEXCUBE generates Form 1099-R for each customer for a distribution code. You have the option of combining distributions with the same code from any number of different plan/product types.

 IRA codes that you have marked for not reporting to the IRS will not be available for generation of 1099-R forms.

Form 1099-R contains the following details:

- Your bank's name, address and identification number;
- The customer's name, social security number and address;

- Plan/product types that are being reported;
- The distribution code and description;
- Gross distribution – this is the total distribution amount for the distribution code that you have chosen across all the selected plan types;
- Taxable amount – this is the same as the total (gross) distribution amount.
- Total distribution – this is a confirmation that the gross distribution amount mentioned in the form is the total distribution for the selected distribution code.
- Federal Income Tax withheld – this is the total amount withheld as tax for all the distributions (from all the selected plan/product types) for the selected distribution code.

9.6.4 Filing IRS Forms Electronically

IRS regulations stipulate that any entity filing 250 or more forms of each type must do so in electronic or magnetic form. You can access IRS's Filing Information Returns Electronically (FIRE) system over a dial-up network and through a browser or through communication software like ProComm. You can log on to the system using the logon name, password and PIN provided to you by the IRS.

9.7 Customer Account Opening Confirmation Report


You can generate a report for the customer, confirming that his / her account with the bank has been successfully opened. This report contains the following details:

- Customer number
- Client account number
- Matter
- Account details

You can generate the Customer Account Opening Confirmation report for one customer or all the customers at once, as of a specific date. To generate the report, invoke 'Customer Account Opening Confirmation' screen.

You can invoke this screen by typing the code 'CSR PACCO' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screen is as shown below:



Customer Report

You can generate customer account opening confirmation report for one or all the customers. Indicate your choice here. If you select 'Single Customer', you have to specify the customer number in the space provided.

Customer Number

If you wish to generate a report specific to one customer, specify the customer number. The option list displays all valid customer numbers maintained in the system. Select the appropriate one.

Date

Specify the date as of which you want to generate the report.

Once you have set the preferences, click 'OK' button. The system displays the print option screen, where you can set your preferences as to viewing and printing the report.

9.8 Netting Report

You can generate a Customer, Currency and Date wise report to retrieve details of contracts/amounts that were netted.

You can specify the following preferences for the report:

- *Report Type* - You can indicate whether the report should contain details of contracts/amounts that have the same Value Date or whether the details should be generated as per the Netting Reference Number. If you indicate that the report should be generated for a Netting Reference Number you will have to identify the number in the respective field.

- *Date* – indicate whether you would like to generate the report for a specific date range or for all dates. Depending on your specification the netting details report will be generated for all contracts that were netted within your branch for the given date range (start and end date inclusive) or it will be generated for all contracts regardless of the date on which they were netted.
- *Customer* – indicate whether the report should contain details of all customers whose contracts were netted or for a single customer. For a single customer you will have to identify the CIF ID of the customer from the option list.
- *Currency* - You can indicate whether the report should be generated for all currencies or for a specific currency. Identify the currency for which the report should be generated in case of a single currency.

 **Note**

- If you fail to specify a date, the generated report will return data for the Current System Date.
- If you indicate that the report should be generated for a specific Currency and fail to specify the Currency, the report will contain details of all currencies. Similarly, if you indicate that the report should be generated for a specific Customer and fail to identify the customer the report will be generated for all customers.

9.8.1 Contents of the Report

The report options that you selected while generating the report are printed at the beginning of the report.

The contents of the report are discussed below:

Body of the Report


Counterparty	This is the name of the counterparty whose netted contract details are being displayed.
Contract Reference Number	This is the reference number of the contract which was netted.
Component	This is the name of the component (Amount Tag) involved in the transaction.
Amount	This is the amount for which the particular entry was passed.
Account Due	This is the account to which the netted amount is either debited/credited.

9.9 Combined Statement Reports

This report is an ad-hoc combined statement of accounts for a customer, generated for a particular period. This report is grouped account class wise. This report helps in providing a single statement to the customers who own multiple accounts.

You can invoke 'Statement of Combined Generation' screen by typing 'CIRCSTAD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:



The screenshot shows a dialog box titled "Combined statement generation -- Webpage Dialog". It contains four input fields arranged vertically: "Branch Code", "Customer No", "From Date", and "To Date". Each field has a small icon to its right, likely representing a dropdown or search function. At the bottom right of the dialog, there are two buttons: "Ok" and "Exit".

Specify the following details here:

Branch Code

Select the branch code from the adjoining option-list. The list displays all valid branch codes.

Customer No

Select the customer number from the adjoining option-list. This list displays all valid customers maintained in the system.

From Date

Select the From date for statement generation. By default the current application date is displayed here.

To Date

Select the To date for statement generation. By default the current application date is displayed here.

Click 'OK' button to generate the report. Click 'Exit' to return to the Reports Browser.

9.9.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Customer Name, Customer Address, Account Class, Account Number, Opening balance, Currency and Branch.

Body of the Report


Date of transaction	This indicates the transaction date
Transaction Description	This is the description of the transaction
Reference	This is the Reference of the transaction
Credit	This indicates the Credit amount
Debit	This indicates the Debit amount
Balance	This indicates the Balance
Credit Total	This indicates the credit total
Transaction Code	This indicates the code of the transaction
Debit total	This indicates the debit total

9.10 Missing Signature Report

This is an exception report listing all the customers, of a specified branch, whose signatures have not yet been captured in the system.

While opening accounts, customer's signature/photographs/thumb impression are captured and linked to the account. This facilitates the signature verification in the system at the time of making payment. Branches can generate this ad-hoc report, and capture the missing signature in the system.

You can invoke 'Signatures not Captured' screen by typing 'CIRSNREP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



Specify the following details here:

Branch Code

Select the branch code from the adjoining option-list. The list displays all valid branch codes.

Click 'OK' button to generate the report. Click 'Exit' to return to the Reports Browser.

9.10.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The Header carries the Branch, Date, User ID and the Module for which the report is generated.

Body of the report

The generated report will have the following information:

Customer ID	This indicates the unique id of the customer
Customer Name	This indicates the name of the customer
Open Date	This indicates the date on which the account is opened
Authorizer ID	This indicates the id of the authorizer

10. Screen Glossary

10.1 Function ID List

The following table lists the function id and the function description of the screens covered as part of this User Manual.

Function ID	Function Description
ACDADCRP	Ad-hoc Report Generation
ACDCBIR	Customer Summary Query
ACDCODQS	Overdrawn Accounts Query
ACDFUNCO	Uncollected Funds Query
ACDSCPQR	Customer Information Query
ACDSQASL	Customer Asset & Liability Query
ACDSQPRO	Customer Projections Query
BADIDBAT	Intra Day Batch Start
CIRCSTAD	Combined Statement Generation
CIRSNREP	Signatures not captured
CODSTTYP	Static Type Maintenance
CSDALGGN	Algorithm Generation Input
CSDALGMT	Algorithm Maintenance
CSDINSTR	Instructions Maintenance
CSDPROVN'	Provisioning Coverage Details
CSDRELMN	Relationship Maintenance
CSDSTNAR	Statement Narratives Maintenance
CSRACCO	Customer Account Opening Confirmation
CSSINSTR	Instructions Summary
CSSJOBBER	Jobs Browser
LDDECMNT	Corporate Deposits Exposure Category Maintenance

Function ID	Function Description
LDDTMNT	Corporate Deposits Category Type Maintenance
LDDPRULE	Corporate Deposits Provisioning Rule Maintenance
LDDPRVMN	Corporate Deposits Provisioning Percentage Maintenance
LDSETMNT	Corporate Deposits Category Type Summary
MSDCUSAD	Customer Address Maintenance
SMDEMPMT	Employer Maintenance
STDACCLS	Account Class Maintenance
STDACLOC	Account Address Location Maintenance
STDACTFR	Account Class Transfer
STDAMDMT	Gateway Amendment Maintenance
STDBALAC	Balance Account Code Maintenance
STDCCMNT	Customer Classification Maintenance
STDCIFNM	Customer Name Maintenance
STDCULMT	Customer Tax Allowance Maintenance
STDCULOC	Location Maintenance
STDCUREL	Customer Linkage Maintenance
STDCUSPR	Customer Prefix Maintenance
STDCUSVW	360 Degree Corporate Customer View
STDCUSST'	Customer Sector Maintenance
STDDOCQU	Customer Document Expiry Query Screen
STDFIEMT	Financial Institution Exemption Maintenance Screen
STDFLTDS	Float Days Maintenance
STDGRMNT	Group Code Maintenance
STDGROUP	Customer Group Maintenance
STDKYCMN	KYC Maintenance

Function ID	Function Description
STDKYCTP	KYC Type Maintenance
STDLEDMT	Lead Maintenance
STDPRCTY	Province City Maintenance
STDPLMNT	Postal Code and Locality Maintenance Screen
STDREFQU	Referral Queue
STDRELMT	Relation Maintenance
STDRETVW	360 Degree Retail Customer View
STDRKMNT	Risk Category Maintenance
STSDSNMN	Specially Designated Nationals Maintenance
STDSRQST	Service Request Input
STDSTMNT	Manual Status Change Input
STD TAXWV	Tax Waiver Maintenance
STD TOLMT	Turnover Limit Maintenance
STSACTFR	Account Class Transfer
STSCUSVW	360Degree Customer View Entry Point
STSFIENT	Financial Institution Exemption Summary Screen
STSPRCTY	Province City Summary
STSREFQU	Referral Queue Summary
STSSRQST	Service Request Fetch



Core Entities
October [2013]
Version 11.3.81.02.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax:+91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2013], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.