# Development of Gateway Screen and LOV Enhancer Oracle Banking Corporate Lending Release 14.7.2.0.0 Part No. F92377-01 [November] [2023]



## Contents

1		Preface		. 3
	1.1	Audi	ence	.3
	1.2	2 Relat	ted Documents	.3
2		Overvie	w of Gateway Screen Development for Oracle FLEXCUBE	.4
	2.1	Radx	ml	.4
	2.2	2 Desig	gn Steps	.4
		2.2.1	Design Process:	5
		2.2.2	Action	
		2.2.3	Function Id	5
		2.2.4	Save Xml Path	6
		2.2.5	Gateway Specific changes	6
3		Overvie	w of LOV Enhancer	.7
	3.1	Exte	rnal Lov	.7
	3.2	2 Com	bined Lov	.7

## 1 Preface

This document describes the process of FLEXCUBE Screen Development using Enterprise Limits and Collateral Management Development Workbench.

## 1.1 Audience

This document is intended for FLEXCUBE Application developers/users that use ODT to develop various FLEXCUBE components.

To Use this manual, you need conceptual and working knowledge of the below:

Proficiency	Resources
FLEXCUBE Functional Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Technical Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Object Naming conventions	Development Overview Guide
Working knowledge of Web based	Self Acquired
applications	
Working knowledge of Oracle Database	Oracle Documentations
Working knowledge of PLSQL & SQL	Self Acquired
Language	
Working knowledge of XML files	Self Acquired
Essential knowledge on FLEXCUBE	<u> Development Workbench – Administration</u>
ODT	<u>Development Workbench – Getting Started</u>

#### 1.2 Related Documents

Oracle FLEXCUBE Enterprise Limits and Collateral Management ODT Screen Development

## 2 Overview of Gateway Screen Development for Oracle FLEXCUBE

Oracle FLEXCUBE ODT provides the developer with a user friendly console for designing and developing screens for Oracle FLEXCUBE.

ODT assist developers in designing screens with the capability of generating front end scripting files, PL/SQL Packages, Static data scripts, XSDs, Excel templates and html files. This generated code performs validations and does some processing which is common across screens in FLEXCUBE; only the Business logic specific to the screen has to be added by the Developer in back end and front end units.

#### **Example**

Release Name: FC 12.1

Release Type: KERNEL, CLUSTER, CUSTOM

ODT will generate all files and developers are supposed to add the business logic in designated units depending on the Release Type.

### 2.1 Radxml

ODT saves all the activities carried out by the developer in an xml file hereby referred to as **radxml**. Persistence of the screens is achieved through radxml. All the units required for the working of a screen can be generated from its radxml.

If some changes are required on the screen in a future release, the same radxml can be loaded and changes can be done on this radxml. ODT can segregate the changes done on different releases and saves the radxml accordingly.

Radxml will adhere to following naming convention

Function Id name + \_RAD.xml

Example: STDCULND\_RAD

### 2.2 Design Steps

Sequence of Steps to be followed while developing a screen in ODT is:

1. Identifying the data sources and their relations

- 2. Logically grouping the data sources into Data Blocks
- 3. Designing Screen Layout
- 4. Logically grouping the Block Fields into Field sets
- 5. Attaching Call forms and launch forms if any
- 6. Defining Actions

Refer respective sections for detailed explanation of each step

#### Saving Radxml

While Development, save radxml at constant intervals. Click on save icon in the top right for having the work. Radxml would be saved in the user directory maintained

#### 2.2.1 Design Process:

Click on Function Generation node in the browser tree found in the Landing page of ODT. Function Generation Page window gets launched.

While creating a new function in Function Generation page in ODT, below information needs to be provided in the Header section

The Header portion of the Function Generation Page screens consists of the following fields:

#### 2.2.2 Action

New and Load options are provided for this field.

For a new screen development, select the action as New; if an existing screen radxml has to be loaded for customization select Load option

If the action is load then corresponding radxml has to be loaded using browser option in Save Xml Path; all the header information will get populated.

#### 2.2.3 Function Id

If the Action is selected as New, the function Id name needs to be specified. Function Id is the unique name with which a screen is identified.

Function Id name should follow the FLEXCUBE standard naming convention.

- Function Id name to have maximum length of 8 characters
- For detail screens the third character should be 'D'
- For report screens the third character should be 'R'
- For call form function ids the third character should be 'C'
- First 2 characters should specify the module name for which the particular function id is used (recommended).

#### 2.2.4 Save Xml Path

The label description of the field will change depending on the action .If the action is load, ODT attaches a Browse button to it so that user can browse the radxml and load it.

#### 2.2.5 Gateway Specific changes

Design of screen will be as any other normal maintenance screen, only change with in preference user has to select the screen as gateway. Below mentioned screen will help in better understanding.

Function Generation				_ ×
				🖬 🗙 🗉 C 🎸 🧃 🔿
Action New V Function Id STDC001 Save XML Path	Function Type Parent Parent Function Parent Xml	V N	Function Category Maintenance V Header Template None V Footer Template None V	
Search	Preferences			<b>š</b>
Preferences DataSource LiatSource DataBlocks Screens FieldStds Actions CaliForms LaunchForms Summary	Head Office Function Ogging Required Ogging Required Oncode Auto Authorization Tank Modifications Field Log Required Muttle Branch Access Excel Sport Required Auto Automation Field GateWay Screen Menu Datam Parameter Value Mappings	Module Notule Description Module Group Branch Program Id Process Code SVN Repository URL		
				Control String 🕂 🗕
	Function Id	Module *	Module Description	·
	STDC001	٩		

Fig 2.2.5.1: Preferences Screen

Once gateway screen checkbox is selected then in generation screen only front-end units, xsd's and INC's will only be generated. Below screen shows generation screen.

Front-End Files	System Packages	Hook Packages		Meta Data	Others	^
☑ RadXML ☑ Screen Xmi ☑ System JS	Man Package Spec Main Package Body Notification Trogers Upload Package Body Upload Package Body Java Classes	Kermel Package Spec Kermel Package Body Cluster Package Spec Cluster Package Body Cluster Package Body Clustor Package Body	G Menu Details G Datasource Details G LOV Details G Biock Details G Streen Details G Amendable Details G Amendable Details G Ammary Details G Summary Details G Summary Details G Symbol Details	Zi Labol Details     Silocie NC Columns     Silocie NC Columns     Silocie NC Columns     Silocie NC Columns     Silocie	⊘ Xsos Green Himi Upload Table Trigger Upload Tables Definition Archive Table Definition	v

Fig 2.2.5.2: Generation Screen

User has to generate the above selected units and has to deploy in FCUBS. Code has to be written in gateway flow to make this screen work. For generation and design please use <u>Oracle FLEXCUBE</u> <u>Enterprise Limits and Collateral Management ODT Screen Development</u>.

## 3 Overview of LOV Enhancer

Lov Enhancer is used to map Lov's of Screens to External or Combined Lovs.

### 3.1 External Lov

Lov of a screen is mapped to External Lov. Where all the data populated and data fetched in the lov will be from external system. User has to simply select the lov as External in the screen. Below screen will help in better understanding.

				Populate Combined	Details
	Lov Id		Internal/External/Combin	ed	
LOV_ACCOUNT		External			
LOV_ACCOUNT_OFF		External	<ul> <li></li> </ul>		
LOV_ADDRESS_CODE		Internal	<ul> <li></li> </ul>		
LOV_AML_CUST_GRP		Internal	<ul> <li></li> </ul>		
LOV_AMTCCY1		Internal	<ul> <li></li> </ul>		
LOV_BUSINESS_ACT		Internal	<ul> <li></li> </ul>		
LOV_CHG_GRP		Internal	<ul> <li></li> </ul>		
LOV_CHKLST		Internal	·		
LOV_CLG_GRP		Internal	<ul> <li></li> </ul>		
LOV_CLSCCY		Internal	<ul> <li></li> </ul>		
LOV_ALG_ID		Internal	<ul> <li></li> </ul>		
LOV_BIC		Internal	<ul> <li></li> </ul>		
LOV_COLLATERAL_TYPE		Internal	<ul> <li></li> </ul>		
LOV_COUNTRY		Internal	<ul> <li></li> </ul>		
LOV_CREDIT_RATING		Internal	·		
LOV_CURRENT_EMPLOYER		Internal	<ul> <li></li> </ul>		
LOV_CUSTPREFIX1		Internal	<ul> <li></li> </ul>		
LOV_CUSTPREFIX2		Internal	·		
LOV_CUST_CAT		Internal	•		~
, ,			-	Genera	te Close

Fig 3.1.1: Lov Enhancer Screen External

## 3.2 Combined Lov

User can use combination of lovs from external and internal. Where we will provide details of external Lov's bind variable and reduction field details. Please check the below screen.

v Details			Populate	Combined De	tails
LOV_Name LOV_AML_CUST_GRP Function ID Name STDCIF	xlemal	Internal/Extern	al/Combined		1
External LOV Name LOV_EXT_AML_CUST	oternal V				
LOV Function Name fn_function()	nternal V				
tion Fields Bind Variables	× bendmo				
	nternal V				
Bind Variables Mapping	niernal 🗸				
	iternal 🗸				
Bind Variables Available Bind Variables Mapped	iternal 🗸				
BIND1	nlernal 🗸				
	nternal 🗸				
	nlemai 🗸				
44	nternal 🗸				
	nternal 🗸				
	tlernal 🗸				
	iternal 🗸				
	tlemal 🗸				
	nternal 🗸				
Ok	Cancel Iternal 🗸				
	nlernal 🗸				1
				Generate	Clos

Fig 3.2.1: Lov Enhancer Screen Combined

Here user will provide details for external LOV.

When generated after the modifications, INC will be generated with below kind of data

```
UPDATE CSTB_LOV_INFO SET LOV_TYPE = 'E' WHERE FUNCTION_ID='STDCIF' AND LOV_ID IN ('LOV_ACCOUNT','LOV_ACCOUNT_OFF')
```

/

UPDATE CSTB\_LOV\_INFO SET LOV\_TYPE = 'C' WHERE FUNCTION\_ID='STDCIF' AND LOV\_ID IN ('LOV\_AML\_CUST\_GRP')

/

DELETE CSTB\_CMB\_LOV\_INFO A WHERE A.FUNCTION\_ID IN ('STDCIF');

```
INSERT INTO CSTB_CMB_LOV_INFO (FUNCTION_ID, LOV_ID, EXTERNAL_LOV_ID, LOV_FUNCTION, REDUCTION_LIST, BIND_LIST) VALUES ('STDCIF','LOV_AML_CUST_GRP','LOV_EXT_AML_CUST','fn_function()','','1~')
```

/

### COMMIT;

nformatio	on Description	Information Code					P	pulate	Combined D	etails	
i File S	aved				Internal/External/Combined				,		
			External	~							
			External	~							
			Internal	~							
			Internat	$\sim$							
			Combine	sd 🗸							
		Ok	Internal	~							
	LOAT RIC	<u></u>	Internal	~							
			Internal	~							
	LOV_CHG_GRP		Internal	~							
				,							
			Internal	~							
	LOV_CLO_GRP		Internal	~							
	LOV_CLECCY		Internal	~							
	LOV_COLLATERAL_TYPE		Internal	~							
	LOV_COUNTRY		Internat	$\sim$							
	LOV_CREDIT_RATING		Internal	~							
	LOV_CURRENT_EMPLOYER		Internal	$\sim$							
	LOV_CUSTPREFIX1		Internal	~							
	LOV_CUSTPREFIX2		Internal	~							
	LOV_CUST_CAT		Internal	~						~	
			-						Generate	Close	
									concrete	1	

Fig 3.2.3: Generation Screen



Development of Gateway Screen and LOV Enhancer [November] [2023] Version 14.7.2.0.0

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India

Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001 www.oracle.com/financialservices/

Copyright © 2007, 2023, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.