

Oracle® Database

Database Client Installation Guide



18c for HP-UX Itanium
E83741-01
November 2018

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Database Database Client Installation Guide, 18c for HP-UX Itanium

E83741-01

Copyright © 2015, 2018, Oracle and/or its affiliates. All rights reserved.

Primary Author: Prakash Jashnani

Contributing Authors: Douglas Williams

Contributors: Mark Bauer, David Austin, Neha Avasthy, Prasad Bagal, Subhranshu Banerjee, Mark Bauer, Tammy Bednar, Eric Belden, Gavin Bowe, Robert Chang, Darcy Christensen, Kiran Chamala, Jonathan Creighton, Benoit Dageville, Sudip Datta, Jim Erickson, Marcus Fallen, Joseph Francis, Mark Fuller, Allan Graves, Barbara Glover, Asad Hasan, Thirumaleshwara Hasandka, Prasad Kuruvadi Nagaraj, Clara Jaeckel, Aneesh Khandelwal, Joel Kallman, Eugene Karichkin, Jai Krishnani, Sangeeth Kumar, Ranjith Kundapur, Kevin Jernigan, Christopher Jones, Simon Law, Bryn Llewellyn, Saar Maoz, Sreejith Minnanghat, Gopal Mulagund, Sue Lee, Rich Long, Barb Lundhild, Rolly Lv, Rudregowda Mallegowda, Padmanabhan Manavazhi, Mughees Minhas, Krishna Mohan, Matthew McKerley, John McHugh, Gurudas Pai, Satish Panchumarthy, Rajesh Prasad, Rajendra Pingte, Apparsamy Perumal, Srinivas Poovala, Mohammed Shahnawaz Quadri, Hanlin Qian, Gurumurthy Ramamurthy, Hema Ramamurthy, Sunil Ravindrachar, Mark Richwine, Dipak Saggi, Trivikrama Samudrala, Shachi Sanklecha, David Schreiner, Ara Shakian, Mohit Singhal, Dharma Sirnappalli, Akshay Shah, James Spiller, Roy Swonger, Binoy Sukumaran, Kamal Tbeileh, Ravi Thammaiah, Shekhar Vaggu, Parvathi Subramanian, Ajesh Viswambharan, Peter Wahl, Terri Winters, Sergiusz Wolicki, Sivakumar Yarlagadda, Zakia Zerhouni

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience	vii
Documentation Accessibility	vii
Set Up Java Access Bridge to Implement Java Accessibility	viii
Command Syntax	viii
Related Documentation	ix
Conventions	ix

1 Oracle Database Client Installation Checklist

Server Hardware Checklist for Oracle Database Client Installation	1-1
Operating System Checklist for Oracle Database on HP-UX Itanium	1-2
Server Configuration Checklist for Oracle Database Client	1-2
Oracle User Environment Configuration Checklist for Oracle Database Installation	1-4
Storage Checklist for Oracle Database Client	1-5
Installer Planning Checklist for Oracle Database Client	1-5

2 Checking and Configuring Server Hardware for Oracle Database Client

Logging In to a Remote System Using X Window System	2-1
Checking Server Hardware and Memory Configuration	2-2

3 Configuring Operating Systems for Oracle Database Client on HP-UX Itanium Systems

Guidelines for HP-UX Itanium Operating System Installation	3-1
Reviewing Operating System Security Common Practices	3-1
About Operating System Requirements	3-2
Operating System Requirements for HP-UX Itanium Systems	3-2
Supported HP-UX Release on Itanium	3-2
Additional Drivers and Software Packages for HP-UX Itanium Systems	3-3
Installation Requirements for ODBC and LDAP	3-4

About ODBC Drivers and Oracle Database	3-4
Installing ODBC Drivers for HP-UX Itanium Systems	3-4
About LDAP and Oracle Plug-ins	3-4
Installing the LDAP Package	3-5
Installation Requirements for Programming Environments for HP-UX Itanium Systems	3-5
Installation Requirements for Web Browsers	3-6
Checking the Software Requirements on HP-UX Itanium	3-6

4 Configuring Users, Groups and Environments for Oracle Database Client

Required Operating System Groups and Users	4-1
Determining If an Oracle Inventory and Oracle Inventory Group Exist	4-2
Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist	4-2
About Oracle Installation Owner Accounts	4-3
Identifying an Oracle Software Owner User Account	4-3
Creating Operating System Oracle Installation User Accounts	4-4
Creating an Oracle Software Owner User	4-4
Environment Requirements for Oracle Software Owners	4-4
Procedure for Configuring Oracle Software Owner Environments	4-5
Setting Remote Display and X11 Forwarding Configuration	4-7
Unsetting Oracle Installation Owner Environment Variables	4-8

5 Installing Oracle Database Client

Accessing the Installation Software	5-1
Downloading Oracle Software	5-2
Downloading the Installation Archive Files from OTN	5-2
Downloading the Software from Oracle Software Delivery Cloud Portal	5-2
Copying the Software to the Hard Disk	5-3
Mounting Disks on HP-UX Itanium Systems	5-3
About Character Set Selection During Installation	5-4
Running the Installer in a Different Language	5-5
Installing the Oracle Database Client Software	5-5
Running Setup Wizard to Install Oracle Database Client	5-5
Using Oracle Net Configuration Assistant	5-6
Relinking Oracle Database Client Binaries After Installation	5-7

6 Oracle Database Client Postinstallation Tasks

Required Postinstallation Tasks	6-1
---------------------------------	-----

Downloading and Installing Release Update Patches	6-1
Recommended Postinstallation Tasks	6-2
Creating a Backup of the root.sh Script	6-2
Setting Language and Locale Preferences for Client Connections	6-3

7 Removing Oracle Database Software

About Oracle Deinstallation Options	7-1
Oracle Deinstallation (Deinstall)	7-3
Deinstallation Examples for Oracle Database Client	7-4

A Installing and Configuring Oracle Database Using Response Files

How Response Files Work	A-1
Reasons for Using Silent Mode or Response File Mode	A-2
Using Response Files	A-2
Preparing Response Files	A-3
Editing a Response File Template	A-3
Recording Response Files	A-4
Running Oracle Universal Installer Using a Response File	A-5

Index

List of Tables

1-1	Server Hardware Checklist for Oracle Database Client Installations	1-1
1-2	Operating System General Checklist for Oracle Database on HP-UX Itanium	1-2
1-3	Server Configuration Checklist for Oracle Database Client	1-2
1-4	User Environment Configuration for Oracle Database	1-4
1-5	Storage Checklist for Oracle Database Client	1-5
1-6	Oracle Universal Installer Planning Checklist for Oracle Database Client Installation	1-5
3-1	HP-UX Itanium Minimum Operating System Requirements	3-3
3-2	Requirements for Programming Environments for HP-UX Itanium Systems	3-5
A-1	Response Files for Oracle Database Client	A-3

Preface

This guide explains how to install and configure single-instance Oracle Database.

This guide also provides information about Optimal Flexible Architecture, cloning an Oracle home, and how to remove the database software.

- [Audience](#)
This guide is intended for anyone responsible for installing Oracle Database 18c.
- [Documentation Accessibility](#)
- [Set Up Java Access Bridge to Implement Java Accessibility](#)
Install Java Access Bridge so that assistive technologies on Microsoft Windows systems can use the Java Accessibility API.
- [Command Syntax](#)
Refer to these command syntax conventions to understand command examples in this guide.
- [Related Documentation](#)
The related documentation for Oracle Database products includes the following manuals:
 - [Conventions](#)

Audience

This guide is intended for anyone responsible for installing Oracle Database 18c.

Additional installation guides for Oracle Database, Oracle Real Application Clusters, Oracle Clusterware, Oracle Database Examples, and Oracle Enterprise Manager Cloud Control are available at the following URL:

<http://docs.oracle.com>

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Set Up Java Access Bridge to Implement Java Accessibility

Install Java Access Bridge so that assistive technologies on Microsoft Windows systems can use the Java Accessibility API.

Java Access Bridge is a technology that enables Java applications and applets that implement the Java Accessibility API to be visible to assistive technologies on Microsoft Windows systems.

Refer to *Java Platform, Standard Edition Accessibility Guide* for information about the minimum supported versions of assistive technologies required to use Java Access Bridge. Also refer to this guide to obtain installation and testing instructions, and instructions for how to use Java Access Bridge.

Related Topics

- *Java Platform, Standard Edition Java Accessibility Guide*

Command Syntax

Refer to these command syntax conventions to understand command examples in this guide.

Convention	Description
\$	Bourne or BASH shell prompt in a command example. Do not enter the prompt as part of the command.
%	C Shell prompt in a command example. Do not enter the prompt as part of the command.
#	Superuser (root) prompt in a command example. Do not enter the prompt as part of the command.
monospace	UNIX command syntax
backslash \	A backslash is the UNIX and Linux command continuation character. It is used in command examples that are too long to fit on a single line. Enter the command as displayed (with a backslash) or enter it on a single line without a backslash: <code>dd if=/dev/rdskc0t1d0s6 of=/dev/rst0 bs=10b \ count=10000</code>
braces { }	Braces indicate required items: <code>.DEFINE {macrol}</code>
brackets []	Brackets indicate optional items: <code>cvtcrt termname [outfile]</code>
ellipses ...	Ellipses indicate an arbitrary number of similar items: <code>CHKVAL fieldname value1 value2 ... valueN</code>
<i>italic</i>	Italic type indicates a variable. Substitute a value for the variable: <code><i>library_name</i></code>

Convention	Description
vertical line	A vertical line indicates a choice within braces or brackets: FILE filesize [K M]

Related Documentation

The related documentation for Oracle Database products includes the following manuals:

Related Topics

- *Oracle Database Concepts*
- *Oracle Database New Features Guide*
- *Oracle Database Licensing Information*
- *Oracle Database Readme*
- *Oracle Universal Installer User's Guide*
- *Oracle Grid Infrastructure Installation Guide*
- *Oracle Database Release Notes for HP-UX Itanium*
- *Oracle Database Client Installation Guide for HP-UX Itanium*
- *Oracle Database Examples Installation Guide*
- *Oracle Real Application Clusters Installation Guide for Linux and UNIX*
- *Oracle Database Administrator's Reference for Linux and UNIX-Based Operating Systems*
- *Oracle Automatic Storage Management Administrator's Guide*
- *Oracle Database Upgrade Guide*
- *Oracle Database 2 Day DBA*
- *Oracle Application Express Installation Guide*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1

Oracle Database Client Installation Checklist

Use checklists to review system requirements, and to plan and carry out Oracle Database Client installation.

Oracle recommends that you use checklists as part of your installation planning process. Using checklists can help you to confirm that your server hardware and configuration meet minimum requirements for this release and can help you carry out a successful installation.

- [Server Hardware Checklist for Oracle Database Client Installation](#)
Use this checklist to check hardware requirements for Oracle Database Client installations.
- [Operating System Checklist for Oracle Database on HP-UX Itanium](#)
Use this checklist to check minimum operating system requirements for Oracle Database.
- [Server Configuration Checklist for Oracle Database Client](#)
Use this checklist to check minimum server configuration requirements for Oracle Database Client installations.
- [Oracle User Environment Configuration Checklist for Oracle Database Installation](#)
Use this checklist to plan operating system users, groups, and environments for Oracle Database management.
- [Storage Checklist for Oracle Database Client](#)
Use this checklist to review storage minimum requirements and assist with configuration planning.
- [Installer Planning Checklist for Oracle Database Client](#)
Use this checklist to assist you to be prepared before starting Oracle Universal Installer.

Server Hardware Checklist for Oracle Database Client Installation

Use this checklist to check hardware requirements for Oracle Database Client installations.

Table 1-1 Server Hardware Checklist for Oracle Database Client Installations

Check	Task
Server Make and Architecture	Confirm that server make, model, core architecture, and host bus adaptors (HBA) or network interface controllers (NICs) are supported to run with Oracle Database and Oracle Grid Infrastructure. Ensure the server has a DVD drive, if you are installing from a DVD.

Table 1-1 (Cont.) Server Hardware Checklist for Oracle Database Client Installations

Check	Task
Runlevel	3
Server Display Cards	At least 1024 x 768 display resolution, which Oracle Universal Installer requires.
Minimum network connectivity	Client is connected to a network.
Minimum RAM	At least 256 MB of RAM.

Operating System Checklist for Oracle Database on HP-UX Itanium

Use this checklist to check minimum operating system requirements for Oracle Database.

Table 1-2 Operating System General Checklist for Oracle Database on HP-UX Itanium

Item	Task
Operating system general requirements	The following HP-UX Itanium version is supported: HP-UX 11.31 September 2014 B.11.31.1409 or later Review the system requirements section for a list of patch requirements.

Server Configuration Checklist for Oracle Database Client

Use this checklist to check minimum server configuration requirements for Oracle Database Client installations.

Table 1-3 Server Configuration Checklist for Oracle Database Client

Check	Task
Disk space allocated to the /tmp directory	At least 130 MB of space in the temporary disk space (/tmp) directory.

Table 1-3 (Cont.) Server Configuration Checklist for Oracle Database Client

Check	Task
Swap space allocation relative to RAM	<p>256 MB: 3 times the size of the RAM Between 256 MB and 512 MB: 2 times the size of the RAM Between 512 MB and 2 GB: 1.5 times the size of the RAM Between 2 GB and 16 GB: Equal to the size of the RAM More than 16 GB: 16 GB</p> <p>Note: Configure swap for your expected system loads. This installation guide provides minimum values for installation only. Refer to your operating system documentation for additional memory tuning guidance.</p>
Oracle Inventory (oraInventory) and OINSTALL Group Requirements	<ul style="list-style-type: none"> • For upgrades, Oracle Universal Installer (OUI) detects an existing oraInventory directory from the <code>/etc/oraInst.loc</code> file, and uses the existing oraInventory. • For new installs, if you have not configured an oraInventory directory, then the installer creates an Oracle inventory that is one directory level up from the Oracle base for the Oracle Grid Infrastructure install, and designates the installation owner's primary group as the Oracle Inventory group. <p>The Oracle Inventory directory is the central inventory of Oracle software installed on your system. Users who have the Oracle Inventory group as their primary group are granted the OINSTALL privilege to write to the central inventory.</p> <p>The OINSTALL group must be the primary group of all Oracle software installation owners on the server. It should be writable by any Oracle installation owner.</p>
Groups and users	<p>Oracle recommends that you create groups and user accounts required for your security plans before starting installation. Installation owners have resource limits settings and other requirements. Group and user names must use only ASCII characters.</p>
Mount point paths for the software binaries	<p>Oracle recommends that you create an Optimal Flexible Architecture configuration as described in the appendix "Optimal Flexible Architecture" in <i>Oracle Database Installation Guide</i> for your platform.</p>
Ensure that the Oracle home (the Oracle home path you select for Oracle Database) uses only ASCII characters	<p>The ASCII character restriction includes installation owner user names, which are used as a default for some home paths, as well as other directory names you may select for paths.</p>
Determine root privilege delegation option for installation	<p>During installation, you are asked to run configuration scripts as the <code>root</code> user. You can either run these scripts manually as <code>root</code> when prompted, or you can provide configuration information and passwords using a root privilege delegation option such as Sudo.</p> <p>To enable Sudo, have a system administrator with the appropriate privileges configure a user that is a member of the sudoers list, and provide the username and password when prompted during installation.</p>

Table 1-3 (Cont.) Server Configuration Checklist for Oracle Database Client

Check	Task
Set locale (if needed)	Specify the language and the territory, or locale, in which you want to use Oracle components. A locale is a linguistic and cultural environment in which a system or program is running. NLS (National Language Support) parameters determine the locale-specific behavior on both servers and clients. The locale setting of a component determines the language of the user interface of the component, and the globalization behavior, such as date and number formatting.

Related Topics

- *Oracle Database Globalization Support Guide*

Oracle User Environment Configuration Checklist for Oracle Database Installation

Use this checklist to plan operating system users, groups, and environments for Oracle Database management.

Table 1-4 User Environment Configuration for Oracle Database

Check	Task
Review Oracle Inventory (oraInventory) and OINSTALL Group Requirements	<p>The physical group you designate as the Oracle Inventory directory is the central inventory of Oracle software installed on your system. It should be the primary group for all Oracle software installation owners. Users who have the Oracle Inventory group as their primary group are granted the OINSTALL privilege to read and write to the central inventory.</p> <ul style="list-style-type: none"> • If you have an existing installation, then OUI detects the existing oraInventory directory from the <code>/var/opt/oracle/oraInst.loc</code> file, and uses this location. • If you are installing Oracle software for the first time, then you can specify the Oracle inventory directory and the Oracle base directory during the Oracle software installation, and Oracle Universal Installer will set up the software directories for you. Ensure that the directory paths that you specify are in compliance with the Oracle Optimal Flexible Architecture recommendations. <p>Ensure that the group designated as the OINSTALL group is available as the primary group for all planned Oracle software installation owners.</p>
Create operating system groups and users for standard or role-allocated system privileges	<p>Create operating system groups and users depending on your security requirements, as described in this install guide.</p> <p>Set resource limits settings and other requirements for Oracle software installation owners.</p> <p>Group and user names must use only ASCII characters.</p>

Table 1-4 (Cont.) User Environment Configuration for Oracle Database

Check	Task
Unset Oracle Software Environment Variables	If you have had an existing installation on your system, and you are using the same user account to install this installation, then unset the ORACLE_HOME, ORACLE_BASE, ORACLE_SID, TNS_ADMIN environment variables and any other environment variable set for the Oracle installation user that is connected with Oracle software homes.
Configure the Oracle Software Owner Environment	Configure the environment of the <code>oracle</code> or <code>grid</code> user by performing the following tasks: <ul style="list-style-type: none"> Set the default file mode creation mask (<code>umask</code>) to 022 in the shell startup file. Set the <code>DISPLAY</code> environment variable.

Storage Checklist for Oracle Database Client

Use this checklist to review storage minimum requirements and assist with configuration planning.

Table 1-5 Storage Checklist for Oracle Database Client

Check	Task
Minimum local disk storage space for Oracle Database Client software	At least 405 MB for an Instant Client installation At least 2.6 GB for Administrator installation type At least 2.0 GB for Runtime installation type At least 3.07 GB for Custom installation type (all components)

Installer Planning Checklist for Oracle Database Client

Use this checklist to assist you to be prepared before starting Oracle Universal Installer.

Table 1-6 Oracle Universal Installer Planning Checklist for Oracle Database Client Installation

Check	Task
Read the Release Notes	Review release notes for your platform, which are available for your release at the following URL: http://docs.oracle.com/en/database/database.html
Review the Licensing Information	You are permitted to use only those components in the Oracle Database media pack for which you have purchased licenses. For more information about licenses, refer to the following URL: <i>Oracle Database Licensing Information</i>

Table 1-6 (Cont.) Oracle Universal Installer Planning Checklist for Oracle Database Client Installation

Check	Task
Review Oracle Support Certification Matrix	<p>New platforms and operating system software versions might be certified after this guide is published, review the certification matrix on the My Oracle Support website for the most up-to-date list of certified hardware platforms and operating system versions:</p> <p>https://support.oracle.com/</p> <p>You must register online before using My Oracle Support. After logging in, from the menu options, select the Certifications tab. On the Certifications page, use the Certification Search options to search by Product, Release, and Platform. You can also search using the Certification Quick Link options such as Product Delivery, and Lifetime Support.</p>
Run OUI with CVU and use fixup scripts	<p>Oracle Universal Installer is fully integrated with Cluster Verification Utility (CVU), automating many CVU prerequisite checks. Oracle Universal Installer runs all prerequisite checks and creates fixup scripts when you run the installer. You can run OUI up to the Summary screen without starting the installation.</p> <p>You can also run CVU commands manually to check system readiness. For more information, see:</p> <p><i>Oracle Clusterware Administration and Deployment Guide</i></p>
Ensure cron jobs do not run during installation	<p>If the installer is running when daily cron jobs start, then you may encounter unexplained installation problems if your cron job is performing cleanup, and temporary files are deleted before the installation is finished. Oracle recommends that you complete installation before daily cron jobs are run, or disable daily cron jobs that perform cleanup until after the installation is completed.</p>
Decide the client installation type	<p>You can choose one of the following installation types when installing Oracle Database Client:</p> <ul style="list-style-type: none"> • Instant Client: Enables you to install only the shared libraries required by Oracle Call Interface (OCI), Oracle C++ Call Interface (OCCI), Pro*C, or Java database connectivity (JDBC) OCI applications. This installation type requires much less disk space than the other Oracle Database Client installation types. For more information about Oracle Database Instant Client see the following URL: http://www.oracle.com/technetwork/database/features/instant-client/index.html • Administrator: Enables applications to connect to an Oracle Database instance on the local system or on a remote system. It also provides tools that enable you to administer Oracle Database. • Runtime: Enables applications to connect to an Oracle Database instance on the local system or on a remote system. • Custom: Enables you to select individual components from the list of Administrator and Runtime components.
Obtain your My Oracle Support account information.	<p>During installation, you require a My Oracle Support user name and password to configure security updates, download software updates, and other installation tasks. You can register for My Oracle Support at the following URL:</p> <p>https://support.oracle.com/</p>

Table 1-6 (Cont.) Oracle Universal Installer Planning Checklist for Oracle Database Client Installation

Check	Task
Decide if you need 32-bit client software	<p>The 64-bit Oracle Database Client software does not contain any 32-bit client binaries. If you require 32-bit client binaries on 64-bit platforms, then install the 32-bit binaries from the respective 32-bit client software into a separate Oracle home.</p> <p>The 64-bit Oracle Database Client preinstallation requirements apply to 32-bit Oracle Database Client also.</p> <p>For more information, refer to My Oracle Support note 883702.1: https://support.oracle.com/rs?type=doc&id=883702.1</p>
Oracle Database Client and Oracle Database interoperability	<p>For information about interoperability between Oracle Database Client and Oracle Database releases, see My Oracle Support Note 207303.1: https://support.oracle.com/rs?type=doc&id=207303.1</p>

2

Checking and Configuring Server Hardware for Oracle Database Client

Verify that servers where you install Oracle Database Client meet the minimum requirements for installation.

This section provides minimum server requirements to complete installation of Oracle Database Client. It does not provide system resource guidelines, or other tuning guidelines for particular workloads.

- [Logging In to a Remote System Using X Window System](#)
Use this procedure to run Oracle Universal Installer (OUI) by logging on to a remote system where the runtime setting prohibits logging in directly to a graphical user interface (GUI).
- [Checking Server Hardware and Memory Configuration](#)
Use this procedure to gather information about your server configuration.

Logging In to a Remote System Using X Window System

Use this procedure to run Oracle Universal Installer (OUI) by logging on to a remote system where the runtime setting prohibits logging in directly to a graphical user interface (GUI).

OUI is a graphical user interface (GUI) application. On servers where the runtime settings prevent GUI applications from running, you can redirect the GUI display to a client system connecting to the server.

Note:

If you log in as another user (for example, `oracle` or `grid`), then repeat this procedure for that user as well.

1. Start an X Window System session. If you are using an X Window System terminal emulator from a PC or similar system, then you may need to configure security settings to permit remote hosts to display X applications on your local system.
2. Enter a command using the following syntax to enable remote hosts to display X applications on the local X server:

```
# xhost + RemoteHost
```

RemoteHost is the fully qualified remote host name. For example:

```
# xhost + somehost.example.com  
somehost.example.com being added to the access control list
```

3. If you are not installing the software on the local system, then use the `ssh` command to connect to the system where you want to install the software:

```
# ssh -Y RemoteHost
```

RemoteHost is the fully qualified remote host name. The `-Y` flag ("yes") enables remote X11 clients to have full access to the original X11 display. For example:

```
# ssh -Y somehost.example.com
```

4. If you are not logged in as the `root` user, and you are performing configuration steps that require `root` user privileges, then switch the user to `root`.

 **Note:**

For more information about remote login using X Window System, refer to your X server documentation, or contact your X server vendor or system administrator. Depending on the X server software that you are using, you may have to complete the tasks in a different order.

Checking Server Hardware and Memory Configuration

Use this procedure to gather information about your server configuration.

1. To determine the physical RAM size on the server:

```
# /usr/contrib/bin/machinfo | grep -i Memory
```

2. To determine the size of the configured swap space:

```
# /usr/sbin/swapinfo -a
```

If necessary, see your operating system documentation for information about how to configure additional swap space.

3. To determine the amount of space available in the `/tmp` directory:

```
# bdf /tmp
```

If the free space available in the `/tmp` directory is less than what is required, then complete one of the following steps:

- Delete unnecessary files from the `/tmp` directory to meet the disk space requirement.
- When you set the Oracle user's environment, also set the `TMP` and `TMPDIR` environment variables to the directory you want to use instead of `/tmp`.

4. To determine the amount of free disk space on the system:

```
# bdf
```

5. To determine if the system architecture can run the software:

```
# uname -m
```

Verify that the processor architecture matches the Oracle software release to install. For example, you should see the following for a x86-64 bit system:

```
ia64 (itanium)
```

If you do not see the expected output, then you cannot install the software on this system.

6. To view the shared memory kernel parameters (`shmmni`, `shmseg`, and `shmmax`) and determine if any changes are necessary for your system:

```
# kctune -v shmmni  
# kctune -v shmseg  
# kctune -v shmmax
```

Use the `kctune shmni=1024` command to set the memory kernel parameter to the required value.

3

Configuring Operating Systems for Oracle Database Client on HP-UX Itanium Systems

Complete operating system configuration requirements and checks for Oracle HP-UX Itanium systems before you start installation.

- [Guidelines for HP-UX Itanium Operating System Installation](#)
Be aware of these operating system guidelines before proceeding with an Oracle installation.
- [Reviewing Operating System Security Common Practices](#)
Secure operating systems are an important basis for general system security.
- [About Operating System Requirements](#)
Depending on the products that you intend to install, verify that you have the required operating system kernel and packages installed.
- [Operating System Requirements for HP-UX Itanium Systems](#)
The compilers and patches listed in this section are supported for this release on HP-UX Itanium systems for Oracle Database, Oracle Database Client, and Oracle Grid Infrastructure 18c.
- [Additional Drivers and Software Packages for HP-UX Itanium Systems](#)
You are not required to install additional drivers and packages, but you may choose to install or configure these drivers and packages.
- [Checking the Software Requirements on HP-UX Itanium](#)
Check your software to see if they meet the minimum version, compiler, and patch requirements for installation.

Guidelines for HP-UX Itanium Operating System Installation

Be aware of these operating system guidelines before proceeding with an Oracle installation.

Refer to your HP-UX documentation to obtain information about installing HP-UX Itanium on your servers.

Reviewing Operating System Security Common Practices

Secure operating systems are an important basis for general system security.

Ensure that your operating system deployment is in compliance with common security practices as described in your operating system vendor security guide.

About Operating System Requirements

Depending on the products that you intend to install, verify that you have the required operating system kernel and packages installed.

Requirements listed in this document are current as of the date listed on the title page. To obtain the most current information about kernel requirements, see the online version at the following URL:

<http://docs.oracle.com>

Oracle Universal Installer performs checks on your system to verify that it meets the listed operating system package requirements. To ensure that these checks complete successfully, verify the requirements before you start OUI.

Note:

Oracle does not support running different operating system versions on cluster members, unless an operating system is being upgraded. You cannot run different operating system version binaries on members of the same cluster, even if each operating system is supported.

Operating System Requirements for HP-UX Itanium Systems

The compilers and patches listed in this section are supported for this release on HP-UX Itanium systems for Oracle Database, Oracle Database Client, and Oracle Grid Infrastructure 18c.

The platform-specific hardware and software requirements included in this guide were current when this guide was published. However, because new platforms and operating system software versions might be certified after this guide is published, review the certification matrix on the My Oracle Support website for the most up-to-date list of certified hardware platforms and operating system versions:

<https://support.oracle.com/>

Identify the requirements for your HP-UX Itanium system, and ensure that you have supported compilers and required patches installed before starting installation.

- [Supported HP-UX Release on Itanium](#)
Use the following information to check the minimum supported HP-UX Itanium distribution:

Supported HP-UX Release on Itanium

Use the following information to check the minimum supported HP-UX Itanium distribution:

Table 3-1 HP-UX Itanium Minimum Operating System Requirements

Item	Requirements
HP-UX 11.31 operating system	HP-UX 11.31 September 2014 B.11.31.1409 or later.
Patches for HP-UX 11.31	<p>The following patches must be installed:</p> <p>PHCO_43503 - 11.31 diskowner(1M) cumulative patch PHKL_40941 - 11.31 scheduler cumulative patch PHKL_42916 - 11.31 SCSI cumulative I/O patch PHKL_42996 - 11.31 scheduler cumulative patch PHKL_43775 - 11.31 vm cumulative patch PHKL_44248 - 11.31 SCSI cumulative I/O patch PHKL_44417 - 11.31 vm cumulative patch PHKL_44565 - 11.31 vm cumulative patch PHSS_37042 - 11.31 hppac PHSS_39094 - 11.31 linker + fdp cumulative patch PHSS_39102 - 11.31 Integrity Unwind Library PHSS_42686 - 11.31 assembler patch PHSS_43205 - 11.31 Math Library Cumulative Patch PHSS_43291 - 11.31 X/Motif runtime patch PHSS_43733 - 11.31 LIBCL patch PHSS_43740 - 11.31 Integrity Unwind Library PHSS_44164 - 11.31 linker + fdp cumulative patch PHSS_44402 - 11.31 linker + fdp cumulative patch</p>
Oracle Clusterware	<ul style="list-style-type: none"> • HP Serviceguard A.11.20 • HP Serviceguard A.11.20 extension for RAC

 **Note:**

HP Serviceguard is optional. It is required only if you want to use shared logical volumes for Oracle Clusterware or database files.

Additional Drivers and Software Packages for HP-UX Itanium Systems

You are not required to install additional drivers and packages, but you may choose to install or configure these drivers and packages.

- [Installation Requirements for ODBC and LDAP](#)
Review these topics to install Open Database Connectivity (ODBC) and Lightweight Directory Access Protocol (LDAP).

- [Installation Requirements for Programming Environments for HP-UX Itanium Systems](#)
Ensure that your system meets the requirements for the programming environment you want to configure.
- [Installation Requirements for Web Browsers](#)
Web browsers are required only if you intend to use Oracle Enterprise Manager Database Express and Oracle Enterprise Manager Cloud Control. Web browsers must support JavaScript, and the HTML 4.0 and CSS 1.0 standards.

Installation Requirements for ODBC and LDAP

Review these topics to install Open Database Connectivity (ODBC) and Lightweight Directory Access Protocol (LDAP).

- [About ODBC Drivers and Oracle Database](#)
Open Database Connectivity (ODBC) is a set of database access APIs that connect to the database, prepare, and then run SQL statements on the database.
- [Installing ODBC Drivers for HP-UX Itanium Systems](#)
If you intend to use ODBC, then download and install the most recent ODBC Driver Manager for HP-UX Itanium.
- [About LDAP and Oracle Plug-ins](#)
Lightweight Directory Access Protocol (LDAP) is an application protocol for accessing and maintaining distributed directory information services over IP networks.
- [Installing the LDAP Package](#)
LDAP is included in a default operating system installation.

About ODBC Drivers and Oracle Database

Open Database Connectivity (ODBC) is a set of database access APIs that connect to the database, prepare, and then run SQL statements on the database.

An application that uses an ODBC driver can access non-uniform data sources, such as spreadsheets and comma-delimited files.

Installing ODBC Drivers for HP-UX Itanium Systems

If you intend to use ODBC, then download and install the most recent ODBC Driver Manager for HP-UX Itanium.

<http://www.unixodbc.org>

Review the minimum supported ODBC driver releases, and install ODBC drivers of the following or later releases for HP-UX Itanium:

ODBC Driver Manager 2.3.4

To use ODBC, you must also install `gcc 4.2.3` or later.

About LDAP and Oracle Plug-ins

Lightweight Directory Access Protocol (LDAP) is an application protocol for accessing and maintaining distributed directory information services over IP networks.

You require the LDAP package if you want to use features requiring LDAP, including the Oracle Database scripts `odisrvreg` and `oidca` for Oracle Internet Directory, or `schemasync` for third-party LDAP directories.

Installing the LDAP Package

LDAP is included in a default operating system installation.

If you did not perform a default operating system installation, and you intend to use Oracle scripts requiring LDAP, then use a package management system for your distribution to install a supported LDAP package for your distribution, and install any other required packages for that LDAP package.

Installation Requirements for Programming Environments for HP-UX Itanium Systems

Ensure that your system meets the requirements for the programming environment you want to configure.

Table 3-2 Requirements for Programming Environments for HP-UX Itanium Systems

Programming Environments	Support Requirements
Java Database Connectivity (JDBC) / Oracle Call Interface (OCI)	JDK 8 (1.8.0.06 or later) with the JNDI extension with Oracle Java Database Connectivity and Oracle Call Interface drivers.
Oracle C++ Oracle C++ Call Interface Pro*C/C++ Oracle XML Developer's Kit (XDK)	<p>Compiler Version: A.06.28 Patch for HP-UX 11i V3 (11.31) on HP-UX Itanium:</p> <ul style="list-style-type: none"> PHSS_40631 - 11.31 HP C/aC++ Compiler (A.06.24) PHSS_40633 - 11.31 u2comp/be/plugin (C.06.24) PHSS_43741 - 11.31 aC++ Runtime (IA: A.06.28, PA: A.03.90)
Pro*COBOL	Micro Focus Server Express 5.1
Pro*FORTRAN	Micro Focus Visual COBOL for Eclipse 2.2 - Update 2 HP FORTRAN/90 - Sep 2008 - release

 **Note:**


These are not mandatory for the database installation.

 **Note:**

Additional patches may be needed depending on applications you deploy.

Table 3-2 (Cont.) Requirements for Programming Environments for HP-UX Itanium Systems

Programming Environments	Support Requirements
VERITAS File System	PHKL_44199 - 11.31 VRTS 5.0 MP1P13 VRTSvxf Kernel Patch
HP Caliper and Gmake	HP Caliper 5.7 Gmake 3.81
gcc	gcc 4.2.3
unzip	Unzip 6.0 or later. Unzip is required to extract the image files for Oracle Database and Oracle Grid Infrastructure installations.

 **Note:**
 The VERITAS file system is optional. This patch is required only if you want to use a VERITAS File System 5.0.

Installation Requirements for Web Browsers

Web browsers are required only if you intend to use Oracle Enterprise Manager Database Express and Oracle Enterprise Manager Cloud Control. Web browsers must support JavaScript, and the HTML 4.0 and CSS 1.0 standards.

<https://support.oracle.com>

Related Topics

- *Oracle Enterprise Manager Cloud Control Basic Installation Guide*

Checking the Software Requirements on HP-UX Itanium

Check your software to see if they meet the minimum version, compiler, and patch requirements for installation.

1. To determine the distribution and version of HP-UX installed:

```
# uname -a
HP-UX hostname B.11.31 U ia64 4156074294 unlimited-user license
```

In this example, the version of HP-UX is 11.31 and the processor is Itanium.

2. To determine the compiler installed:

```
# /usr/sbin/swlist -l product | grep -i compiler
```

3. To determine if a patch is installed:

```
# /usr/sbin/swlist -l patch | grep PHSS_42686
```

Alternatively, to list all installed patches:

```
# /usr/sbin/swlist -l patch | more
```

If a required patch is not installed, then download it from the HP Support Center website and install it:

<https://www.support.hp.com/>

If the website has a recent version of the patch, then download and install that version.

4. To verify if the system meets the minimum patch bundle requirements:

```
# /usr/sbin/swlist -l bundle |grep QPK
```

The QPK (Quality Pack) bundles have version numbers of the form B.11.31.0809.326a (for the September 2008 release), B.11.31.0903.334a (for the March 2009 release), and so on.

If a required bundle, product, or fileset is not installed, then install it. See your operating system or software documentation for information about installing products.

 **Note:**

There may be more recent versions of the patches listed in the preceding paragraph that are installed on the system. If a listed patch is not installed, then determine if a more recent version is installed before installing the version listed.

5. If you require a CSD for WebSphere MQ, then refer to the following website for download and installation information:

<https://www.ibm.com/support/>

4

Configuring Users, Groups and Environments for Oracle Database Client

Before installation, create operating system groups and users, and configure user environments.

- [Required Operating System Groups and Users](#)
Oracle software installations require an installation owner, an Oracle Inventory group, which is the primary group of all Oracle installation owners, and at least one group designated as a system privileges group.
- [Creating Operating System Oracle Installation User Accounts](#)
Before starting installation, create Oracle software owner user accounts, and configure their environments.
- [Unsetting Oracle Installation Owner Environment Variables](#)
Unset Oracle installation owner environment variables before you start the installation.

Required Operating System Groups and Users

Oracle software installations require an installation owner, an Oracle Inventory group, which is the primary group of all Oracle installation owners, and at least one group designated as a system privileges group.

Review group and user options with your system administrator. If you have system administration privileges, then review the topics in this section and configure operating system groups and users as needed.

- [Determining If an Oracle Inventory and Oracle Inventory Group Exist](#)
Determine if you have an existing Oracle central inventory, and ensure that you use the same Oracle Inventory for all Oracle software installations. Also, ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.
- [Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist](#)
Create an Oracle Inventory group manually as part of a planned installation, particularly where more than one Oracle software product is installed on servers.
- [About Oracle Installation Owner Accounts](#)
Select or create an Oracle installation owner for your installation, depending on the group and user management plan you want to use for your installations.
- [Identifying an Oracle Software Owner User Account](#)
You must create at least one software owner user account the first time you install Oracle software on the system. Either use an existing Oracle software user account, or create an Oracle software owner user account for your installation.

Determining If an Oracle Inventory and Oracle Inventory Group Exist

Determine if you have an existing Oracle central inventory, and ensure that you use the same Oracle Inventory for all Oracle software installations. Also, ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

When you install Oracle software on the system for the first time, OUI creates the `oraInst.loc` file. This file identifies the name of the Oracle Inventory group (by default, `oinstall`), and the path of the Oracle central inventory directory. If you have an existing Oracle central inventory, then ensure that you use the same Oracle Inventory for all Oracle software installations, and ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

```
oraInst.loccentral_inventory_locationgroup  
  
inventory_loc=central_inventory_location  
inst_group=group
```

Use the `more` command to determine if you have an Oracle central inventory on your system. For example:

```
# more /var/opt/oracle/oraInst.loc  
  
inventory_loc=/u01/app/oraInventory  
inst_group=oinstall
```

Use the command `grep groupname /etc/group` to confirm that the group specified as the Oracle Inventory group still exists on the system. For example:

```
$ grep oinstall /etc/group  
oinstall:x:54321:grid,oracle
```



Note:

Do not put the `oraInventory` directory under the Oracle base directory for a new installation, because that can result in user permission errors for other installations.

Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist

Create an Oracle Inventory group manually as part of a planned installation, particularly where more than one Oracle software product is installed on servers.

By default, if an `oraInventory` group does not exist, then the installer uses the primary group of the installation owner for the Oracle software being installed as the `oraInventory` group. Ensure that this group is available as a primary group for all planned Oracle software installation owners.

```
oraInst.loc  
  
# /usr/sbin/groupadd -g 54321 oinstall
```

About Oracle Installation Owner Accounts

Select or create an Oracle installation owner for your installation, depending on the group and user management plan you want to use for your installations.

You must create a software owner for your installation in the following circumstances:

- If an Oracle software owner user does not exist; for example, if this is the first installation of Oracle software on the system.
- If an Oracle software owner user exists, but you want to use a different operating system user, with different group membership, to separate Oracle Grid Infrastructure administrative privileges from Oracle Database administrative privileges.

In Oracle documentation, a user created to own only Oracle Grid Infrastructure software installations is called the Grid user (`grid`). This user owns both the Oracle Clusterware and Oracle Automatic Storage Management binaries. A user created to own either all Oracle installations, or one or more Oracle database installations, is called the Oracle user (`oracle`). You can have only one Oracle Grid Infrastructure installation owner, but you can have different Oracle users to own different installations.

Oracle software owners must have the Oracle Inventory group as their primary group, so that each Oracle software installation owner can write to the central inventory (`oraInventory`), and so that OCR and Oracle Clusterware resource permissions are set correctly. The database software owner must also have the OSDBA group and (if you create them) the OSOPER, OSBACKUPDBA, OSDGDBA, OSRACDBA, and OSKMDBA groups as secondary groups.

Identifying an Oracle Software Owner User Account

You must create at least one software owner user account the first time you install Oracle software on the system. Either use an existing Oracle software user account, or create an Oracle software owner user account for your installation.

To use an existing user account, obtain from your system administrator the name of an existing Oracle installation owner. Confirm that the existing owner is a member of the Oracle Inventory group.

```
oinstalloinstall
$ grep "oinstall" /etc/group
oinstall:x:54321:oracle
```

You can then use the `ID` command to verify that the Oracle installation owners you intend to use have the Oracle Inventory group as their primary group. For example:

```
id oracle
uid=54321(oracle) gid=54321(oinstall) groups=54321(oper),54322(dba)
```

After you create operating system groups, create or modify Oracle user accounts in accordance with your operating system authentication planning.

Creating Operating System Oracle Installation User Accounts

Before starting installation, create Oracle software owner user accounts, and configure their environments.

Oracle software owner user accounts require resource settings and other environment configuration. To protect against accidents, Oracle recommends that you create one software installation owner account for each Oracle software program you install.

- [Creating an Oracle Software Owner User](#)
If the Oracle software owner user (`oracle`) does not exist, or if you require a new Oracle software owner user, then create it as described in this section.
- [Environment Requirements for Oracle Software Owners](#)
You must make the following changes to configure Oracle software owner environments:
- [Procedure for Configuring Oracle Software Owner Environments](#)
Configure each Oracle installation owner user account environment:
- [Setting Remote Display and X11 Forwarding Configuration](#)
If you are on a remote terminal, and the local system has only one visual (which is typical), then use the following syntax to set your user account `DISPLAY` environment variable:

Creating an Oracle Software Owner User

If the Oracle software owner user (`oracle`) does not exist, or if you require a new Oracle software owner user, then create it as described in this section.

The following example shows how to create the user `oracle` with the user ID 54321; with the primary group `oinstall`; and with secondary group `dba`.

```
# /usr/sbin/useradd -u 54321 -g oinstall -G dba, oracle
```

You must note the user ID number for installation users, because you need it during preinstallation.

For Oracle Grid Infrastructure Installations, user IDs and group IDs must be identical on all candidate nodes.

Environment Requirements for Oracle Software Owners

You must make the following changes to configure Oracle software owner environments:

- Set the installation software owner user (`grid, oracle`) default file mode creation mask (`umask`) to 022 in the shell startup file. Setting the mask to 022 ensures that the user performing the software installation creates files with 644 permissions.
- Set `ulimit` settings for file descriptors and processes for the installation software owner (`grid, oracle`).
- Set the `DISPLAY` environment variable in preparation for running an Oracle Universal Installer (OUI) installation.

▲ Caution:

If you have existing Oracle installations that you installed with the user ID that is your Oracle Grid Infrastructure software owner, then unset all Oracle environment variable settings for that user.

Procedure for Configuring Oracle Software Owner Environments

Configure each Oracle installation owner user account environment:

1. Start an X terminal session (`xterm`) on the server where you are running the installation.
2. Enter the following command to ensure that X Window applications can display on this system, where `hostname` is the fully qualified name of the local host from which you are accessing the server:

```
$ xhost + hostname
```

3. If you are not logged in as the software owner user, then switch to the software owner user you are configuring. For example, with the user `grid`:

```
$ su - grid
```

On systems where you cannot run `su` commands, use `sudo` instead:

```
$ sudo -u grid -s
```

4. To determine the default shell for the user, enter the following command:

```
$ echo $SHELL
```

5. Open the user's shell startup file in any text editor:

- Bash shell (`bash`):

```
$ vi .bash_profile
```

- Bourne shell (`sh`) or Korn shell (`ksh`):

```
$ vi .profile
```

- C shell (`csh` or `tcsh`):

```
% vi .login
```

6. Enter or edit the following line, specifying a value of `022` for the default file mode creation mask:

```
umask 022
```

7. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variables are set in the file, then remove these lines from the file.
8. Save the file, and exit from the text editor.
9. To run the shell startup script, enter one of the following commands:

- Bash shell:

```
$ . ~/.bash_profile
```

- Bourne, Bash, or Korn shell:

```
$ . ~/.profile
```

- C shell:

```
% source ~/.login
```

10. Use the following command to check the PATH environment variable:

```
$ echo $PATH
```

Remove any Oracle environment variables.

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ export DISPLAY=local_host:0.0
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, `local_host` is the host name or IP address of the system (your workstation, or another client) on which you want to display the installer.

12. If the `/tmp` directory has less than 1 GB of free space, then identify a file system with at least 1 GB of free space and set the `TMP` and `TMPDIR` environment variables to specify a temporary directory on this file system:

Note:

You cannot use a shared file system as the location of the temporary file directory (typically `/tmp`) for Oracle RAC installations. If you place `/tmp` on a shared file system, then the installation fails.

- a. Use the `df -h` command to identify a suitable file system with sufficient free space.
- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ sudo - s
# mkdir /mount_point/tmp
# chmod 775 /mount_point/tmp
# exit
```

- c. Enter commands similar to the following to set the `TMP` and `TMPDIR` environment variables:

Bourne, Bash, or Korn shell:

```
$ TMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TMP TMPDIR
```

C shell:

```
% setenv TMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```


13. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the `umask` command displays a value of `22`, `022`, or `0022` and that the environment variables you set in this section have the correct values.

Setting Remote Display and X11 Forwarding Configuration

If you are on a remote terminal, and the local system has only one visual (which is typical), then use the following syntax to set your user account `DISPLAY` environment variable:

Remote Display

Bourne, Korn, and Bash shells

```
$ export DISPLAY=hostname:0
```

C shell

```
% setenv DISPLAY hostname:0
```

For example, if you are using the Bash shell and if your host name is `local_host`, then enter the following command:

```
$ export DISPLAY=node1:0
```

X11 Forwarding

To ensure that X11 forwarding does not cause the installation to fail, use the following procedure to create a user-level SSH client configuration file for Oracle installation owner user accounts:

1. Using any text editor, edit or create the software installation owner's `~/.ssh/config` file.
2. Ensure that the `ForwardX11` attribute in the `~/.ssh/config` file is set to `no`. For example:

```
Host *
    ForwardX11 no
```

3. Ensure that the permissions on `~/.ssh` are secured to the Oracle installation owner user account. For example:

```
$ ls -al .ssh
total 28
drwx----- 2 grid oinstall 4096 Jun 21 2015
drwx----- 19 grid oinstall 4096 Jun 21 2015
-rw-r--r--  1 grid oinstall 1202 Jun 21 2015 authorized_keys
-rwx----- 1 grid oinstall  668 Jun 21 2015 id_dsa
-rwx----- 1 grid oinstall  601 Jun 21 2015 id_dsa.pub
-rwx----- 1 grid oinstall 1610 Jun 21 2015 known_hosts
```

Unsetting Oracle Installation Owner Environment Variables

Unset Oracle installation owner environment variables before you start the installation.

The environment variables you have set for the Oracle installation owner account you use to run the installation can cause issues if they are set to values that conflict with the values needed for installation.

If you have set `ORA_CRS_HOME` as an environment variable, following instructions from Oracle Support, then unset it before starting an installation or upgrade. You should never use `ORA_CRS_HOME` as an environment variable except under explicit direction from Oracle Support.

If you have had an existing installation on your system, and you are using the same user account to install this installation, then unset the following environment variables: `ORA_CRS_HOME`, `ORACLE_HOME`, `ORA_NLS10`, `TNS_ADMIN`, and any other environment variable set for the Oracle installation user that is connected with Oracle software homes.

Also, ensure that the `$ORACLE_HOME/bin` path is removed from your `PATH` environment variable.

5

Installing Oracle Database Client

Oracle Database Client installation software is available in multiple media, and can be installed using several options.

The Oracle Database Client software is available on installation media, or you can download it from the Oracle Technology Network website, or the Oracle Software Delivery Cloud portal. In most cases, you use the graphical user interface (GUI) provided by Oracle Universal Installer (OUI) to install the software. However, you can also use Oracle Universal Installer to complete silent mode installations, without using the GUI.

Note:

You cannot use Oracle Universal Installer from an earlier Oracle release to install components from this release.

- [Accessing the Installation Software](#)
You can download Oracle Database software from the Oracle Technology Network website or the Oracle Software Delivery Cloud portal. In some cases, Oracle Database software may be available on installation media also.
- [About Character Set Selection During Installation](#)
Before you create the database, decide the character set that you want to use.
- [Running the Installer in a Different Language](#)
Describes how to run the installer in other languages.
- [Installing the Oracle Database Client Software](#)
These topics explain how to run the Setup Wizard to perform most database client installations.
- [Relinking Oracle Database Client Binaries After Installation](#)
After an Oracle Database Client installation, if required, you can modify the binaries using the `relink as_installed` option.

Accessing the Installation Software

You can download Oracle Database software from the Oracle Technology Network website or the Oracle Software Delivery Cloud portal. In some cases, Oracle Database software may be available on installation media also.

To install the software from the hard disk, you must either download it and unpack it, or copy it from the installation media, if you have it.

- [Downloading Oracle Software](#)
Select the method you want to use to download the software.
- [Downloading the Installation Archive Files from OTN](#)
Download installation archive files from Oracle Technology Network.

- [Downloading the Software from Oracle Software Delivery Cloud Portal](#)
You can download the software from Oracle Software Delivery Cloud as Media Packs.
- [Copying the Software to the Hard Disk](#)
Oracle recommends that you copy the installation software to the hard disk to enable the installation to run faster.

Downloading Oracle Software

Select the method you want to use to download the software.

You can download the trial version of the installation files from the Oracle Technology Network (OTN) or the Oracle Software Delivery Cloud portal and extract them on your hard disk. Ensure that you review and understand the terms of the license. Most downloads include the development license.

Downloading the Installation Archive Files from OTN

Download installation archive files from Oracle Technology Network.

1. Use any browser to access the software download page from Oracle Technology Network:
<http://www.oracle.com/technetwork/indexes/downloads/index.html>
2. Go to the download page for the product to install.
3. On the download page, identify the required disk space by adding the file sizes for each required file.
The file sizes are listed next to the file names.
4. Select a file system with enough free space to store and expand the archive files.
In most cases, the available disk space must be at least twice the size of all of the archive files.
5. On the file system, create a parent directory for each product (for example, `OraDB18c`) to hold the installation directories.
6. Download all of the installation archive files to the directory you created for the product.
7. Verify that the files you downloaded are the same size as the corresponding files on Oracle Technology Network. Also verify the checksums are the same as noted on Oracle Technology Network using a command similar to the following, where *filename* is the name of the file you downloaded:

```
cksum filename.zip
```
8. Extract the files in each directory that you just created.

Downloading the Software from Oracle Software Delivery Cloud Portal

You can download the software from Oracle Software Delivery Cloud as Media Packs.

A Media Pack is an electronic version of the software that is also available to Oracle customers on CD-ROM or DVD.

1. Use any browser to access the Oracle Software Delivery Cloud portal:

<https://edelivery.oracle.com/>

2. Complete the export validation process by entering information (name, company, email address, and country) in the online form.
3. In the Media Pack Search page, specify the product pack and platform to identify the media pack that you want to download. If you do not know the name of the product pack, then you can search for it using the license list.
4. Optionally, select the relevant product to download from the Results list.
5. In the search results page, click **Readme** to download and review the readme file for download instructions and product information.
6. After you review the readme file, select the media pack that you want to download from the search results to download the individual zip files for the media pack, and follow the Download Notes instructions in this page. After you download and extract the contents of the zip files, you can install the software.

 **Note:**

Print the page with the list of downloadable files. It contains a list of part numbers and their corresponding descriptions that you may refer during the installation process.

7. After you download the files, click **View Digest** to verify that the MD5 or SHA-1 checksum matches the value listed on the media download page.

Copying the Software to the Hard Disk

Oracle recommends that you copy the installation software to the hard disk to enable the installation to run faster.

Before copying the installation media content to the hard disk, you must mount the disk. Review these sections if you need instructions for how to mount the installation media and copy its contents to the hard disk.

- [Mounting Disks on HP-UX Itanium Systems](#)
On most HP-UX systems, the disk mounts automatically when you insert it into the disk drive. If the disk does not mount automatically, then follow these steps to mount it.

Mounting Disks on HP-UX Itanium Systems

On most HP-UX systems, the disk mounts automatically when you insert it into the disk drive. If the disk does not mount automatically, then follow these steps to mount it.

1. If necessary, switch the user to `root`:

```
$ sudo - root
```
2. If necessary, unmount the currently mounted disc, then remove it from the drive:

```
# /usr/sbin/umount /SD_DVD
```

In this example, `/SD_DVD` is the mount point directory for the disc drive.

3. Insert the appropriate disc into the disc drive to mount it:

```
# /usr/sbin/mount -F cdfs -o rr /dev/dsk/cxydz /SD_DVD
```

In this example, `/SD_DVD` is the disc mount point directory and `/dev/dsk/cxydz` is the device name for the disc device, for example `/dev/dsk/c0t2d0`.

4. If Oracle Universal Installer displays the Disk Location dialog box, enter the disc mount point directory path, for example:

```
/SD_DVD
```

About Character Set Selection During Installation

Before you create the database, decide the character set that you want to use.

After a database is created, changing its character set is usually very expensive in terms of time and resources. Such operations may require converting all character data by exporting the whole database and importing it back. Therefore, it is important that you carefully select the database character set at installation time.

Oracle Database uses character sets for the following:

- Data stored in SQL character data types (`CHAR`, `VARCHAR2`, `CLOB`, and `LONG`).
- Identifiers such as table names, column names, and PL/SQL variables.
- Stored SQL and PL/SQL source code, including text literals embedded in this code.

Starting with Oracle Database 12c Release 2 (12.2), the default database character set of a database created from the General Purpose/Transaction Processing or the Data Warehousing template is Unicode `AL32UTF8`.

Unicode is the universal character set that supports most of the currently spoken languages of the world. It also supports many historical scripts (alphabets). Unicode is the native encoding of many technologies, including Java, XML, XHTML, ECMAScript, and LDAP. Unicode is ideally suited for databases supporting the Internet and the global economy.

Because `AL32UTF8` is a multibyte character set, database operations on character data may be slightly slower when compared to single-byte database character sets, such as `WE8ISO8859P1` or `WE8MSWIN1252`. Storage space requirements for text in most languages that use characters outside of the ASCII repertoire are higher in `AL32UTF8` compared to legacy character sets supporting the language. English data may require more space only if stored in `CLOB` (character large object) columns. Storage for non-character data types, such as `NUMBER` or `DATE`, does not depend on a character set. The universality and flexibility of Unicode usually outweighs these additional costs.

Consider legacy character sets only when the database need to support a single group of languages and the use of a legacy character set is critical for fulfilling compatibility, storage, or performance requirements. The database character set to be selected in this case is the character set of most clients connecting to this database.

The database character set of a multitenant container database (CDB) determines which databases can be plugged in later. Ensure that the character set you choose for the CDB is compatible with the database character sets of the databases to be plugged into this CDB. If you use Unicode `AL32UTF8` as your CDB character set, then you can plug in a pluggable database (PDB) in any database character set supported by Oracle Database on Linux.

 **See Also:**

Oracle Database Globalization Support Guide for more information about choosing a database character set for a multitenant container database (CDB)

Running the Installer in a Different Language

Describes how to run the installer in other languages.

Your operating system locale determines the language in which the database installer runs. You can run the installer in one of these languages:

- Brazilian Portuguese (pt_BR)
- French (fr)
- German (de)
- Italian (it)
- Japanese (ja)
- Korean (ko)
- Simplified Chinese (zh_CN)
- Spanish (es)
- Traditional Chinese (zh_TW)

To run the database installer in a supported language, change the locale in which your operating system session is running before you start the installer.

If the selected language is not one of the supported languages, then the installer runs in English.

Installing the Oracle Database Client Software

These topics explain how to run the Setup Wizard to perform most database client installations.

- [Running Setup Wizard to Install Oracle Database Client](#)
Use the `runInstaller` command to start the Oracle Database Client installation.
- [Using Oracle Net Configuration Assistant](#)
Run Oracle Net Configuration Assistant in standalone mode after the Oracle Database Client installation is complete to configure the listener, naming methods, net service names, and directory server usage.

Running Setup Wizard to Install Oracle Database Client

Use the `runInstaller` command to start the Oracle Database Client installation.

Have all the information you need to provide regarding users groups, and storage paths before you start the installation.

Oracle recommends that you have your My Oracle Support credentials available during installation.

During installation, you are asked to run configuration scripts as the `root` user. You can either run these scripts manually as `root` when prompted, or you can provide configuration information and passwords using a root privilege delegation option such as `sudo`.

1. Log in as the Oracle installation owner user account (`oracle`).
2. On the installation media, or where you have downloaded the installation binaries, run the `runInstaller` command to start the Oracle setup wizard.

For example:

- On installation media:

```
/dev/dvd-rw/media/runInstaller
```

- On a hard disk:

```
$ cd /home/oracle_sw/  
$ ./runInstaller
```

 **Note:**

Run the `runInstaller` command from the Oracle home directory only. Do not use the `runInstaller` command that resides at `$ORACLE_HOME/oui/bin/`, or any other location, to install Oracle Database, Oracle Database Client, or Oracle Grid Infrastructure.

3. Select your installation type.

Installation screens vary depending on the installation option you select. Respond to the configuration prompts as needed.

 **Note:**

At any time during installation, if you have a question about what you are being asked to do, click **Help**.

Using Oracle Net Configuration Assistant

Run Oracle Net Configuration Assistant in standalone mode after the Oracle Database Client installation is complete to configure the listener, naming methods, net service names, and directory server usage.

Oracle recommends that you have information ready about the host name of the computer where the Oracle database is installed.

To start Oracle Net Configuration Assistant in standalone mode:

1. Run `netca` from the `$ORACLE_HOME/bin` directory.
2. Respond to the configuration prompts and screens as needed. The screens vary depending on the options you select. At any time during the configuration, if you have a question about what you are being asked to do, click **Help**.

Related Topics

- *Oracle Database Net Services Administrator's Guide*

Relinking Oracle Database Client Binaries After Installation

After an Oracle Database Client installation, if required, you can modify the binaries using the `relink as_installed` option.

For example, you might want to relink the Oracle Database Client binaries every time you apply an operating system patch or after an operating system upgrade.

▲ Caution:

Before relinking executables, you must shut down all executables that run in the Oracle home directory that you are relinking. In addition, shut down applications linked with Oracle shared libraries.

1. Login as the Oracle Database Client owner user (`oracle`).
2. Set the `ORACLE_HOME` environment variable

```
$ ORACLE_HOME=/u01/app/oracle/product/18.0.0/client_1
```
3. Go to the `$ORACLE_HOME/bin` directory:

```
$ cd $ORACLE_HOME/bin
```
4. Run the `relink` script with the `as_installed` option to relink the binaries.

```
$ ./relink as_installed
```

The relinking is complete and the log files are generated under the `$ORACLE_HOME/install` directory.

6

Oracle Database Client Postinstallation Tasks

Complete configuration tasks after you install Oracle Database.

You are required to complete some configuration tasks after Oracle Database Client is installed. In addition, Oracle recommends that you complete additional tasks immediately after installation. You must also complete product-specific configuration tasks before you use those products.

Note:

This chapter describes basic configuration only. Refer to product-specific administration and tuning guides for more detailed configuration and tuning information.

- [Required Postinstallation Tasks](#)
Download and apply required patches for your software release after completing your initial installation.
- [Recommended Postinstallation Tasks](#)
Oracle recommends that you complete these tasks after installation.

Required Postinstallation Tasks

Download and apply required patches for your software release after completing your initial installation.

- [Downloading and Installing Release Update Patches](#)
Download and install Release Updates (RU) and Release Update Revisions (RUR) patches for your Oracle software after you complete installation.

Downloading and Installing Release Update Patches

Download and install Release Updates (RU) and Release Update Revisions (RUR) patches for your Oracle software after you complete installation.

Starting with Oracle Database 18c, Oracle provides quarterly updates in the form of Release Updates (RU) and Release Update Revisions (RUR). Oracle no longer releases patch sets. For more information, see My Oracle Support Note 2285040.1.

Check the My Oracle Support website for required updates for your installation.

1. Use a web browser to view the My Oracle Support website:
<https://support.oracle.com>
2. Log in to My Oracle Support website.

 **Note:**

If you are not a My Oracle Support registered user, then click **Register for My Oracle Support** and register.

3. On the main My Oracle Support page, click **Patches & Updates**.
4. In the **Patch Search** region, select **Product or Family (Advanced)**.
5. On the **Product or Family (Advanced)** display, provide information about the product, release, and platform for which you want to obtain patches, and click **Search**.

The Patch Search pane opens, displaying the results of your search.

6. Select the patch number and click **ReadMe**.

The README page is displayed. It contains information about the patch and how to apply the patches to your installation.

7. Uncompress the Oracle patch updates that you downloaded from My Oracle Support.

 **Note:**

Do not delete or move the `.patch_storage` directory even after you have successfully installed the latest release update or release update revision patch as OPatch stores the patch information in the `$ORACLE_HOME/.patch_storage` directory.

Related Topics

- [My Oracle Support note 2285040.1](#)

Recommended Postinstallation Tasks

Oracle recommends that you complete these tasks after installation.

- [Creating a Backup of the root.sh Script](#)
Oracle recommends that you back up the `root.sh` script after you complete an installation.
- [Setting Language and Locale Preferences for Client Connections](#)
Configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set.

Creating a Backup of the root.sh Script

Oracle recommends that you back up the `root.sh` script after you complete an installation.

If you install other products in the same Oracle home directory subsequent to this installation, then Oracle Universal Installer updates the contents of the existing `root.sh` script during the installation. If you require information contained in the original `root.sh` script, then you can recover it from the backed up `root.sh` file.

Setting Language and Locale Preferences for Client Connections

Configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set.

You must configure client applications connecting to an Oracle Database according to your locale preferences and your I/O device character set. If your applications do not have their own specific methods to configure locale preferences, then the method you use to configure an Oracle database client connection depends on the access API you use to connect to the database. Check your application documentation, before you configure locale preferences for your applications.

For applications that connect to Oracle Databases using Oracle Call Interface (OCI) use `NLS_LANG` and other client settings with names that start with `NLS_` to set the locale conventions and client character set for Oracle Database sessions. It is important that you set the character set part of the `NLS_LANG` value properly. The character set you set must correspond to the character set used by your I/O devices, which in case of Microsoft Windows is either the ANSI Code Page (for GUI applications), such as `WE8MSWIN1252`, or the OEM Code Page (for Console mode applications), such as `US8PC437`. By doing this, the OCI API is notified about the character set of data that it receives from the application. OCI can then convert this data correctly to and from the database character set.

`NLS_LANG` and the other NLS settings can be specified either as environment variables or as Windows Registry settings. Environment variable values take precedence over Registry values.

Oracle Universal Installer sets a default value for the `NLS_LANG` setting in Registry when it creates a new Oracle home. The `NLS_LANG` value is based on the language of the Windows user interface, which is the language of Windows menu items and dialog box labels.

Caution:

Failure to set the client character set correctly can cause data loss.

Java applications that connect to Oracle Databases by using Oracle JDBC do not use `NLS_LANG`. Instead, Oracle JDBC maps the default locale of the Java VM in which the application runs to the Oracle Database language and territory settings. Oracle JDBC then configures the connected database session using these settings. Because Java works internally in Unicode, the client character set is always set to Unicode. Unless an application explicitly changes it, the default locale of the Java VM is set based on the locale of the user operating system on which the Java VM runs. Check your Java VM documentation for information about configuring the Java VM default locale.

 **Note:**

In 3-tier architecture deployments, application servers that are database clients can have settings in their configuration files that specify the NLS_LANG value or the Java VM locale. Check the documentation accompanying these servers.

Related Topics

- *Oracle Database Administrator's Reference for Microsoft Windows*

 **See Also:**

Oracle Database Globalization Support Guide for more information about configuring user locale preferences

7

Removing Oracle Database Software

These topics describe how to remove Oracle software and configuration files.

Use the `deinstall` command that is included in Oracle homes to remove Oracle software. Oracle does not support the removal of individual products or components.

▲ Caution:

If you have a standalone database on a node in a cluster, and if you have multiple databases with the same global database name (GDN), then you cannot use the `deinstall` command to remove one database only.

- [About Oracle Deinstallation Options](#)
You can stop and remove Oracle Database software and components in an Oracle Database home with the `deinstall` command.
- [Oracle Deinstallation \(Deinstall\)](#)
You can run the `deinstall` command from an Oracle home directory after installation.
- [Deinstallation Examples for Oracle Database Client](#)
Use these examples to help you understand how to run the `deinstall` command.

About Oracle Deinstallation Options

You can stop and remove Oracle Database software and components in an Oracle Database home with the `deinstall` command.

You can remove the following software using `deinstall`:

- Oracle Database
- Oracle Grid Infrastructure, which includes Oracle Clusterware and Oracle Automatic Storage Management (Oracle ASM)
- Oracle Real Application Clusters (Oracle RAC)
- Oracle Database Client

The `deinstall` command is available in Oracle home directories after installation. It is located in the `$ORACLE_HOME/deinstall` directory.

`deinstall` creates a response file by using information in the Oracle home and using the information you provide. You can use a response file that you generated previously by running the `deinstall` command using the `-checkonly` option. You can also edit the response file template.

If you run `deinstall` to remove an Oracle Grid Infrastructure installation, then the deinstaller prompts you to run the `deinstall` command as the `root` user. For Oracle Grid Infrastructure for a cluster, the script is `rootcrs.sh`, and for Oracle Grid Infrastructure for a standalone server (Oracle Restart), the script is `roothas.sh`.

 **Note:**

- You must run the `deinstall` command from the same release to remove Oracle software. Do not run the `deinstall` command from a later release to remove Oracle software from an earlier release. For example, do not run the `deinstall` command from the 18c Oracle home to remove Oracle software from an existing 11.2.0.4 Oracle home.
- Starting with Oracle Database 12c Release 1 (12.1.0.2), the `roothas.sh` script replaces the `roothas.pl` script in the Oracle Grid Infrastructure home for Oracle Restart, and the `rootcrs.sh` script replaces the `rootcrs.pl` script in the Grid home for Oracle Grid Infrastructure for a cluster.

If the software in the Oracle home is not running (for example, after an unsuccessful installation), then `deinstall` cannot determine the configuration, and you must provide all the configuration details either interactively or in a response file.

In addition, before you run `deinstall` for Oracle Grid Infrastructure installations:

- Dismount Oracle Automatic Storage Management Cluster File System (Oracle ACFS) and disable Oracle Automatic Storage Management Dynamic Volume Manager (Oracle ADVM).
- If Grid Naming Service (GNS) is in use, then notify your DNS administrator to delete the subdomain entry from the DNS.

Files Deleted by `deinstall`

When you run `deinstall`, if the central inventory (`oraInventory`) contains no other registered homes besides the home that you are deconfiguring and removing, then `deinstall` removes the following files and directory contents in the Oracle base directory of the Oracle Database installation owner:

- `admin`
- `cfgtoollogs`
- `checkpoints`
- `diag`
- `oradata`
- `fast_recovery_area`

Oracle strongly recommends that you configure your installations using an Optimal Flexible Architecture (OFA) configuration, and that you reserve Oracle base and Oracle home paths for exclusive use of Oracle software. If you have any user data in these locations in the Oracle base that is owned by the user account that owns the Oracle software, then `deinstall` deletes this data.

▲ Caution:

`deinstall` deletes Oracle Database configuration files, user data, and fast recovery area (FRA) files even if they are located outside of the Oracle base directory path.

Oracle Deinstallation (Deinstall)

You can run the `deinstall` command from an Oracle home directory after installation.

Purpose

`deinstall` stops Oracle software, and removes Oracle software and configuration files on the operating system for a specific Oracle home.

Syntax

The `deinstall` command uses the following syntax:

```
./deinstall [-silent] [-checkonly] [-paramfile complete path of input response file]
[-params name1=value name2=value . . .]
[-o complete path of directory for saving files]
[-tmpdir complete path of temporary directory to use]
[-logdir complete path of log directory to use] [-help]
```

Parameters

Parameter	Description
<code>-silent</code>	<p>Use this flag to run <code>deinstall</code> in noninteractive mode. This option requires one of the following:</p> <ul style="list-style-type: none"> A working system that it can access to determine the installation and configuration information. The <code>-silent</code> flag does not work with failed installations. A response file that contains the configuration values for the Oracle home that is being deinstalled or deconfigured. <p>You can generate a response file to use or modify by running the <code>deinstall</code> command with the <code>-checkonly</code> flag. <code>deinstall</code> then discovers information from the Oracle home to deinstall and deconfigure. It generates the response file that you can then use with the <code>-silent</code> option.</p> <p>You can also modify the template file <code>deinstall.rsp.tmpl</code>, located in the <code>\$ORACLE_HOME/deinstall/response</code> directory.</p>

Parameter	Description
<code>-checkonly</code>	Use this flag to check the status of the Oracle software home configuration. Running <code>deinstall</code> with the <code>-checkonly</code> flag does not remove the Oracle configuration. The <code>-checkonly</code> flag generates a response file that you can use with the <code>deinstall</code> command and <code>-silent</code> option.
<code>-paramfile</code> <i>complete path of input response file</i>	Use this flag to run <code>deinstall</code> with a response file in a location other than the default. When you use this flag, provide the complete path where the response file is located. The default location of the response file is <code>\$ORACLE_HOME/deinstall/response</code> .
<code>-params</code> [<i>name1=value name2=value name3=value . . .</i>]	Use this flag with a response file to override one or more values to change in a response file you have created.
<code>-o</code> <i>complete path of directory for saving response files</i>	Use this flag to provide a path other than the default location where the response file (<code>deinstall.rsp.tmpl</code>) is saved. The default location of the response file is <code>\$ORACLE_HOME/deinstall/response</code> .
<code>-tmpdir</code> <i>complete path of temporary directory to use</i>	Use this flag to specify a non-default location where <code>deinstall</code> writes the temporary files for the deinstallation.
<code>-logdir</code> <i>complete path of log directory to use</i>	Use this flag to specify a non-default location where <code>deinstall</code> writes the log files for the deinstallation.
<code>-local</code>	Use this flag on a multinode environment to deinstall Oracle software in a cluster. When you run <code>deinstall</code> with this flag, it deconfigures and deinstalls the Oracle software on the local node (the node where <code>deinstall</code> is run). On remote nodes, it deconfigures Oracle software, but does not deinstall the Oracle software.
<code>-help</code>	Use this option to obtain additional information about the command option flags.

Deinstallation Examples for Oracle Database Client

Use these examples to help you understand how to run the `deinstall` command.

You can run `deinstall` from the `$ORACLE_HOME/deinstall` directory. The deinstallation starts without prompting you for the Oracle home path.

```
$ ./deinstall
```

If you have a response file, then use the optional flag `-paramfile` to provide a path to the response file.

You can generate a deinstallation response file by running the `deinstall` command with the `-checkonly` flag. Alternatively, you can use the response file template located at `$ORACLE_HOME/deinstall/response/deinstall.rsp.tmpl`.

In the following example, the `deinstall` command is in the path `/u01/app/oracle/product/18.0.0/client_1/deinstall`. It uses a response file called `my_db_paramfile.tmpl` in the software owner location `/home/usr/oracle`:

```
$ cd /u01/app/oracle/product/18.0.0/client_1/deinstall
$ ./deinstall -paramfile /home/usr/oracle/my_db_paramfile.tmpl
```

A

Installing and Configuring Oracle Database Using Response Files

Review the following topics to install and configure Oracle products using response files.

- [How Response Files Work](#)
Response files can assist you with installing an Oracle product multiple times on multiple computers.
- [Reasons for Using Silent Mode or Response File Mode](#)
Review this section for use cases for running the installer in silent mode or response file mode.
- [Using Response Files](#)
Review this information to use response files.
- [Preparing Response Files](#)
Review this information to prepare response files for use during silent mode or response file mode installations.
- [Running Oracle Universal Installer Using a Response File](#)
After creating the response file, run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation.

How Response Files Work

Response files can assist you with installing an Oracle product multiple times on multiple computers.

When you start Oracle Universal Installer (OUI), you can use a response file to automate the installation and configuration of Oracle software, either fully or partially. OUI uses the values contained in the response file to provide answers to some or all installation prompts.

Typically, the installer runs in interactive mode, which means that it prompts you to provide information in graphical user interface (GUI) screens. When you use response files to provide this information, you run the installer from a command prompt using either of the following modes:

- **Silent mode**
If you include responses for all of the prompts in the response file and specify the `-silent` option when starting the installer, then it runs in silent mode. During a silent mode installation, the installer does not display any screens. Instead, it displays progress information in the terminal that you used to start it.
- **Response file mode**
If you include responses for some or all of the prompts in the response file and omit the `-silent` option, then the installer runs in response file mode. During a response file mode installation, the installer displays all the screens, screens for

which you specify information in the response file, and also screens for which you did not specify the required information in the response file.

You define the settings for a silent or response file installation by entering values for the variables listed in the response file. For example, to specify the Oracle home name, provide the Oracle home path for the `ORACLE_HOME` environment variable:

```
ORACLE_HOME=/u01/app/oracle/product/18.0.0/dbhome_1
```

Reasons for Using Silent Mode or Response File Mode

Review this section for use cases for running the installer in silent mode or response file mode.

Mode	Uses
Silent	<p>Use silent mode for the following installations:</p> <ul style="list-style-type: none"> Complete an unattended installation, which you schedule using operating system utilities such as <code>at</code>. Complete several similar installations on multiple systems without user interaction. Install the software on a system that does not have X Window System software installed on it. <p>The installer displays progress information on the terminal that you used to start it, but it does not display any of the installer screens.</p>
Response file	Use response file mode to complete similar Oracle software installations on more than one system, providing default answers to some, but not all of the installer prompts.

Using Response Files

Review this information to use response files.

Use the following general steps to install and configure Oracle products using the installer in silent or response file mode:



Note:

You must complete all required preinstallation tasks on a system before running the installer in silent or response file mode.

1. Prepare a response file.
2. Run the installer in silent or response file mode.
3. Run the root scripts as prompted by Oracle Universal Installer.
4. If you completed a software-only installation, then run Net Configuration Assistant and Oracle DBCA in silent or response file mode to create the database listener and an Oracle Database instance respectively.

Preparing Response Files

Review this information to prepare response files for use during silent mode or response file mode installations.

- [Editing a Response File Template](#)
For Oracle Database Client, response files are located in the `$ORACLE_HOME/response` directory.
- [Recording Response Files](#)
You can use Oracle Universal Installer (OUI) in interactive mode to record response files, which you can then edit and use to complete silent mode or response file mode installations.

Editing a Response File Template

For Oracle Database Client, response files are located in the `$ORACLE_HOME/response` directory.

All response file templates contain comment entries, sample formats, examples, and other useful instructions. Please read these instructions as they help you specify values for the variables listed in the response files and customize your installation.

The following table lists the response files provided with this software:

Table A-1 Response Files for Oracle Database Client

Response File	Description
<code>client_install.rsp</code>	Silent installation of Oracle Database Client
<code>netca.rsp</code>	Silent configuration of Oracle Net using Oracle Net Configuration Assistant.

Caution:

When you modify a response file template and save a file for use, the response file may contain plain text passwords. Ownership of the response file should be given to the Oracle software installation owner only, and permissions on the response file should be changed to 600. Oracle strongly recommends that database administrators or other administrators delete or secure response files when they are not in use.

To copy and modify a response file:

1. Copy the response file from the response file directory to a directory on your system:

```
$ cp /directory_path/inventory/response/response_file.rsp local_directory
```

In this example, `directory_path` is the path of the directory where you have copied the installation binaries.

2. Open the response file in a text editor:

```
$ vi /local_dir/response_file.rsp
```

3. Follow the instructions in the file to edit it.

 **Note:**

The installer or configuration assistant fails if you do not correctly configure the response file. Also, ensure that your response file name has the `.rsp` suffix.

4. Secure the response file by changing the permissions on the file to 600:

```
$ chmod 600 /local_dir/response_file.rsp
```

Ensure that only the Oracle software owner user can view or modify response files or consider deleting them after the installation succeeds.

 **Note:**

A fully-specified response file for an Oracle Database Client installation contains the passwords for database administrative accounts and for a user who is a member of the OSDBA group (required for automated backups).

Related Topics

- [Oracle Universal Installer User's Guide](#)

Recording Response Files

You can use Oracle Universal Installer (OUI) in interactive mode to record response files, which you can then edit and use to complete silent mode or response file mode installations.

You can save all the installation steps into a response file during installation by clicking **Save Response File** on the Summary page. You can use the generated response file for a silent installation later.

When you record the response file, you can either complete the installation, or you can exit from the installer on the Summary page, before OUI starts to set up the software to the system.

If you use record mode during a response file mode installation, then the installer records the variable values that were specified in the original source response file into the new response file.

 **Note:**

OUI does not save passwords while recording the response file.

To record a response file:

1. Complete preinstallation tasks for an Oracle Database Client installation.

When you run the installer to record a response file, it checks the system to verify that it meets the requirements to install the software. For this reason, Oracle recommends that you complete all of the required preinstallation tasks and record the response file while completing an installation.

2. Ensure that the Oracle software owner user (typically `oracle`) has permissions to create or write to the Oracle home path that you will specify when you run the installer.
3. On each installation screen, specify the required information.
4. When OUI displays the Summary screen, perform the following steps:
 - a. Click **Save Response File**. In the window, specify a file name and location for the new response file. Click Save to write the responses you entered to the response file.
 - b. Click **Finish** to continue with the installation.

Click **Cancel** if you do not want to continue with the installation. The installation stops, but the recorded response file is retained.

 **Note:**

Ensure that your response file name has the `.rsp` suffix.

5. Before you use the saved response file on another system, edit the file and make any required changes. Use the instructions in the file as a guide when editing it.

Running Oracle Universal Installer Using a Response File

After creating the response file, run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation.

Run Oracle Universal Installer at the command line, specifying the response file you created. The Oracle Universal Installer executable, `runInstaller`, provides several options. For help information on the full set of these options, run the `runInstaller` command with the `-help` option. For example:

```
$ directory_path/runInstaller -help
```

The help information appears in a window after some time.

To run the installer using a response file:

1. Complete the preinstallation tasks as for a normal installation
2. Log in as the software installation owner user.
3. If you are completing a response file mode installation, then set the operating system `DISPLAY` environment variable for the user running the installation.

 **Note:**

You do not have to set the `DISPLAY` environment variable if you are completing a silent mode installation.

4. To start the installer in silent or response file mode, enter a command similar to the following:

```
$ /directory_path/runInstaller [-silent] [-noconfig] \  
-responseFile responsefilename
```

 **Note:**

Do not specify a relative path to the response file. If you specify a relative path, then the installer fails.

In this example:

- `directory_path` is the path of the directory where you have copied the installation binaries.
 - `-silent` runs the installer in silent mode.
 - `-noconfig` suppresses running the configuration assistants during installation, and a software-only installation is performed instead.
 - `responsefilename` is the full path and file name of the installation response file that you configured.
5. If this is the first time you are installing Oracle software on your system, then Oracle Universal Installer prompts you to run the `oraInstRoot.sh` script.

Log in as the `root` user and run the `oraInstRoot.sh` script:

```
$ su root  
password:  
# /u01/app/oraInventory/oraInstRoot.sh
```

 **Note:**

You do not have to manually create the `oraInst.loc` file. Running the `oraInstRoot.sh` script is sufficient as it specifies the location of the Oracle Inventory directory.

6. When the installation completes, log in as the `root` user and run the `root.sh` script. For example

```
$ su root  
password:  
# /oracle_home_path/root.sh
```


Index

Numerics

32-bit client software, [1-5](#)

B

Bash shell

 default user startup file, [4-5](#)

bash_profile file, [4-5](#)

Bourne shell

 default user startup file, [4-5](#)

C

C shell

 default user startup file, [4-5](#)

CDBs

 character sets, [5-4](#)

central inventory

 See Oracle inventory directory

character sets, [5-4](#)

checklists

 and installation planning, [1-1](#)

command syntax conventions, [viii](#)

commands

 /usr/sbin/swapinfo, [2-2](#)

 bdf, [2-2](#)

 grep -i Memory, [2-2](#)

 kctune, [2-2](#)

 root.sh, [6-2](#)

 umask, [4-4](#)

 useradd, [4-4](#)

cron jobs, [1-5](#)

D

dbca.rsp file, [A-3](#)

default file mode creation mask

 setting, [4-4](#)

deinstall, [7-1](#)

 See also removing Oracle software

deinstall command, [7-1](#)

deinstallation, [7-1](#)

 examples, [7-4](#)

df command, [4-5](#)

disks

 mounting, [5-3](#)

display variable, [1-4](#)

E

enterprise.rsp file, [A-3](#)

environment variables

 ORACLE_BASE, [4-5](#)

 ORACLE_HOME, [4-5](#)

 ORACLE_SID, [4-5](#)

 removing from shell startup file, [4-5](#)

 SHELL, [4-5](#)

 TEMP and TMPDIR, [4-5](#)

errors

 X11 forwarding, [4-7](#)

F

file mode creation mask

 setting, [4-4](#)

files

 bash_profile, [4-5](#)

 dbca.rsp, [A-3](#)

 editing shell startup file, [4-5](#)

 enterprise.rsp, [A-3](#)

 login, [4-5](#)

 profile, [4-5](#)

 response files, [A-3](#)

filesets, [3-2](#)

G

globalization, [1-5](#)

 localization for client connections, [6-3](#)

 NLS_LANG

 and client connections, [6-3](#)

groups

 creating an Oracle Inventory Group, [4-2](#)

 OINSTALL group, [1-2](#)

H

hardware requirements, [1-1](#)
 display, [1-1](#)

I

installation
 accessing installation software, [5-1](#)
 response files, [A-3](#)
 preparing, [A-3](#), [A-4](#)
 templates, [A-3](#)
 silent mode, [A-6](#)
 installation planning, [1-1](#)
 installation software, accessing, [5-1](#)
 installer
 supported languages, [5-5](#)

J

JDK requirements, [3-2](#)

K

Korn shell
 default user startup file, [4-5](#)

L

licensing, [1-5](#)
 login file, [4-5](#)

M

mask
 setting default file mode creation mask, [4-4](#)
 mixed binaries, [3-2](#)
 mode
 setting default file mode creation mask, [4-4](#)
 multitenant container database
 character sets, [5-4](#)

N

netca.rsp file, [A-3](#)
 noninteractive mode
 See response file mode

O

oinstall group
 creating, [4-2](#)
 OINSTALL group1, [1-4](#)
 See also Oracle Inventory directory

operating system
 different on cluster members, [3-2](#)
 requirements, [3-2](#)
 operating system privileges groups, [1-4](#)
 operating system requirements, [1-2](#)
 ORAchk
 and Upgrade Readiness Assessment, [1-5](#)
 Oracle Database Client
 installation, [5-1](#)
 Oracle Database Client, installation, [5-5](#)
 Oracle Database Client, relinking, [5-7](#)
 Oracle Database Configuration Assistant
 response file, [A-3](#)
 Oracle home
 ASCII path restriction for, [1-2](#)
 Oracle Inventory, [1-4](#)
 identifying existing, [4-2](#)
 Oracle Net Configuration Assistant
 response file, [A-3](#)
 Oracle Net Configuration Assistant, installation,
 [5-6](#)
 Oracle Software Owner user
 creating, [4-3](#), [4-4](#)
 Oracle Software Owner users
 determining default shell, [4-5](#)
 Oracle Universal Installer
 response files
 list of, [A-3](#)
 oracle user, [1-4](#)
 creating, [4-3](#)
 Oracle user
 determining default shell, [4-5](#)
 ORACLE_BASE environment variable
 removing from shell startup file, [4-5](#)
 ORACLE_HOME environment variable
 removing from shell startup file, [4-5](#)
 ORACLE_SID environment variable
 removing from shell startup file, [4-5](#)
 OSDBA, [1-4](#)
 OTN website
 downloading installation software from, [5-2](#)

P

patch updates, [6-1](#)
 postinstallation
 recommended tasks
 root.sh script, backing up, [6-2](#)
 profile file, [4-5](#)

R

release update revisions, [6-1](#)
 release updates, [6-1](#)

removing Oracle software, [7-1](#)
 examples, [7-4](#)
 response file installation
 preparing, [A-3](#)
 response files
 templates, [A-3](#)
 silent mode, [A-6](#)
 response file mode, [A-1](#)
 about, [A-1](#)
 reasons for using, [A-2](#)
 See also response files, silent mode
 response files, [A-1](#)
 about, [A-1](#)
 creating with template, [A-3](#)
 dbca.rsp, [A-3](#)
 enterprise.rsp, [A-3](#)
 general procedure, [A-2](#)
 netca.rsp, [A-3](#)
 passing values at command line, [A-1](#)
 specifying with Oracle Universal Installer, [A-5](#)
 See also silent mode.
 root user
 logging in as, [2-1](#)
 root.sh script
 backing up, [6-2](#)
 rootcrs.sh, [7-1](#)
 roothas.sh, [7-1](#)

S

shell
 determining default shell for Oracle user, [4-5](#)
 SHELL environment variable
 checking value of, [4-5](#)
 shell startup file
 editing, [4-5](#)
 removing environment variables, [4-5](#)
 silent mode
 about, [A-1](#)
 reasons for using, [A-2](#)
 silent mode installation, [A-6](#)
 software requirements, [3-2](#)
 ssh
 and X11 Forwarding, [4-7](#)
 startup file
 for shell, [4-5](#)
 supported languages
 installer, [5-5](#)
 swap space
 allocation, [1-2](#)

swap space (*continued*)
 system requirements, [1-1](#)

T

TEMP environment variable
 commands
 env, [4-5](#)
 env command, [4-5](#)
 environment
 checking settings, [4-5](#)
 setting, [4-5](#)
 umask, [4-5](#)
 umask command, [4-5](#)
 TMPDIR environment variable
 setting, [4-5](#)
 troubleshooting
 cron jobs and installation, [1-5](#)
 disk space errors, [1-2](#)
 environment path errors, [1-2](#)
 installation owner environment variables and
 installation errors, [4-8](#)
 unset environment variables, [1-2](#)
 typographic conventions, [ix](#)

U

umask command, [4-4](#)
 uninstall
 See removing Oracle software
 UNIX commands
 xhost, [2-1](#)
 UNIX workstation
 installing from, [2-1](#)
 unset installation owners environment variables,
[4-8](#)
 upgrading
 and ORAchk Upgrade Readiness
 Assessment, [1-5](#)
 useradd command, [4-4](#)
 users
 creating the oracle user, [4-3](#)

X

X Window System
 enabling remote hosts, [2-1](#)
 X11 forwarding errors, [4-7](#)
 xhost command, [2-1](#)