# Oracle® Communications Billing and Revenue Management Moving Accounts Between Database Schemas



Release 15.1 F93201-01 April 2025

ORACLE

Oracle Communications Billing and Revenue Management Moving Accounts Between Database Schemas, Release 15.1

F93201-01

Copyright © 2017, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

### Contents

#### Preface

Audience	vii
Documentation Accessibility	vii
Diversity and Inclusion	vii

#### 1 Understanding Account Migration

About Account Migration	1-1
About the AMM Application	1-1
AMM Process Overview	1-2
About the Account Search Configuration File	1-3
About the pin_amt Utility	1-3
About the AMM Controller	1-4
How AMM Controller Processes Batches with Nongroup Members	1-4
How AMM Controller Processes Batches with Account Group Members	1-5
About the AMM Mover	1-5
About Distributed Transactions	1-6
About Using Multiple AMM Controllers	1-7
Account Migration Performance	1-7

### 2 Migrating Hierarchical and Sharing Accounts

About Migrating Hierarchical and Sharing Accounts	2-1
About Searching for Member and Nongroup Member Accounts	2-1
About Account Groups	2-2
About Migrating Account Groups	2-2

### 3 Account Migration Restrictions

Account Activity Prevented during Account Migration	3-1
Do Not Rerate Events during Account Migration	3-1
Do Not Alter Account Group Members	3-1
Migration Prevented during Account Activity	3-2
Unique POIDs Required across All Database Schemas	3-2

Transient Objects Are Not Migrated	3-2
Some Client Applications May Fail during Account Migration	3-2
AMM Does Not Support LDAP Manager	3-3
Using BRM Reports after Migration	3-3

### 4 Installing and Configuring BRM for Account Migration

System Requirements	4-1
General Software Requirements	4-1
Software Requirements for Account Migration Manager	4-1
Installing AMM	4-2
Configuring All Primary and Secondary Database Schemas	4-2
Installing the AMM Software on the Primary Installation Machine	4-4
Configuring Your Oracle DM to Check for Invalid Objects	4-4
Connecting AMM to Your Database Schemas	4-5
Configuring Database and AMM Mover Information for Multischema Systems	4-5
Configuring AMM Controller Definitions	4-6
Specifying Schema Alias Information for Multischema Systems	4-6
AMM Infranet.properties File Parameters	4-7
Configuring AMM for Additional Database Schemas	4-8
Configuring AMM for New Custom Tables	4-9
Tuning Your Database for Optimal Account Migration Performance	4-9

### 5 Using Account Migration Manager

Overview of Account Migration Tasks	5-1
Creating the Account Search Configuration File	5-2
Sample Account Search Configuration File	5-4
Submitting the Account Search File	5-4
Enabling Migration Jobs in the Queue	5-5
Starting the AMM Controller	5-5
Monitoring the AMM Controller	5-6
Checking the AMM Controller Status	5-6
Checking the AMM Controller Log File	5-6
Monitoring the AMM Controller in Real Time	5-6
Monitoring Account Migration	5-6
Monitoring Job Status	5-7
Checking Job Details	5-7
Checking Account Group Details	5-8
Handling Account Migration Failures	5-8
Finding Debugging Information	5-9
Reprocessing Failed Batches	5-9



Purging Migrated Objects from the Source Database Schema	5-9
Deleting Jobs from the Source Database Schema	5-9
Stopping the AMM Controller	5-10
Pausing and Resuming Account Migration	5-10
Automating Account Migration	5-11

#### 6 Modifying Applications to Work with AMM

Enabling ECE to Rate Events during Account Migration	6-1
Configuring ECE to Use the AMM Acknowledgment Queue	6-2
Modifying Custom Client Applications for AMM	6-3
Modifying Custom BRM Reports for AMM	6-4
AMM Return Codes and Messages	6-4

#### 7 Modifying the Account Migration Manager

Creating Custom Account Search Criteria	7-1
Creating a Search Template	7-1
Sample Search Template	7-2
Adding New Entries to the Account Search Configuration File	7-2
Sample Account Search Configuration File	7-2
Implementing and Compiling the Conversion Interface	7-3
Sample Class Implementing Conversion Interface	7-3
Verifying Your Search Criteria	7-3
Verifying That the Search Criteria Creates Valid SQL Statements	7-4
Verifying That the Search Criteria Finds Correct Accounts	7-4

#### 8 Account Migration Utilities

pin_amt	8-1
pin_amt_test	8-3

### A AMM Job Management Tables

About AMM Job Management Tables A-2
-------------------------------------

#### B Account Migration Flags

About Job Status Flags	B-1
About Batch Status Flags	B-1
About Group Status Flags	B-2
About Group Status Flags	в-1 В-2



### C AMM Entity Relationship Diagram

AMM Entity Relationship Diagram

C-1



### Preface

This book describes how to move accounts between BRM database schemas. You move accounts to balance the number of accounts between schemas.

### Audience

This book is for system administrators and operations personnel.

### **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

#### Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

### **Diversity and Inclusion**

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.



# 1 Understanding Account Migration

Learn about account migration which is the process of transferring data associated with selected accounts from the source database schema to a destination schema. In Oracle Communications Billing and Revenue Management (BRM) you use Account Migration Manager (AMM) to migrate accounts.

Topics in this document:

- About Account Migration
- About the AMM Application
- AMM Process Overview
- About Distributed Transactions
- About Using Multiple AMM Controllers
- Account Migration Performance

### About Account Migration

Account migration is the process of transferring data associated with selected accounts from the data's source database schema to a destination schema.

You use the AMM application to perform all account migration tasks. You provide information on the accounts to migrate and how to access the source and destination database schemas. See "About the AMM Application".

You migrate account objects to redistribute the data in the following situations:

- One BRM database schema contains significantly more or fewer accounts than other BRM database schemas (for example, when you add a schema to an existing multischema system).
- The number of events per account is significantly greater in one schema than another.
- The time it takes to complete a billing run becomes erratic.

You achieve optimal migration performance and the smallest impact on your operations if you schedule migrations for maintenance windows. If you need to migrate a large number of accounts, but your maintenance window is only a couple of hours, you can perform migrations over several days. The AMM software processes jobs in stages, enabling you to pause and resume account migration without affecting database integrity.

For information on scheduling migration, see "Automating Account Migration".

### About the AMM Application

AMM is an application that migrates accounts and their associated objects from a source schema in a BRM database to a destination schema in the same database.

The AMM software migrates accounts based on the information you provide in the account search configuration file for that migration task. In this file, you specify a group of accounts to



migrate based on specific criteria, such as account creation date or account status. The accounts and associated objects that meet these criteria form a *job*.

Jobs are processed by the AMM software through a queue system, with each job processed in the order received. To improve migration performance, AMM subdivides jobs into *batches* containing a configurable number of accounts.

Batches are assigned to a configurable number of threads, which process the batches in parallel. Each batch is migrated in a single distributed transaction, during which activity is prevented on the accounts in the batch. Depending on the success of the batch migration, changes to the database are either committed or rolled back.

The AMM software does not automatically remove migrated objects from the source database schema for performance reasons. Instead, it flags the migrated objects as *invalid* to prevent BRM applications from accessing them. You can use the AMM software to purge invalid objects from the database at any time.

#### AMM Process Overview

Figure 1-1 shows the AMM process overview.



#### Figure 1-1 AMM Process Overview

The account migration process can be divided into the following stages:

- The account search configuration file containing information on the accounts to migrate and access information for the source and destination database schemas is provided as input to the pin\_amt utility. See "About the Account Search Configuration File".
- 2. The **pin\_amt** utility processes the account search configuration file.
- 3. Every account to be migrated is set up as an individual job. The jobs are divided into batches and placed in the queue. See "About the pin\_amt Utility".
- 4. The AMM Controller allocates batches to threads and passes batches to the AMM Mover. See "About the AMM Controller".
- 5. The AMM Mover migrates the batch of accounts by moving the associated data from the source schema to the destination schema. See "About the AMM Mover".



### About the Account Search Configuration File

The account search configuration file provides the details on which accounts to migrate, their source and destination storage locations, and the size of each batch.

You can also migrate accounts based on custom criteria. See "Creating Custom Account Search Criteria".

### About the pin\_amt Utility

The **pin\_amt** utility is a standalone utility that generates account migration jobs for the AMM Controller to process. This utility can perform all its functions, such as finding accounts to migrate and submitting and enabling jobs, whether the AMM Controller is online or offline.

You use the pin\_amt utility to perform the following tasks:

- Start, stop, resume, and monitor the AMM Controller
- Find all accounts in the source database schema that meet your search criteria
- Enable account migration jobs in the queue
- Delete jobs from the job management tables
- Purge invalid objects from the source schema

When you submit an account search configuration file, the pin\_amt utility does the following:

- 1. Searches the source database schema for all accounts that meet the criteria in the account search configuration file, excluding all accounts that are part of hierarchical and sharing groups.
- 2. Divides the list of account POIDs into batches.
- 3. Populates the job management tables in the primary, source, and destination schemas with the list of account POIDs to migrate. See "AMM Job Management Tables".
- 4. Determines whether group migration is enabled.
  - If group migration is enabled, pin\_amt proceeds with steps 5 through 10.
  - If group migration is disabled, the account search is complete. The AMM Controller can begin processing the job when the job is enabled in the queue. See "About the AMM Controller".
- 5. Searches all hierarchical accounts and sharing groups in the source schema for accounts that meet the search criteria.
- 6. Determines whether to search for and exclude accounts belonging to cross-schema sharing groups from migration.
  - When cross-schema sharing groups are disabled, pin\_amt does not search for crossschema sharing group members.
  - When cross-schema sharing groups are enabled, **pin\_amt** finds accounts that are members of cross-schema sharing groups and excludes them from migration.



#### Note:

AMM performs a check on an account and only its immediate child account. Ensure you perform extra validation to ensure accounts picked by AMM are not part of a cross-schema sharing group.

- 7. When an account meets the search criteria, **pin\_amt** finds all other accounts related to it and organizes them into an account group.
- 8. Determines whether the size of the account group exceeds the maximum. If it does, AMM excludes the account group from the job.

#### Note:

You specify the maximum size of an account group by using the account search configuration file. See "Creating the Account Search Configuration File".

- 9. Divides all members of one account group into batches. All batches in the group are assigned the same group ID and flagged as containing account group members.
- **10.** Populates the job management tables in the primary, source, and destination schemas with the list of account POIDs to migrate. See "AMM Job Management Tables".

#### About the AMM Controller

The AMM Controller is a server process that checks the queue for jobs to process. By default, your system contains one AMM Controller, which processes one job at a time. For information about using multiple AMM Controllers, see "About Using Multiple AMM Controllers".

The AMM Controller processes group member and nongroup member batches in different ways:

- How AMM Controller Processes Batches with Nongroup Members
- How AMM Controller Processes Batches with Account Group Members

#### How AMM Controller Processes Batches with Nongroup Members

When processing batches that contain nongroup members, the AMM Controller does the following:

- Assigns batches to threads, which run in parallel. Each thread processes one batch at a time. If there are more batches than threads, each thread must process multiple batches in sequence. You use a configuration file to configure the number of AMM Controller threads. See "Connecting AMM to Your Database Schemas".
- 2. Changes the batch status to IN\_PROGRESS. See "About Batch Status Flags".
- 3. Passes the job ID, batch number, and schema qualifications to the AMM Mover on the destination database schema for processing. See "About the AMM Mover".
- Determines whether the AMM Mover successfully migrated accounts.
  - If migration is successful, the AMM Controller commits the changes to all database schemas and changes the batch status to FINISHED. See "About Batch Status Flags".



 If migration fails, the AMM Controller rolls back the changes and updates the batch status to FAILED. See "About Batch Status Flags".

#### How AMM Controller Processes Batches with Account Group Members

When processing batches that contain account group members, the AMM Controller does the following:

- 1. Changes the account group status to GROUP\_DISABLING. See "About Group Status Flags".
- 2. Locks the appropriate base table records in the source database schema so that applications cannot access group member accounts during migration.
- 3. Marks all account group members in the source schema as invalid.
- 4. Determines whether all account group members were disabled in the source schema.
  - If all accounts were successfully disabled, the AMM Controller changes the account group status to GROUP\_READY. See "About Group Status Flags".
  - If any accounts were not disabled, the AMM Controller changes the account group status to FAILED. See "About Group Status Flags".
- 5. Changes the account group status to GROUP\_IN\_PROGRESS.
- 6. Passes individual batches in the account group to the AMM Mover for processing.
  - a. Assigns an individual batch in the group to a thread.
  - b. Changes the batch status to IN\_PROGRESS.
  - c. Passes the job ID, batch number, and schema qualifications to the AMM Mover. See "About the AMM Mover".
  - d. Determines whether the AMM Mover successfully migrated the batch and sets the batch status to FINISHED or FAILED.
- 7. Determines whether all batches in the account group migrated successfully.
  - If all batches migrated successfully, the AMM Controller enables all account group members in the destination database schema and changes the account group status to GROUP\_FINISHED. See "About Group Status Flags".
  - If any batch failed to migrate, the AMM Controller changes the account group status to GROUP\_FAILED. See "About Group Status Flags".

#### Note:

When an account group fails to migrate, all its accounts remain disabled in the source and destination schemas. You must fix the error and migrate the job again before your BRM system can access the accounts.

#### About the AMM Mover

The AMM Mover is the process that actually moves accounts from one database schema to another. Each schema contains at least one AMM Mover.



### Note: The AMM Mover performs the following functions regardless of whether a batch contains group-member or nongroup member accounts.

When the AMM Mover receives a batch, it does the following:

- 1. Locks the appropriate base table records in the source database schema so that applications cannot access accounts during migration.
- 2. Migrates the objects for an account batch from the source schema to the destination schema in a single distributed transaction. See "About Distributed Transactions".
- 3. Marks all migrated objects in the source schema as invalid.
- 4. Updates the account POIDs in the uniqueness table to reflect the account's new location. For example, if an account is migrated from schema 0.0.0.1 to schema 0.0.0.2, the account POID changes from 0.0.0.1 /account 2286 0 to 0.0.0.2 /account 2286 0.

### **About Distributed Transactions**

The AMM software migrates each batch of accounts as a single distributed transaction by using schema qualifications. This means that changes can be made to the primary, source, and destination database schemas and then committed or rolled back in one transaction, ensuring the integrity of the database.

Figure 1-2 shows the schema qualifications for a multischema system with three database schemas, one AMM Controller, and two threads:



#### Figure 1-2 AMM Database Schema Connections

### About Using Multiple AMM Controllers

#### Note:

Implementing multiple AMM Controllers is for advanced users only. Use multiple AMM Controllers only if you understand the impact on migration performance.

Using multiple AMM Controllers enables you to process multiple account migration jobs in parallel. However, you receive performance improvements only in the following situations:

- Your system contains more than three database schemas.
- No two migration jobs use the same schema at the same time.

When multiple jobs use the same schema, as shown in Figure 1-3, migration performance degrades significantly.





For more information, contact your Oracle BRM representative.

### Account Migration Performance

Account migration is resource intensive and can overload your BRM system.

Signs that your system is overloaded during account migration:

- Batch processing times steadily increase, without returning to their initial processing times.
- The AMM software is processing fewer than five accounts per second.
- You receive a distributed transaction time-out error (Oracle error 2049).
- There are a high number of waits for undo segment extension and latch free operations.

If your system exhibits any of these signs, you need to tune your Oracle database. For guidelines, see "Tuning Your Database for Optimal Account Migration Performance" or contact your Oracle BRM representative.



# 2 Migrating Hierarchical and Sharing Accounts

Learn how to migrate hierarchical and sharing groups from one database schema to another in Oracle Communications Billing and Revenue Management (BRM).

Topics in this document:

- About Migrating Hierarchical and Sharing Accounts
- About Searching for Member and Nongroup Member Accounts
- About Account Groups
- About Migrating Account Groups

### About Migrating Hierarchical and Sharing Accounts

You can configure AMM to migrate hierarchical account groups and charge and discount sharing groups from a source BRM database schema to a destination schema. In this configuration, AMM does the following:

- Searches for accounts in two phases. See "About Searching for Member and Nongroup Member Accounts".
- Organizes accounts that meet the search criteria by account group. See "About Account Groups".
- Migrates entire account groups. See "About Migrating Account Groups".

By default, group migration is disabled. You specify whether to migrate account groups by using the **migration\_mode** entry in the account search file (*BRM\_homelapps/amt/* **account\_search.cfg**). See "Creating the Account Search Configuration File".

#### Note:

When you enable group migration, you must perform extra verification steps to prevent accounts from being severed from their associated account group. See "Checking Account Group Details".

### About Searching for Member and Nongroup Member Accounts

When you enable group migration, AMM searches for accounts as follows:

- 1. AMM searches for nongroup member accounts only. That is, AMM excludes all hierarchical and sharing group accounts from the account search. Accounts meeting the search criteria are divided into batches, and each batch is flagged as containing nongroup member accounts only.
- AMM searches for accounts belonging to hierarchical and sharing groups only. If an
  account meets the search criteria, AMM finds all other account members that are related to



the account. These accounts are organized into an *account group*. See "About Account Groups".

Each account group is divided into batches, which are assigned an account group ID and flagged as containing account group members.

#### Note:

You can configure AMM to exclude from migration any accounts belonging to a cross-schema sharing group, which means that members can reside in multiple database schemas. To do so, set the **cross\_schema\_group** parameter to **true** in the account search file. See "Creating the Account Search Configuration File".

All accounts meeting the search criteria, both group member and nongroup member accounts, still form one job.

#### About Account Groups

An account group consists of all account members that are related to a specific account. When AMM finds an account that meets the search criteria, it finds the parent account and all other child accounts in the group. If one of the accounts is also a member of another group, it finds all members of the other group as well.



#### Figure 2-1 One Account Group

For example, in Figure 2-1, account A meets the search criteria. Because account A is a child in a hierarchical account group, AMM finds the parent account and all child accounts in that group. Because one hierarchical account member is also a member of a charge sharing group, AMM finds all accounts in the charge sharing group as well. In this example, the account group consists of all accounts in the hierarchical account group and the charge sharing group.

### About Migrating Account Groups

AMM migrates account group member and nongroup member batches in different ways:

ORACLE

- **Batches containing nongroup members in one transaction.** During migration, AMM disables all accounts that belong to a single batch.
  - If the batch migrates successfully, AMM commits the changes to all database schemas and enables the accounts in the *destination* schema.
  - If the batch fails to migrate, AMM rolls back the changes and re-enables the accounts in the source database schema.
- Batches containing account group members by account group ID. AMM disables all accounts that belong to an account group before migration begins. After migration starts, AMM monitors whether all batches for the account group migrate successfully.
  - If all batches migrate successfully, AMM commits the changes to all database schemas and enables the accounts in the *destination* schema.
  - If even one batch in the group fails, AMM leaves all account group members disabled in both source and destination schemas. You must fix the error and use AMM to reprocess the job before your BRM system can access the accounts.



# 3 Account Migration Restrictions

Learn about the account migration restrictions for using Oracle Communications Billing and Revenue Management (BRM) Account Migration Manager (AMM).

Topics in this document:

- Account Activity Prevented during Account Migration
- Do Not Rerate Events during Account Migration
- Do Not Alter Account Group Members
- Migration Prevented during Account Activity
- Unique POIDs Required across All Database Schemas
- Transient Objects Are Not Migrated
- Some Client Applications May Fail during Account Migration
- AMM Does Not Support LDAP Manager
- Using BRM Reports after Migration

### Account Activity Prevented during Account Migration

To prevent applications from accessing or modifying accounts that are being migrated, AMM locks the accounts in Oracle. Only one batch of accounts per thread is locked at a time and only while the accounts are being physically migrated.

#### Note:

When migrating account groups, AMM locks all accounts in the account group before migration begins.

If an application attempts to access a locked account, the Oracle Data Manager (DM) returns a PIN\_ERR\_INVALID\_OBJECT error.

### Do Not Rerate Events during Account Migration

Because the AMM software may suspend some events that you want to rerate, you *must not* rerate events during account migration.

### Do Not Alter Account Group Members

AMM checks account group relationships only when you first create a job, and does not reverify relationships during the migration process. Therefore, once an account group is included in a migration job, you:

Must not add members to the account group



Must not modify relationships between account group members

If you need to alter an account group *after* it is included in a job but *before* the job completes migration, you must:

- **1.** Delete the migration job.
- 2. Modify the account group.
- 3. Re-create the account migration job.

### Migration Prevented during Account Activity

AMM does not migrate accounts while they are being accessed or modified by BRM or another application. For best performance, stop all account activity before you migrate accounts.

If you cannot restrict all access to the accounts in your database schemas, AMM can still process account migration jobs. However, AMM does not migrate any batch that contains active accounts. You can check for failed batches and resubmit them for migration once account activity stops.

### Unique POIDs Required across All Database Schemas

The AMM software can migrate only accounts that have a unique POID. Starting with Infranet Release 6.2 ServicePack 1, the multischema software automatically creates unique POIDs across all database schemas in your system.

If your database contains accounts created both prior to and after Release 6.2 ServicePack 1 was installed, AMM migrates only those accounts created *after* 6.2 ServicePack 1 was installed. For information on how to migrate accounts created prior to 6.2 ServicePack 1, contact your Oracle BRM representative.

#### Note:

If your BRM system uses a custom POID generation scheme, make sure the sequence number generation algorithm creates unique POIDs across all of your database schemas.

### Transient Objects Are Not Migrated

While the pin\_amt utility migrates account objects, it does not migrate any transient objects.

### Some Client Applications May Fail during Account Migration

BRM client applications may generate error messages and fail to commit changes to the database during account migration. For example, if a CSR opens an account in Billing Care just prior to the account being migrated to another database schema, an error might result.

In that case, the CSR must restart Billing Care and access the account again so it retrieves the account's new location.



#### Note:

If your system contains custom client applications that connect to the BRM database and search accounts based on POID, you must modify your application. See "Modifying Custom Client Applications for AMM".

### AMM Does Not Support LDAP Manager

Currently, you cannot use AMM to migrate accounts if your BRM system includes LDAP Manager.

### Using BRM Reports after Migration

To use BRM Reports after you migrate accounts, you must use BRM Reports Release 6.2 ServicePack 1 or later. If you use an earlier version of BRM Reports with AMM, your reports will retrieve and process duplicate data from your source and destination database schemas.

For example, if an account object is migrated from schema **0.0.0.1** to schema **0.0.0.2**, earlier versions of BRM Reports retrieve the account object from both schemas while BRM Reports 6.2 ServicePack 1 and later retrieve the account object only from schema **0.0.0.2**.

For information on how to modify custom reports to work with AMM, see "Modifying Custom BRM Reports for AMM".



### 4

# Installing and Configuring BRM for Account Migration

Learn how to install and configure software required for account migration with the Oracle Billing and Revenue Management (BRM).

Topics in this document:

- System Requirements
- Installing AMM
- Configuring AMM for Additional Database Schemas
- Configuring AMM for New Custom Tables
- Tuning Your Database for Optimal Account Migration Performance

### System Requirements

The system requirements for account migration consists of the following:

- General Software Requirements
- Software Requirements for Account Migration Manager

#### General Software Requirements

Before installing AMM, you must install:

- The compatible version of the Oracle Database software.
- PERL libraries and the JRE required for installing BRM components.
- **Multidatabase Manager**. See "Installing a Multischema System" in *BRM Installation Guide*.

For information about the compatible software versions for your release, see *BRM Compatibility Matrix.* 

#### Software Requirements for Account Migration Manager

AMM is available for Oracle databases and the Linux operating system. For information on disk space requirements for the Linux operating system, see "Disk Space Requirements" in *BRM Installation Guide*.

If you plan to use AMM software for account migration, you must also install:

Java Development Kit



### **Installing AMM**

The instructions in this section assume that you have two BRM installation machines and two database schemas in your multischema environment as shown in Figure 4-1.





Installing AMM involves the following general steps:

- 1. Configuring All Primary and Secondary Database Schemas
- 2. Installing the AMM Software on the Primary Installation Machine
- 3. Configuring Your Oracle DM to Check for Invalid Objects
- 4. Connecting AMM to Your Database Schemas

### Configuring All Primary and Secondary Database Schemas

Before you can install AMM, you must configure your primary and secondary database schemas for account migration.

First, ensure that you assigned unique database instance names to each schema in your system:

- 1. Open the tnsnames.ora file in a text editor.
- 2. If necessary, assign a unique database instance name to each schema. For example, for the first schema:

```
Alias1 = (DESCRIPTION = (ADDRESS = (PROTOCOL= TCP)(Host=DatabaseHost1Name)(Port=
1521))
(CONNECT DATA = (SID = DatabaseSID1)) )
```

For the second schema:



```
Alias2 = (DESCRIPTION = (ADDRESS = (PROTOCOL= TCP)(Host=DatabaseHost2Name)(Port=
1521))
(CONNECT_DATA = (SID = DatabaseSID2)) )
```

3. Save and close the file.

Then perform the following steps on *each* database schema in your multischema system:

 Using SQL\*Plus, log in to the database schema as the SYSTEM user and grant database linking privileges to the BRM user pin:

% sqlplus system/password@databaseAlias

SQL> grant create database link to pin;

Grant succeeded.

2. Verify that JServer is installed on your system:

```
SQL> SELECT object_name, object_type FROM all_objects WHERE
object_type = 'PACKAGE' and object_name = 'DBMS_JAVA';
```

If JServer is installed on your system, you receive the following:

OBJECT	NAME	OBJECT	TYPE
DBMS J	AVA	PACKAGE	Ξ

If JServer is not installed, you receive the following:

no rows selected

- 3. Install JServer if it is not already installed on your system:
  - Add the following entry to the Oracle initS/D.ora file (\$ORACLE\_HOME/dbs/ initS/D.ora) for the schema's database instance:

java\_pool\_size=20971520

- b. Restart Oracle so that the schema's database instance is initialized with your changes.
- c. Install JServer manually by running the Oracle initjvm script:

```
% sqlplus sys/password@databaseAlias
SQL> @$ORACLE_HOME/javavm/install/initjvm.sql
```

For information, see your Oracle documentation.

4. Modify the entries listed in Table 4-1 in the Oracle initS/D.ora file (\$ORACLE\_HOME/dbs/ initS/D.ora) of the schema's database instance:

#### Table 4-1 initSID.ora Entries

Entry	Description		
global_names Specifies whether a database link is required to have the sai the database schema to which it connects. Set this to False			
utl_file_dir	Specifies the location of the Oracle <b>utl_file</b> . Set this to a writable directory for the user <b>oracle</b> .		

5. Restart Oracle so that the schema's database instance is initialized with your changes.

### Installing the AMM Software on the Primary Installation Machine

#### Note:

If you already installed the product, you must uninstall its features before reinstalling them.

To install AMM, perform the following steps on the primary installation machine:

- 1. Install AMM. See "Installing Individual BRM Components" in BRM Installation Guide.
- Verify that the BRM\_home/setup/scripts/pin\_multidb.conf file contains accurate information about each database schema in your system. The pin\_amt\_install script uses the information in this file to set up your AMM environment.
- 3. For optimal performance, store your AMM job management tables and indexes in their own physical tablespaces. Map the following entries to four separate physical tablespaces by modifying the BRM\_home/setup/scripts/pin\_tables.values file:

```
$PIN_CONF_TBLSPACE14
$PIN_CONF_TBLSPACE15
$PIN_CONF_TBLSPACEX16
$PIN_CONF_TBLSPACEX17
```

See "Database Configuration and Tuning" in BRM Installation Guide.

 Log in as user pin, go to the BRM\_home/setup/scripts directory, and run the pin\_amt\_install script:

```
# su - pin
% cd BRM_home/setup/scripts
% perl pin amt install.pl
```

- Verify that installation was successful by checking the AMM installation log file (BRM\_home/setup/scripts/pin\_amt\_install.log).
- 6. Restart the BRM server.

### Configuring Your Oracle DM to Check for Invalid Objects

During account migration, the AMM software marks all migrated objects in the source database schema as invalid. To prevent BRM applications from accessing these objects, you must configure your Oracle Data Manager (DM) to check for invalid objects during account searches.

#### Note:

If you do not make this change, BRM applications retrieve duplicate data from your source and destination database schemas. For example, if an account is migrated from schema **0.0.0.1** to schema **0.0.0.2**, the application retrieves the account object from both schemas.



To configure your system to check for invalid objects, perform the following on *every* machine containing an Oracle DM:

- 1. Add the following line to the BRM\_homelsys/dm\_oracle/pin.conf file:
  - dm dm\_nul\_poid\_db\_chk 1
- 2. Restart dm\_oracle so that your Oracle DM is initialized with your changes.

#### Connecting AMM to Your Database Schemas

During installation, the Installer stores the configuration data, such as the database schema connection details and the number and configuration of your AMM Controllers, in the Oracle wallet. AMM retrieves the data from the Oracle wallet. However, if the configuration entries are also stored in the AMM **Infranet.properties** file, AMM retrieves the data from the AMM **Infranet.properties** file. Use the Oracle wallet to provide the information necessary for AMM, such as passwords, to access the data for the accounts in your system.

For more information viewing and storing the configuration entries in the Oracle wallet, see the "About the Oracle Wallet" section in *BRM System Administrator's Guide.* 

#### Configuring Database and AMM Mover Information for Multischema Systems

Verify that the AMM **Infranet.properties** file contains a set of **0.0.0***.x* entries for each database schema in your system. For example, if you have three database schemas in your system, the file should contain a set of entries prefixed by **0.0.0.1**, a set prefixed by **0.0.0.2**, and a set prefixed by **0.0.0.3**. Also, update the BRM wallet in the primary schema to include the user passwords for all the secondary schemas. Example 4-1 shows the entries for a system with two database schemas.

Verify that the **Infranet.properties** file contains information on the AMM Mover associated with each database schema. If a schema contains more than one AMM Mover, make sure to update the **Infranet.properties** file accordingly.

#### Example 4-1 Example Configuration Information for Multischema Systems

```
# primary database schema
0.0.0.1 user name=pin57204
0.0.0.1 instance name=futt11
0.0.0.1 primary=true
# AMT mover
0.0.0.1 mover log file dir=unknown
0.0.0.1_mover_log_file_flag=N
0.0.1_grp_srch_log_file_dir=unknown
0.0.0.1 grp srch log file flag=N
#
# secondary database schema
0.0.0.2 user name=pin57204m2
0.0.0.2 instance name=futt11m2
0.0.0.2_primary=false
# AMT mover
0.0.0.2 mover log file dir=unknown
0.0.0.2 mover log file flag=N
0.0.0.2 grp srch log file dir=unknown
0.0.0.2 grp srch log file flag=N
```



#### Configuring AMM Controller Definitions

The installer creates a set of **Controller\_1** entries for setting up one AMM Controller in the AMM **Infranet.properties** file and populates them with default values, as shown in Example 4-2.

Example 4-2 AMM Controller Definitions

```
# controller definitions
#
controller_1_log_directory=/export/BRM_home/apps/amt
controller_1_port_number=18566
controller_1_server=slc00qhm
controller_1_thread_count=2
controller_1_syslog_priority=7
controller_1_event_generation=false
controller_1_concurrent_job_number=20
controller_1_hold_period=120
controller_1_amt_queue_owner_name=pinq
controller_1_amt_queue_name=ifw_sync_queue_amt
#
```

Access the Oracle wallet and verify that the entries are as required.

If you require more than one AMM Controller, determine the optimal number of AMM Controllers for your system. Make sure that you provide the optimal number of threads for each AMM Controller in your system. See "About Using Multiple AMM Controllers" for more information.

For the additional controllers, create a set of **Controller\_2** entries, **Controller\_3** entries, and so on in the **Infranet.properties** file.

#### Specifying Schema Alias Information for Multischema Systems

When you use multischema systems, the database layer of your BRM system consists of one primary schema and one or more secondary schemas in a single database. As a result, the schema alias is the same for both schemas.

Access the Oracle wallet and enter an alias for the secondary schema in the file.

Example 4-3 shows the entries for a multischema system:

#### Example 4-3 Example Alias Information for Multischema System

```
#
# Connection entries for the Primary Database Schema
0.0.0.1_user_name=pin
0.0.0.1_instance_name=SchemalAlias
0.0.0.1_primary=true
0.0.0.1_mover_log_file_dir=./mover/log
0.0.0.1_mover_log_file_flag=y
# Connection entries for the Secondary Database Schema
0.0.0.2_user_name=pin
0.0.0.2_instance_name=Schema2Alias
0.0.0.2_primary=false
0.0.0.2_mover_log_file_dir=./mover/log
0.0.0.2_mover_log_file_flag=y
```



### AMM Infranet.properties File Parameters

Table 4-2 shows the parameters used in defining the AMM Infranet.properties file.

Table 4-2	AMM Infranet.properties	Values
-----------	-------------------------	--------

Entry	Value	Description
0.0.0.x_user_name	String	Specifies the Oracle user name for the specified database schema.
0.0.0.x_instance_name	String	Specifies the SQL*Net database alias name you assigned in the tnsnames.ora file.
0.0.0.x_primary	true or false	Flag that indicates whether the database schema is the primary schema. For the primary schema, set this to <b>true</b> . For all secondary schemas, set this to <b>false</b> .
0.0.0. <i>x</i> _mover_log_file_dir	Path name	Specifies the directory of the AMM Mover log file on the specified database schema.
		Important: This path must match the path specified in the utl_file_dir entry of the initSID.ora file.
0.0.0. <i>x</i> _mover_log_file_flag	Y or N	Specifies whether you want the AMM Mover to create log files on the specified database schema.
0.0.0.x_grp_srch_log_file_flag	Y or N	Specifies whether you want AMM to create a log file for the account group stored procedure.
		<b>Note:</b> The stored procedure finds all account group members related to a specific account.
0.0.0.x_grp_srch_log_file_dir	Path name	Specifies the directory for the account group stored procedure log file.
controller_ <i>N</i> _log_directory	Path name	Specifies the directory in which to create the AMM Controller log file.
controller_ <i>N</i> _port_number	Integer > 1024	Specifies the TCP/IP port number for the connection between the <b>pin_amt</b> utility and the AMM Controller. Each AMM Controller instance requires a unique port number.
controller_ <i>N</i> _server	String	Specifies the host name of the machine that runs the AMM Controller.
controller_ <i>N</i> _thread_count	Positive integer	Specifies the number of AMM Controller processing threads. For optimal performance, the number of AMM Controller threads should be 1 to 2 times the number of CPUs on the destination schema that are dedicated to AMM.
controller_N_syslog_priority	1 (low) through 7 (high)	AMM Controller log message priority threshold. Messages with a lower priority are suppressed.
pin_amt_log_directory	Path name	Specifies the path to the <b>pin_amt</b> log file.
controller_ <i>N</i> _event_generation	true or false	Specifies whether the AMM Controller migrates accounts when ECE is running. This configures AMM to notify ECE when accounts are migrated.
		The default is <b>false</b> .
controller_ <i>N</i> _concurrent_job_nu mber	Positive integer	Specifies how many jobs the AMM Controller starts concurrently. The default is <b>20</b> .
		Note: This entry is required only if the controller_N_event_generation entry is set to Y.

Entry	Value	Description
controller_N_hold_period	Positive integer	Specifies how long the AMM Controller waits, in minutes, before it starts to migrate accounts. This provides time for your ECE to process any events targeted for accounts that are being migrated. The default is <b>120</b> .
		<b>controller_</b> <i>N</i> <b>_event_generation</b> entry is set to <b>Y</b> .
controller_ <i>N</i> _amt_queue_owner _name	String	Specifies the user that created the acknowledgment queue. <b>Note:</b> This entry is required only if the <b>controller_</b> <i>N</i> <b>_event_generation</b> entry is set to <b>Y</b> .
controller_ <i>N</i> _amt_queue_name	String	Specifies the name of the acknowledgment queue. The AMM Controller dequeues ECE acknowledgment events from this queue. <b>Note:</b> This entry is required only if the
		<b>controller_</b> <i>N</i> <b>_event_generation</b> entry is set to <b>Y</b> .
infranet.login.type	1 or 0	Specifies whether AMM requires a user name and password to log in to the Connection Manager (CM).
		<ul> <li>1 specifies that AMM must provide a user name and password.</li> </ul>
		<ul> <li>0 specifies that AMM uses a "trusted" login that comes through a CM Proxy, for example, and does not require a user name and password in the properties file.</li> </ul>
		<b>Note:</b> This entry is required only if the <b>controller</b> _ <i>N</i> _ <b>event</b> _ <b>generation</b> entry is set to <b>Y</b> .
publish_migrated_objects	String	Specifies the storable classes whose objects are stored in the MIGRATED_OBJECTS_T cross-reference table. You can list multiple storable classes by using a comma (,) as a delimiter. For example: /service,/billinfo,/payinfo.
		<b>Note:</b> This entry is required only if you integrate AMM with your external application using Oracle Application Integration Architecture (Oracle AIA) in a multischema environment.

### Configuring AMM for Additional Database Schemas

You must reconfigure the AMM software whenever you add a database schema to an existing multischema system.

To configure AMM for additional database schemas, perform the following procedure on the primary installation machine:

1. Delete all existing account migration jobs in the queue:

% pin\_amt -d JobID

2. Log in as user pin and run the pin\_amt\_install.pl script:

```
# su - pin
% cd BRM_home/setup/scripts
% perl pin amt install.pl
```

This script reinstalls the job management tables on your database schemas.



### **Configuring AMM for New Custom Tables**

AMM migrates data to and from the tables listed in the AMM data dictionary. This list includes all BRM tables and any custom tables that were on your system when you installed AMM. If you add any tables after you install AMM, you must update the AMM data dictionary.

To update the AMM data dictionary, perform the following on your primary installation machine:

1. Log in as user pin and go to the BRM\_home/setup/scripts directory:

```
% su - pin
% cd BRM home/setup/scripts
```

2. Run the pin\_amt\_install.pl script with the -m parameter:

```
% perl pin_amt_install.pl -m
```

This script updates the AMM data dictionary tables (AMT\_META\_DATA\_T and AMT\_POID\_TYPE\_MAP\_T) on all database schemas in your system.

# Tuning Your Database for Optimal Account Migration Performance

To tune your database for optimal account migration performance:

- Use cost-based optimization.
- Set the number of Oracle rollback segments to approximately two times the number of AMM Controller threads. Multiple rollback segments enable Oracle to automatically allocate one rollback segment for each transaction.
- Set the transactions\_per\_rollback\_segment parameter in the \$ORACLE\_HOME/dbs/ initS/D.ora file to a small number. For best results, set it to 1 or 2.
- Set the initial size for the rollback segment to twice the total data volume of the account batch. You can estimate the account batch data volume by multiplying the average number of events per batch with the batch size.

#### Note:

Use the EVENT\_T and major child tables, such as EVENT\_BAL\_IMPACTS\_T, to determine the average number of events per batch. Typically, 90% of the account batch data volume can be attributed to event data.

- Set the optimal size for the rollback segments to twice the initial size.
- Set the next size for the rollback segments to half the initial size.
- Set the maximum number of extends to unlimited.

For more information, see your Oracle documentation. For information on additional ways to tune your database for AMM, contact your Oracle BRM representative.



## 5 Using Account Migration Manager

Learn how to use the Oracle Communications Billing and Revenue Management (BRM) Account Migration Manager (AMM) software to migrate accounts from a source database schema to a destination database schema in the same database.

Topics in this document:

- Overview of Account Migration Tasks
- Creating the Account Search Configuration File
- Submitting the Account Search File
- Enabling Migration Jobs in the Queue
- Starting the AMM Controller
- Monitoring the AMM Controller
- Monitoring Account Migration
- Handling Account Migration Failures
- Purging Migrated Objects from the Source Database Schema
- Deleting Jobs from the Source Database Schema
- Stopping the AMM Controller
- Pausing and Resuming Account Migration
- Automating Account Migration

### **Overview of Account Migration Tasks**

Migrating accounts includes the following general tasks. Although you can perform some tasks at any time, the following order is recommended:

1. Create the account search configuration file.

See "Creating the Account Search Configuration File" for more information.

2. Submit the account migration job.

See "Submitting the Account Search File" for more information.

 For account group migration, run a group\_details report to verify that each account group includes all account members.

See "Checking Account Group Details" for more information.

#### Note:

You must verify that the job includes all accounts in the account group. Any missing accounts will be stored in a separate database schema from the account group, which severs the account's relationship with the group.



4. Enable the account migration job.

See "Enabling Migration Jobs in the Queue" for more information.

5. Start the AMM Controller.

See "Starting the AMM Controller" and "Monitoring the AMM Controller" for more information.

6. Monitor the job's progress.

See "Monitoring Account Migration" for more information.

7. Fix account migration failures, when necessary.

See "Handling Account Migration Failures" for more information.

8. Purge the migrated accounts from the source database schema.

See "Purging Migrated Objects from the Source Database Schema" for more information.

9. Stop the AMM Controller.

See "Stopping the AMM Controller" for more information.

See "Deleting Jobs from the Source Database Schema" for information on deleting jobs from the source database schema.

### Creating the Account Search Configuration File

You use the account search configuration file to specify the source and destination database schemas, the search criteria, the maximum number of accounts in a job, and the number of accounts in each batch.

AMM can search for accounts that meet five default criteria:

- Account creation date
- Account status
- Billing day of month
- Charge offer name
- POID

If you would like to migrate accounts that meet custom criteria, see "Creating Custom Account Search Criteria".

To create an account search configuration file:

- Copy the sample account search configuration file (*BRM\_homelapps/amt/* account\_search.cfg) and save it with another name. Use this file, which contains all of the configuration entries, as a template.
- 2. Edit the entries listed in Table 5-1 in the file.

#### Note:

Only the source database schema, destination database schema, batch size, and one other entry is required. If you do not want to use an entry, leave it blank.

Parameter	Description	Required
src_database	Specifies the source database schema, which is the schema from which you are migrating accounts. For example, enter <b>0.0.0.1</b> .	
	This value must match one of the database numbers specified in the Infranet.properties file.	
dest_database	Specifies the destination database schema, which is the schema to which you are migrating accounts. For example, enter <b>0.0.0.2</b> .	YES
	This value must match one of the database numbers specified in the Infranet.properties file.	
start_creation_date	Use this parameter to migrate accounts that were created in a specific date range. AMM migrates accounts created between midnight (00:00:00) on the start date and 23:59:59 on the end date. For example, to migrate accounts created after midnight on August 1, 2004, enter <b>08/01/2004</b> .	no
	Important: If you set this parameter, you must also set the end_creation_date parameter.	
end_creation_date	Use this parameter to migrate accounts that were created in a specific date range. AMM migrates accounts created between midnight (00:00:00) on the start date and 23:59:59 on the end date. For example, to migrate accounts created on or before 11:59:59 p.m. on August 10, 2004, enter <b>08/10/2004</b> .	
	<b>Important:</b> If you set this parameter, you must also set the <b>start_creation_date</b> parameter.	
migration_mode	Specifies whether to migrate account groups. When AMM finds an account that belongs to a hierarchical account or charge or discount sharing group, AMM migrates all accounts related to that account.	no
	<ul> <li>IncludeAccountGroup specifies to migrate accounts groups.</li> <li>ExcludeAccountGroup specifies to exclude account groups from migrations.</li> <li>The default is ExcludeAccountGroup.</li> </ul>	
	Important: If you set this parameter, you must also set the max_group_size parameter.	
max_group_size	Specifies the maximum size of an account group that AMM can migrate. If an account group exceeds the maximum number of accounts, AMM excludes the account group from the job. The default is <b>100</b> .	no
product_name	Migrates accounts that purchased the specified charge offer. For example, <b>Offer</b> <b>1b - Email Account</b> .	no
account_status	<ul> <li>Migrates accounts based on the specified account status:</li> <li>Active specifies to migrate active accounts only.</li> <li>Inactive specifies to migrate inactive accounts only.</li> <li>Closed specifies to migrate closed accounts only.</li> </ul>	no
bill_day_of_month	Migrates accounts that have the specified billing day of month. You can specify any number from 1 through 31. For example, enter <b>4</b> to migrate all accounts that are billed on the 4th of the month.	no
max_accounts	Specifies the maximum number of accounts to move in a job.	no

#### Table 5-1 account\_search.cfg Parameters

Table 5-1 (Cont.) account\_search.cfg Parameters

Parameter	Description			
batch_size	Specifies the number of accounts in each batch. You can specify any amount from 1 through 1,000. However, for optimal performance, set this to an integer between 50 and 100.			
	Important:			
	<ul> <li>Using a batch size of more than 50 accounts does not improve performance.</li> <li>If you set this to a number greater than 100, you must increase the size of your Oracle rollback segments. For more information, contact your Oracle BRM representative.</li> </ul>			
poid_list	Migrates accounts based on the POID. Use comma separators, for example, <b>22860, 22861, 22862.</b> Limit the number of accounts to 1,000 or less.			
cross_schema_group	Specifies whether to migrate accounts that are members of a sharing group:	no		
	<ul> <li>Enabled: AMM checks whether an account member is a member of a cross-schema sharing group. If an account is a member, AMM does not migrate it.</li> <li>Disabled: AMM does not check whether an account is a member of a cross-schema sharing group.</li> <li>The default is Disabled.</li> </ul>			

**3.** Save the file.

### Sample Account Search Configuration File

The following sample account search configuration file specifies to:

- Migrate accounts from database schema 0.0.0.1 to database schema 0.0.0.2.
- Migrate in batches of 50 accounts.
- Migrate only nonmember accounts.
- Migrate accounts that meet the following criteria:
  - Created between January 1, 2004 and June 31, 2004
  - Have an active account status
  - Purchased the Offer 1b Email Account charge offer

```
src_database=0.0.0.1
dest_database=0.0.0.2
start_creation_date=01/01/2004
end_creation_date=06/31/2004
migration_mode=ExcludeAccountGroup
max_group_size=
product_name=Offer 1b - Email Account
account_status=Active
bill_day_of_month=
max_accounts=
batch_size=50
poid_list=
```

### Submitting the Account Search File

When you submit an account search file, the **pin\_amt** utility searches the source database schema and populates the job management tables on the primary, source, and destination database schemas with a list of accounts meeting the specified criteria.



1. Submit your account search information to the **pin\_amt** utility:

```
% pin_amt -s AccountSearchFile
submitted job
job_id=30
```

The **pin\_amt** utility notifies you if it successfully submitted the file and gives you the job ID number.

2. Write down the job ID number, because you will need it later.

### Enabling Migration Jobs in the Queue

The AMM Controller can only begin processing an account migration job after it's enabled in the queue.

To enable a job in the queue, enter this command:

```
% pin_amt -e JobID
enabled job
```

### Starting the AMM Controller

After it is started, the AMM Controller runs as a server process, continuously checking for jobs to process in the queue.

To start the AMM Controller:

1. Go to the BRM\_homelsyslamt directory.



2. Run the following command:

```
% pin_amt -c start [-a ControllerID]
controller is started
controller_id=1
```

#### Note:

If your system contains multiple AMM Controllers, use the **-a** option to specify which AMM Controller to start. By default, **pin\_amt** starts Controller 1.

The **pin\_amt** utility notifies you if the AMM Controller started successfully and which AMM Controller is active.



### Monitoring the AMM Controller

You can monitor the AMM Controller's status at any time by using the **pin\_amt** utility or checking the AMM Controller log file.

#### Checking the AMM Controller Status

To check whether the AMM Controller is up and running, enter this command:

```
% pin_amt -c status [-a ControllerID]
controller status is up
```

#### Note:

If your system contains multiple AMM Controllers, use the **-a** option to specify which AMM Controller to check.

The **pin\_amt** utility notifies you that the AMM Controller is up or down. If the AMM Controller is down or cannot be started, check the AMM Controller log file for more information.

#### Checking the AMM Controller Log File

The AMM Controller log file contains a detailed list of all transactions processed by the AMM Controller. This log is created in the directory specified in the **controller\_***N***\_log\_directory** entry of the **Infranet.properties** file. You can open the log file by using a text editor.

#### Monitoring the AMM Controller in Real Time

You can use the **pin\_amt** utility to see what the AMM Controller is doing in real time.

To monitor the AMM Controller in real time, enter this command:

```
% pin_amt -c log [-a ControllerID]
```

#### Note:

If your system contains multiple AMM Controllers, use the **-a** option to specify which AMM Controller to check.

A separate Xterm window opens. For best viewing, set the Xterm width to 120. If an Xterm window fails to open, make sure your **DISPLAY** environment variable is set correctly.

### **Monitoring Account Migration**

You can monitor the status of jobs in the queue by running three special AMM reports: **list\_jobs**, **job\_details**, and **group\_details**.



page 1

page 1

#### Monitoring Job Status

The **list\_jobs** report provides the status of each job in the queue, including the number of batches that failed to migrate.

To run the list\_jobs report, enter this command:

% pin\_amt -r list\_jobs

Sample output from a list\_jobs report:

Tue Mar 12

Job Name	User Name	Job ID	Total Account batches	Failed Account batches	Succ. Account batches	Job Status	Proc. time[sec]	Job creation time	Accounts
test.cfg	pin	1	6	0	6	FINISHED	40	02/02/2002 13:39	100
srch.cfg	pin	2	3	0	3	FINISHED	25	02/15/2002 12:00	50
mar1.cfg	pin	3	8	1	7	FINISHED	205	03/01/2002 18:42	400

AMT jobs

If any batches failed, you can see greater detail on why the batch failed by running the **job\_details** report.

#### **Checking Job Details**

The **job\_details** report provides detailed information about a job's status, including why a batch failed.

To run the job\_details report, enter this command:

% pin\_amt -r job\_details
enter job id:

Sample output from a job\_details report:

Tue Mar 12

#### AMT job details

Account Processing start Batch processing Job ID batches Status Error Message date time[sec] Accounts \_\_\_\_\_ \_\_\_\_\_ \_\_\_\_\_ \_\_\_\_ \_\_\_\_\_ 1 FINISHED 25 5 50 03/01/2002 18:42 3 2 FAILED ORA-02055: distributed 03/01/2002 18:42 5 0 update operation failed; rollback required ORA-02049: timeout: distributed transaction waiting for lock ORA-06512: at "PIN.AMT MV", line 454 ORA-06512: at line 1 25 3 FINISHED 03/01/2002 18:42 50 03/01/2002 18:43 25 4 FINISHED 50 5 FINISHED 03/01/2002 18:43 25 50 6 FINISHED 03/01/2002 18:44 25 50 03/01/2002 18:44 7 FINISHED 25 50 8 FINISHED 03/01/2002 18:45 25 50



The report lists any error messages from the Oracle database. For information, see the Oracle documentation.

#### **Checking Account Group Details**

The **group\_details** report lists the accounts in each account group and provides information about each group's migration status. You use this information to verify that all account members are included in a group.

#### Note:

All accounts in a hierarchical account or charge or discount sharing group must reside in the same database schema. Any accounts separated from a parent account will no longer be associated with the account group.

To run the group\_details report, enter this command:

```
% pin_amt -r group_details
enter job id:
enter group id:
```

Sample output from a group\_details report:

Tue Mar 12

			AMT group details				
Job ID	Account batches	Batch Status	Group ID	Group Status			
3	1	FINISHED	1	NOT_PROCESSED			

Tue Mar 12

AMT group member details

Account

batches	Accounts ID	Accounts DE
1	17009	2
1	17289	2
1	16489	2
1	17313	2
1	16465	2
1	17066	2

### Handling Account Migration Failures

An account batch may fail for several reasons. The most common reasons are as follows:

- An application is accessing or modifying the data you are attempting to migrate.
- The database is down.



page 1

page 1

#### Finding Debugging Information

For information on why a batch failed, you can run a **job\_details** report or check any of the following files, which are located in the directories you specified in the **Infranet.properties** file.

- AMM installation log file (pin\_amt\_install.log)
- AMM Controller log file (controller\_N\_YYYYMMDDhhmm.log)
- pin\_amt log file (pin\_amt.log)
- AMM configuration file (Infranet.properties)
- Account search configuration file (account\_search.cfg)
- AMM Mover log files (amt\_migrate\_JobID\_BatchNumber.log)
- AMM delete log file (amt\_delete\_JobID\_BatchNumber.log)

If you need assistance in resolving migration failures, send these files along with any additional information about the problem to your Oracle BRM representative.

#### **Reprocessing Failed Batches**

To reprocess a batch that failed:

- **1.** Fix the problem.
- 2. Change the status of the batch from FAILED to NOT PROCESSED:

% pin\_amt -b JobID:BatchNumber

3. Enable the job in the queue again:

% pin\_amt -e JobID

The AMM Controller processes all batches that have a NOT PROCESSED status and ignores batches with a FINISHED status.

### Purging Migrated Objects from the Source Database Schema

After you successfully migrate your accounts, you can improve your overall system performance by purging the migrated (invalid) objects from your source database schema. Also, because the purging process uses only one thread, purges accounts sequentially, and doesn't affect data used by BRM, you can purge accounts at any time.

To purge successfully migrated objects from the source database schema, enter this command:

pin\_amt -p SourceDatabaseSchema

### Deleting Jobs from the Source Database Schema

You can use the delete option to:

- Remove both failed and successfully migrated jobs from your database schemas
- Free up disk space

The delete option performs the following actions listed in Table 5-2:



#### Table 5-2 Delete Job Actions

Јор Туре	Action
Failed jobs	Deletes the job from the AMM job management tables.
Successfully migrated jobs	<ul> <li>Deletes the job from the AMM job management tables.</li> <li>Deletes account-related data from the source database schema.</li> </ul>

To delete a job, run the **pin\_amt** script with the delete option:

```
pin_amt -d JobID
```

### Stopping the AMM Controller

You can stop the AMM Controller at any time. If you stop the AMM Controller while it is processing a batch, it finishes the batch before stopping.

To stop the AMM Controller, enter this command:

% pin\_amt -c stop controller is stopped controller id=1

### Pausing and Resuming Account Migration

If a job contains a large number of accounts, but you only have a limited amount of time in which to migrate accounts, you can migrate the job in stages. The AMM software allows you to start an account migration job and then pause it when your window of opportunity is over. When you reach the next window of opportunity, you can resume the job where it left off.

#### Note:

An AMT Controller must completely finish migrating one job before it can start migrating another job. Therefore, if you pause one job and then enable a second job, the AMT Controller cannot begin processing the second job until the first job is finished.

To pause an account migration job, enter this command:

```
% pin_amt -c pause
paused controller
controller id=1
```

To resume an account migration job, enter this command:

% pin\_amt -c continue
continued controller
controller id=1



### **Automating Account Migration**

You can use an external scheduler, such as **cron**, to automate account migration during your maintenance window. If you need to migrate a large number of accounts, you can set up **cron** to stop and restart account migration at specific times.

For example, scheduling account migration for every Sunday from 2:00 a.m. to 4:00 a.m. requires these tasks:

- **1.** Stop the AMM Controller.
- 2. Create your account search configuration files.
- 3. Submit your jobs.
- 4. Enable your jobs in the queue.
- 5. Configure one **cron** job to start the AMM Controller every Sunday at 2:00 a.m. and check for errors. See "AMM Return Codes and Messages".
- 6. Configure a second **cron** job to stop the AMM Controller every Sunday at 4:00 a.m. and check for errors.



## 6 Modifying Applications to Work with AMM

Learn how to modify your custom client applications and custom reports to work with the Oracle Communications Billing and Revenue Management (BRM) Account Migration Manager (AMM) software.

Topics in this document:

- Enabling ECE to Rate Events during Account Migration
- Modifying Custom Client Applications for AMM
- Modifying Custom BRM Reports for AMM
- AMM Return Codes and Messages

### Enabling ECE to Rate Events during Account Migration

When you enable ECE to rate events during account migration, the AMM business events listed in Table 6-1 automatically notify ECE that an account migration job is occurring. They enable ECE to:

- Track the status of the migration
- Notify BRM if ECE fails to clear its rated event data store before the migration begins (a migration prerequisite)
- · Continue rating events while the accounts are migrated
- Update its information about the target database schema for successfully migrated accounts

Table 6-1 ECE Response to AMM Business Events

AMM Business Event	ECE Response	
HoldCDRProcessing		Gets the migration job ID, the source database schema, and the target database schema from this event.
	2.	Queries the BRM database for the list of accounts that belong to the migration job.
	3.	Waits for all existing rated events associated with those accounts to be extracted from the Oracle NoSQL database data store.
	4.	Does one of the following:
		If the extraction succeeds:
		<ul> <li>Assigns the IN_ACCOUNT_MIGRATION status to the accounts.</li> </ul>
		<ul> <li>Updates their target database schema information.</li> </ul>
		<ul> <li>Sends an ACKHoldCDRProcessing acknowledgment to the BRM acknowledgment queue.</li> </ul>
		<ul> <li>Continues rating incoming usage events for the migrated accounts but does not extract them from the Oracle NoSQL database data store.</li> </ul>
		If the extraction fails, ECE sends a NACKHoldCDRProcessing acknowledgment to BRM, and BRM does not migrate the accounts.

AMM Business Event	ECE Response	
MigrateAcct	Sends an ACKMigrateAcct acknowledgment to the AMM acknowledgment queue.	
MigrateSource	Sends an ACKMigrateSource acknowledgment to the AMM acknowledgment queue.	
MigrateDestination	Sends an ACKMigrateDestination acknowledgment to the AMM acknowledgment queue.	
ResumeCDRProcessing	<ol> <li>Gets the migration job ID, the source database schema, and the target database schema from this event.</li> </ol>	
	2. Queries the BRM database for the list of accounts that belong to the migration job.	
	3. Removes the IN_ACCOUNT_MIGRATION status from those accounts.	
	<ol> <li>Loads all the rated events that were generated while the accounts' status was IN_ACCOUNT_MIGRATION into the new target database schema.</li> </ol>	

#### Table 6-1 (Cont.) ECE Response to AMM Business Events

To enable ECE to rate events during account migration:

- 1. Configure the definition of your system's AMM controllers for ECE:
  - a. Go to the *BRM\_homelsyslamt* directory and open the *Infranet.properties* file in a text editor.
  - b. Verify that the following entry is set to true:

controller\_1\_event\_generation=true

- c. If more than one controller is defined in the file, ensure that each controller's controller\_controller\_number\_event\_generation= entry is set to true.
- d. Save and close the file.

The change takes effect the next time the **pin\_amt** utility is run. For more information, see the discussion about that utility in *BRM System Administrator's Guide*.

- 2. Configure ECE to use the AMM acknowledgment queue.
- 3. Verify that Customer Updater is correctly configured for your system and running.

ECE receives AMM business events from the BRM Account Synchronization DM database queue through Customer Updater. Because account migration involves multiple database schemas, Customer Updater must be configured to support all the database schemas in your system. It must also be configured to send AMM-related acknowledgments from ECE to your system's AMM acknowledgment queue.

- Verify that BRM Gateway is correctly configured for your system and running.
- 5. Verify that Rated Event Formatter is correctly configured for your system and running.

#### Configuring ECE to Use the AMM Acknowledgment Queue

The AMM acknowledgment queue is used to send AMM-related acknowledgments from ECE to BRM; it is an Oracle AQ database queue on the BRM system.

To configure ECE to use the AMM acknowledgment queue:

- 1. Access the ECE configuration MBeans:
  - a. Log on to the driver machine.
  - b. Start the ECE charging servers (if they are not started).



c. Connect to the ECE charging server node enabled for JMX management.

This is the charging server node set to **start CohMgt = true** in the *ECE\_homel* **oceceserver/config/eceTopology.conf** file.

- d. Start a JMX editor that enables you to edit MBean attributes, such as JConsole.
- e. In the editor's MBean hierarchy, find the ECE configuration MBeans.
- 2. Expand the ECE Configuration node.
- 3. Expand charging.connectionConfigurations.oracleQueueConnection.
- 4. Expand Attributes.
- Set the amtAckQueueName attribute to the fully qualified name of the acknowledgment queue to which the pin\_amt utility listens to AMM-related acknowledgment events:

schema.ammAcknowledgmentQueue

where:

- schema is the name of the BRM database schema in which the AMM acknowledgment queue resides.
- ammAcknowledgmentQueue is the name of the AMM acknowledgment queue.

For example:

PIN01.ECE\_AMT\_ACK\_QUEUE

6. Save your changes.

### Modifying Custom Client Applications for AMM

Custom client applications that connect to a specific database schema and try to access an object based on a POID may receive a PIN\_ERR\_INVALID\_OBJ error if the object was migrated to another database schema. You must modify any custom client applications to handle that error and then perform a global search to find the object's correct location.

To obtain the correct POID of an object, modify your application to call the PCM\_OP\_GLOBAL\_SEARCH opcode from its exception handling routine.

This example shows a call to the PCM\_OP\_GLOBAL\_SEARCH opcode when the PIN\_ERR\_INVALID\_OBJ error is returned from the Oracle DM:

```
/* Error? */
if (PIN_ERR_IS_ERR(ebufp)) {
  PIN_ERR_LOG_EBUF(PIN_ERR_LEVEL_ERROR,
  "sample_read_obj_search error", ebufp);
  }
  /* Call the DM to do a global search.*/
  PCM_OP(ctxp, PCM_OP_GLOBAL_SEARCH, 0, flistp, &r_flistp, ebufp);
  return;
```

The following opcodes return the PIN\_ERR\_INVALID\_OBJ error when a POID specified in an input flist is invalid:

- PCM\_OP\_READ\_OBJ
- PCM\_OP\_READ\_FLDS



- PCM\_OP\_WRITE\_FLDS
- PCM\_OP\_INC\_FLDS
- PCM\_OP\_DELETE\_OBJ
- PCM\_OP\_DELETE\_FLDS
- PCM\_OP\_TRANS\_OPEN

### Modifying Custom BRM Reports for AMM

After account migration, any custom BRM reports created prior to Infranet Release 6.2 ServicePak1 might retrieve and process duplicate data from your source and destination database schemas. For example, if an account object is migrated from database schema **0.0.0.1** to database schema **0.0.0.2**, your report might retrieve the account object from both database schemas.

To prevent this, use the Oracle Business Intelligence Publisher to add the following line to the WHERE clause of each custom report's query:

TABLE\_T.POID\_DB > 0

where TABLE\_T satisfies these conditions:

- It is a database table used by the report.
- It is one of the tables moved from the source database schema to the destination database schema when account data is migrated.
- It is associated with every record the report must retrieve.

#### Note:

If a single table does not satisfy the last condition, add the same line for several tables that together satisfy the last condition.

### AMM Return Codes and Messages

AMM uses the return codes and messages shown in Table 6-2. To automate account migration, you can modify your external application to check for the following return codes and respond appropriately.

Return Code Number	Return Code	Return Message
100	CONTROLLER_STARTED_SUCC	controller is started
101	CONTROLLER_STOPPED_SUCC	controller is stopped
102	CONTROLLER_PAUSED_SUCC	paused controller
103	CONTROLLER_CONTINUED_SUCC	continued controller
104	CONTROLLER_UP_SUCC	controller status is up
105	CONTROLLER_DOWN_SUCC	controller status is down

Return Code Number	Return Code	Return Message
106	SUBMIT_JOB_SUCC	submitted job
107	DELETE_JOB_SUCC	deleted job
108	PURGE_DATABASE_SUCC	purged database
109	ENABLE_JOB_SUCC	enabled job
110	REPORT_SUCC	generated report
111	ENABLE_BATCH_SUCC	enabled batch
200	CONTROLLER_RUNNING_ERROR	ERROR: controller is already running
201	CONTROLLER_PAUSED_ERROR	ERROR: controller is already paused
202	CONTROLLER_SPEC_ACCESS_ERROR	ERROR: controller specification does not exist
203	CONTROLLER_COMM_ERROR	ERROR: controller cannot be reached
204	SEARCH_SPEC_IO_ERROR	ERROR: account search specification could not be accessed
205	OPERATION_ROLLBACK_ERROR	ERROR: operation rollback
206	SEARCH_SPEC_PARSE_ERROR	ERROR: account search specification cannot be parsed
207	OPERATION_PERM_ERROR	ERROR: operation not permitted for current user OR job_id/batch_id does not exist
208	CONTROLLER_UNKNOWN_HOST_ERROR	ERROR: controller host not found
209	CONTROLLER_PROCESS_ERROR	ERROR: controller process could not be created
210	REPORT_PROCESS_ERROR	ERROR: external process interruption
211	REPORT_SCRIPT_ACCESS_ERROR	ERROR: reporting tool not found or report type does not exist
212	OPT_PARAM_REQ_ERROR	ERROR: one optional parameter is required
213	CONFIG_FILE_ACCESS_ERROR	ERROR: configuration file cannot be accessed
214	INIT_ERROR	ERROR: could not create new object
215	EMPTY_RESULTSET_ERROR	ERROR: account search resulted in 0 accounts, job submission failed
216	CONVERSION_CLASS_LOAD_ERROR	ERROR: dynamic loading of custom Conversion class failed

Table 6-2 (Cont.) AMM Return Codes and Messages

# 7 Modifying the Account Migration Manager

Learn how to create custom search criteria for the Oracle Communications Billing and Revenue Management (BRM) Account Migration Manager (AMM).

Topics in this document:

Creating Custom Account Search Criteria

### **Creating Custom Account Search Criteria**

AMM allows you to migrate accounts that meet custom criteria. For example, you can create custom criteria for finding and migrating accounts located in a certain state or belonging to a particular service provider.

To create a custom search criteria, perform these tasks:

- 1. Creating a Search Template
- 2. Adding New Entries to the Account Search Configuration File
- 3. Implementing and Compiling the Conversion Interface
- 4. Verifying Your Search Criteria

#### Creating a Search Template

AMM searches for accounts in a database schema by using SQL statements generated from an account search template. Before AMM can generate a SQL statement with new search criteria, you must first create a template for it in the custom account search properties file.

To create a template for your search criteria:

- Open the custom account search properties file (BRM\_homelapps/amt/com/portal/amt/ custom\_account\_search.properties) in a text editor.
- 2. Add SQL fragments for your search criteria by using the following syntax:

```
criteria_name=AND SQL_condition \n
```

Where:

- criteria\_name is the name of your selection criteria.
- SQL\_condition is a valid SQL condition that searches a BRM table and references one
  or more search variables, as shown below. Search variables must be surrounded by
  curly braces "{ }" and match an entry in the account\_search.cfg file.

```
condition_text '{SearchVariable}'...
```



Note:

SearchVariable must use a unique name and must not match one of the BRM-defined search variable names. For the list of BRM-defined search variables, see "Creating the Account Search Configuration File".

For information on the SQL condition, see your Oracle documentation.

3. Save and exit the file.

#### Sample Search Template

The following sample search template enables AMM to search for accounts located in a particular state. It tells AMM to search the ACCOUNT\_NAME\_INFO\_T table for objects with the **state** field set to a specified value.

```
# select accounts based on state
cust_acct_search_account_state_constraint=\
AND EXISTS \n\
(SELECT an.obj_id0 FROM account_nameinfo_t an \n\
WHERE an.obj id0 = a.poid id0 and an.state = '{account state}') \n
```

#### Adding New Entries to the Account Search Configuration File

When building a query, AMM replaces the search variables in your account search template with values from the account search configuration file (*BRM\_homelapps/amt/account\_search.cfg*).

To add an entry for your search variable:

- 1. Open the BRM\_homelapps/amt/account\_search.cfg file in a text editor.
- 2. Add your new search entry and comments to the file.



SearchVariable must match the search variable name referenced in the custom\_account\_search.properties file.

- You should add comments about the new search entry and

valid values.

SearchVariable=

3. Save and exit the file.

#### Sample Account Search Configuration File

A sample search entry for the **account\_state** search criteria:

```
# - Migrates accounts located in a specific state. Valid values
# are California and Oregon.
account state=
```



### Implementing and Compiling the Conversion Interface

Each custom search variable must have a corresponding Java implementation of the **Conversion** interface.

1. Run the appropriate profile script for your shell. This script sets your CLASSPATH and PATH environment variables to the appropriate values. For example, for the c shell:

```
% cd BRM_home/apps/amt
```

- % source profile.csh
- 2. Create a class that implements the Conversion interface.
- Save and compile your SearchVariable.java source file in the BRM\_homelapps/amt/com/ portal/amt directory.

```
% cd BRM_home/apps/amt/com/portal/amt
```

```
% javac SearchVariable.java
```

This creates a SearchVariable.class file in the same directory.

#### Note:

For AMM to successfully build a search with your custom search criteria:

- The class name must match the search variable name used in the custom\_account\_search.properties and account\_search.cfg files.
- The class must reside in the *BRM\_homelapps/amt/com/portal/amt* directory.

#### Sample Class Implementing Conversion Interface

The following sample class, **account\_state.class**, allows users to search for accounts from California or Oregon.

```
package com.portal.amt;
public class account_state implements Conversion {
    public String convert(String stateName) throws ConversionException {
        String stateCode = null;
        if(stateName.equals("California")) {
            stateCode = "CA";
        } else if(stateName.equals("Oregon")) {
            stateCode = "OR";
        } else {
            throw new
               ConversionException("Error: account_state " + stateName + " unknown.");
        }
        return(stateCode);
    }
}
```

### Verifying Your Search Criteria

Before migrating accounts with the new search criteria, verify its accuracy by:

1. Verifying That the Search Criteria Creates Valid SQL Statements



2. Verifying That the Search Criteria Finds Correct Accounts

#### Verifying That the Search Criteria Creates Valid SQL Statements

Use the "pin\_amt\_test" utility to verify that your custom search template generates a valid SQL statement.

- Open your account search configuration file (*BRM\_homelapps/amt/account\_search.cfg*) in a text editor.
- 2. Enter values for the source and destination database schemas, the batch size, and your custom search criteria.

For example, you might enter the following to test the **account\_state** criteria:

```
src_database=0.0.0.1
dest_database=0.0.0.2
start_creation_date=
end_creation_date=
product_name=
account_status=
bill_day_of_month=
max_accounts=
batch_size=50
poid_list=
account_state=California
```

- **3.** Save and exit the file.
- Use the pin\_amt\_test utility to generate a SQL statement with your new search criteria.

```
% pin_amt_test -c AccountSearchFile
```

If successful, the utility displays the resulting SQL statement. For example, the sample **account\_state** criteria generates the following:

```
Compile: account_search.cfg
------
account search SELECT statement:
-- acct_search_select: default
SELECT
DISTINCT a.poid_id0
FROM account_t a
WHERE
....
```

If the compilation failed, the utility returns the file name and line number where the error occurred. For example, the utility returns the following when users enter an invalid state for the sample **account\_state** criteria:

```
compile: account_search.cfg
-----
account_search.cfg:32: mapping of account_state field value Florida failed
```

5. Verify that the resulting SQL statement is correct.

#### Verifying That the Search Criteria Finds Correct Accounts

Use the **pin\_amt\_test** utility to verify that your search criteria works properly. This utility only displays results on the screen and does not migrate your objects.

To verify your search query:



- 1. Create a database schema with a precisely defined set of account data. The database schema should contain a small number of accounts.
- 2. Create a list of account POIDs that meet the custom criteria you are testing. For example, write down the POIDs of all accounts created in California.
- 3. Open your account search configuration file (*BRM\_homelapps/amt/account\_search.cfg*) in a text editor.
- Enter values for the source and destination database schemas, the batch size, and your custom search criteria.

For example, you might enter the following to test the **account\_state** criteria:

```
src_database=0.0.0.1
dest_database=0.0.0.2
start_creation_date=
end_creation_date=
product_name=
account_status=
bill_day_of_month=
max_accounts=
batch_size=50
poid_list=
account_state=California
```

- 5. Save and exit the file.
- Use the pin\_amt\_test utility to run your search query against the source database schema:

```
% pin_amt_test -e AccountSearchFile
```

7. The utility prints to the screen a list of account POIDs that meet your search criteria. Compare this list of POIDs with the list you created in step 2.

If the lists match, your new search criteria works properly and you can start using it to migrate accounts.

If the lists do not match, make sure:

- Your search template generates a valid SQL statement.
- Your search template, search configuration file, and class all refer to the same variable name.



# 8 Account Migration Utilities

Learn about the syntax and parameters for the Oracle Communications Billing and Revenue Management (BRM) account migration utilities.

Topics in this document:

- pin\_amt
- pin\_amt\_test

### pin\_amt

Use this utility to migrate accounts from a source database schema to a destination database schema in the same BRM database.

You define which accounts to migrate in the account search configuration file in the *BRM\_homelapps/amt* directory. See "Creating the Account Search Configuration File".

#### Note:

To connect to the BRM database, the **pin\_amt** utility needs a configuration file in the *BRM\_homelsyslamt* directory. For information on how to create this file, see "Connecting AMM to Your Database Schemas".

#### Location

BRM\_homelbin

#### Syntax

```
pin_amt [-f ConfigFileName] [-a ControllerID]
    [-c start | stop | pause | continue | status | log]
    [-s AccountSearchFile] [-d JobID]
    [-r list_jobs | job_details | group_details]
    [-p SourceDatabaseSchema] [-e JobID][-b JobID:BatchNumber][-h]
```

#### Parameters

#### -f ConfigFileName

Specifies the name of the configuration file that defines how to connect to each database schema in your system. By default, the **pin\_amt** utility looks in the *BRM\_homelsyslamt* directory. If your configuration file is located in a different directory, you must specify the entire path for the file.

If you use the *BRM\_homelsys/amt/Infranet.properties* file, you can ignore this parameter.

#### -a ControllerID

Specifies the AMM Controller to use.



Use this option only with the **-c** option and only when your system contains multiple AMM Controllers. If your system contains only one AMM Controller, ignore this option.

#### -c start | stop | pause | continue | status | log

Sets the AMM Controller. When your system contains multiple AMM Controllers, you must also use the **-a** option.

Use one of these options with the parameter:

-c start starts the AMM Controller.

-c stop stops the AMM Controller. If you stop the AMM Controller while it is processing a batch, it finishes processing the batch before stopping.

-c pause pauses the processing of a job in the queue. If you pause the Controller while it is processing a batch, it finishes processing the batch before pausing.

-c continue restarts processing a job that was paused.

-c status displays the current status of the AMM Controller.

-c log displays all AMM Controller transactions in real time through an Xterm window. To use this option, you must set the **DISPLAY** environment variable correctly.

#### -s AccountSearchFile

Specifies the name of the configuration file that defines which accounts to migrate. For information on how to create the file, look at the sample account search configuration file (*BRM\_homelapps/amt/account\_search.cfg*).

By default, the **pin\_amt** utility looks in the current working directory. If your configuration file is located in a different directory, you must specify the entire path for the file.

#### -d JobID

Deletes the specified job from the job management tables. When deleting a job that migrated successfully, this option also purges all migrated accounts from the source database schema.

#### -e JobID

Enables the specified job in the queue.

#### -r list\_jobs | job\_details | group\_details

Runs the preconfigured report. Use one of these options with the parameter:

-r list\_jobs displays the status of all jobs currently in the queue.

- -r job\_details displays the details of the specified job.
- -r group\_details displays the details of the specified account group.

#### -p SourceDatabaseSchema

Purges all accounts that were successfully migrated from the source database schema. For example, to purge invalid objects from your primary schema, enter the following:

pin\_amt -p 0.0.0.1

-h

Displays the syntax and parameters for this utility.

#### -b JobID:BatchNumber

Changes the status of the batch from FAILED to NOT PROCESSED, and the job from FINISHED to DISABLED. For information, see "About Batch Status Flags" and "About Job Status Flags".

#### Results

The pin\_amt utility notifies you when it successfully completes a command.

For error information about each job, run a report or look in the AMM Mover log file. The log file is in the directory specified by the **0.0.0**.*x*\_mover\_log\_file\_dir entry in the Infranet.properties file.



For error information about the AMM Controller, look in the AMM Controller log file. The log file is in the directory specified by the **controller\_***N***\_log\_directory** entry in the **Infranet.properties** file.

The history of all **pin\_amt** commands is located in the **pin\_amt** log file.

### pin\_amt\_test

Use this utility to test your custom BRM account search criteria. This utility safely runs your search criteria against a source database schema and displays either a SQL SELECT statement or a list of account POIDs meeting your search criteria.

You define which custom search criteria to test in the account search configuration file (*BRM\_homelapps/amt/account\_search.cfg*). See "Creating the Account Search Configuration File".

#### Note:

To connect to the BRM database, the **pin\_amt\_test** utility needs a configuration file in the *BRM\_homelsyslamt* directory. For information on how to create this file, see "Connecting AMM to Your Database Schemas".

#### Location

BRM\_homelapps/amt

Syntax

#### **Parameters**

#### -f ConfigFileName

Specifies the name of the configuration file that defines how to connect to each database schema in your system. By default, the **pin\_amt\_test** utility looks in the *BRM\_homelsyslamt* directory. If your configuration file is located in a different directory, you must specify the entire path for the file.

If you use the BRM\_homelsyslamt/Infranet.properties file, you can ignore this parameter.

#### -c AccountSearchFile

Displays the SQL SELECT statement generated with the account search criteria specified in *AccountSearchFile*.

By default, the **pin\_amt\_test** utility looks in the current working directory. If your account search file is located in a different directory, you must specify the entire path for the file.

#### -e AccountSearchFile

Runs the SQL SELECT statement for the specified search criteria against the source database schema and displays the list of account POIDs meeting the search criteria. By default, the **pin\_amt\_test** utility looks in the current working directory. If your account search file is located in a different directory, you must specify the entire path for the file.

#### -h

Displays the syntax and parameters for this utility.



#### Results

The **pin\_amt\_test** utility prints to the screen the SQL SELECT statement, a list of accounts meeting your search criteria, or an Oracle error message. For information about Oracle error messages, see your Oracle documentation.



# A AMM Job Management Tables

This appendix describes the tables used for account migration in Oracle Communications Billing and Revenue Management (BRM).

Topics in this document:

• About AMM Job Management Tables

### About AMM Job Management Tables

Job management tables are created on your database schemas during installation and are populated with information about each migration job.

The AMM installer creates the tables listed in Table A-1 on your schemas:

Table A-1 AMM Job Management Tables

Table Name	Schema	Description	When Populated
AMT_ACCOUNT_BATCH_TABLE_T	Primary only	Stores the list of tables containing data to migrate for a particular batch.	Populated by the AMM Mover when it migrates a particular batch.
AMT_METADATA_T	All schemas	AMM data dictionary. This lists all default BRM tables as well as any custom tables you created.	During installation and when you run <b>pin_amt_install.pl -m</b> to refresh the AMM data dictionary.
		If you add any tables after you install AMM, you must refresh the AMM data dictionary. See "Configuring AMM for New Custom Tables".	
AMT_POID_TYPE_MAP_T	All schemas	Maps the POID type to the table name. This table is static.	During installation and when you run <b>pin_amt_install.pl -m</b> to refresh the data dictionary.

# B Account Migration Flags

This appendix describes the flags used in account migration in Oracle Communications Billing and Revenue Management (BRM).

Topics in this document:

- About Job Status Flags
- About Batch Status Flags
- About Group Status Flags

### About Job Status Flags

The AMM software sets jobs to a status listed in Table B-1. You can see a job's status by running a **list\_jobs** report. See "Monitoring Job Status".

Status	Description
DISABLED	The job has been submitted but not enabled.
NOT_PROCESSED	The account migration job is enabled and waiting in the queue to be processed.
PRE_MIGRATION_WAITING	AMM is notifying ECE to suspend events for all accounts in the job.
PRE_MIGRATION	ECE acknowledged that it is suspending events for all accounts in the job. AMM is waiting a specified amount of time before starting migration.
READY	The job is ready to be processed.
IN_PROGRESS	The job is being processed by the AMM Controller.
FAILED	The job has been terminated.
BAL_MIGRATED	The account discount balance migrated successfully.
POST_MIGRATION_WAITING	AMM is notifying ECE that the job migrated successfully.
POST_MIGRATION	ECE acknowledged that it updated all account information.
PRE_JOB_RECYCLE	AMM is notifying ECE to resume processing events for accounts in the job.
JOB_RECYCLE	ECE acknowledged that it is ready to begin reprocessing events for accounts in the job.
FINISHED	The job has completed successfully.

#### Table B-1 Job Status Flags

### About Batch Status Flags

AMM sets account batches to a status listed in Table B-2. You can check a batch's status by running a **job\_details** report. See "Checking Job Details".

#### Table B-2 Batch Status Flags

Status	Description
NOT_PROCESSED	The account batch has not yet been migrated.
IN_PROGRESS	The account batch is currently being migrated.
FAILED	The account batch failed to migrate. All changes to the database have been rolled back.
FINISHED	The account batch migrated successfully. All changes to the database have been committed.

### About Group Status Flags

AMM sets account groups to a status listed in Table B-3. You can check an account group's status by running a **group\_details** report. See "Checking Account Group Details".

#### Table B-3Group Status Flags

Status	Description
NOT_PROCESSED	The account group has not yet been migrated.
GROUP_DISABLING	All account group members are being disabled in the source database schema. That is, AMM is marking all account group members as invalid to prevent applications from accessing those accounts.
FAILED	AMM did not disable all account group members in the source schema.
GROUP_READY	All account group members were successfully disabled in the source schema. AMM can begin processing batches.
GROUP_IN_PROGRESS	The account group is currently being migrated.
GROUP_FAILED	The account group failed to migrate to the destination schema.
GROUP_FINISHED	The account group migrated successfully.

# C AMM Entity Relationship Diagram

This appendix describes the entity relationship diagram for the Oracle Communications Billing and Revenue Management (BRM) Account Migration Manager (AMM).

Topics in this document:

AMM Entity Relationship Diagram

### AMM Entity Relationship Diagram

Figure C-1 shows the Account Migration Manager Entity Relationship (ER) Diagram.



