

Oracle® Banking Payments

India NEFT User Guide



Release 14.7.0.0.0

F90928-02

February 2025

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Banking Payments India NEFT User Guide, Release 14.7.0.0.0

F90928-02

Copyright © 2017, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1 Preface

Purpose	1-1
Audience	1-1
Documentation Accessibility	1-1
Critical Patches	1-2
Diversity and Inclusion	1-2
Conventions	1-2
Related Resources	1-2
Screenshot Disclaimer	1-2
Acronyms and Abbreviations	1-3
Basic Actions	1-3
Symbols, Definitions and Abbreviations	1-4

2 Domestic Low Value Payments - NEFT

Overview of National Electronic Funds Transfer (NEFT)	2-1
NEFT Maintenance	2-2

3 NEFT Outbound Payments

NEFT Outbound Transaction Input	3-1
NEFT Outbound Transaction Input	3-1
Main Tab	3-3
Additional Details Tab	3-5
Pricing Tab	3-6
UDF Button	3-7
MIS Button	3-8
Saving of Outbound Transaction	3-9
NEFT Inbound Transaction Summary	3-9
NEFT Outbound Transaction View	3-11
Exceptions Tab	3-12
UDF Button	3-12
MIS Button	3-13
View Queue Action Log	3-14

Accounting Details	3-15
All Messages	3-16
View Repair Log	3-17
NEFT Outbound Transaction View Summary	3-17
NEFT Outbound Transaction Booking via Upload	3-18
Single Payment Service	3-18
C2B File Upload	3-19
NEFT Outbound Payments Processing	3-19
NEFT Outbound Payment Validations	3-19
Beneficiary ID Validation	3-20
Mandatory Fields/ Referential Data Checks	3-20
Account Type Validation	3-21
LEI Validation	3-21
NRE Account Validation	3-22
Processing Cutoff Check	3-22
Intra Bank Transfer Check	3-22
Network Validations and Special Character Replacement	3-22
Computation of Charge and Tax	3-23
Exception Queue	3-23
Authorization Limit Check	3-23
Transaction Cutoff Time Validations	3-23
Sanction Check	3-24
FX Limit Check	3-24
External Credit Approval Check	3-24
Network Cutoff Time Check	3-24
Transaction Accounting	3-24
Dispatch Accounting	3-25
Future Valued Transaction Processing	3-25
Branch Holiday Parameter	3-25
N06 Message Generation and Dispatch	3-26
Notification	3-26
Indo Nepal Remittance Processing	3-26
Prefunded Payments Processing	3-26
NEFT Message Browser	3-27
NEFT Outbound Message Browser	3-27
Negative Acknowledgement Processing Details	3-29
NEFT Acknowledgment Processing	3-30
SFMS ACK/NAK Messages Processing	3-30
Credit Confirmation ACK Message - N10 Processing	3-31

4 NEFT Inbound Payments

NEFT Inbound Transaction Input	4-1
NEFT Inbound Transaction Input	4-1
Main Tab	4-2
Additional Details Tab	4-3
Pricing Tab	4-4
UDF Button	4-5
MIS Button	4-6
NEFT Inbound Transaction Summary	4-7
NEFT Inbound Payment View	4-8
Exceptions Tab	4-10
UDF Button	4-10
MIS Button	4-11
View Queue Action Log	4-12
Accounting Details	4-13
All Messages	4-14
View Repair Log	4-15
NEFT Inbound Payments View Summary	4-15
NEFT Inbound Payments Processing	4-17
NEFT Inbound Payment Validations	4-17
Initial Validations	4-17
Business Override Checks	4-17
Process Exception Checks	4-18
Network Validations	4-18
LEI Validation	4-18
Non - NRE A/c to NRE A/c Payment Check	4-18
Credit Card Payment Processing	4-19
Authorization Limit Check	4-20
Future Valued Check	4-20
FX Limit Check	4-20
N04 and N02 Messages Matching & Release Final Credit	4-20
Accounting Handoff	4-21
Notifications	4-21
NEFT Message Browser	4-21
NEFT N04 Browser	4-21
View Message	4-22
View Settlement	4-23
View Accounting	4-25
NEFT Inbound Message Browser	4-25
NEFT Acknowledgment Processing	4-27
Message Dispatch - Outbound N10 Credit Confirmation ACK Message	4-27

NEFT N04 Manual Initiation	4-27
NEFT N04 Input	4-27
NEFT N04 Input Detailed Summary	4-28
NEFT N04 Manual Processing	4-29
N02 Message processing	4-30

5 NEFT Return Payments

NEFT Inbound Return Payments	5-1
NEFT Inbound Payments - Returns Processing	5-1
NEFT Return of Inbound Payment	5-3
NEFT Return of Inbound Payment Summary	5-4
NEFT Outbound Return Payments	5-5
NEFT Outbound Payments - Returns Processing	5-6
NEFT Return of Outbound Payment	5-7
NEFT Return of Outbound Payment Summary	5-8

6 NEFT Reject Payments

NEFT - Network Rejects	6-1
N03 Transaction Summary View	6-1
N03 Message Processing	6-2

1

Preface

- [Purpose](#)
- [Audience](#)
This manual is intended for the following User/User Roles:
- [Documentation Accessibility](#)
- [Critical Patches](#)
- [Diversity and Inclusion](#)
- [Conventions](#)
- [Related Resources](#)
- [Screenshot Disclaimer](#)
- [Acronyms and Abbreviations](#)
- [Basic Actions](#)
- [Symbols, Definitions and Abbreviations](#)
The following are some of the Symbols you are likely to find in the manual:

Purpose

This guide is designed to help acquaint you with the Oracle Banking Payments application. This guide provides answers to specific features and procedures that the user need to be aware of the module to function successfully.

Audience

This manual is intended for the following User/User Roles:

Table 1-1 User Roles

Role	Function
Implementation & IT Staff	Implementation & Maintenance of the Software

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Critical Patches

Oracle advises customers to get all their security vulnerability information from the Oracle Critical Patch Update Advisory, which is available at [Critical Patches](#), [Security Alerts and Bulletins](#). All critical patches should be applied in a timely manner to make sure effective security, as strongly recommended by [Oracle Software Security Assurance](#).

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Related Resources

For more information on any related features, refer to the following documents:

- *Getting Started User Guide*
- *Oracle Banking Security Management System User Guide*
- *Oracle Banking Microservices Platform Foundation User Guide*
- *Routing Hub Configuration User Guide*
- *Oracle Banking Common Core User Guide*
- *Interest and Charges User Guide*
- *Oracle Banking Liquidity Management Configuration Guide*
- *Oracle Banking Liquidity Management File Upload User Guide*

Screenshot Disclaimer

Personal information used in the interface or documents is dummy and does not exist in the real world. It is only for reference purposes.

Acronyms and Abbreviations

The list of the acronyms and abbreviations that are used in this guide are as follows:

Table 1-2 Acronyms and Abbreviations

Abbreviation	Description
DDA	Demand Deposit Accounts
ECA	External Credit Approval
EOD	End of Day
IBAN	International Bank Account Number

Basic Actions

The basic actions performed in the screens are as follows:

Table 1-3 Basic Actions

Actions	Description
New	Click New to add a new record. The system displays a new record to specify the required data. The fields marked with asterisk are mandatory. - This button is displayed only for the records that are already created.
Save	Click Save to save the details entered or selected in the screen.
Unlock	Click Unlock to update the details of an existing record. The system displays an existing record in editable mode. - This button is displayed only for the records that are already created.
Authorize	Click Authorize to authorize the record created. A maker of the screen is not allowed to authorize the same. Only a checker can authorize a record. - This button is displayed only for the already created records. For more information on the process, refer Authorization Process.
Approve	Click Approve to approve the initiated record. - This button is displayed once the user click Authorize .
Audit	Click Audit to view the maker details, checker details of the particular record. - This button is displayed only for the records that are already created.
Close	Click Close to close a record. This action is available only when a record is created.
Confirm	Click Confirm to confirm the action performed.
Cancel	Click Cancel to cancel the action performed.
Compare	Click Compare to view the comparison through the field values of old record and the current record. - This button is displayed in the widget once the user click Authorize .
View	Click View to view the details in a particular modification stage. - This button is displayed in the widget once the user click Authorize .

Table 1-3 (Cont.) Basic Actions

Actions	Description
View Difference only	Click View Difference only to view a comparison through the field element values of old record and the current record, which has undergone changes. - This button is displayed once the user click Compare .
Expand All	Click Expand All to expand and view all the details in the sections. - This button is displayed once the user click Compare .
Collapse All	Click Collapse All to hide the details in the sections. - This button is displayed once the user click Compare .
OK	Click OK to confirm the details in the screen.

Symbols, Definitions and Abbreviations

The following are some of the Symbols you are likely to find in the manual:

Table 1-4 Symbols





Icons	Function
	Exit
	Add row
	Delete row
	Option List

Table 1-5 Common Icons and its Definitions

Icon Names	Applicable Stages	Operation
Minimize	Initiation, Approval and Hand-off Retry	Users can minimize the transaction input screen. When the screen is minimized, it appears as to a separate tab within the same web page.
Maximize	Initiation, Approval and Hand-off Retry	User can maximize the transaction input screen.
Close	Initiation, Approval and Hand-off Retry	Users can close the transaction input screen. The system displays a warning message to the user that any unsaved data would be lost. User can either choose to ignore the message and close the screen or choose to 'save and close' the transaction.

2

Domestic Low Value Payments - NEFT

- [Overview of National Electronic Funds Transfer \(NEFT\)](#)
National Electronic Funds Transfer (NEFT) is a nation-wide payment system facilitating one-to-one funds transfer in India. Retail and Corporate Customers make use of this mode of payment. It is done via electronic messages conforming as per SFMS standards.
- [NEFT Maintenance](#)

Overview of National Electronic Funds Transfer (NEFT)

National Electronic Funds Transfer (NEFT) is a nation-wide payment system facilitating one-to-one funds transfer in India. Retail and Corporate Customers make use of this mode of payment. It is done via electronic messages conforming as per SFMS standards.

Key features of National Electronic Funds Transfer (NEFT)

- Supports following transactions types and messages:
 - Outbound, Inbound and Return transactions
 - N10 Credit confirmation and F20,F25,F26 and F27 Acknowledgement messages
 - End of Day (EOD) and Start of Day (SOD) messages
 - Indo Nepal Remittances
 - Inbound credit to Loan account and GL account
 - Inbound transaction for Credit Card payments
 - Outbound Prefunded transactions
- Supports following functionalities:
 - 24x7 processing
 - Legal Entity Identifier (LEI) validations
 - Account Type validations - NRE Account
 - Beneficiary registration for outbound transactions
 - Non STP functionality for inbound transactions
 - Bulking of individual N06 messages (10 messages per bundle) and dispatching to SFMS
 - Return processing as per settlement batches
 - Notification to channels on transaction processing
- Initiation of NEFT Outbound transactions using following options:
 - UI screens
 - Single Payment Service
 - Bulk file upload - C2B Pain.001 file
 - GEFU Upload

- Supports maintenance for SFMS Connectivity

NEFT Maintenance

This section lists the key common maintenance that are required for processing of outbound and inbound NEFT Payments:

- India Payments Common Preferences (PMDNFTPF)
- Network Maintenance (PMDNWMNT)
- Source Maintenance (PMDSORCE)
- Source Network Preferences (PMDSORNW)
- Queue Connection Profile Maintenance (PMDQPROF)
- Beneficiary Registration (PMDBENRN)
- India Payment Account Preferences (PMDEXACP)
- India Tax Preference Detailed (PMDINTXP)
- Dispatch Parameters Maintenance (PADISPTM)
- IFSC Directory (PMDIFSMN)
- Branch and IFSC Code Mapping (PMDIFSBR)

For more details on above mentioned maintenance screens, refer to Payments Core User Guide and Common Core - Core Entities and Services User Guide.

3

NEFT Outbound Payments

- [NEFT Outbound Transaction Input](#)
- [NEFT Outbound Payments Processing](#)
- [NEFT Message Browser](#)
- [NEFT Acknowledgment Processing](#)

NEFT Outbound Transaction Input

- [NEFT Outbound Transaction Input](#)
- [NEFT Outbound Transaction View](#)
- [NEFT Outbound Transaction Booking via Upload](#)

NEFT Outbound Transaction Input

The NEFT Outbound Transaction Input screen allows user to perform NEFT Outbound transaction. All transactions entered using this screen has payment type as 'NEFT' and transaction type as 'Outbound'.

1. On Homepage, specify **PTDOTONL** in the text box, and click next arrow.
NEFT Outbound Transaction Input screen is displayed.

Figure 3-1 NEFT Outbound Transaction Input

- On **NEFT Outbound Transaction Input** screen, specify the fields.
For more information about the fields, refer to field description below:

Table 3-1 NEFT Outbound Transaction Input - Field Description

Field	Description
Transaction Branch	System defaults the Transaction Branch on clicking 'New'.
Host Code	System defaults the Host Code of transaction branch on clicking 'New'.
Source Code	Specify the Source Code via which the payment request is received from the list of values. This lists all source codes created in this host.
Network Code	System displays the Network Code if only one Network is maintained with payment type as NEFT for the host code. If more than one networks are present, you can specify the network code from the available list of values.
Transaction Reference Number	System generates the transaction reference number. For more details on the format, refer the Payments Core User Guide. <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> Note: This transaction reference number is passed in the UTR (Unique Transaction Reference Number) - tag 2020, in the NEFT messages.</p> </div>

Table 3-1 (Cont.) NEFT Outbound Transaction Input - Field Description

Field	Description
UTR Number	System generates UTR number for NEFT outgoing transactions in following format: 'N' + Julian Date + 10-digit unique Number. Refer format table given below.
Related Reference	System defaults transaction reference number. However you can modify this.
Source Reference	System defaults the Source Reference Number for the payment requests received from channels or any other source. You can input the value for manually booked transaction. The maximum length of this field accepts up to 35 characters.
Prefunded Payments	Check this box to indicate that Pre funded payments are allowed for the source.
Indo Nepal Remittance	Select this checkbox to indicate that the outgoing NEFT is Indo Nepal Remittance.

Component	Description	Digits	Position, Length	Example
Initial Character for NEFT	It is always 'N'	1	1,1	N
Date	Julian Date (DDYY)	5	2,5	1-Sep-2022 = 24422
10-digit No	Server ID - If clustered, each app server will have a number	2	7,2	1 App Server = 01
--	Seconds - Seconds Elapsed past date change 1 Minute = 00060 Seconds 1 Hour = 03600 Seconds 24 Hours = 86400 Seconds Left Padded with 0s	5	9,5	For e.g. If time is 18:00 as per the host date, then Seconds will be calculated as 64800.
--	Sequence No - Sequential Serial Number generated per second Sequence	3	13,3	For e.g., Seconds and Serial Number Representation for 5 Transactions processed @ 18:00 648000001 - 64800004 64800 - Seconds, 001 - Serial Number

- [Main Tab](#)
- [Additional Details Tab](#)
- [Pricing Tab](#)
- [UDF Button](#)
- [MIS Button](#)
- [Saving of Outbound Transaction](#)
- [NEFT Inbound Transaction Summary](#)

Main Tab

- On **Main Tab**, specify the fields.

Figure 3-2 NEFT Inbound Transaction Input - Main Tab

Table 3-2 NEFT Inbound Transaction Input_Main Tab - Field Description

Field	Description
Creditor Details	All open and authorized accounts maintained in External Account maintenance are listed. You can select the creditor account. The list of values search page displays the Account along with Customer No & Customer Name.
Beneficiary Account Number	Specify the Beneficiary Account Number. You can select the Beneficiary Account Number from the list of values. The list of values lists Loan Account numbers along other customer account.
Beneficiary Account Type	System defaults the Beneficiary Account Type based on the Beneficiary Account Number selected.
Beneficiary Name	System defaults Beneficiary name on the Beneficiary Account Number selected.
Credit Account Number	System displays the biller account which is resolved based on the Credit Card Number received in N02 file as Beneficiary Account.
Credit Account Currency	System displays the Credit Account Currency.
Credit Account Branch	System displays the Credit Account Branch.
Transaction Currency	System defaults the Transaction Currency as 'INR'. This is not modifiable.
Transaction Amount	Specify the Transaction Amount. This field is populated as the transfer amount converted in credit account currency.
Beneficiary Bank Details	--
Debtor Details	Specify the Debtor Account Number.
Debtor Account Type	Select the Debtor Account type from the following: <ul style="list-style-type: none"> • Savings Bank (10) • Current Account (11) • Cash Credit (13) • Loan Account (14) • Overdraft (12) • NRE (40)
Debtor Name	Specify the Debtor name for the Debtor account specified.
IFSC Code	Select the IFSC Code from the list of values. All the valid IFSC codes are listed.

Table 3-2 (Cont.) NEFT Inbound Transaction Input_Main Tab - Field Description

Field	Description
Booking Date	System defaults the Booking Date as current date.
Instruction Date	System defaults this date as current date and the payment is processed on the Instruction Date. System allows to modify the Instruction Date.
Activation Date	System derives the Activation Date on clicking Enrich button.

Additional Details Tab

- On **Additional Details Tab**, specify the fields.

Figure 3-3 NEFT Outbound Transaction Input - Additional Details Tab

The screenshot shows a web form with the following sections and fields:

- Debtor Additional Details:** Address Line 1, Address Line 2, Address Line 3, Address Line 4.
- Creditor Additional Details:** Address Line 1, Address Line 2, Address Line 3, Address Line 4.
- Sender To Receiver Information:** Debtor LEI, Beneficiary LEI, Sender To Receiver Information 3, Sender To Receiver Information 4, Sender To Receiver Information 5, Sender To Receiver Information 6.
- Indo Nepal Information:** Beneficiary Identification, Beneficiary Contact Number, Commission, NSBL Account Number, Other Bank Account Number, Other Bank Name.

At the bottom, there is a blue bar with the following fields: UDF | MIS, Maker ID, Maker Date Stamp, Checker ID, Checker Date Stamp, Authorization Status, and an Exit button.


This tab contains the below fields to capture the address details of debtor/creditor and remittance information from the sender to receiver.

Table 3-3 NEFT Outbound Transaction Input_Additional Details Tab - Field Description

Field	Description
Debtor Additional Details	--
Address Line 1 to 4	Specify the Address.
Creditor Additional Details	--
Address Line 1 to 4	Specify the Address.
Sender To Receiver Information	System populates the static text automatically on clicking Enrich button in the Sender to Receiver Information fields, if the Debtor account type is NRE.
Debtor LEI	Specify the Debtor LEI.
Beneficiary LEI	Specify the Beneficiary LEI.
Sender to Receiver Information 3-6	Specify the Sender to Receiver Information.
Indo Nepal Information	--
Beneficiary Identification	Specify the citizenship/ PAN card/ passport number of the beneficiary or 'X' if no information is available.

Table 3-3 (Cont.) NEFT Outbound Transaction Input_Additional Details Tab - Field Description


Field	Description
Beneficiary Contact Number	Specify the mobile or land line number of the beneficiary.
Commission	Specify the Commission/Charges depending upon the transaction amount.
NSBL Account Number	Specify the Account number of customer to be credited, if user is account holder in Nepal State Bank or 'X' if cash is to be disbursed.
Other Bank Account Number	Specify the Account number of customer to be credited, if user is account holder in other bank or 'X' if not available.
Other Bank Name	Specify the name of other bank or 'X' if not available.

 **Note:**
For Indo Nepal Information fields validation details, refer to [Indo Nepal Remittance Processing](#).

Pricing Tab

- On **Pricing Tab**, specify the fields.

Figure 3-4 NEFT Inbound Transaction Input - Pricing Tab





You can view the pricing details populated by system in this screen.

Table 3-4 NEFT Inbound Transaction Input_Pricing Tab - Field Description

Field	Description
Pricing Component	System defaults the pricing component based on the Pricing code linked in Network Currency Preferences.
Pricing Currency	System defaults the Pricing Currency.

Table 3-4 (Cont.) NEFT Inbound Transaction Input_Pricing Tab - Field Description

Field	Description
Pricing Amount	<p>System defaults the pricing amount from Pricing Value Maintenance screen (PPDVLMNT) as applicable for the payment value date, Payment Source code and Debit Customer Service Model. However you can modify this value.</p> <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> Note:</p> <p>Currency conversions related to charge computation are completed and final amount is populated component wise in the Pricing Tab.</p> </div>
Waived	<p>System defaults the waiver. However you can modify this value.</p> <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> Note:</p> <p>If charge/tax is already waived at price value maintenance, then you cannot uncheck the waiver flag.</p> </div>
Debit Amount	System defaults the customer debit amount for charge/tax.

UDF Button

1. This sub-screen defaults values of UDF fields that are part of the UDF group specified for the 'Manual' source.
2. Click the **UDF button** to invoke the 'UDF' sub-screen.
3. On **UDF Button**, specify the fields.

Figure 3-5 UDF Button




Table 3-5 UDF Button - Field Description

Field	Description
Field Label	System displays all fields that are part of the associated UDF group.

Table 3-5 (Cont.) UDF Button - Field Description

Field	Description
Field Value	System displays the default value, where exists for the UDF fields. You can change the default value or specify value for other fields (where default value does not exist).

MIS Button

1. You can maintain the MIS information for the Transaction. If the MIS details are not entered for the Transaction the same is defaulted from the product maintenance.
2. Click the **MIS** button to invoke the 'MIS' sub-screen.
3. On **MIS Button**, specify the fields.

Figure 3-6 MIS Button

The screenshot shows a window titled "MIS Details" with a close button (X) in the top right corner. At the top, there is a "Transaction Reference Number *" field and a "MIS Group" dropdown menu with a "Default" button next to it. Below these are two main sections: "Transaction MIS" and "Composite MIS". Each section contains a list of input fields, each with a small "p" icon to its right. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

Table 3-6 MIS Button - Field Description

Field	Description
Transaction Reference	System displays the transaction reference number of the transaction.
MIS Group	You can select the MIS group code from the option list, or specify the code for the MIS group in the Source maintenance. The system displays all valid MIS groups for different sources in the MIS group list in the Source maintenance. When booking a transaction from this screen, the MIS group linked to the 'Manual' source is populated by default.
Default button	After selecting a MIS group different from the default MIS Group, click this button to populate any default MIS values and link them to the Transaction MIS and Composite MIS classes.
Transaction MIS	You can populate the default MIS values for Transaction MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.

Table 3-6 (Cont.) MIS Button - Field Description

Field	Description
Composite MIS	You can populate the default MIS values for Composite MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.

Saving of Outbound Transaction

System performs the following mandatory field checks and the referential checks during the save of NEFT Outbound payment transaction. If any of the below validation fails, then the transaction is rejected with an error code.

Following fields are mandatory for requesting NEFT Outbound payments:

- Transaction Branch
- Source Code
- Network code
- Source Reference (for requests received through other channels, Source reference is updated automatically)
- Debtor Account Number
- IFSC Code
- Beneficiary Account Number (creditor account)
- Beneficiary Account Type
- Transfer Currency
- Transfer Amount
- Debit/Credit Value Date

Following are the validations on clicking the 'Save' button:

- On the requests initiated from channels, Source reference number is expected as mandatory.
- System validates whether account record is open and authorized.
- Holiday check for instruction date is done, based on the local branch holidays maintained
- Upon saving the transaction, system throws error messages for validation failures, if any. For the error messages displayed, respective action can be taken and can be re-submitted.

NEFT Inbound Transaction Summary

1. On Homepage, specify **PTSITONL** in the text box, and click next arrow.
NEFT Inbound Transaction Summary screen is displayed.

Figure 3-7 NEFT Inbound Transaction Summary

2. Search using one or more of the following parameters:
 - Authorized
 - Source Code
 - Network Code
 - Transaction Branch
 - Transaction Reference Number
 - Reference Number
 - Source Reference Number
 - Batch Time
 - Booking Date
 - Instruction Date
 - Activation Date
 - Transaction Currency
 - Transaction Amount
 - Debtor Account Number
 - Debtor Account Type
 - IFSC Code
 - Beneficiary Account Number
 - Beneficiary Account Type
 - Transaction
 - Queue Code
 - Credit to GL
3. Once you specified the parameters, click the Search button. System displays the records that match the search criteria.

NEFT Outbound Transaction View

The NEFT Outbound Transaction View screen allows user to view the NEFT Outbound transactions.

1. On Homepage, specify **PTDOVIEW** in the text box, and click next arrow.
NEFT Outbound Transaction View screen is displayed.

Figure 3-8 NEFT Outbound Transaction View

The screenshot displays the 'View Detailed' window for NEFT Outbound Transaction View. It features a search bar at the top with the text 'Enter Query'. Below this, there are several sections of input fields:

- Transaction Information:** Transaction Branch *, Host Code *, Source Code *, Network Code *, Return Of Inbound (No), Transaction Reference *, UTR Number, Related Reference, Source Reference, File Reference Number.
- Debtor Details:** Debtor Account Number, Debtor Account Type, Debtor Name, Customer No, Debtor Information (SMS), Debtor Mobile Number, Debtor Email ID.
- Payment Details:** Booking Date (YYYY-MM-DD), Requested Value Date (YYYY-MM-DD), Value Date (YYYY-MM-DD), Activation Date (YYYY-MM-DD), Transaction Currency, Transaction Amount, Remarks, Debit Value Date (YYYY-MM-DD), Credit Value Date (YYYY-MM-DD).
- External System Status:** Sanction Check Status, Sanction Check Reference, External Credit Approval Status, External Credit Approval Reference.
- Dispatch Details:** Dispatch Status, Dispatch Reference Number, Dispatch Date (YYYY-MM-DD), Return Message Type, Reason Code, Reason Description.
- Beneficiary Bank Details:** Beneficiary ID, IFSC Code, Bank Name, Branch Name.
- Beneficiary Details:** Beneficiary Account Number, Beneficiary Account Type, Beneficiary Name.
- Transaction Status:** Transaction Status (dropdown), Prefunded Payments (checkbox), Indo Nepal Remittance (checkbox).
- Pending Queue Details:** Queue Code (dropdown), View Queue button.
- Sanction Seizure:** Sanction Seizure (checkbox).
- Credit Confirmation Details:** N10 Message reference, Credited Date, Credited Time.

At the bottom, there are navigation tabs: Main, Additional Details, Pricing, Exceptions. A footer bar contains: UDF | MIS | View Queue Action | Accounting Entries | All Messages | View Repair Log. The bottom-most bar includes: Maker ID, Maker Date Stamp, Checker ID, Checker Date Stamp, Authorization Status, and an Exit button.

2. From this screen, click **Enter Query**. The Transaction Reference field gets enabled which opens an LOV screen.
3. Click the Fetch button and select the required transaction.
4. Along with the transaction details in the Main and Pricing tabs, you can also view the Status details for the following:
 - External System Status
 - Transaction Status (updated as 'Settled' on receiving N10 acknowledgment message)

- Pending Queue Details
 - Sanction Seizure
 - Dispatch Details
 - Credit Confirmation Details
5. Click **Execute Query** to populate the details of the transaction in the Outbound NEFT Transaction View screen. System displays all the fields in the below mentioned tabs based on the transaction reference number selected.

For more details on Main, Additional Details and Pricing tabs refer to 'PTDOTONL' screen details above.

- [Exceptions Tab](#)
- [UDF Button](#)
- [MIS Button](#)
- [View Queue Action Log](#)
- [Accounting Details](#)
- [All Messages](#)
- [View Repair Log](#)
- [NEFT Outbound Transaction View Summary](#)

Exceptions Tab

- On **Exceptions Tab**, specify the fields.

Figure 3-9 NEFT Outbound Transaction View - Exceptions Tab

Click on the 'Exceptions' tab to invoke this screen. All the details pertaining to Return Details, Network Reject Details and External System Status id are displayed here for the entered Transaction Reference Number.

UDF Button

1. This sub-screen defaults values of UDF fields that are part of the UDF group specified for the 'Manual' source.

2. Click the **UDF button** to invoke the 'UDF' sub-screen.
3. On **UDF Button**, specify the fields.

Figure 3-10 UDF Button




Table 3-7 UDF Button - Field Description

Field	Description
Field Label	System displays all fields that are part of the associated UDF group.
Field Value	System displays the default value, where exists for the UDF fields. You can change the default value or specify value for other fields (where default value does not exist).

MIS Button

1. You can maintain the MIS information for the Transaction. If the MIS details are not entered for the Transaction the same is defaulted from the product maintenance.
2. Click the **MIS button** to invoke the 'MIS' sub-screen.
3. On **MIS Button**, specify the fields.

Figure 3-11 MIS Button





Table 3-8 MIS Button - Field Description

Field	Description
Transaction Reference	System displays the transaction reference number of the transaction.
MIS Group	You can select the MIS group code from the option list, or specify the code for the MIS group in the Source maintenance. The system displays all valid MIS groups for different sources in the MIS group list in the Source maintenance. When booking a transaction from this screen, the MIS group linked to the 'Manual' source is populated by default.
Default button	After selecting a MIS group different from the default MIS Group, click this button to populate any default MIS values and link them to the Transaction MIS and Composite MIS classes.
Transaction MIS	You can populate the default MIS values for Transaction MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.
Composite MIS	You can populate the default MIS values for Composite MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.

View Queue Action Log

1. You can view all the queue actions for the respective transaction initiated. You can invoke this screen by clicking the **View Queue Action** tab in main screen, where the Transaction Reference Number is auto populated and Queue movement related details are displayed.
2. Click the **View Queue Action Log** button to invoke the sub-screen.

Figure 3-12 View Queue Action Log



3. Following details are displayed:
 - Transaction Reference Number
 - Network Code
 - Action
 - Remarks
 - Queue Code

- Authorization Status
- Maker ID
- Maker Date Stamp
- Checker ID
- Checker Date Stamp
- Queue Status
- Queue Reference No
- Primary External Status
- Secondary External Status
- External Reference Number


You can view the request sent and the corresponding response received for each row in Queue Action Log.

4. Also, you can view the request sent to and the response received from external systems for the following:
 - Sanction System
 - External Credit Approval
 - External Account Check
 - External FX fetch
 - External Price Fetch
 - Accounting System

Accounting Details

1. Click the **Accounting Details** tab and view the accounting entries for the transaction initiated.

Figure 3-13 Accounting Entries




2. By default, the following attributes are displayed:
 - Event Code
 - Transaction Date
 - Value Date
 - Account
 - Account Branch
 - TRN Code
 - Dr/Cr
 - Amount Tag
 - Account Currency
 - Transaction Amount
 - Netting
 - Offset Account
 - Offset Account Branch
 - Offset TRN Code
 - Offset Amount Tag
 - Offset Currency
 - Offset Amount
 - Offset Netting
 - Handoff Status

All Messages

- You can invoke this screen by clicking 'All Messages' tab in the screen.


Figure 3-14 All Messages



View Repair Log

1. You can view all the Repair actions for the respective transaction initiated. You can invoke this screen by clicking the **View Repair Log** button in View-screen, where the Transaction Reference Number is auto populated and related details are displayed.
2. Click the **View Repair Log** button to invoke the sub-screen.

Figure 3-15 View Repair Log




3. Following details are displayed:
 - Queue Reference No
 - Field Name
 - Old Value
 - Repaired Data
 - Error

NEFT Outbound Transaction View Summary

1. On Homepage, specify **PTSOVIEW** in the text box, and click next arrow. **NEFT Outbound Transaction View Summary** screen is displayed.

Figure 3-16 NEFT Outbound Transaction View Summary



2. Search using one or more of the following parameters:
 - Source Code
 - Network Code
 - Transaction Branch
 - Transaction Reference
 - Related Reference
 - Booking Date
 - Instruction Date
 - Activation Date
 - Transaction Currency
 - Transaction Amount
 - Debtor Account Number
 - Debtor Account Type
 - IFSC Code
 - Beneficiary Account Number
 - Queue Code
 - Authorization Status
 - Transaction Status
 - Dispatch Status
 - Dispatch Reference Number
 - Prefunded Payments
 - Sanction Seizure
 - N02 Return Message Reference Number
 - Customer No
 - UTR Number
 - Indo Nepal Remittance
 - Prefunded Payments
 - File Reference Number
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.

NEFT Outbound Transaction Booking via Upload

- [Single Payment Service](#)
- [C2B File Upload](#)

Single Payment Service

Oracle Banking Payments allows you to book the Outbound NEFT payments via Single Payout Service (SOAP/ ReST) and also via the Customer to Bank (C2B) pain.001 bulk file upload.

C2B File Upload

Oracle Banking Payments allows to you to process the Outbound NEFT payment requests received in bulk payment files in pain.001 format from Corporate customers to banks(C2B). After validating the bulk file, the Outbound NEFT transactions are created and processed individually. All the transactions created based on the bulk file received are auto authorized.

NEFT transaction Network code is derived using Network Resolution Rule (PMDNWRLE) maintained for the Channel Type 'C2B'.

NEFT Outbound Payments Processing

- [NEFT Outbound Payment Validations](#)
- [N06 Message Generation and Dispatch](#)
- [Notification](#)
- [Indo Nepal Remittance Processing](#)
- [Prefunded Payments Processing](#)

NEFT Outbound Payment Validations

Following processing changes/ initial validations are done as part of the transaction saving:

- Beneficiary ID Validations
- Mandatory Fields / Referential data checks
- Account Type Validations
- NRE Account Validations
- Processing Cutoff Check
- Intra Bank Transfer Check

For current dated transactions, following processing changes are covered during transaction authorization:

- Network Validations and Special Character Replacement
- Computation of Charge & Tax
- Exception Queue
- Authorization Limits Check
- Transaction cutoff time validation
- Sanction Check
- FX Limit Check
- ECA Check
- Network Cutoff time Check
- Transaction Accounting
- Dispatch Accounting
- Future Value Dated Transaction
- Branch Holiday Parameter

- Beneficiary ID Validation
- Mandatory Fields/ Referential Data Checks
- Account Type Validation
- LEI Validation
- NRE Account Validation
- Processing Cutoff Check
- Intra Bank Transfer Check
- Network Validations and Special Character Replacement
- Computation of Charge and Tax
- Exception Queue
- Authorization Limit Check
- Transaction Cutoff Time Validations
- Sanction Check
- FX Limit Check
- External Credit Approval Check
- Network Cutoff Time Check
- Transaction Accounting
- Dispatch Accounting
- Future Valued Transaction Processing
- Branch Holiday Parameter

Beneficiary ID Validation

System validates the Beneficiary ID provided and populates the respective beneficiary details.

Beneficiary Address Details maintained on Beneficiary Registration Detailed (PMDBENRN) screen.

When the user selects a valid Beneficiary ID while initiating Outbound payment, the Beneficiary Address Details are auto-populated to the 'Creditor Additional Details' section on the 'Additional Details' tab of the NEFT Outgoing Transaction Input Detailed (PTDOTONL) screen.

The address details fields are still enabled for any edition even after the system defaults the address details.

The 'Creditor Additional Details' fields remain enabled for edition if the beneficiary ID is not selected.

Beneficiary Address Details are auto-populated to NEFT Outbound Transaction View (PTDOVIEW) screens when the 'SSI_LABEL' tag in SPS Service contains valid Beneficiary ID maintained in the system.

Mandatory Fields/ Referential Data Checks

Validation of the IFSC Code is done as per the maintenance done in the Local Payment Bank Directory (STDBKMNT) and all the valid IFSC codes are maintained in this screen. Transaction is rejected in case of validation failure.

Debtor Account Branch IFSC check

- This is derived based on the Branch and bank code mapped to the IFSC code in the STDBKMNT screen if maintained. This is also populated in the N06 message in the field:5756 (Sending branch's IFSC).
- If the Debtor account branch IFSC (Field:5756) is not derived, then the transaction is moved to Process Exception (PE) queue.

System validates the Debtor Account Type for outbound transactions. If the debtor account type is NRE/NRO, then the field (:6305 - Sender's Account type) is updated with 40 or 10 respectively.

- If the Debtor account type is NRE(40) or NRO, then the Sender to Receiver Information field in the Additional Details tab in PTDOTONL screen is, automatically populated with a static text.
- This static message is displayed in the N06 message in the field: 7495.

System validates the Transfer Amount, if it is within the Min/Max Transaction limit and Per day limit as maintained in the Payment Common Preferences screen (PMDNFTPF). If the transaction does not match the criteria, it is rejected.

Account Type Validation

The system checks the Account Type Value present in the incoming channel requests for Debtor Account Type and Beneficiary Account Type.

If the user selects any value other than the LOV available for Debtor Account Type and Beneficiary Account Type, the system rejects the transaction. The error message applicable is PM-MSG-005 'Debtor Account Type is invalid' or PT-TXP-017 'Beneficiary Account Type is invalid.'

The Beneficiary Account Type field is optional. The system checks the Account Type restrictions validations for Beneficiary Account Type, only when Beneficiary Account Type value is present.

LEI Validation

Debtor LEI

The LEI validation is are done, if the transaction amount is more than the LEI Threshold Amount maintained in India Payments Common Preferences (PMDNFTPF).

The field 'Debtor LEI' is populated when the below conditions satisfy, and LEI validation is applicable:

- Debtor is a 'Non-Individual' i.e. Customer Type of the Debit account customer is not 'Individual'.
- LEI is maintained for the Debtor in the India Payments Customer Preferences (PMDEXLEI) and the Value Date of the transaction is equal to (or) less than the LEI expiry date.

An error is raised when all below-listed conditions satisfy, and LEI validation is applicable:

- Debtor is a 'Non-Individual' i.e. Customer Type of the Debit account customer is not 'Individual'.
- LEI is not maintained for the Debtor in the India Payments Customer Preferences (PMDEXLEI) or LEI is maintained but the Value Date of the transaction is more than the LEI expiry date.

Beneficiary LEI

The Beneficiary LEI field is optional. If the user inputs a value, then the system checks the length of the value. If the length is not 20 characters, the system displays the error.

LEI Validation Failure

In case of LEI validation failure:

- For manually booked transactions, the error message is shown on enrich user action.
- For uploaded transactions, the transaction is rejected outright.

NRE Account Validation

When the user clicks the 'Enrich/Save' button, the system checks for the following NRE account type validations:

- If you select Beneficiary Account Type 'NRE' (40), then you must select Debtor Account Type also 'NRE' (40). Else system rejects the transaction with an error message PTTXP-018 'If Beneficiary Account Type is NRE, then Debtor Account Type must be NRE.'
- If you select Debtor Account Type 'NRE' (40), then you can select Beneficiary Account Type as any account from drop-down lists, such as Savings Bank (10), Current Account (11), Cash Credit (13), Loan Account (14), Overdraft (12), NRE (40), and Credit Card (52).

Processing Cutoff Check

If Transaction Processing Time is greater than Processing cutoff time, then NEFT outbound transaction moves to Processing Cutoff Queue (PQSPRCUQ). All actions such as Release, Carry Forward, Cancel, Authorize, Delete are allowed.

Intra Bank Transfer Check

For Intra Bank Transfer Check the system checks the following:

- System checks if the beneficiary bank IFSC code is of the same bank branch. A 'Branch' record is present in the screen Branch IFSC Code Mapping 'PMDIFSBR' for the given IFSC Code.
- If a record is found in screen Branch IFSC Code Mapping 'PMDIFSBR' for the given IFSC Code, then the system checks the following:
 - If the Intra Bank Transfer flag is 'N' the system gives an error message PT-TXP-023 'Intra Bank Transfer is not allowed'.
 - If the 'Intra Bank Transfer' flag is 'Y' the system allows to process as 'Outbound NEFT payment and generate N06 message for dispatch to Network even if beneficiary bank IFSC code is of the same bank branch.

Network Validations and Special Character Replacement

IBAN check is not applicable for NEFT Outbound payments.

Debtor Details, Beneficiary Details, Beneficiary Bank details, Additional Debtor/Creditor Details, Sender to Receiver Information entered for a payment transaction is validated against the valid characters allowed for the network.

In case of Network character validation failure, transaction is moved to repair queue with error details.

Permitted character set for NEFT Transfers are as below:

- Alphabetical characters - A to Z (upper case), a to z (lower case)
- Numeric characters - 0 to 9
- Special characters /-?:()., '+ space cr lf
- Special characters entered in a payment transaction are validated and replaced with specific characters as defined in Special Characters maintenance

Computation of Charge and Tax

Charge and tax for NEFT Payment transactions are calculated based on the Pricing Code specified in the India Payments Common Preferences screen (PMDNFTPF). Charges and tax are applied to the NEFT transactions based on the pricing code linked.

For current dated transactions, following processing changes are covered during transaction authorization.

Exception Queue

Exception Queue checks are applicable as per the functionality. For more details on these queues, refer to Exception Queues user manual.

Authorization Limit Check

Two levels of Authorization limit check is done before the process cut over check.

Transaction Cutoff Time Validations

Transaction cut off time validation is based on the Transaction Cut-off Time Maintenance (PMDCTOFF) screen. Transaction cutoff time check is done only for transaction with payment activation date is current date.

Transaction Cut-off time for the payment network and Transaction Type 'Outbound' is fetched from the maintenance for the following combination:

- Source - Specific/ALL
- Service Model - Specific/ALL
- Customer - Specific/ALL

Sl. No.	Network	Transaction Type	Source	CSM	Customer
1	Network ID	Outbound	Specific	Specific	Specific
2	Network ID	Outbound	All	Specific	Specific
3	Network ID	Outbound	Specific	Specific	All
4	Network ID	Outbound	All	Specific	All
5	Network ID	Outbound	Specific	All	All
6	Network ID	Outbound	All	All	All

If payment processing time is lesser than or equal to the Cut-off date time derived, then the payment is considered as 'Pre Cut-off' payment and proceeds with further processing.

If payment save date time or payment receipt date time exceeds the Cut-off date time derived then the payment is considered as 'Post Cut-off' payment and post cut off status is updated for the transaction.

The failed transactions are further moved to Process cutoff queue and the transactions can be processed further from this queue. For more details on queue, refer to Exception Queue user manual.

Sanction Check

If sanction screening is required for the Network and the customer, request is sent to External Sanction System.

If the sanction check status of the transaction is 'Approved', then further processing continues. If the contract's sanction check response status is 'Override' or 'Rejected' or 'Timed Out', then transaction is logged in 'Sanction Check Exception Queue' and the processing of the transaction is stopped at this stage.

FX Limit Check

FX Limit Check and Currency conversion is not applicable for NEFT.

External Credit Approval Check

Debit accounting entries pertaining to payment amount and charge/tax amounts are sent to external DDA system for credit approval.

External Credit Approval is done for all the external accounts for which 'External Credit Approval Required' flag is enabled. ECA system for the credit check is derived based on the External Account maintenance.

If the ECA response status for a payment transaction is 'Approved', then further processing continues. If ECA validation fails i.e. the status is 'Override', 'Rejected', or 'Timed out', then the transaction is logged in ECA Exception queue.

Network Cutoff Time Check

The system checks the network cutoff time based on the cut off time maintained in Network Maintenance Detailed (PMDNWMNT) for the network. The system considers the application server time for cutoff time check. The system automatically roll-over the transactions that are not processed within the Network cutoff time and again calculates the Activation Date considering network holidays. These transactions do not move to Network cutoff Queue.

The unprocessed transactions in the queue are further moved to Warehouse queue. These transactions are processed as future value transactions from Warehouse queue and goes through all the transaction processing.

Transaction Accounting

Debit liquidation accounting entries have both payment entries and charge/tax entries. Accounting details are handed off to accounting system with debit/credit liquidation accounting code linked at Network Currency preferences. Following are the entries posted for the transactions booked:

Dr / Cr	Account	Value Date	TXN_CCY
Dr	Customer Account	Debit Value Date	Account Currency
Cr	Intermediary GL	Debit Value Date	Transfer ccy
Dr	Intermediary GL	Credit Value Date	Transfer ccy
Cr	Clearing GL	Credit Value Date	Transfer ccy

Accounting handoff is done after Network cutover check.

- Additionally, charge/tax related entries are handed off along with debit liquidation details as per existing process.
- On payment reject, the reversal entries are posted. However, charges are not reversed as per existing process.

Dispatch Accounting

Dispatch accounting is applicable for NEFT outbound payments. System triggers the DCLG event on the dispatch of N06 bundle (as defined in number of transactions per Dispatch). For all the transactions in the bundle, a single entry is posted with the sum of total amount and the no of transactions.

Dr / Cr	Account	Value Date	TXN_CCY
Dr	Clearing GL	Debit Value Date	Account Currency
Cr	Network/Nostro Account	Credit Value Date	Transfer ccy

Future Valued Transaction Processing

Future dated NEFT transactions are processed by separate jobs and run on receipt of the Start of Day (SOD, IFN 972) Message.

System identifies the transactions from the Warehouse queue. The transaction job picks up the future dated transactions with the Activation date equal to the current date and also it is equal to the SOD date of the latest IFN 972 message received.

Processing of transactions is completed till sanction check on booking date itself. Transaction processing starts from initial validations again, on the activation date.

- NEFT Outbound payment rules allow the customers to send the payment requests with future value date. Such requests are processed by the system till sanction check on booking date and is marked as future valued.
- On value date future dated transaction job processes the payments starting from the initial validations. Future dated transactions are processed by separate jobs.

Branch Holiday Parameter

In addition to Currency and Network Holidays, Branch holidays is considered in determining the Value date and Activation date for NEFT payments.

Processing Branch holidays is considered in the Dates resolution only if a particular parameter in India Payment Common Preferences for the 'Outbound' or 'Inbound' transaction type is checked.

N06 Message Generation and Dispatch

NEFT outbound transactions generates a 'N06' outbound payment message.

As per the number of transactions per dispatch maintained in Payments Common Preferences screen (PMDNFTPF), system bundles the no. of transactions and dispatches N06 message, once the defined number of transactions are met.

On the time interval specified in the Dispatch maintenance, even if the number of transactions are not met, residual messages are dispatched as bundle.

The N06 messages in the bundle are dispatched /handed off to SFMS network for further processing.

Upon successful processing of N06, dispatch accounting is generated and is handed off.

Notification

After receiving the N10 message successfully, notification is sent to the Originator (Debtor).

Indo Nepal Remittance Processing

System performs following validations/processing once the user selects the 'Indo Nepal Remittance' check box:

- System fetches the Beneficiary Bank IFSC and Beneficiary Account Number from the India Payments Common Preferences Screen (PMDNFTPF) and auto-populates the values on the input screen.
- System disables the 'Sender to Receiver Information' fields and enables the 'Indo Nepal Information' fields under the 'Additional Details' tab.
- System validates the transfer amount to check the maximum per transaction limit. In case this validation fails:
 - For manually inputted transactions, screens display an appropriate error message.
 - For uploaded transactions, the system rejects the transaction.
- The Indo Nepal Information six lines fields defined for Indo Nepal Remittance are mandatory and cannot be blank.
- When you click the Save button, the system validates Indo Nepal Information six lines fields, In case these fields are blank:
 - For manually inputted transactions, screens display an appropriate error message.
 - For uploaded transactions, the system rejects the transaction.
- System validates and allows only numeric values in the Commission field. For any other value, the screen displays an appropriate error message.

Prefunded Payments Processing

Customer number/debtor account number is not mandatory.

If Debtor Account currency is not provided in the outbound request, then it gets defaulted to Transfer Currency (INR) in transaction.

If the 'Prefunded Payments GL' check box is selected, the system skips the below processing:

- ECA Check
- Pricing
- FX Limit Check

The 'Prefunded Payments GL' is always used as Debit account while posting the debit liquidation entries. The 'Prefunded Payments GL' value maintained in the Source Maintenance (PMDSORCE).

LEI Validation Failure

In case of LEI validation failure:

- For manually booked transactions, the error message is shown on enrich user action.
- For uploaded transactions, the transaction is rejected outright.

Sender To Receiver Information

Debtor LEI	The LEI validation is done, if transaction amount is more than the LEI Threshold Amount maintained in India Payments Common Preferences (PMDNFTPF).
Beneficiary LEI	The Beneficiary LEI field is optional. If the user inputs a value, then the system checks the length of the value. If the length is not 20 characters, the system displays the error.
Sender To Receiver Information 3-6	At the NEFT payment type product processor level, system performs the below field length validation for the fields Sender To Receiver Information 3-6. If the below condition is matched, then that particular transaction is moved to Repair queue for user action. <ul style="list-style-type: none"> • Condition: (The Entered Characters :xxx) Is exceeding the Maximum length Allowed 35.

NEFT Message Browser


- [NEFT Outbound Message Browser](#)
- [Negative Acknowledgement Processing Details](#)
- [NEFT N04 Browser](#)
- [NEFT Inbound Message Browser](#)

NEFT Outbound Message Browser


The NEFT Outbound Message Browser screen allows user to view the following outbound NEFT messages generated:

- N06 - Outbound Payment Transfer
 - N07 - Return of Inbound Transfer
 - N10 - Credit Confirmation for Inbound Transfer
1. On Homepage, specify **PTSOUTBR** in the text box, and click next arrow.
NEFT Outbound Message Browser screen is displayed.

Figure 3-17 NEFT Outbound Message Browser



2. Search for the records using one or more of the following parameters:
 - Dispatch Reference Number
 - Dispatch Date
 - Batch Time
 - Dispatch Status
 - Message Type
 - Linked Sequence Number
3. Following sub screens/ actions are available in the message browser screen:

Action	Description
View Message	Select a record and click on 'View Message' button to view the dispatched message.
View Accounting	<p>Select a record and click on 'View Accounting' to view the Dispatch accounting details for the N06 and N07 message generated.</p> <p>System displays the DCLG event and its respective accounting entries passed during the N06 and N07 dispatch. Single entry is posted for the bundle dispatched, with total sum of amounts. Entries posted are - Dr. Clearing GL and Cr. Network/ Nostro account.</p> <p>In case of auto reversals (for SFMS NAKs such as F25 and F26) of the N06 dispatched, system displays the reversal accounting entries of DCLG.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> Note:</p> <p>Dispatch accounting is not applicable for N10 messages.</p> </div>

Action	Description
View Transaction	Select a record and click on 'View Transaction' to view the complete transaction details. View Summary screen is launched on clicking 'View Transaction'. You can double click the record or select a record and click on 'Details' button to view the detailed transaction screen. System launches the NEFT Outbound View Detailed screen (PTDOVIEW).
View ACK/NAK Message	You can view the F20, F25, F26, F27 ACK/NAK messages received and matched for the corresponding N06 dispatch.
Process NAK	Process NAK option helps to validate the negative acknowledgment and perform appropriate action like reverse or regenerate the transaction. You can click the 'Process NAK' option to launch Negative Acknowledgment Processing Details screen.

Negative Acknowledgement Processing Details

1. On Homepage, specify **PTDNAKPR** in the text box, and click next arrow.
Negative Acknowledgement Processing Details screen is displayed.

Figure 3-18 Negative Acknowledgement Processing Details

2. Following fields are auto populated:
 - Sequence Number
 - Bank Application Identifier
 - Originating Branch IFSC
 - Error Code
 - Received Date
 - NAK Type
3. User can perform following actions:
 - Regenerate Messages
 - Reject Messages

- Authorize
- Delete
- View Queue Action

NEFT Acknowledgment Processing

- [SFMS ACK/NAK Messages Processing](#)
- [Credit Confirmation ACK Message - N10 Processing](#)

SFMS ACK/NAK Messages Processing

Message Name	Message Description
F20	This is an acknowledgment message from SFMS.
F25	This is a Negative acknowledgment message from SFMS. User can take manual action on outgoing payment transaction.
F26	This is a Negative acknowledgment message from SFMS user. User can take manual action on outgoing payment transaction.
F27	This is an acknowledgment message from Bank API (IDRBT/RBI). If this message is Negative Acknowledgment, then user can take manual action on outgoing payment transaction.

Processing Steps:

On receipt of incoming F20/F27 ACK messages from SFMS, system parses the message and process. The parent transaction is fetched based on following matching fields: (Note: F20/F27 ACK is received for the N06 messages sent in a bundle of 10)

- Matching:
 - External Application Sequence number mentioned in the F20/F27 message is matched against the sequence number sent in the original outgoing payment transaction/message (N06) in Block A header and the IFSC Code of the Originating branch (Our IFSC Code).
- Message Status Update: If matched,
 - For F20 (Message Identifier in the format) received, original outgoing payment gets updated
 - i.e, All the '10' transactions sent in the N06 bundle having the same sequence number is updated
- For F27 (Message Identifier in the format) received,
 - System checks the 'Bank API Response Code' field
 - i.e, All the '10' transactions sent in the N06 bundle having the same sequence number is updated

NAK Processing:

On receipt of incoming F25/F26/F27 NAK messages from SFMS, system parses the message and process. The parent transaction is fetched based on following matching fields: (Note: F25/F26/F27 ACK is received for the N06 messages sent in a bundle of 10)

- Matching:

- External Application Sequence number mentioned in the F25/F26/F27 message is matched against the sequence number sent in the original outgoing payment transaction/message (N06) in Block A header and the IFSC Code of the Originating branch (Our IFSC Code).

Manual action and Message Status Update: If matched,

- System waits for user action to be taken from the new screen – Negative Acknowledgement Message Details. Screen PTSFNAKQ will no longer be used and removed from the system.
- Below steps are performed form new screen - Negative Acknowledgement Message Details:
 - User will select the N06 single record from PTSOUTBR and click ‘Process NAK’ option. In case, multiple records are selected and ‘Process NAK’ option is clicked then system throws an error.
 - System opens the Negative Acknowledgement message details screen.
 - Transaction Details section of the screen lists out the transactions bundled in the original N06 message. By default, all the messages are selected. So, the manual action is applicable for all the underlying transactions in the N06 bundled message.

Dispatch Reversal Accounting for NEFT Outbound	Event	Dr/Cr	Account	Account Type	Amount Tag
NEFT Outbound	DCLG	Dr	Nostro Account	Account	FILE_AMT
NEFT Outbound	DCLG	Cr	Network Clearing GL	GL	FILE_AMT

Dispatch Reversal Accounting for NEFT Outbound	Event	Dr/Cr	Account	Account Type	Amount Tag
NEFT Outbound	DRLQ	Dr	Network Clearing GL	GL	XFER_AMT
NEFT Outbound	DRLQ	Cr	Intermediary GL	GL	XFER_AMT
NEFT Outbound	DRLQ	Dr	Intermediary GL	GL	XFER_AMT
NEFT Outbound	DRLQ	Cr	Customer Account	Account	XFER_AMT

Credit Confirmation ACK Message - N10 Processing

The beneficiary (Creditor) bank sends a positive acknowledgment message (N10) to the Remitter (debtor) bank, upon the successful credit to the beneficiary for the outbound payment. The Inbound N10 credit acknowledgment received, has the bundle of outbound transactions grouped in a single message.

Following details are updated, upon receiving the successful N10 credit acknowledgment message:

- ‘Transaction Status’ field in the NEFT Outbound Payments view screen (PTDOVIEW) is updated as ‘Settled’.
- System updates the value ‘Credit Confirmation Details’ for the respective outbound transactions with - N10 Message Reference, Credited Date and Credited Time.
- Success notification for the acknowledgment received for outbound transactions can be viewed in the Notify Message Details screen (PMSNOTFY).

- And the N10 generated and the message details can be verified in the NEFT Inbound Message Browser (PTSINBRW).

4

NEFT Inbound Payments

- [NEFT Inbound Transaction Input](#)
- [NEFT Inbound Payments Processing](#)
- [NEFT Message Browser](#)
- [NEFT Acknowledgment Processing](#)
- [NEFT N04 Manual Initiation](#)

NEFT Inbound Transaction Input

Inbound NEFT payments are received as N02 messages from RBI clearing. In a single inbound payment message (N02), group of transactions are bundled together (bundle of 10) and settled in the defined batch time.

- [NEFT Inbound Transaction Input](#)
- [NEFT Inbound Payment View](#)

NEFT Inbound Transaction Input

The NEFT Inbound Transaction Input screen allows user to manually create a NEFT Inbound Payment by providing the details.

1. On Homepage, specify **PTDITONL** in the text box, and click next arrow.
NEFT Inbound Transaction Input screen is displayed.

Figure 4-1 NEFT Inbound Transaction Input

NEFT Incoming Payment Transaction Input Detailed

New Enter Query

Transaction Branch *
Host Code *
Source Code *
Network Code *

Transaction Reference *
Related Reference
Source Reference
Batch Time
 Credit to GL

Main Additional Details Pricing

Creditor Details

Beneficiary Account Number
Beneficiary Account Type
Beneficiary Name
Credit Account Number
Credit Account Currency
Credit Account Branch

Transaction Currency INR
Transaction Amount

Debtor Details

Debtor Account Number
Debtor Account Type
Debtor Name
IFSC Code

Booking Date YYYY-MM-DD
Instruction Date YYYY-MM-DD
Activation Date YYYY-MM-DD

UDF | MIS

Maker Id
Maker Date Stamp

Checker ID
Checker Date Stamp

Authorization Status

- On **NEFT Inbound Transaction Input** screen, specify the fields.
For more information about the fields, refer to field description below:

Table 4-1 NEFT Inbound Transaction Input - Field Description

Field	Description
Transaction Branch	System defaults the Transaction Branch on clicking 'New'.
Host Code	System defaults the Host Code of transaction branch on clicking 'New'.
Source Code	Specify the Source Code via which the payment request is received from the list of values.
Network Code	System defaults the Network code as 'NEFT' on clicking 'New'.
Transaction Reference Number	System generates the transaction reference number. For more details on the format, refer the <i>Payments Core User Guide</i> .
UTR Number	System defaults the UTR number same as transaction reference number on clicking 'New' button.
Related Reference	System defaults transaction reference number. However you can modify this.
Source Reference	Specify the Source Reference Number, if required.
Batch Time	Specify the Batch time, in which the transaction is to be picked.
Credit to GL	Check this flag to enable credit to GL account.

- [Main Tab](#)
- [Additional Details Tab](#)
- [Pricing Tab](#)
- [UDF Button](#)
- [MIS Button](#)
- [NEFT Inbound Transaction Summary](#)

Main Tab

- On **Main Tab**, specify the fields.

Figure 4-2 NEFT Inbound Transaction Input - Main Tab

The screenshot shows the 'Main Tab' of the NEFT Inbound Transaction Input screen. It features two columns of input fields: 'Creditor Details' and 'Debtor Details'. The 'Creditor Details' column includes fields for Beneficiary Account Number, Beneficiary Account Type (a dropdown menu), Beneficiary Name, Credit Account Number, Credit Account Currency, Credit Account Branch, Transaction Currency (pre-filled with 'INR'), and Transaction Amount. The 'Debtor Details' column includes fields for Debtor Account Number, Debtor Account Type (a dropdown menu), Debtor Name, IFSC Code, Booking Date, Instruction Date, and Activation Date. At the bottom of the main content area, there is a blue bar with buttons for 'UDF', 'MIS', and 'Enrich'. The footer of the screen contains fields for 'Maker Id', 'Maker Date Stamp', 'Checker ID', 'Checker Date Stamp', 'Authorization Status', and an 'Exit' button.

Table 4-2 NEFT Inbound Transaction Input_Main Tab - Field Description

Field	Description
Creditor Details	All open and authorized accounts maintained in External Account maintenance are listed. You can select the creditor account. The list of values search page displays the Account along with Customer No & Customer Name.
Beneficiary Account Number	Specify the Beneficiary Account Number. You can select the Beneficiary Account Number from the list of values. The list of values lists Loan Account numbers along other customer account.
Beneficiary Account Type	System defaults the Beneficiary Account Type based on the Beneficiary Account Number selected.
Beneficiary Name	System defaults Beneficiary name on the Beneficiary Account Number selected.
Credit Account Number	System displays the biller account which is resolved based on the Credit Card Number received in N02 file as Beneficiary Account.
Credit Account Currency	System displays the Credit Account Currency.
Credit Account Branch	System displays the Credit Account Branch.
Transaction Currency	System defaults the Transaction Currency as 'INR'. This is not modifiable.
Transaction Amount	Specify the Transaction Amount. This field is populated as the transfer amount converted in credit account currency.
Beneficiary Bank Details	--
Debtor Details	Specify the Debtor Account Number.
Debtor Account Type	Select the Debtor Account type from the following: <ul style="list-style-type: none"> • Savings Bank (10) • Current Account (11) • Cash Credit (13) • Loan Account (14) • Overdraft (12) • NRE (40)
Debtor Name	Specify the Debtor name for the Debtor account specified.
IFSC Code	Select the IFSC Code from the list of values. All the valid IFSC codes are listed.
Booking Date	System defaults the Booking Date as current date.
Instruction Date	System defaults this date as current date and the payment is processed on the Instruction Date. System allows to modify the Instruction Date.
Activation Date	System derives the Activation Date on clicking Enrich button.

Additional Details Tab

- On **Additional Details Tab**, specify the fields.

Figure 4-3 NEFT Inbound Transaction Input - Additional Details Tab

This tab contains the below fields to capture the address details of debtor/creditor and remittance information from the sender to receiver.


Table 4-3 NEFT Inbound Transaction Input_ Additional Details Tab - Field Description

Field	Description
Creditor Additional Details	--
Address Line 1 to 4	Specify the Address.
Debtor Additional Details	--
Address Line 1 to 4	Specify the Address.
Sender To Receiver Information	System populates the static text automatically on clicking Enrich button in the Sender to Receiver Information fields, if the Debtor Account Type is NRE.
Sender to Receiver Information 1- 6	Specify the Sender to Receiver Information.

Pricing Tab

- On **Pricing Tab**, specify the fields.

Figure 4-4 NEFT Inbound Transaction Input - Pricing Tab



You can view the pricing details populated by system in this screen.

Table 4-4 NEFT Inbound Transaction Input_Pricing Tab - Field Description

Field	Description
Pricing Component	System defaults the pricing component based on the Pricing code linked in Network Currency Preferences.
Pricing Currency	System defaults the Pricing Currency.
Pricing Amount	System defaults the pricing amount from Pricing Value Maintenance screen (PPDVLMNT) as applicable for the payment value date, Payment Source code and Debit Customer Service Model. However you can modify this value. <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> Note: Currency conversions related to charge computation are completed and final amount is populated component wise in the Pricing Tab.</p> </div>
Waived	System defaults the waiver. However you can modify this value. <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> Note: If charge/tax is already waived at price value maintenance, then you cannot uncheck the waiver flag.</p> </div>
Debit Amount	System defaults the customer debit amount for charge/tax.

UDF Button

1. This sub-screen defaults values of UDF fields that are part of the UDF group specified for the 'Manual' source.
2. Click the **UDF button** to invoke the 'UDF' sub-screen.

3. On **UDF Button**, specify the fields.

Figure 4-5 UDF Button




Table 4-5 UDF Button - Field Description

Field	Description
Field Label	System displays all fields that are part of the associated UDF group.
Field Value	System displays the default value, where exists for the UDF fields. You can change the default value or specify value for other fields (where default value does not exist).

MIS Button

1. You can maintain the MIS information for the Transaction. If the MIS details are not entered for the Transaction the same is defaulted from the product maintenance.
2. Click the **MIS** button to invoke the 'MIS' sub-screen.
3. On **MIS Button**, specify the fields.

Figure 4-6 MIS Button




Table 4-6 MIS Button - Field Description

Field	Description
Transaction Reference	System displays the transaction reference number of the transaction.
MIS Group	You can select the MIS group code from the option list, or specify the code for the MIS group in the Source maintenance. The system displays all valid MIS groups for different sources in the MIS group list in the Source maintenance. When booking a transaction from this screen, the MIS group linked to the 'Manual' source is populated by default.
Default button	After selecting a MIS group different from the default MIS Group, click this button to populate any default MIS values and link them to the Transaction MIS and Composite MIS classes.
Transaction MIS	You can populate the default MIS values for Transaction MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.
Composite MIS	You can populate the default MIS values for Composite MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.

NEFT Inbound Transaction Summary

1. On Homepage, specify **PTSITONL** in the text box, and click next arrow. **NEFT Inbound Transaction Summary** screen is displayed.

Figure 4-7 NEFT Inbound Transaction Summary

2. Search using one or more of the following parameters:
 - Authorized
 - Source Code
 - Network Code
 - Transaction Branch
 - Transaction Reference Number

- Reference Number
 - Source Reference Number
 - Batch Time
 - Booking Date
 - Instruction Date
 - Activation Date
 - Transaction Currency
 - Transaction Amount
 - Debtor Account Number
 - Debtor Account Type
 - IFSC Code
 - Beneficiary Account Number
 - Beneficiary Account Type
 - Transaction
 - Queue Code
 - Credit to GL
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.

NEFT Inbound Payment View

1. On Homepage, specify **PTDIVIEW** in the text box, and click next arrow.
NEFT Inbound Payment View screen is displayed.

Figure 4-8 NEFT Inbound Payment View

2. From this screen, click **Enter Query**. The Transaction Reference field gets enabled which opens an LOV screen.
3. Click the Fetch button and select the required transaction.
4. Along with the transaction details in the Main and Pricing tabs, you can also view the Status details for the following:
 - Creditor Details
 - Debtor Details
 - External System Status
 - Transaction Status
 - Pending Queue Details
 - Sanction Seizure
 - Dispatch Details
 - Credit Confirmation Details
5. Click **Execute Query** to populate the details of the transaction in the Inbound NEFT Payment View screen. System displays all the fields in the below mentioned tabs based on the transaction reference number selected.

For more details on Main, Additional Details and Pricing tabs refer to 'PTDITONL' screen details above.

- [Exceptions Tab](#)

- [UDF Button](#)
- [MIS Button](#)
- [View Queue Action Log](#)
- [Accounting Details](#)
- [All Messages](#)
- [View Repair Log](#)
- [NEFT Inbound Payments View Summary](#)

Exceptions Tab

- On **Exceptions Tab**, specify the fields.

Figure 4-9 NEFT Inbound Payment View - Exceptions Tab

Click on the 'Exceptions' tab to invoke this screen. All the details pertaining to Return Details, Network Reject Details and External System Status id are displayed for the entered Transaction Reference Number.

UDF Button

1. This sub-screen defaults values of UDF fields that are part of the UDF group specified for the 'Manual' source.
2. Click the **UDF button** to invoke the 'UDF' sub-screen.
3. On **UDF Button**, specify the fields.

Figure 4-10 UDF Button



Table 4-7 UDF Button - Field Description

Field	Description
Field Label	System displays all fields that are part of the associated UDF group.
Field Value	System displays the default value, where exists for the UDF fields. You can change the default value or specify value for other fields (where default value does not exist).

MIS Button

1. You can maintain the MIS information for the Transaction. If the MIS details are not entered for the Transaction the same is defaulted from the product maintenance.
2. Click the **MIS** button to invoke the 'MIS' sub-screen.
3. On **MIS Button**, specify the fields.

Figure 4-11 MIS Button





Table 4-8 MIS Button - Field Description

Field	Description
Transaction Reference	System displays the transaction reference number of the transaction.
MIS Group	You can select the MIS group code from the option list, or specify the code for the MIS group in the Source maintenance. The system displays all valid MIS groups for different sources in the MIS group list in the Source maintenance. When booking a transaction from this screen, the MIS group linked to the 'Manual' source is populated by default.
Default button	After selecting a MIS group different from the default MIS Group, click this button to populate any default MIS values and link them to the Transaction MIS and Composite MIS classes.
Transaction MIS	You can populate the default MIS values for Transaction MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.
Composite MIS	You can populate the default MIS values for Composite MIS classes for the MIS group. Alternatively, you can change one or more default MIS values or specify additional MIS values. Or, you can select MIS values from the option list.

View Queue Action Log

1. You can view all the queue actions for the respective transaction initiated. You can invoke this screen by clicking the **View Queue Action** tab in main screen, where the Transaction Reference Number is auto populated and Queue movement related details are displayed.
2. Click the **View Queue Action Log** button to invoke the sub-screen.

Figure 4-12 View Queue Action Log



3. Following details are displayed:
 - Transaction Reference Number
 - Network Code
 - Action
 - Remarks
 - Queue Code

- Authorization Status
- Maker ID
- Maker Date Stamp
- Checker ID
- Checker Date Stamp
- Queue Status
- Queue Reference No
- Primary External Status
- Secondary External Status
- External Reference Number


You can view the request sent and the corresponding response received for each row in Queue Action Log.

4. Also, you can view the request sent to and the response received from external systems for the following:
 - Sanction System
 - External Credit Approval
 - External Account Check
 - External FX fetch
 - External Price Fetch
 - Accounting System

Accounting Details

1. Click the **Accounting Details** tab and view the accounting entries for the transaction initiated.

Figure 4-13 Accounting Entries




2. By default, the following attributes are displayed:
 - Event Code
 - Transaction Date
 - Value Date
 - Account
 - Account Branch
 - TRN Code
 - Dr/Cr
 - Amount Tag
 - Account Currency
 - Transaction Amount
 - Netting
 - Offset Account
 - Offset Account Branch
 - Offset TRN Code
 - Offset Amount Tag
 - Offset Currency
 - Offset Amount
 - Offset Netting
 - Handoff Status

All Messages

- You can invoke this screen by clicking 'All Messages' tab in the screen.


Figure 4-14 All Messages



View Repair Log

1. You can view all the Repair actions for the respective transaction initiated. You can invoke this screen by clicking the **View Repair Log** button in View-screen, where the Transaction Reference Number is auto populated and related details are displayed.
2. Click the **View Repair Log** button to invoke the sub-screen.

Figure 4-15 View Repair Log



3. Following details are displayed:
 - Queue Reference No
 - Field Name
 - Old Value
 - Repaired Data
 - Error

NEFT Inbound Payments View Summary

1. On Homepage, specify **PTSIVIEW** in the text box, and click next arrow. **NEFT Inbound Payments View Summary** screen is displayed.

Figure 4-16 NEFT Inbound Payments View Summary

2. Search using one or more of the following parameters:
 - Source Code
 - Network Code
 - Transaction Reference
 - Related Reference Number
 - Source Reference
 - Value Date
 - Transaction Currency
 - Transaction Amount
 - Debtor Account Number
 - Debtor Account Type
 - IFSC Code
 - Beneficiary Account Number
 - Beneficiary Account Type
 - Batch Time
 - Queue Code
 - Authorization Status
 - Transaction Status
 - Sanction Seizure
 - N02 Message Reference Number
 - Credit to GL
3. Once you specified the parameters, click the Search button. System displays the records that match the search criteria.

NEFT Inbound Payments Processing

- [NEFT Inbound Payment Validations](#)

NEFT Inbound Payment Validations

Following validations and process changes are handles as part of the NEFT Incoming payments.

- [Initial Validations](#)
- [Business Override Checks](#)
- [Process Exception Checks](#)
- [Network Validations](#)
- [LEI Validation](#)
- [Non - NRE A/c to NRE A/c Payment Check](#)
- [Credit Card Payment Processing](#)
- [Authorization Limit Check](#)
- [Future Valued Check](#)
- [FX Limit Check](#)
- [N04 and N02 Messages Matching & Release Final Credit](#)
- [Accounting Handoff](#)
- [Notifications](#)

Initial Validations

During initial validation, system checks if the incoming N02 message is for Return of outgoing payment or Normal Incoming payment.

If the field (:2006) 'Related Reference number' has any value, then the N02 message is identified as Return of outgoing payment. For more details on Return, refer to Return of payments section.

If the field (:2006) 'Related Reference number' does not have any value and only the field (:2020) 'Transaction reference number' has value, it is processed as incoming payment.



Note:

This is the transaction reference specified by the sender's bank in originating N06 message and it is stored in the Related Reference field in the incoming payment screen.

Business Override Checks

This is applicable for NEFT transfers as per current functionality.

Process Exception Checks

If Account Type and Account Number mapping is not done by the beneficiary bank or in case of account type mismatch, transaction moves to Process Exception queue.

In case of account type mismatch (Beneficiary account type in the system and the account type sent in the message), transaction moves to Process Exception queue.

Network Validations

Debtor/Creditor/Bank/Additional details for a payment transaction are validated against valid characters allowed for the network. In case of Network character validation failure, transaction is moved to repair queue.

LEI Validation

System validates the Beneficiary LEI field value received in the incoming message when all below listed conditions satisfy as part of Repair Validations processing step:

- Transaction amount is more than the LEI Threshold Amount maintained in India Payments Common Preferences (PMDNFTPF).
- Beneficiary is a 'Non-Individual' .i.e. Customer Type is not 'Individual'.

The incoming transaction moves to Business Override Queue (BO) when any of the below Beneficiary LEI validation fails:

- Beneficiary LEI is not available in the incoming message.
- Beneficiary LEI is available in the incoming message but there is no LEI captured at beneficiary customer level (no maintenance).
- Beneficiary LEI is available in the incoming message, but the LEI captured at beneficiary customer level is different from Beneficiary LEI value received.
- Beneficiary LEI is available in the incoming message, but the LEI captured at beneficiary customer level is expired (Expiry Date is less than value date of the transaction).

On Approval from Business Override Queue, the transaction is processed further.

Note:

Beneficiary LEI is validated only for Customer Transfer (pacs.008) message for Incoming RTGS (Only Incoming NEFT / RTGS Customer Transfer in scope).

Since the Beneficiary LEI is received in Line 2 of Sender to Receiver Information field and within '//BL/' & '/', the LEI is extracted and validated.

Non - NRE A/c to NRE A/c Payment Check

System checks if the sender's account type (field:6305) belongs to Non-NRE account type.

This is identified based on the below values present in the field:

- 10 - Savings Bank
- 11 - Current Account

- 13 - Cash Credit
- 14 - Loan Account
- 12 - Overdraft
- 40 - NRE

System checks the Beneficiary account type (field:6310) belongs to NRE account type. This is identified based on the above values present in the field.

If it is resolved as Non-NRE a/c type to NRE a/c type payment, the Inbound payment transaction is moved to the Repair queue. Available actions in the Repair queue are:

- Repair - Repair processing logic is the same as per functionality.
- Return - Refer to Return of Payments section for more details

In all other account type cases, the transaction moves to the next processing stage.

Validations for Repair Queue:

- Beneficiary Name Check is done. If the validation fails, the Inbound payment transaction is moved to the Repair queue.
- In cases of Invalid beneficiary account or Credit to FCY account, the Inbound payment transaction is moved to the Repair queue.
- If Beneficiary account branch could not be derived based on the Beneficiary branch IFSC (:5569) from the incoming N02 message, then it is moved to the Repair queue.

System validates whether account record is open and authorized.

Credit Card Payment Processing

Incoming NEFT payments processing remains the same, except changes done for credit card payments. The following are the processing steps:

- System checks the Account type received in N02 field 6310. If the value of this field is '52', it indicates that it is a credit card payment.
- System then checks the beneficiary branch IFSC received in N02 field 5569 and validates it for credit card IFSC.
- System checks the credit account resolution as follows:
 - The 16-digit beneficiary account is the credit card number and not the valid customer account number to be credited.
 - Beneficiary name matching validation is not applicable.
 - System checks the first 6-digits of the beneficiary account number (Credit Card Number) against the BIN No. maintained on the Biller maintenance screen.
 - As per BIN No., the system fetches the Credit Account of the biller maintained in the Biller Maintenance screen.
 - For uploaded transactions in case, the system is unable to derive IFSC or the BIN No. then the transaction moves to the Process Exception queue.
 - For manual input screen on click of Enrich user action screen displays an error message.
- For normal Inbound NEFT transactions, if the Beneficiary account is a valid account then the Beneficiary account number populates in the credit account number field. It means that

for normal inbound NEFT transactions Beneficiary Account Number and Credit Account Number have the same value.

- System checks the accounting entries as follows:
 - System considers the credit account from the Credit Account Number' field while posting the accounting entries to credit the transaction amount.
 - System maps the Beneficiary Account Number to the field ' as it is from the N02 field 6061, during Accounting Handoff to FC core.

Authorization Limit Check

Authorization limit check supports only one Auth Limit Queue.

Future Valued Check

This is not applicable for NEFT Inbound Payments.

FX Limit Check

FX Limit check is not applicable for NEFT Inbound payments.

N04 and N02 Messages Matching & Release Final Credit

Following are the processing steps:

- After the successful EAC Check – Approved, System does not immediately post accounting entries for the incoming credit payments.
- Incoming Payments transactions are marked with below transaction status as:
 - 'Active', (After ECA Check -Approved, but N04 for the batch time/date not received)
 - 'Processed', (After N04 for the corresponding batch time/date received)
 - 'Returned', (In case of return due to valid reasons)
- N04 Match and RCLG Accounting:
 - System checks if N04 is received for the corresponding N02s based on the fields below.
 - On receipt of N04, system performs automatic matching of the N04 with N02s based on the fields (:3535) 'Batch Time, (:3385) 'Date', Receiver IFSC code present in the N04 message against the fields (:3535) 'Batch Time, Originating Date, Receiver IFSC code present in the N02 message.

Note:

While N02 messages are continuously received, N04 end of batch settlement message is sent by RBI Clearing Centre at the end of every 30-minute batch time.

- If matched, system triggers the RCLG event as - Dr. Nostro Account and Cr. Clearing GL.

Transaction accounting

System releases the final credit (DRLQ/CRLQ accounting entries posting) to the beneficiary account. Such successful incoming payment transactions statuses are marked as 'Processed'.

- If Incoming payment could not be credited to the beneficiary account for any valid reasons such as Beneficiary Name Mismatch, Beneficiary Account Invalid, Inward Credit to NRE from Non-NRE account etc.), such transactions are 'Returned' from 'Repair' Queue.
- There can be transactions pending in the exception queues (such as Process Exception/ Business Override/Repair Queue/Authorization Limit Check/ Sanction Check/Pricing Queue/EAC) which can be settled any time before B+2 cut-off time. (Refer Returns Processing section for B+2).
 - Such transactions are placed into the success path of the incoming process flow post Repair/Approval from the respective exception queues.
 - System checks if the corresponding N04 message is received and matched before final credit to beneficiary. If matched, then it triggers DRLQ, CRLQ events as part of transaction accounting.

Accounting Handoff

Accounting details are handed off to the accounting system for posting the entries. Following entries are posted for - Receipt accounting and Transaction accounting:

Dr / Cr	Account	Value Date	TXN_CCY
Dr	Nostro Account	Message Processing Date	Transfer Currency
Cr	Clearing GL	Message Processing Date	Transfer Currency

Dr / Cr	Account	Value Date	TXN_CCY
Dr	Clearing GL	Activation Date	Account Currency
Cr	Intermediary GL	Activation Date	Transfer Currency
Dr	Intermediary GL	Activation Date	Transfer Currency
Cr	Customer	Activation Date	Transfer Currency

Notifications

After processing the N10 message successfully, a notification is sent to the external system, to further send it to Beneficiary.

NEFT Message Browser

- [NEFT Outbound Message Browser](#)
- [Negative Acknowledgement Processing Details](#)
- [NEFT N04 Browser](#)
- [NEFT Inbound Message Browser](#)

NEFT N04 Browser

1. On Homepage, specify **PTSNFN04** in the text box, and click next arrow.
NEFT N04 Browser screen is displayed.

Figure 4-17 NEFT N04 Browser

NEFT N04 Browser

Search Advanced Search Reset Clear All

Case Sensitive

Message Reference Number Batch Number

Received Date Process Status

Records per page: 15 | 1 Of 1 | Go Lock Columns: 0

Message Reference Number	Batch Number	Received Date	Received Time	Process Status	Error Code	Error Description	No of Inbound Credits (Field 5267)	No of Outbo
--------------------------	--------------	---------------	---------------	----------------	------------	-------------------	------------------------------------	-------------

View Message | View Settlement | View Accounting


Exit

2. Search using one or more of the following parameters:
 - Message Reference Number
 - Batch Number
 - Received Date
 - Process Status
3. Once you specified the parameters, click the Search button. System displays the records that match the search criteria.
4. User can perform following actions:
 - [View Message](#)
 - [View Settlement](#)
 - [View Accounting](#)

View Message

- On **View Message**, specify the fields.

Figure 4-18 NEFT N04 Browser - View Message




You can view the message details and its respective fields by selecting a record.

View Settlement

1. On **View Settlement**, specify the fields.

Figure 4-19 NEFT N04 Browser - View Settlement



2. You can view the all the N02 messages matched for the corresponding N04 messages received in the 'View Settlement' screen.

Matching of the N04 message against the N02 messages are done based on the fields:

- N04 Fields: Batch Time(3535), Date (3385), Receiver IFSC Code in N04 message.
- N02 Fields: Batch Time(3535), Originating Date, Receiver IFSC Code in N02 message.

3. On **NEFT N04 Browser - View Settlement** sub screen, specify the fields.

For more information about the fields, refer to field description below:

Table 4-9 NEFT N04 Browser_View Settlement - Field Description

Field	Description
Inbound Credits	--
No of Inbound Credits (Field 5267)	System displays the total no of inbound credits as received in N04 message.
Sum of Inbound Credits (Field 4410)	System displays the total sum of inbound credits as received in N04 message.
No of Actual Inbound Credits	System displays the actual number of successful final credits after settlement to beneficiary as received in N02 message.
Sum of Actual Inbound Credits	System displays the actual sum of successful final credits after settlement to beneficiary as received in N02 message.
Return Transactions	--
No of Return Transactions (Field 5047)	System displays the total no of return transactions as received in N04 message.
Sum of Return Transactions (Field 4460)	System displays the total sum of return transactions as received in N04 message.
No of Actual Return Transactions	System displays the number of successful returns after R-Matching and final settlement to the original debtor as received in N02 message.
Sum of Actual Return Transactions	System displays the sum amount of successful returns after R-Matching and final settlement to the original debtor as received in N02 message. Grid displays the details about the N02 Messages references and its respective details like: <ul style="list-style-type: none"> • N02 Message Reference Number • No of Inward Credits • Sum of Inward Credits • No of Return Transactions Received • Sum of Return Transactions Received
View Return Transactions	On clicking the 'View Return Transactions' button, Outbound View Summary screen (PTSOVIEW) is launched and lists the underlying outbound payment transactions (in case of returns), in the system.
View Inward Credits	On clicking the 'View Inward Credits' button, Inbound View Summary screen (PTSIVIEW) is launched and lists the underlying inbound payment transactions created in the system.
View Message	You can select a N02 Reference listed in the grid and click on 'View Message' button to view the N02 message details.
Outbound Debits	--
No of Outbound Debits (Field 5175)	System displays the total no of outbound debits as received in N04 message.
Sum of Outbound Debits (Field 4105)	System displays the total sum of outbound debits as received in N04 message.
No of Outbound Debit Transaction Accepted (Field 5180)	System displays the total no of outbound debits accepted in N04 message.
Sum of Outbound Debit Transaction Accepted (Field 4110)	System displays the total sum of outbound debit accepted in N04 message.
No of Outbound Debit Transaction Rejected (Field 5185)	System displays the total no of outbound debit rejected in N04 message.


Table 4-9 (Cont.) NEFT N04 Browser_View Settlement - Field Description

Field	Description
Sum of Outbound Debit Transaction Rejected (Field 4115)	System displays the total sum of outbound debit rejected in N04 message.

View Accounting

- On **View Accounting**, specify the fields.

Figure 4-20 NEFT N04 Browser - View Accounting




You can view the RCLG accounting entries passed on the receipt of N04 message for the record selected.

NEFT Inbound Message Browser

The NEFT Inbound Message Browser screen allows user to view all the inbound NEFT messages such as N02, N03, N04, N09 and N10 generated.

1. On Homepage, specify **PTSINBRW** in the text box, and click next arrow.
NEFT Inbound Message Browser screen is displayed.

Figure 4-21 NEFT Inbound Message Browser



2. Search using one or more of the following parameters:
 - Generated Reference Number
 - Message Reference Number
 - Batch Number
 - Received Date
 - Message Type
3. Once you specified the parameters, click the Search button. System displays the records that match the search criteria.

 **Note:**

Inbound SFMS ACK/NAK Messages, can be viewed against respective N06 dispatch in NEFT outbound browser (PTSOUTBR).

4. User can perform following actions:

Action	Description
View Message	All the messages - N02, N03, N04, N09 and N10 are listed in this Inbound browser screen. Select a record and click on 'View Message' button to view the message details.
Process NAK	Click the 'Process NAK' option to launch N03 Transaction Summary View Screen (PTSN03TX). Process NAK option helps to validate the negative acknowledgment and perform appropriate action like reverse or regenerate the transaction.

NEFT Acknowledgment Processing

- [Message Dispatch - Outbound N10 Credit Confirmation ACK Message](#)

Message Dispatch - Outbound N10 Credit Confirmation ACK Message

After processing the CRLQ event, a background job generates the 'Credit Acknowledgment Message' for the incoming payment transactions.

This process groups the number of incoming payments and generates a single 'Credit Acknowledgment Message' for those transactions (Number of transactions for group is parametrized in network maintenance).

NEFT N04 Manual Initiation

- [NEFT N04 Input](#)
- [NEFT N04 Manual Processing](#)

NEFT N04 Input

The NEFT N04 Input screen allows user to manually initiate incoming N04 message.

1. On Homepage, specify **PTDMNN04** in the text box, and click next arrow.

NEFT N04 Input screen is displayed.

Figure 4-22 NEFT N04 Input

The screenshot shows the 'NEFT N04 Input Detailed' window. At the top, there are 'New' and 'Enter Query' buttons. Below are several input fields with red asterisks indicating they are required:

- Host Code *
- Network Code *
- Source Code *
- Transaction Branch *
- Message Reference Number *
- Batch Number *
- Value Date * (format: YYYY-MM-DD)

Below these are four summary sections, each with two input fields:

- Inbound Credits:** No of Inbound Credits (Field 5267), Sum of Inbound Credits (Field 4410)
- Return Transactions:** No of Return Transactions (Field 5047), Sum of Return Transactions (Field 4460)
- Outbound Debits:** No of Outbound Debits (Field 5175), Sum of Outbound Debits (Field 4105)
- Outbound Debit Transaction Accepted:** No of Outbound Debit Transaction Accepted (Field 5180), Sum of Outbound Debit Transaction Accepted (Field 4110)
- Outbound Debit Transaction Rejected:** No of Outbound Debit Transaction Rejected (Field 5185), Sum of Outbound Debit Transaction Rejected (Field 4115)

At the bottom, there are fields for 'Maker ID', 'Checker ID', 'Authorization Status', 'Maker Date Stamp', and 'Checker Date Stamp'. An 'Exit' button is located in the bottom right corner.

2. On **NEFT N04 Input** screen, specify the fields.

For more information about the fields, refer to field description below:

Table 4-10 NEFT N04 Input - Field Description

Field	Description
Host Code	System defaults the Host Code of transaction branch on clicking 'New'.
Network Code	System defaults the Network Code of transaction branch on clicking 'New'.
Source Code	Specify the Source Code from the list of values.
Transaction Branch	System defaults the Transaction Branch on clicking 'New'.
Message Reference Number	System generates the unique Message Reference Number for N04 message.
Batch Number	Specify the NEFT Batch Number from the list of values.
Value Date	Specify the Value Date.
Inbound Credits	--
No of Inbound Credits (Field 5267)	By default, system populates value as '0'. You can modify the value.
Sum of Inbound Credits (Field 4410)	By default, system populates value as '0.00'. You can modify the value.
Return Transactions	System defaults the transaction.
No of Return Transactions (Field 5047)	By default, system populates value as '0'. You can modify the value.
Sum of Return Transactions (Field 4460)	By default, system populates value as '0.00'. You can modify the value.
Outbound Debits	--
No of Outbound Debits (Field 5175)	By default, system populates value as '0'. You can modify the value.
Sum of Outbound Debits (Field 4105)	By default, system populates value as '0.00'. You can modify the value.
No of Outbound Debit Transaction Accepted (Field 5180)	By default, system populates value as '0'. You can modify the value.
Sum of Outbound Debit Transaction Accepted (Field 4110)	By default, system populates value as '0.00'. You can modify the value.
No of Outbound Debit Transaction Rejected (Field 5185)	By default, system populates value as '0'. You can modify the value.
Sum of Outbound Debit Transaction Rejected (Field 4115)	By default, system populates value as '0.00'. You can modify the value.

- [NEFT N04 Input Detailed Summary](#)

NEFT N04 Input Detailed Summary

1. On Homepage, specify **PTSMNN04** in the text box, and click next arrow.
NEFT N04 Input Detailed Summary screen is displayed.

Figure 4-23 NEFT N04 Input Detailed Summary

2. Search using one or more of the following parameters:
 - Message Reference Number
 - Batch Number
 - Value Date
 - Source Code
 - Network Code
 - Transaction Branch
 - Authorization Status
 - Maker ID
 - Checker ID
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.

NEFT N04 Manual Processing

You can initiate N04 message manually from the N04 Manual screen. On clicking 'New' option, system performs below action:

- Auto populate Host Code, Transaction Branch and Message Reference Number.
- Enter Batch Number and Value date.
- Default Inbound credits, Return Transactions and Outbound Debits fields to 0 and 0.00 appropriately. However, you can still update the value and Save the transaction.

Once the transaction is saved, authorizer will authorize the transaction. Audit trail is visible at the bottom of the screen.

After authorization, system creates a dummy N04 message entry in DB table PMTB_NEFT_N04_MSG_IN.

Validations are performed before inserting the dummy N04 entry to DB table.

For dummy N04 message, system generates receipt accounting entries i.e., Dr Nostro Account and Cr Intermediary GL.

This dummy N04 message can be browsed from screen NEFT N04 Browser (PTSNFN04) using search criteria. Dummy N04 message is not available on PTSINBRW screen.

Summary of all the N04 messages generated manually can be viewed from new screen PTSMNN04.

- [N02 Message processing](#)

N02 Message processing

System will match the dummy N04 message with N02 transactions which are in active status and corresponding to the batch number and value date of Dummy N04.

For the matched records, system will process the N02 similar to when N04 is received from RBI.

5

NEFT Return Payments

- [NEFT Inbound Return Payments](#)
- [NEFT Outbound Return Payments](#)

NEFT Inbound Return Payments

- [NEFT Inbound Payments - Returns Processing](#)
- [NEFT Return of Inbound Payment](#)

NEFT Inbound Payments - Returns Processing

For the NEFT Inbound Payments, the returns processing as per B+2 Settlement cycle:

- The Beneficiary bank must credit the beneficiary or return the transaction (N07) to the originating bank within B+2 hours or else it would have to be returned as NEFT Outgoing transactions (N06), wherein B is Batch Time received in the N02 message. Return cutoff time is captured in Network Maintenance.
- The Return can be initiated for the below reasons:
 - Inward Credit to a NRE account from a Non-NRE account
 - Invalid Beneficiary account
 - Rejection/Cancellation from the Incoming Exception queues (such as Process Exception/Business Override/Repair Queue/Authorization Limit Check/ Sanction Check/Pricing Queue/EAC)
- Returns (Cancel action) can be done from any Queue where user can input the Return reason Code and Return Reason.
- All manual rejection within B+2 settlement period generates N07 message.
- As per the changes to support B+2 settlement cycle, the batch time in N07 is sent as the next available batch time. User does not have option to input/modify the batch time.
- The below screen is launched to handle returns manually and generate N07 within B+2 cutoff time.

Figure 5-1 Cancel Details

On approving Cancel Action from Exception Queues, Inbound transaction is liquidated to Return GL and the transaction is marked as 'Return Initiated'.

Event	Dr/Cr	Account	Account Type	Amount Tag
DRLQ	Dr	Network Clearing GL	GL	XFER_AMT
CRLQ	Cr	Intermediary GL	GL	XFER_AMT

Event	Dr/Cr	Account	Account Type	Amount Tag
DRLQ	Dr	Intermediary GL	GL	XFER_AMT
CRLQ	Cr	Return GL	GL	XFER_AMT

You have to maintain a source code as INBOUNDN0 with Prefunded GL flag checked and Prefunded GL as Return GL. Source Network Preferences for transaction Type 'Outgoing' is to be maintained.

An outbound transaction is auto created on processing the return of incoming NEFT transactions, with 'Prefunded GL' flag checked. Outbound transaction Reference is populated as Return reference of the original inbound transaction. The mapping for the outbound transaction is detailed in the below table:

Outbound Transaction Fields	Mapping Details
Host Code, Transaction Branch & Network Code	Same as Inbound Transaction
Source Code	INBOUNDN02
Transaction Reference	Return Reference
UTR Number	Return Reference
Source Reference	Inbound Transaction Reference
Return of Inbound Flag	Marked as Yes
Prefunded Flag	Checked
Booking Date	Current Date
Value Date	Current Date
Activation Date	Current Date
Transaction Currency & Amount	As received in Inbound Transaction
Debtor Details	Beneficiary Details of Inbound transaction
Beneficiary Details	Debtor Details of Inbound Transaction
Beneficiary Bank Details	Debtor Bank Details of Inbound Transaction
Additional Details - Debtor Address	Beneficiary Address Details of inbound transaction
Additional Details - Beneficiary Address	Debtor Address Details of inbound transaction
Sender to Receiver Information	Third line populated as Return of

Event	Dr/Cr	Account	Account Type	Amount Tag
DRLQ	Dr	Return GL	GL	XFER_AMT
CRLQ	Cr	Intermediary GL	GL	XFER_AMT
DRLQ	Dr	Intermediary GL	GL	XFER_AMT
CRLQ	Cr	Network Clearing GL	GL	XFER_AMT

Return cutoff time check

- If Return cutoff time is over, the Return Message Type is updated as N06 and generation of N06 is done similar to normal outbound transactions.

- If Return cutoff time is not yet reached, Return Message Type is updated as N07.

Dispatch Processing of N07 Messages

- System checks whether N04 message is received for the Original inbound N02 message. If yes, N07 message record is marked as 'Ready for Dispatch'.
- Only the records marked as Ready for Dispatch is picked up for N07 generation.
- When the generation of N06/N07 message is completed for transactions, then the related Inbound transaction status is marked as 'Returned'.

NEFT Return of Inbound Payment

The NEFT Return of Inbound Payment screen allows user to view the return transactions pertaining to the inbound payments.

1. On Homepage, specify **PTDINRTN** in the text box, and click next arrow.
NEFT Return of Inbound Payment screen is displayed.

Figure 5-2 NEFT Return of Inbound Payment

2. On **NEFT Return of Inbound Payment** screen, specify the fields.
For more information about the fields, refer to field description below:

Table 5-1 NEFT Return of Inbound Payment - Field Description

Field	Description
Return Reference Number	Specify the Return Reference and click on 'Enter Query'. You can view the inbound transactions that are returned, with payment type as 'NEFT' and Transaction status - 'Returned'.
Return Date	System displays the Return Date as the current date by default.
Transaction Branch	System defaults the Transaction Branch on clicking 'New'.
Host Code	System defaults the Host Code of transaction branch on clicking 'New'.

Table 5-1 (Cont.) NEFT Return of Inbound Payment - Field Description

Field	Description
Original Transaction Reference	System displays the Original Transaction Reference for which the transaction is Returned.
Network Code	System defaults the Network Code based on the Return Reference Number selected.
Original Transaction Type	System defaults the Original Transaction Type based on the Return Reference Number selected.
Original Payment Type	System defaults the Original Payment Type based on the Return Reference Number selected.
Return Details	--
Return Reason Code	System displays the Return Reason Code as received in N02 message.
Return Reason	System displays the Return Reason based on the selected Reject Code.
Originator Bank IFSC	System displays the IFSC code of the originator of the transaction.
Originator Branch	System displays the Name of the Originator Branch.
Originator Bank	System displays the Originator Bank as received in N02 message.
Network Reject Details	These fields are applicable while querying for a particular Return record which is rejected by the RBI/Clearing Center.
Reject Reference	System displays the Reject Reference details.
Reject Received Date	System displays the date on which the network reject was received.
Reject Code	System displays the Network Reject Code.
Reject Reason	System displays the reason for Network Reject.

3. User can view following Original Transaction Details:

- Transfer Currency
- Transfer Amount
- Debtor Account Number
- Debit Account Type
- Debtor Name
- Creditor Account Number
- Creditor Account Type
- Creditor Name
- Creditor IFSC Code
- [NEFT Return of Inbound Payment Summary](#)

NEFT Return of Inbound Payment Summary

1. On Homepage, specify **PTSINRTN** in the text box, and click next arrow.
NEFT Return of Inbound Payment Summary screen is displayed.

Figure 5-3 NEFT Return of Inbound Payment Summary

2. Search using one or more of the following parameters:
 - Authorization Status
 - Return Reference Number
 - Original Transaction Reference Number
 - Transfer Currency
 - Debtor Account Number
 - Creditor Account Number
 - Creditor IFSC Code
 - Original Payment Type
 - Original Transaction Type
 - Originator Bank IFSC
 - Return Reason Code
 - Network Code
 - Reject Code
 - Reject Reference
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.

NEFT Outbound Return Payments

- [NEFT Outbound Payments - Returns Processing](#)
- [NEFT Return of Outbound Payment](#)

NEFT Outbound Payments - Returns Processing

Return of outgoing payment is received in the same message as N02 incoming payment transaction.

Processing of Incoming N02 Return

Incoming N02 messages can be received as result of any outgoing payment being returned by beneficiary bank.

The parent transaction is fetched based on following matching fields:

R-transaction	Message type	First Level Matching	First Level Matching	Second level Matching (provided first level is successful)	Second level Matching (provided first level is successful)
--	--	Field No/ Field Name	Original transaction field	Field No/Field Name	Original transaction field (N06)
Return of Outgoing Payment	N02	:2006 Related Reference Number	Transaction Reference Number (N06)	:4038 Amount 5756: Sending branch's IFSC 6305: Sending customer a/c type 6021: Sending customer a/c # 6091: Sending customer a/c name 5569: Beneficiary branch's IFSC 6310: Beneficiary customer a/c type 6061: Beneficiary customer a/c # 6081: Beneficiary customer a/c name	Transfer Amount Bank Code (Our IFSC Code) Debtor Account Type Debtor Account Number Debtor Name Beneficiary Bank Details > IFSC Code Beneficiary Account Type Beneficiary Account Number Beneficiary Name

On finding a parent match, a return transaction is internally created. Return reference, return date, reason code (:6346 field) and rejection reason (:6366) are stored for the returned transaction.

EAC check is performed before accounting handoff for the reversal. There is no sanction check.

Return accounting entries are processed with value date as return processing date. Charges applied as part of original transaction are reversed.

Original transaction status is updated as 'Returned'. Return details are captured for the original transaction and are available for view.

Following are the entries posted for the return of outbound transaction with the negative of transfer amount:

Dr/Cr	Account	Value Date	TXN_CCY
Dr	Clearing GL	Return Processing Date	Account Currency

Dr/Cr	Account	Value Date	TXN_CCY
Cr	Intermediary GL	Return Processing Date	Transfer Currency
Dr	Intermediary GL	Return Processing Date	Transfer Currency
Cr	Customer Account	Return Processing Date	Transfer Currency

NEFT Return of Outbound Payment

The NEFT Return of Outbound Payment screen allows user to view the return transactions pertaining to the outbound payments.

1. On Homepage, specify **PTDOTRTN** in the text box, and click next arrow.

NEFT Return of Outbound Payment screen is displayed.

Figure 5-4 NEFT Return of Outbound Payment

2. On **NEFT Return of Outbound Payment** screen, specify the fields.
For more information about the fields, refer to field description below:

Table 5-2 NEFT Return of Outbound Payment - Field Description

Field	Description
Return Reference Number	Specify the Return Reference and click on 'Enter Query'. You can view the outbound transactions that are returned, with payment type as 'NEFT' and Transaction status - 'Returned'.
Return Date	System displays the Return Date as the current date by default.
Transaction Branch	System defaults the Transaction Branch on clicking 'New'.
Host Code	System defaults the Host Code of transaction branch on clicking 'New'.
Original Transaction Reference	System displays the Original Transaction Reference for which the transaction is Returned.

Table 5-2 (Cont.) NEFT Return of Outbound Payment - Field Description

Field	Description
Network Code	System defaults the Network Code based on the Return Reference Number selected.
Original Transaction Type	System defaults the Original Transaction Type based on the Return Reference Number selected.
Original Payment Type	System defaults the Original Payment Type based on the Return Reference Number selected.
Return Details	--
Return Reason Code	System displays the Return Reason Code as received in N07 message.
Return Reason	System displays the Return Reason based on the Reject Code selected.
Originator Bank IFSC	System displays the IFSC code of the originator of the transaction.
Originator Branch	System displays the Name of the Originator Branch.
Originator Bank	System displays the Originator Bank name.
Network Reject Details	These fields are applicable while querying for a particular Return record which is rejected by the RBI/Clearing Center.
Reject Reference	System displays the Reject Reference details.
Reject Received Date	System displays the date on which the network reject was received.
Reject Code	System displays the Network Reject Code.
Reject Reason	System displays the reason for Network Reject.

3. User can view following Original Transaction Details:
 - Transfer Currency
 - Transfer Amount
 - Debtor Account Number
 - Debit Account Type
 - Debtor Name
 - Creditor Account Number
 - Creditor Name
 - Creditor IFSC Code
 - [NEFT Return of Outbound Payment Summary](#)

NEFT Return of Outbound Payment Summary

1. On Homepage, specify **PTSOTRTN** in the text box, and click next arrow.
NEFT Return of Outbound Payment Summary screen is displayed.

Figure 5-5 NEFT Return of Outbound Payment Summary

2. Search using one or more of the following parameters:
 - Authorization Status
 - Return Reference Number
 - Original Transaction Reference Number
 - Transfer Currency
 - Debtor Account Number
 - Creditor Account Number
 - Creditor IFSC Code
 - Original Payment Type
 - Original Transaction Type
 - Originator Bank IFSC
 - Return Reason Code
 - Network Code
 - Reject Code
 - Reject Reference
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.

6

NEFT Reject Payments

- [NEFT - Network Rejects](#)

NEFT - Network Rejects

- [N03 Transaction Summary View](#)
- [N03 Message Processing](#)

N03 Transaction Summary View

The N03 Transaction Summary screen allows user to view and process the N03 and N09 Reject messages.

1. On Homepage, specify **PTSN03TX** in the text box, and click next arrow.
N03 Transaction Summary View screen is displayed.

Figure 6-1 N03 Transaction Summary View

The screenshot displays the N03/N09 Transaction Summary Screen. It includes a search bar with 'Advanced Search', 'Reset', and 'Clear All' options. Below the search bar, there are several input fields for search criteria: 'Generated Reference Number', 'Original Transaction Reference', 'Matched Status' (dropdown), 'Batch Number', 'Authorization Status' (dropdown), 'Message Reference Number', 'Message Type' (dropdown), 'Value Date' (YYYY-MM-DD), 'Received Date' (YYYY-MM-DD), 'UTR Reference Number', 'Reject Code', 'Amount', and 'Process Status' (dropdown). A table below these fields shows columns for 'Generated Reference Number', 'Message Reference Number', 'N03/N09 Reference Number', 'UTR Reference Number', 'Original Transaction Reference', 'Message Type', 'Reject Code', 'Reject Reason', 'Reject Type', and 'Matched Status'. The table is currently empty. At the bottom, there are navigation buttons: 'View Transaction', 'Regenerate Message', 'Reject Transactions', 'Authorize', 'Delete', 'View Queue Action', and an 'Exit' button.

2. Search using one or more of the following parameters:
 - Generated Reference Number
 - Original Transaction Reference
 - Matched Status
 - Batch Number
 - Authorization Status
 - Message Reference Number
 - Message Type
 - Value Date

- Received Date
 - UTR Reference Number
 - Reject Code
 - Amount
 - Process Status
3. Once you specified the parameters, click the Search button.
System displays the records that match the search criteria.
 4. User can perform following actions:
 - View Transaction
 - Regenerate Messages
 - Reject Messages
 - Authorize
 - Delete
 - View Queue Action

N03 Message Processing

NEFT Clearing Centre Reject of outbound Payment (N06) or Reject of N07 is explained in this section.

System parses the inbound N03 reject message which has a group of outbound payment transactions bundled in a single message.

Processing Steps:

On receipt of incoming N03 reject message from SFMS, the parent transaction is fetched based on following matching fields:

- Field (:2006) 'Related Reference Number' in the N03 message (Repeated Groups) is matched against the 'Transaction reference number' field (:2020) of the original outgoing payment transaction/message (N06 – Repeating Group).
OR
- Field (:2006) 'Related Reference Number' in the N03 message (Repeating Groups) is matched against 'Transaction reference number' field (:2020) of the return transaction/message (N07 – Repeating Group).

System checks the field (:6346) 'Reject Code', (:6366) 'Rejection Reason'

**The reason codes that --
are used for (N03)
rescheduling at RBI
NEFT center are:**

094	Batch does not exist on Saturday
098	Holiday at RBI
099	Past Value Date
100	Late Arrival for a batch

When the reject code is of 'Reschedule Type'

N06 - Network Reject (Reschedule)

No further action is required on the original transaction.

 **Note:**

As per RBI Circular, this message (N03) is for the information of the originating bank and no re-initiation of the message is required.

Transactions in the 'Rescheduled' message status is allowed for further processing in its life-cycle (Return, Credit Done).

Network Reject details are updated with Reject Reference, Reject Code, Rejection Reason (as per N03 Mapping) for the Outbound Payment.

This can be viewed in the Outbound - View Screen.

N07 - Network Reject (Reschedule)

Network Reject details are updated with Reject Reference, Reject Code, Rejection Reason (as per N03 Mapping) for the Inward Return.

This can be viewed in the Inbound - View Screen.

No further action is required on the return transaction.

Glossary

PTDINRTN

[NEFT Return of Inbound Payment](#)

PTDITONL

[NEFT Inbound Transaction Input](#)

PTDIVIEW

[NEFT Inbound Payment View](#)

PTDMNN04

[NEFT N04 Input](#)

PTDNAKPR

[Negative Acknowledgement Processing Details](#)

PTDOTONL

[NEFT Outbound Transaction Input](#)

PTDOTRTN

[NEFT Return of Outbound Payment](#)

PTDOVIEW

[NEFT Outbound Transaction View](#)

PTSINBRW

[NEFT Inbound Message Browser](#)

PTSINRTN

[NEFT Return of Inbound Payment Summary](#)

PTSITONL

[NEFT Inbound Transaction Summary](#)

PTSIVIEW

[NEFT Inbound Payments View Summary](#)

PTSMNN04

[NEFT N04 Input Detailed Summary](#)

PTSN03TX

[N03 Transaction Summary View](#)

PTSNFN04

[NEFT N04 Browser](#)

PTSOTONL

[#unique_141](#)

PTSOTRTN

[NEFT Return of Outbound Payment Summary](#)

PTSOUTBR

[NEFT Outbound Message Browser](#)

PTSOVIEW

[NEFT Outbound Transaction View Summary](#)