Oracle® Fusion Middleware Administering the WebLogic Messaging Bridge for Oracle WebLogic Server





Oracle Fusion Middleware Administering the WebLogic Messaging Bridge for Oracle WebLogic Server, 14c (14.1.2.0.0)

F61266-01

Copyright © 2007, 2024, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Pre	eface
Aud	ience
Doc	ument

Audience		
Documentation Accessibility		
Diversity and Inclusion		
Related Documentation		
Conventions		

Understanding the Messaging Bridge 1

What is a Messaging Bridge?	
Messaging Bridge Components	
Resource Adapters	1-2
Source and Target Bridge Destinations	1-4
JMS Bridge Destinations	1-4
General Bridge Destinations	1-5
Messaging Bridge Instance	1-5
Configuring and Managing a Messaging Bridge	1-5
Create a Messaging Bridge Instance	1-5
Configuring Messaging Bridges for High Availability	1-6

2 Designing a Messaging Bridge

When to use a Messaging Bridge	2-1
Store and Forward Messaging	2-1
Replicating a Topic	2-1
When to Avoid Using a Messaging Bridge	2-2
Selecting a Quality-of-Service (QOS) Level	2-2
Messaging Persistence	2-3
Message Ordering	2-3
Setting the Number of Connection Factories	2-3
Preserving Message Properties	2-4
Using the JMSXUserID Property with a Messaging Bridge	2-5
Using Distributed Destinations as Source and Target Destinations	2-5



٧

νi

3 Interoperating with Different WebLogic Server Releases or Foreign Providers

Interoperating with Different WebLogic Server Releases	3-1
Supported Configurations and Compatibility	3-1
Naming Guidelines for WebLogic Servers and Domains	3-1
Configuring Interoperability for WebLogic Domains	3-1
Configuring Interoperability for Exactly-once QOS	3-2
Configuring At-least-once or At-most-once QOS	3-3
Interoperating with Foreign Providers	3-3
FAQs: WebLogic Messaging Bridge	
Why did the messaging bridge fail to connect to the source bridge destination?	4-1
Why are some of my messages not being forwarded?	4-2
Can the messaging bridge handle two-phase or global transactions between separate	4-2
Why are some of my messages not being forwarded? Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message?	
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message	4-2 4-2
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message? When configuring a source or target messaging bridge destination, do I need to set the	4-2 4-2 4-2
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message? When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field? How do I enable debugging for the messaging bridge?	4-2 4-2 4-3
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message? When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field?	4-2 4-2 4-3 4-3
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases? I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message? When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field? How do I enable debugging for the messaging bridge? Can the messaging bridge use distributed destinations as source and target destinations?	4-2 4-2 4-3 4-3 4-3



Preface

This document describes how to configure and manage a WebLogic Messaging Bridge as a forwarding mechanism between any two messaging products—thereby providing interoperability between separate implementations of WebLogic JMS, or between WebLogic JMS and another messaging product.

- Audience
- Documentation Accessibility
- Diversity and Inclusion
- Related Documentation
- Conventions

Audience

This document is a resource for system administrators who want to configure and manage a WebLogic Messaging Bridge. It also contains information that is useful for business analysts and system architects who are evaluating WebLogic Server or considering the use of WebLogic Server JMS for a particular application.

It is assumed that the reader is familiar with programming in Jakarta Platform, Enterprise Edition (Jakarta EE) and JMS concepts. This document emphasizes the value-added features provided by WebLogic Server and key information about how to use WebLogic Server features and facilities to configure and manage a messaging bridge.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve.



Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Related Documentation

For information on topics related to configuring and managing a messaging bridge, see the following documents:

- Administering JMS Resources for Oracle WebLogic Server is a guide to configuring and managing WebLogic JMS resources.
- Developing JMS Applications for Oracle WebLogic Server is a guide to developing WebLogic JMS applications.
- Tuning Performance of Oracle WebLogic Server provides information on how to monitor performance and tune the components in a WebLogic Server.
- Developing Applications for Oracle WebLogic Server is a guide to developing WebLogic Server applications.
- Deploying Applications to Oracle WebLogic Server is the primary source of information about deploying WebLogic Server applications.
- Developing Resource Adapters for Oracle WebLogic Server contains information on WebLogic resource adapters and the WebLogic Server implementation of the Jakarta Connector Architecture.
- Samples and Tutorials
- New and Changed WebLogic Server Features

Samples and Tutorials

Oracle provides a variety of code examples and tutorials that show WebLogic Server configuration and API use, and provide practical instructions on how to perform key development tasks.

For more information, see Sample Applications and Code Examples in *Understanding Oracle WebLogic Server*.

New and Changed WebLogic Server Features

For a comprehensive listing of the new WebLogic Server features introduced in this release, see *What's New in Oracle WebLogic Server*.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.



1

Understanding the Messaging Bridge

This chapter describes WebLogic Messaging Bridge components, concepts and functionality. This chapter includes the following sections:

- What is a Messaging Bridge?
 - The WebLogic Messaging Bridge is a forwarding mechanism that provides interoperability between WebLogic JMS implementations. A messaging bridge also provides interoperability between JMS and other messaging products.
- Messaging Bridge Components
- Configuring and Managing a Messaging Bridge
- Configuring Messaging Bridges for High Availability
 You can target a messaging bridge to a cluster and configure it for high availability and dynamic scalability.

What is a Messaging Bridge?

The WebLogic Messaging Bridge is a forwarding mechanism that provides interoperability between WebLogic JMS implementations. A messaging bridge also provides interoperability between JMS and other messaging products.

Use the Messaging Bridge to integrate your messaging applications between:

- Any two implementations of WebLogic JMS, including those from separate releases of WebLogic Server.
- WebLogic JMS implementations that reside in separate WebLogic domains.
- WebLogic JMS and a third-party JMS product (for example, MQSeries).

A messaging bridge instance forwards messages between a pair of bridge source and target destinations. These destinations are mapped to a pair of bridge source and target destinations. The messaging bridge reads messages from the source bridge destination and forwards those messages to the target bridge destination. For WebLogic JMS and third-party JMS products, a messaging bridge communicates with source and target destinations using the Jakarta Connector Architecture (JCA) resource adapters provided with WebLogic Server. See Figure 1-1.


Note:

Messaging bridge configuration has been simplified since WebLogic Server 12.2.1. You need not explicitly configure and deploy bridge adapters. Instead, a messaging bridge now uses the automatically deployed internal adapters when the bridge is configured with a default adapter JNDI name

(eis.jms.WLSConnectionFactoryJNDINoTX or eis.jms.WLSConnectionFactoryJNDIXA). These internal adapters also have a much larger connection capacity.

Legacy adapters explicitly configured with the default adapter JNDI names still deploy, but are ignored by messaging bridges. The legacy adapter deployments can be removed in the configuration after upgrading to WebLogic Server 12.2.1.

Figure 1-1 WebLogic Messaging Bridge



You designate source and target bridge destinations as either queues, topics, or distributed destinations, as described in *Developing JMS Applications for Oracle WebLogic Server*. Optionally, specify a quality of service (QOS), including message filters, transaction semantics, connection retry policies, and high availability options. After you configure a messaging bridge, you can perform management tasks from the WebLogic Remote Console, including suspending bridge traffic temporarily whenever necessary and monitoring the status of all your configured bridges.

Messaging Bridge Components

The following sections describe resources needed to use a messaging bridge:

- · Resource Adapters
- Source and Target Bridge Destinations
- Messaging Bridge Instance

Resource Adapters

A messaging bridge uses JCA resource adapters to communicate with the configured source and target JMS destinations. Associate both the source and target JMS destinations with a

supported resource adapter in order for the bridge to communicate with them. The JNDI name for the adapter is configured as part of the resource adapter's deployment descriptor. See Table 1-1.

Note:

Messaging bridge configuration has been simplified since WebLogic Server 12.2.1. You need not explicitly configure and deploy bridge adapters. Instead, a messaging bridge now uses the automatically deployed internal adapters when the bridge is configured with a default adapter JNDI name

(eis.jms.WLSConnectionFactoryJNDINoTX or eis.jms.WLSConnectionFactoryJNDIXA). These internal adapters also have a much larger connection capacity.

Legacy adapters explicitly configured with the default adapter JNDI names still deploy, but are ignored by messaging bridges. The legacy adapter deployments can be removed in the configuration after upgrading to WebLogic Server 12.2.1.

When a messaging bridge needs to use a built-in adapter with modified deployment descriptor parameters, explicit deployment of an adapter is required. In this case, the modified adapter must be deployed with a non-default JNDI name, and the messaging bridge adapter JNDI name attribute needs to be configured to match the non-default name.

Resource adapters for different types of JMS destinations are provided in exploded format or in a .rar file. The exploded format gives you an easy way to modify resource adapter deployment descriptor parameters, such as the max-capacity of the connection factory that specifies the maximum number of connections available for bridge instances.

Note:

 Starting from WebLogic Server 12.2.1 release, the explored .rar format for bridge adapters is not available in the installation kit.

These are a couple of workarounds:

- Remove explicit adapter deployments and use the internally deployed adapters. The internal adapters set a higher max-capacity for the connection factory than the original .rar files.
- If you still prefer explicitly deploying an adapter, use one of the .rar files or generate the exploded format by using jar -xf on a .rar file.
- Changing a deployment descriptor for a resource adapter using the exploded format does not update the descriptor packaged in the .rar file. See Setting the Number of Connection Factories.

The supported resource adapters are located in the $WL_HOME \setminus lib$ directory and are described in Table 1-1.



Table 1-1 Messaging Bridge Resource Adapters and JNDI Names

Adapter	JNDI Name	Description	
jms-xa-adp	eis.jms.WLSCo nnectionFacto ryJNDIXA	•	
		 Any WebLogic Server implementation being bridged must be release 7.0 or later. The source and target JMS connection factories must be configured to use the XAConnectionFactory. 	
		Note: Before deploying this adapter, refer to the Configuring Interoperability for WebLogic Domains for specific transactional configuration requirements and guidelines.	
jms-notran- adp	eis.jms.WLSCo nnectionFacto ryJNDINoTX		
		Note: For more information about the acknowledge modes used in non-transacted sessions, see Understanding WebLogic JMS in <i>Developing JMS Applications for Oracle WebLogic Server</i> .	

Source and Target Bridge Destinations

A messaging bridge connects two actual destinations that are mapped to bridge destinations: a source destination *from which* messages are received, and a target destination *to which* messages are sent.

For JMS messaging products, whether it is a WebLogic JMS implementation or a third-party JMS provider, configure a JMS bridge destination instance for each actual source and target JMS destination being mapped to a messaging bridge. A JMS bridge destination instance defines a unique name for a bridge's source and target destinations within a WebLogic domain; the name of the adapter used to communicate with the specified destination; property information to pass to the adapter (such as Connection URL and Connection Factory JNDI Name), and, optionally, a user name and password.

See Create a JMS Bridge Destination in the Oracle WebLogic Remote Console Online Help.

- JMS Bridge Destinations
- General Bridge Destinations

JMS Bridge Destinations

For JMS messaging products, whether it is a WebLogic JMS implementation or a third-party JMS provider, configure a JMS bridge destination instance for each actual source and target JMS destination being mapped to a messaging bridge. A JMS bridge destination instance defines a unique name for a bridge's source and target destinations within a WebLogic domain; the name of the adapter used to communicate with the specified destination; property information to pass to the adapter (such as Connection URL and Connection Factory JNDI Name), and, optionally, a user name and password.

 Interoperating with Different WebLogic Server Releases or Interoperating with Foreign Providers sections for specific configuration requirements and guidelines. When configuring third-party JMS provider bridge destination, use the Foreign JMS Server feature to configure multiple source or target destinations quickly. See Configuring Foreign Server Resources to Access Third-Party JMS Providers in Administering JMS Resources for Oracle WebLogic Server.

General Bridge Destinations

For non-JMS messaging products, you need to configure a general bridge destination instance for each actual source and target destination being mapped to a messaging bridge. A general bridge destination instance defines a unique name for the actual source and target general bridge destinations within the WebLogic domain; the name of the adapter used to communicate with the specified destination; a list of properties to pass to the adapter; and, optionally, a user name and password.



Although WebLogic JMS includes a "General Bridge Destination" framework for accessing non-JMS messaging products, WebLogic Server does not provide adapters for such products. Therefore, you must obtain a custom connector adapter from a third-party OEM vendor and consult their documentation for configuration instructions. Contact BEA Professional Services for information about obtaining a custom connector adapter.

Messaging Bridge Instance

A messaging bridge instance communicates with the configured source and target bridge destinations. For each mapping of a source destination to a target destination, whether it is another WebLogic JMS implementation or a third-party JMS provider, you must configure a messaging bridge instance. Each messaging bridge instance defines the source and target destination for the mapping, a message filtering selector, a QOS, transaction semantics, and various reconnection parameters.

See Create a Messaging Bridge Instance in the *Oracle WebLogic Remote Console Online Help*.

Configuring and Managing a Messaging Bridge

The following sections provide information on how to use the WebLogic Remote Console to configure and manage a messaging bridge:

Create a Messaging Bridge Instance

Create a Messaging Bridge Instance

Creating a messaging bridge consists of the following tasks:

- Create source and target bridge destinations.
- Deploy a resource adapter.
- 3. Create a messaging bridge instance.
- Configure any required high availability parameters. See Configuring Messaging Bridges for High Availability.



Target the messaging bridge.

The WebLogic Remote Console assists you in creating a messaging bridge by deploying an appropriate resource adapter and setting the values of some attributes. Consider changing messaging bridge settings to better suit your environment. See Create a Messaging Bridge Instance in *Oracle WebLogic Remote Console Online Help*.

Configuring Messaging Bridges for High Availability

You can target a messaging bridge to a cluster and configure it for high availability and dynamic scalability.

When the distribution policy property of the messaging bridge is set to **Distributed**, then one instance of the bridge will be created and started on each cluster member. If the distribution policy is set to **Singleton**, then only a single instance of the bridge will be started in the cluster. See Defining the Distribution Policy for JMS Services in *Administering JMS Resources for Oracle WebLogic Server*.

Bridges require the migration policy set to **On-Failure** or **Off**. A validation error will be logged when the users try to configure the migration policy as **Always**. Bridges already have the built-in mechanism to retry failed operations. Therefore, bridges ignore the restart-in-place settings. See Defining the Migration Policy for JMS Services in *Administering JMS Resources for Oracle WebLogic Server*.



Designing a Messaging Bridge

Learn how to design, configure, and tune a Messaging Bridge.

- When to use a Messaging Bridge
- When to Avoid Using a Messaging Bridge
- Selecting a Quality-of-Service (QOS) Level
- Messaging Persistence
- Message Ordering
- Setting the Number of Connection Factories
- Preserving Message Properties
- Using the JMSXUserID Property with a Messaging Bridge
- Using Distributed Destinations as Source and Target Destinations
- Tuning a WebLogic Messaging Bridge

When to use a Messaging Bridge

The following sections provide information on when to use a messaging bridge:

- Store and Forward Messaging
- Replicating a Topic

Store and Forward Messaging

A messaging bridge provides high availability for remote destinations. Store and forward messaging enables a local client to produce to a local destination and have those messages automatically forwarded to the remote destination when it is available. This allows a local client to continue to produce messages when a remote destination is not available. See Messaging Persistence.

Use the WebLogic Messaging Bridge to provide an administrative solution to store and forward messages between:

- Any two implementations of WebLogic JMS, including those from separate releases of WebLogic Server.
- WebLogic JMS implementations that reside in separate WebLogic domains.
- WebLogic JMS with a third-party JMS product (for example, MQSeries).

WebLogic JMS with non-JMS messaging products (only by using specialized connector adapters that are not provided with WebLogic Server)

Replicating a Topic

A messaging bridge can replicate a topic, similar to using the distributed topics feature available in WebLogic Server releases, consequently improving scalability and high availability

in some scenarios. (For information about using distributed topics, see Using Distributed Destinations in *Developing JMS Applications for Oracle WebLogic Server*.) Topic replication is accomplished by configuring the bridge to subscribe to one topic and forward the topic's messages to another topic, in essence creating two topics with the same message stream.

See Create a Messaging Bridge Instance in the *Oracle WebLogic Remote Console Online Help*.

When to Avoid Using a Messaging Bridge

The following sections provide information on when to avoid using messaging bridge:

- Receiving messages from a remote destination—Use a message driven EJB or implement a client consumer directly.
- Sending messages to a local destination—Send directly to the local destination.
- Environment with low tolerance for message latency. Messaging Bridges increase latency
 and may lower throughput. Messaging bridges increase latency for messages as they
 introduce an extra destination in the message path and may lower throughput because
 they forward messages using a single thread.
- Forward messages between WebLogic domains—Use WebLogic Store-and-Forward.
- The source or target is not a JMS provider.

Table 2-1 summarizes information on when to use WebLogic Messaging Bridge or other forwarding technologies:

Table 2-1 Comparing Message Forwarding Technologies

Feature	Messaging Bridge	Message Driven Beans	WebLogic Store-and- Forward
Implementation mechanism	Administrative	Programmatic	Administrative
Support for foreign and legacy providers	Yes	No	No, use to forward messages

Selecting a Quality-of-Service (QOS) Level

The WebLogic Messaging Bridge supports three different QOS levels:

- Exactly-once—The highest QOS guarantees that a message is sent to the remote
 endpoint once and only once. With Exactly-once, messages survive server crashes and
 network down time, while guaranteeing one occurrence of each message at the endpoint.
- At-least-once—Guarantees that a message is sent to the remote endpoint, but with the
 possibility of duplicates. With At-least-once, multiple copies of a message may appear on
 the remote endpoint because of network failures or server crashes that occur when the
 message is in transit.
- At-most-once—The lowest QOS guarantees that each message is sent to the remote
 endpoint only once, if at all. It does not guarantee that a message is sent to the endpoint.
 With At-most-once, messages may get lost because of network failures or server crashes.
 No duplicate messages reach the endpoint.



In some instances, the target destination may not be able to provide the quality of service configured for the bridge. In these cases, configure the bridge instance to allow the quality of service to be degraded by setting the QOSDegradationAllowed flag.

See Create a Messaging Bridge Instance in the *Oracle WebLogic Remote Console Online Help*.

Messaging Persistence

Store-and-forward messaging enables a local JMS client to produce messages to a local destination and have those messages automatically forwarded to a remote destination when it is available. The bridge forwards these messages to the target destination when it is restarted. A messaging bridge stores and forwards messages to a target destination under the following conditions:

- The source destination is a queue.
- The source destination is a topic *and* the Durability Enabled attribute is set. This creates a durable subscription. See Setting Up Durable Subscriptions in *Developing JMS Applications for Oracle WebLogic Server*.

Message Ordering

If an application message is in a transaction, saving the message in the persistent store must be part of the user transaction to preserve exactly-once semantics. In particular, the message is removed from the persistent store as part of the transaction rollback if the application decides to rollback the transaction. However, forwarding is *not* part of the application transaction. The sending agent does not forward a transactional message until the transaction commits. Within a transaction, message ordering is preserved based on when the messages are sent.

To ensure message ordering, configure a message unit-of-order. See Using Message Unit-of-Order in *Developing JMS Applications for Oracle WebLogic Server*.

Setting the Number of Connection Factories

Consider modifying the capacity of the connection factory associated with each resource adaptor by adjusting the max-capacity attribute in the weblogic-ra.xml descriptor file. In general, the value of the max-capacity attribute should be at least two times the number of bridge instances. For example, if your environment has up to ten message bridge instances targeted, a max-capacity attribute setting of 20 in the default configuration is adequate. But if you increase the number of bridge instances to 15, increase the max-capacity attribute to 30.



Do not change Message Bridge adapter initial-capacity value. Oracle recommends that the initial-capacity value be set to zero (the default) as bridge instances may fail to function with ResourceAllocation errors.

Use the following steps to modify the weblogic-ra.xml descriptor file:

- Using the editor of your choice, update the attribute with the desired value. See Example 2-1.
- Deploy the updated adapter.
- 3. Stop and restart any bridge instance that requires the new values.

Example 2-1 Example weblogic-ra.xml Descriptor File

```
<weblogic-connection-factory-dd>
```

</weblogic-connection-factory-dd>

Preserving Message Properties

Set PreserveMsgProperty to preserve message properties in a message header when a message is forwarded by a bridge instance. In previous releases, message properties are inherited from the Default Delivery Mode attribute on the connection factory used when a message is forwarded to its target destination. If the Default Delivery Mode is persistent, a non-persistent message is forwarded as a persistent message resulting in a significant performance loss.

When PreserveMsgProperty is enabled, an incoming non-persistent message is forwarded by the bridge to the target destination as a non-persistent message and an incoming persistent message is forwarded to the target destination as a persistent message.

See Create a Messaging Bridge Instance in the *Oracle WebLogic Remote Console Online Help.*

The behavior of a messaging bridge instance is determined according to the following quidelines:

- The PreserveMsgProperty is not enabled. This setting provides the same forwarding behavior as previous releases.
- The default value of PreserveMsgProperty when configuring a messaging bridge instance is not enabled.
- The PreserveMsgProperty is enabled. Message properties are preserved as described in Table 2-2:

Table 2-2 Message Properties Preserved at Target Destination by WebLogic Server Release

Property	WebLogic Server 9.0 and Higher	Prior to WebLogic Server 9.0	Foreign JMS Servers
Message ID	Yes	No	No
Timestamp	Yes	No	No
User ID	Yes	No	No
Delivery Mode	Yes	Yes	Yes



Table 2-2 (Cont.) Message Properties Preserved at Target Destination by WebLogic Server Release

Property	WebLogic Server 9.0 and Higher	Prior to WebLogic Server 9.0	Foreign JMS Servers
Priority	Yes	Yes	Yes
Expiration Time	Yes	Yes	Yes
Redelivery Limit	Yes	No	No
Unit-of-Order name	Yes	No	No

Using the JMSXUserID Property with a Messaging Bridge

The messaging bridge does not disclose a message's <code>JMSXUserID</code> across messaging bridge boundaries. A <code>JMSXUserID</code> is a system generated property that identifies the user sending the message, see the <code>JMS</code> Specification, published by Oracle, at http://www.oracle.com/technetwork/java/jms/index.html.

Using Distributed Destinations as Source and Target Destinations

A messaging bridge can send to and receive from distributed destinations. Oracle recommends the following configurations:

- If the source is a distributed destination, the bridge is pinned to one of the members when it connects to the destination. It stays connected to that member until an event occurs that breaks the connection. On reconnection, the bridge uses the next available member. Once a bridge is connected, it does not receive messages from other members of the distributed destination. It is a best practice to configure one bridge for each member of a distributed destination using the member's JNDI Name.
- If the target is a distributed destination, the best practice is to send to the distributed destination using the distributed destination's JNDI Name and disable server affinity. This allows the distributed destination to load balance incoming messages. See Load Balancing for JMS in Administering Clusters for Oracle WebLogic Server.

Tuning a WebLogic Messaging Bridge

The main objective when tuning a messaging bridge is to improve overall messaging performance. Raw speed, though important, is only one of several performance-related factors. Other performance factors include reliability, scalability, manageability, monitoring, user transactions, message-driven bean support, and integration with an application server. See Tuning WebLogic Message Bridge in *Tuning Performance of Oracle WebLogic Server*.



Interoperating with Different WebLogic Server Releases or Foreign Providers

This chapter provides interoperability guidelines for using the WebLogic Messaging Bridge to access JMS destinations on different releases of WebLogic Server or when accessing foreign providers.

This chapter includes the following sections:

- Interoperating with Different WebLogic Server Releases
- Interoperating with Foreign Providers

Interoperating with Different WebLogic Server Releases

The following interoperability guidelines apply when using the messaging bridge to access JMS destinations on different releases of WebLogic Server and in other WebLogic Server domains.



When the messaging bridge is used to communicate between two domains running different releases of WebLogic Server, Oracle recommends that the messaging bridge be configured to run on the domain using the latest release of WebLogic Server.

- Supported Configurations and Compatibility
- Naming Guidelines for WebLogic Servers and Domains
- Configuring Interoperability for WebLogic Domains

Supported Configurations and Compatibility

For the most current information on supported configurations and compatibility between current version of WebLogic Server and previous releases, see Supported Configurations and WebLogic Server Compatibility in *What's New in Oracle WebLogic Server*.

Naming Guidelines for WebLogic Servers and Domains

Unique naming rules apply to all WebLogic Server deployments if more than one domain is involved. See Integration and Multi-Domain Best Practices in *Administering JMS Resources for Oracle WebLogic Server*.

Configuring Interoperability for WebLogic Domains

Configuring interoperability between domains depends on the QOS:

- Configuring Interoperability for Exactly-once QOS
- Configuring At-least-once or At-most-once QOS

Configuring Interoperability for Exactly-once QOS

Use the following guidelines to configure interoperability to handle transactional messages (using the Exactly-once QOS) between two WebLogic domains

 You must correctly configure either Cross Domain Security or Security Interop Mode for all participating domains.

Keep all the domains used by your process symmetric with respect to Cross Domain Security configuration and Security Interop Mode. Because both settings are set at the domain level, it is possible for a domain to be in a mixed mode, meaning the domain has both Cross Domain Security and Security Interop Mode set. For more information, see:

- Configuring Secure Inter-Domain and Intra-Domain Transaction Communication in Developing JTA Applications for Oracle WebLogic Server
- Changing the Asynchronous Mode Enabled Attribute in Tuning Performance of Oracle WebLogic Server
- When interoperating between two WebLogic domains, see Naming Guidelines for WebLogic Servers and Domains.
- Ensure that the XA connection factory is enabled for the domains by selecting the XAConnection Factory Enabled.

See Configure Resources for JMS System Modules in the *Oracle WebLogic Remote Console Online Help*.

• Deploy the transaction resource adapter, jms-xa-adp.rar, on the domain where the messaging bridge is running.

Note:

Messaging bridge configuration has been simplified since WebLogic Server 12.2.1. You need not explicitly configure and deploy bridge adapters. Instead, a messaging bridge now uses the automatically deployed internal adapters when the bridge is configured with a default adapter JNDI name

(eis.jms.WLSConnectionFactoryJNDINoTX Or

eis.jms.WLSConnectionFactoryJNDIXA). These internal adapters also have a much larger connection capacity.

Legacy adapters explicitly configured with the default adapter JNDI names still deploy, but are ignored by messaging bridges. The legacy adapter deployments can be removed in the configuration after upgrading to WebLogic Server 12.2.1.

- When configuring the JMS bridge destinations, as described in Create a JMS Bridge Destination in the *Oracle WebLogic Remote Console Online Help*, do the following for both the source and target destinations:
 - In the Adapter JNDI Name field, identify the transaction adapter's JNDI name, eis.jms.WLSConnectionFactoryJNDIXA.
 - Do not enter anything in the Adapter Classpath field.
- Select a Quality Of Service of Exactly-once.



See Create a Messaging Bridge Instance in the *Oracle WebLogic Remote Console Online Help*.

Configuring At-least-once or At-most-once QOS

There are no special security configuration requirements for the bridge to interoperate between two WebLogic domains. However, if you want to provide more secure communication between domains, you can configure Cross Domain Security.

Note:

Keep all the domains used by your process symmetric with respect to Cross Domain Security configuration—all domains use Cross Domain Security (or are on the appropriate exception lists) or none of the domains have Cross Domain Security configured. For more information, see:

- Configuring Cross-Domain Security in Administering Security for Oracle WebLogic Server
- Changing the Asynchronous Mode Enabled Attribute in Tuning Performance of Oracle WebLogic Server

Interoperating with Foreign Providers

When configuring a messaging bridge involves interoperability with a third-party Jakarta Messaging Service provider, you must configure the following:

- Before starting WebLogic Server:
 - Supply the provider's CLASSPATH in the WebLogic Server CLASSPATH.
 - Include the PATH of any native code required by the provider's client-side libraries in the WebLogic Server system PATH. (This variable may vary depending on your operating system.)
- In the JMSBridgeDestination instance for the third-party messaging product being bridged, provide vendor-specific information in the following attributes:
 - Connection URL
 - Initial Context Factory
 - Connection Factory JNDI Name
 - Destination JNDI Name

Note:

The messaging bridge cannot provide the "Exactly-once" quality of service when the source and target bridge destinations are located on the same resource manager (that is, when the bridge is forwarding a global transaction that is using the XA resource of the resource manager). For example, when using MQ Series, it is not possible to use the same Queue Manager for the source and target bridge destinations.



For more information on configuring the remaining attributes for a JMS Bridge Destination, see Create a JMS Bridge Destination in the *Oracle WebLogic Remote Console Online Help*.



4

FAQs: WebLogic Messaging Bridge

This chapter provides answers to frequently asked questions (FAQs) for the WebLogic Messaging Bridge.

This chapter includes the following sections:

- Why did the messaging bridge fail to connect to the source bridge destination?
- Why are some of my messages not being forwarded?
- Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases?
- I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message?
- When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field?
- How do I enable debugging for the messaging bridge?
- · Can the messaging bridge use distributed destinations as source and target destinations?
- Is there another way to monitor the messaging bridge?
- Can I use the Message Bridge in a Mixed or Dynamic Cluster?
- What are the recommendations for the bridge Distribution Policy and Migration Policy settings?

Why did the messaging bridge fail to connect to the source bridge destination?

Either an error occurred when configuring the source bridge destination parameters, or the actual source destination is not running and cannot communicate with the messaging bridge.

- Verify whether the bridge's source destination is correctly configured, by making sure that the following fields on the JMS Bridge Destination Configuration page have been properly completed:
 - Connection URL—this must be the URL of the JNDI provider used to look up the connection factory and actual destination.
 - Destination JNDI Name—this must be the JNDI name of the actual destination mapped to the source bridge destination.
 - Connection Factory JNDI Name—this must be the connection factory used to create a connection for the actual destination mapped to the source bridge destination.
 - User Name/Password—ensure that this user ID has permission to access the actual source destination.
- Verify that the actual source queue or topic destination mapped to the source bridge destination is running and healthy, as follows:
 - Is the WebLogic Server instance hosting the source destination running?

— Is the JMS server hosting the source destination correctly deployed?



This troubleshooting scenario for correcting a source bridge destination connection failure also applies to target bridge destinations.

Why are some of my messages not being forwarded?

Normally, a messaging bridge should forward all messages. If some messages are not being forwarded, here are some possible reasons:

- Some messages may have an expiration time, in which case either the JMS provider for the source or target destination expires the message.
- If you configured the bridge source destination to specify a selector filter, only the filtered messages are forwarded.
- A bridge does not directly provide an option to automatically move messages to an error
 destination, or to automatically delete messages, after a limited number of forward
 attempts. However, a JMS provider may provide such an option, which could, in turn, effect
 any messages on the bridge source destination. If a redelivery limit option is enabled on
 the JMS provider that hosts the bridge source destination, consider reconfiguring the
 provider to prevent the bridge automatic retry mechanism from causing messages to
 exceed the redelivery limit.

Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases?

Yes, see Interoperating with Different WebLogic Server Releases.

I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message?

Associate both the source and target bridge destinations with the appropriate .rar adapters in order for the bridge to communicate with them. For the jms-xa-adp.rar transaction adapter, it must be identified in the Adapter JNDI Name attribute as

eis.jms.WLSConnectionFactoryJNDIXA on the JMS Bridge Destination Æ Configuration tab for both the source and target bridge destinations.





The "failed to find bridge adapter" message does not necessarily indicate a problem if it only occurs once. However, if it occurs repeatedly, you should check the adapter deployment and the adapter JNDI name used in the source and target bridge destinations.

For more information about the bridge resource adapters, see Resource Adapters.

When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field?

Leave the Adapter Classpath field blank when connecting to source and target destinations that are both running in WebLogic Server instances. When connecting to a third-party JMS provider, the bridge destination must supply the provider's CLASSPATH in the WebLogic Server CLASSPATH.

How do I enable debugging for the messaging bridge?

You can enable debugging for the messaging bridge using either of the followings methods:

Add the following lines to your WebLogic start script (before the weblogic.Server line):

```
-Dweblogic.debug.DebugMessagingBridgeStartup=true
-Dweblogic.debug.DebugMessagingBridgeRuntime=true
```

 Add the following statements to the ServerDebug entry in your configuration file (config.xml) for the server that the messaging bridge is running on:

```
DebugMessagingBridgeStartup="true"
DebugMessagingBridgeRuntime="true"
```

After debugging is enabled for the messaging bridge, the debugging messages are sent to the server log by default.

Can the messaging bridge use distributed destinations as source and target destinations?

Yes, the messaging bridge can send to and receive from distributed destinations. Oracle recommends the following configurations:

- If the source is distributed destination, the bridge is pinned to one of the members when it
 connects to the destination. It stays connected only to that member until it reconnects. The
 bridge does not receive messages from the other members of the distributed destination.
 Therefore, the best practice is to configure one bridge for each member of a distributed
 destinations using the member's JNDIName.
- If the target is a distributed destination, the best practice is to send to the distributed destination using the distributed destination's JNDIName and disable server affinity. This allows the distributed destination to load balance incoming messages.



Is there another way to monitor the messaging bridge?

Yes, there is a run-time MBean (MessagingBridgeRuntimeMBean) for each bridge instance. WebLogic Server run-time MBeans provide a snapshot of information about domain resources. When a particular resource in the domain (such as a messaging bridge) is instantiated, an MBean instance is created which collects information about that resource.

The MessagingBridgeRuntimeMBean has a getState() method that currently returns a String ("Active" or "Inactive") and a getDescription() method, which returns a String with more detailed information. The name of a bridge runtime MBean consists of the WebLogic Server instance name and the bridge name. If a bridge named *mybridge*, runs on WebLogic Server instance named *myserver*, the bridge runtime MBean is named *myserver.bridge.mybridge*.

For more information, see:

- Introduction and Roadmap in Developing Custom Management Utilities Using JMX for Oracle WebLogic Server.
- Using the WebLogic Scripting Tool in Understanding the WebLogic Scripting Tool.

Can I use the Message Bridge in a Mixed or Dynamic Cluster?

Yes, a bridge can be targeted to any type of cluster. See the next FAQ entry for more information about tuning a bridge that is cluster-targeted.

What are the recommendations for the bridge Distribution Policy and Migration Policy settings?

The bridge Distribution Policy and Migration Policy settings take effect when a bridge is cluster-targeted. A bridge is cluster-targeted when its target is directly set to a cluster.

When an instance per server is desired for a cluster-targeted bridge, Oracle recommends setting the bridge Distributed Policy and Migration Policy to Distributed/Off respectively - these are the defaults.

When a single instance per cluster is desired for a cluster-targeted bridge, Oracle recommends setting the bridge Distributed Policy and Migration Policy to Singleton/On-Failure respectively. Singleton/On-Failure bridges will not start unless cluster leasing is also configured. (If you cannot cluster-target a bridge and still need singleton behavior in a configured cluster, you can target the bridge to a 'Migratable Target' and configure the Migration Policy on the migratable target to 'Exactly-Once'.)



Oracle recommends against setting a bridge Distributed Policy and Migration Policy to Distributed/On-Failure or Distributed/Always.

Restart-In-Place settings are ignored for a bridge, since a bridge has its own built-in retry logic.

