

Oracle® Key Vault

Root of Trust HSM Configuration Guide



Release 18.4
F29575-01
June 2020

ORACLE®

Copyright © 2013, 2020, Oracle and/or its affiliates.

Primary Author: Mark Doran

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience	vi
Documentation Accessibility	vi
Related Documents	vi
Conventions	vii

1 Getting Started with HSM

1.1	How Oracle Key Vault Works with Hardware Security Modules	1-1
1.2	Installing the HSM Client Software on an Oracle Key Vault Server	1-2
1.3	Enrolling Oracle Key Vault as a Client of the HSM	1-3

2 Configuring an HSM for Oracle Key Vault

2.1	HSM-Enabling in a Standalone Oracle Key Vault Deployment	2-1
2.2	HSM-Enabling in a Primary-Standby Oracle Key Vault Deployment	2-3
2.3	HSMs in a Multi-Master Cluster	2-5
2.3.1	About HSMs in a Multi-Master Cluster	2-5
2.3.2	Configuring an HSM for a Multi-Master Cluster Starting with Single Node (Recommended)	2-6
2.3.3	Configuring an HSM for a Multi-Master Cluster with Multiple Nodes	2-6
2.3.3.1	About Configuring an HSM for a Multi-Master Cluster with Multiple Nodes	2-7
2.3.3.2	Step 1: Create and Copy the Bundle after HSM-Enabling the First Node	2-7
2.3.3.3	Step 2: Configure the Remaining Nodes	2-8
2.4	Backup and Restore Operations in an HSM-Enabled Oracle Key Vault Instance	2-9
2.4.1	Backup Operations in an HSM-Enabled Oracle Key Vault Instance	2-9
2.4.2	Restore Operations in an HSM-Enabled Oracle Key Vault Instance	2-9
2.5	Reverse Migration Operation	2-11
2.5.1	Reverse Migrating a Standalone Deployment	2-11
2.5.2	Reverse Migrating a Primary-Standby Deployment	2-12

3 Upgrade Considerations When Using HSMs in Oracle Key Vault

3.1	Upgrades from Oracle Key Vault Release 12.2	3-1
3.1.1	Upgrading from an Oracle Key Vault Release 12.2 Standalone Deployment	3-1
3.1.2	Upgrading from an Oracle Key Vault Release 12.2 Primary-Standby Deployment	3-2
3.2	Upgrade Considerations for nCipher	3-3
3.2.1	Remaking Hardserver Changes While Upgrading Oracle Key Vault	3-4
3.2.2	Overriding Security Assurances for the Oracle Key Vault Upgrade	3-4
3.3	Using a Token Label After Upgrading Oracle Key Vault without Reverse-Migrating	3-5

4 Support Guidance

4.1	General Troubleshooting	4-1
4.1.1	Trace Files for Diagnosing Issues	4-2
4.1.2	HSM Alert	4-2
4.1.3	Could Not Get Slot for HSM Error	4-3
4.1.4	Could Not Load PKCS#11 Library Error	4-3
4.1.5	Oracle Key Vault Management Console Does Not Start After Restarting HSM-Enabled Oracle Key Vault Server	4-3
4.1.6	Primary-Standby Errors	4-3
4.1.7	Errors from HSM-Enabled Oracle Key Vault Backups	4-4
4.1.8	Restoring an HSM-Enabled Backup	4-4
4.2	Vendor Specific Notes for SafeNet	4-5
4.2.1	Installing the HSM Client Software on the Oracle Key Vault Server for SafeNet	4-5
4.2.2	HSM Credential for SafeNet	4-6
4.2.3	Token Label for SafeNet	4-6
4.2.4	Enrolling Oracle Key Vault as a Client of a SafeNet HSM	4-6
4.2.5	HSM Provider Value for SafeNet	4-7
4.2.6	HSM Vendor Specific Checks for SafeNet	4-7
4.3	Vendor Specific Notes for nCipher	4-9
4.3.1	Installing the HSM Client Software on the Oracle Key Vault Server for nCipher	4-9
4.3.2	HSM Credential for nCipher	4-10
4.3.3	Token Label for nCipher	4-10
4.3.4	Enrolling Oracle Key Vault as a Client of an nCipher HSM	4-10
4.3.5	HSM Provider Value for nCipher	4-11
4.4	Vendor Specific Notes for Utimaco	4-11

4.4.1	Installing the HSM Client Software on the Oracle Key Vault Server for Utimaco	4-12
4.4.2	HSM Credential for Utimaco	4-14
4.4.3	Token Label for Utimaco	4-14
4.4.4	HSM Provider Value for Utimaco	4-14
4.4.5	HSM Vendor Specific Checks for Utimaco	4-14

Preface

Welcome to *Oracle Key Vault Root of Trust HSM Configuration Guide* (formerly *Oracle Key Vault Integration with Hardware Security Module*). This guide explains how to integrate a hardware security module (HSM) with Oracle Key Vault.

- [Audience](#)
- [Documentation Accessibility](#)
- [Related Documents](#)
- [Conventions](#)

Audience

Oracle Key Vault is meant for users who are responsible for deploying, maintaining, and managing security within the enterprise. These users can be database, system, or security administrators. This guide can be used by any information security personnel who is responsible for protecting enterprise data residing in database servers, application servers, operating systems, and other information systems.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see these Oracle resources:

- *Oracle Database Security Guide*
- *Oracle Database Advanced Security Guide*
- *Oracle Database Administrator's Guide*
- *Oracle Data Guard Concepts and Administration*
- *Oracle Real Application Clusters Administration and Deployment Guide*
- *Oracle Fusion Middleware Understanding Oracle GoldenGate*

To download the product data sheet, frequently asked questions, links to the latest product documentation, product download, and other collateral, visit the Oracle Technology Network (OTN). You must register online before using OTN. Registration is free and can be done at

<https://www.oracle.com/database/technologies/security/key-vault.html>

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1

Getting Started with HSM

To integrate a hardware security module (HSM) with Oracle Key Vault, you must install the HSM client software and enroll Oracle Key Vault as an HSM client.

- [How Oracle Key Vault Works with Hardware Security Modules](#)
This guide explains how to configure Oracle Key Vault to use a supported hardware security module (HSM).
- [Installing the HSM Client Software on an Oracle Key Vault Server](#)
After you install Oracle Key Vault, you can install the HSM client software on the Oracle Key Vault server.
- [Enrolling Oracle Key Vault as a Client of the HSM](#)
You must enroll Oracle Key Vault as a client of HSM and ensure connectivity between the HSM client and the HSM.

1.1 How Oracle Key Vault Works with Hardware Security Modules

This guide explains how to configure Oracle Key Vault to use a supported hardware security module (HSM).

A hardware security module (HSM) contains tamper-resistant, specialized hardware that is designed to protect security objects stored within the HSM. HSMs are physical computing devices that safeguard and manage digital keys, and provide cryptographic processing for clients. HSMs do not usually allow security objects to leave the cryptographic boundary of the HSM.

Oracle Key Vault is a key management platform designed to securely store, manage and share security objects. Unlike an HSM, Oracle Key Vault allows trusted clients to retrieve security objects like decryption keys. Oracle Key Vault is a full-stack software appliance that contains an operating system, database, and key-management application. Oracle Key Vault is designed to help organizations store and manage their keys and credentials.

Your organization may require the use of an HSM to protect encryption keys. Because they are designed to not allow keys to leave the cryptographic boundary of the HSM, in most cases it is not practical to connect databases directly to an HSM. Instead, databases will connect to the Oracle Key Vault which will in turn be protected by the HSM. This configuration establishes a Root-of-Trust (RoT) for Oracle Key Vault in the HSM. When an HSM is deployed with Oracle Key Vault, the RoT remains in the HSM. The HSM RoT protects the Transparent Data Encryption (TDE) wallet password, which protects the TDE master key, which in turn protects all the encryption keys, certificates, and other security artifacts managed by the Oracle Key Vault server. Note that the HSM in this RoT usage scenario does not store any customer encryption keys. The customer keys are stored and managed directly by the Oracle Key Vault server.

Using HSM as a RoT is intended to mitigate attempts to recover keys from an Oracle Key Vault server which has been started in an unauthorized environment. Physical

loss of an Oracle Key Vault server from a facility is one example of such a scenario. An unauthorized user attempting to run a lost or stolen Oracle Key Vault server, without authorized access to the HSM, would be prevented from recovering the encryption keys stored on the appliance.

Oracle Key Vault employs a hierarchy of security controls including operating system hardening, database encryption, and data access enforcement using Database Vault. These controls are designed to mitigate the risk of users potentially extracting keys and credentials from systems they can physically access. Administrators do not need to access the internal components of the appliance for normal, day-to-day operations. Oracle Key Vault should be deployed in a secure location, and physical and logical access to the appliance should be controlled and monitored.

If your site uses HSMs from SafeNet, nCipher (a Thales company), or Utimaco, then you can configure these HSM products with Oracle Key Vault in standalone, primary-standby, and multi-master environments.

This guide assumes that you have installed and configured Oracle Key Vault. It also assumes that you have sufficient knowledge of the of the HSM products that you plan to configure.

The general process that you must follow to configure the HSM with Oracle Key Vault is as follows:

1. Install the HSM client software on the Oracle Key Vault server.
2. Enroll Oracle Key Vault as a client of the HSM.
3. Perform further configuration operations, which are as follows:
 - Configure protection for the TDE master encryption key with the HSM.
 - Use an HSM in a primary-standby Oracle Key Vault installation.
 - Use an HSM in an Oracle Key Vault multi-master cluster environment.
 - Perform backup and restore operations in an HSM-enabled Oracle Key Vault instance.
 - When necessary, perform reverse-migration so that the Oracle Key Vault environment is no longer HSM-enabled.

1.2 Installing the HSM Client Software on an Oracle Key Vault Server

After you install Oracle Key Vault, you can install the HSM client software on the Oracle Key Vault server.

1. Ensure that the vendor's software includes a PKCS#11 library.
Refer to the HSM documentation from the HSM vendor for more information.
2. Install the HSM vendor's client software on the Oracle Key Vault server.
You can install SafeNet, nCipher, or Utimaco HSM products.

Related Topics

- [Installing the HSM Client Software on the Oracle Key Vault Server for SafeNet](#)
You must use the SafeNet client version 6.2 for Linux x64 for the installation.

- [Installing the HSM Client Software on the Oracle Key Vault Server for nCipher](#)
The nCipher HSM requires a separate non-HSM computer on the network to use as the remote file system.
- [Installing the HSM Client Software on the Oracle Key Vault Server for Utimaco](#)
The setup files for Utimaco are provided in the `SecurityServerEvaluation-V4.31.1.0.zip` file from Utimaco.

1.3 Enrolling Oracle Key Vault as a Client of the HSM

You must enroll Oracle Key Vault as a client of HSM and ensure connectivity between the HSM client and the HSM.

1. Install the HSM vendor's client software on the Oracle Key Vault server.
2. Ensure that the HSM client software can communicate from Oracle Key Vault to the HSM.

Related Topics

- [Installing the HSM Client Software on an Oracle Key Vault Server](#)
After you install Oracle Key Vault, you can install the HSM client software on the Oracle Key Vault server.
- [Enrolling Oracle Key Vault as a Client of a SafeNet HSM](#)
To perform the enrollment, you use the Oracle Key Vault management console and the command-line interface.
- [Enrolling Oracle Key Vault as a Client of an nCipher HSM](#)
You use both the nCipher user interface and the command line to enroll Oracle Key Vault as a client of an nCipher HSM.

2

Configuring an HSM for Oracle Key Vault

Oracle Key Vault can be configured to use the HSM as the Root of Trust in a standalone, primary-standby, or multi-master cluster environment.

- [HSM-Enabling in a Standalone Oracle Key Vault Deployment](#)
You can use the Oracle Key Vault management console to HSM-enable Oracle Key Vault, which configures additional protection for the TDE master encryption key.
- [HSM-Enabling in a Primary-Standby Oracle Key Vault Deployment](#)
In an Oracle Key Vault primary-standby deployment, you must perform the HSM-enabling tasks separately on the Oracle Key Vault servers that will become primary and standby servers.
- [HSMs in a Multi-Master Cluster](#)
You can configure HSMs in a multi-master cluster with a single node or multiple nodes.
- [Backup and Restore Operations in an HSM-Enabled Oracle Key Vault Instance](#)
You can back up and restore an HSM-enabled Oracle Key Vault instance.
- [Reverse Migration Operation](#)
Reverse migrating an HSM-enabled Oracle Key Vault server reverts the Key Vault server to using the recovery passphrase to protect the TDE wallet.

2.1 HSM-Enabling in a Standalone Oracle Key Vault Deployment

You can use the Oracle Key Vault management console to HSM-enable Oracle Key Vault, which configures additional protection for the TDE master encryption key.

If you plan to use a multi-master cluster, then Oracle recommends that you perform this procedure before you configure the cluster environment. Ensure that you complete the following steps on this server before you start these steps on another Oracle Key Vault server.

1. If you have installed the nCipher client software, then run the following command as user `oracle`:


```
oracle$ /opt/nfast/bin/rfs-sync --update
```

2. Log into the Oracle Key Vault management console as a user with the System Administrator role.

If you are using a multi-master cluster environment, then log into the Oracle Key Vault node that you want to HSM-enable.


3. Click the **System** tab.
The Status page appears.
4. Click **Hardware Security Module** in the left sidebar.

The Hardware Security Module page appears. The red downward arrow shows the non-initialized **Status**. The **Type** field displays **None**.



5. Click **Initialize**.

The Initialize HSM dialog box appears.



6. Enter the HSM credential two times: first in **HSM Credential** and second in **Re-enter HSM Credential**.

Consult the documentation that came with your HSM for this credential. The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. For Utimaco, the credential is the PIN that was initialized when the token was configured.

7. Enter the **Recovery Passphrase** for Oracle Key Vault.
8. If you want Oracle Key Vault to use a specific token to create and use objects in the HSM, then select the **Use Token Label** check box and enter the token label of the token that Oracle Key Vault should use.

Oracle recommends that you select **Use Token Label** if Oracle Key Vault has access to more than one token.

9. Click **Initialize**.

At the end of a successful initialize operation, the **Hardware Security Module** page appears. The initialized **Status** is indicated by an upward green arrow. The **Type** field displays details of the HSM in use.

Hardware Security Module		Initialize	Set Credential	Reverse Migrate
Status	↑			
Type	Token label: myPartition1 Manufacturer ID: Safenet, Inc. Firmware version: 6.109			

10. If you are using an nCipher HSM, then run the following command as user `oracle`:

```
oracle$ /opt/nfast/bin/rfs-sync --commit
```

If you do not perform this step after each initialization when using nCipher, then the multiple features will not be usable, including restoring backups and using the primary-standby configuration.

11. Verify that the operation was successful by checking the most recent initialization log files in the `/var/okv/log/hsm/` directory.

If the initialize operation fails, then you will be redirected to the Hardware Security Module page with non-initialized **Status** and **Type** None. You can find detailed information in the log files in the `/var/okv/log/hsm` directory.

Note:

If you change the HSM credential on the HSM after initialization, then you must also update the HSM credential on the Oracle Key Vault server using the **Set Credential** command before the system restarts. Oracle does not recommend that you change the HSM credential after HSM initialization if there are primary-standby Oracle Key Vault deployments using the HSM, because the standby does not have its credential set by the **Set Credential** command on the primary.

2.2 HSM-Enabling in a Primary-Standby Oracle Key Vault Deployment

In an Oracle Key Vault primary-standby deployment, you must perform the HSM-enabling tasks separately on the Oracle Key Vault servers that will become primary and standby servers.

You must perform this task before pairing these two servers in a primary-standby configuration. If you have already HSM-enabled either the primary or the standby server, or both, but do not follow these steps and then do a primary-standby pairing, then the configuration will fail. If the servers are already paired but neither are HSM-enabled, then you must unpair them, reinstall the standby server, and then follow these steps.

1. Install two separate Oracle Key Vault instances.
2. Choose one to be the primary and the other to be the standby server.
3. Install the HSM client software on both the servers that will be used as the primary and the standby servers.
4. Enroll the designated primary and standby servers as clients of the same HSM.
5. HSM-enable the designated primary server.

If you are using nCipher, ensure that you have already executed `/opt/nfast/bin/rfs-sync --commit` on this server as user `oracle` before continuing.

6. Perform the following steps on the primary server:
 - a. Log in to the designated primary server through SSH as user `support`, switch user (`su`) to `root`, then switch user (`su`) to `oracle`.

```
$ ssh support@okv_primary_instance_ip_address
support$ su root
root# su oracle
```

- b. Securely copy the following files to the designated standby server:

```
oracle$ cd /usr/local/okv/hsm/wallet
oracle$ scp cwallet.sso support@okv_standby_instance_ip_address:/tmp
oracle$ scp encdepwd support@okv_standby_instance_ip_address:/tmp
oracle$ cd /usr/local/okv/hsm/restore
oracle$ scp ewallet.p12 support@okv_standby_instance_ip_address:/tmp
```

7. Perform the following steps on the designated standby server:
 - a. Log in to the designated standby server through SSH as user `support`, then switch user (`su`) to `root`.

```
$ ssh support@okv_standby_instance_ip_address
support$ su root
```

- b. Set up the HSM-related files and in the `okv_security.conf` file, set the `HSM_ENABLED` and `HSM_PROVIDER` parameters.

Earlier versions of Oracle Key Vault may not contain certain parameters in `okv_security.conf` that are present in later versions.

```
root# cd /usr/local/okv/hsm/wallet
root# mv /tmp/encdepwd .
root# mv /tmp/cwallet.sso .
root# chown oracle *
root# chgrp oinstall *
root# cd /usr/local/okv/hsm/restore
root# mv /tmp/ewallet.p12 .
root# chown oracle *
root# chgrp oinstall *
root# vi /usr/local/okv/etc/okv_security.conf
      Set HSM_ENABLED="1"
      Set HSM_PROVIDER="provider_value"
```

In this specification:

- HSM_ENABLED is set in this example to 1 to prepare the designated standby to use the HSM should a switchover or failover occur.
- HSM_PROVIDER refers to the HSM provider. For SafeNet, set this value to 1. For nCipher, set it to 2. For Utimaco, set it to 3.
The HSM_PROVIDER may not be present in the `okv_security.conf` file. If this setting is present, then change it to the setting that is appropriate for the HSM provider. If it is not present, then add the following line. Ensure that the `provider_value` setting is in quotation marks.

```
HSM_PROVIDER="provider_value"
```

- c. Save and quit by entering the following sequence of characters in the `vi` file:

```
:wq!
```

- d. If you are using nCipher, then execute the following commands:

```
root# su - oracle
oracle$ /opt/nfast/bin/rfs-sync --update
```

8. Without restarting the Oracle Key Vault instances, navigate to the primary and standby Oracle Key Vault management consoles and configure primary-standby environment.

Related Topics

- [Oracle Key Vault Administrator's Guide](#)

2.3 HSMs in a Multi-Master Cluster

You can configure HSMs in a multi-master cluster with a single node or multiple nodes.

- [About HSMs in a Multi-Master Cluster](#)
You can configure each node in the cluster to use an HSM to store each node's Root of Trust (RoT) key.
- [Configuring an HSM for a Multi-Master Cluster Starting with Single Node \(Recommended\)](#)
Oracle recommends that to use an HSM with a multi-master cluster, you start with a single HSM-enabled node and add additional HSM-enabled nodes using the node induction process.
- [Configuring an HSM for a Multi-Master Cluster with Multiple Nodes](#)
You can configure HSM for multiple nodes by copying a bundle from the first HSM-enabled node to the other nodes in the cluster before configuring HSM for the other nodes.

2.3.1 About HSMs in a Multi-Master Cluster

You can configure each node in the cluster to use an HSM to store each node's Root of Trust (RoT) key.

This RoT protects master encryption keys that Oracle Key Vault uses. HSMs are built with specialized tamper-resistant hardware which is harder to access than normal servers. This protects the RoT and makes it difficult to extract encrypted data, lowering the risk of compromise. In addition, you can use HSMs in FIPS 140-2 level 3 mode, which enables you to meet certain compliance requirements.

In a multi-master Oracle Key Vault installation, any Key Vault node in the cluster can use any HSM. The nodes in the multi-master cluster will use different TDE wallet passwords and RoT keys and may or may not use different HSM credentials, depending on how you choose to configure each cluster node.

**Note:**

To ensure complete security, you must HSM-enable all Oracle Key Vault nodes in the cluster.

2.3.2 Configuring an HSM for a Multi-Master Cluster Starting with Single Node (Recommended)

Oracle recommends that to use an HSM with a multi-master cluster, you start with a single HSM-enabled node and add additional HSM-enabled nodes using the node induction process.

Oracle recommends the following steps to configure an HSM for a multi-master cluster with a single node:

1. Convert an Oracle Key Vault server into the first node of the cluster.
2. HSM-enable the first node before adding any new nodes.
3. HSM-enable the candidate node before adding it to the cluster.
4. Add the HSM-enabled candidate node to the cluster using a controller node that is also HSM-enabled.

Note the following:

- If any node in the cluster is already HSM-enabled, you cannot add a new node that is not HSM-enabled.
- The Add Node to Cluster page on the controller node will require the controller node's HSM credential.

Related Topics

- [Configuring an HSM for a Multi-Master Cluster with Multiple Nodes](#)
You can configure HSM for multiple nodes by copying a bundle from the first HSM-enabled node to the other nodes in the cluster before configuring HSM for the other nodes.
- *Oracle Key Vault Administrator's Guide*

2.3.3 Configuring an HSM for a Multi-Master Cluster with Multiple Nodes

You can configure HSM for multiple nodes by copying a bundle from the first HSM-enabled node to the other nodes in the cluster before configuring HSM for the other nodes.

- [About Configuring an HSM for a Multi-Master Cluster with Multiple Nodes](#)
The general procedure is to perform steps on first on one node of the cluster, then on the other nodes in the cluster.

- [Step 1: Create and Copy the Bundle after HSM-Enabling the First Node](#)
After HSM-enabling the first node in the multi-master cluster, you must create a bundle and copy it to the other nodes in the cluster.
- [Step 2: Configure the Remaining Nodes](#)
After you configure the first node, you are ready to install the bundle on the remaining nodes.

2.3.3.1 About Configuring an HSM for a Multi-Master Cluster with Multiple Nodes

The general procedure is to perform steps on first on one node of the cluster, then on the other nodes in the cluster.

The instructions for configuring an HSM for a multi-master cluster starting with a single node explain how to configure an HSM for a multi-master cluster, starting with a single node of the cluster and is the recommended way to configure a cluster to use HSM(s). However, if you have already configured a multi-master cluster, you can still configure the cluster to use HSMs. However, there are extra steps needed, involving manually copying a bundle from the first HSM-enabled node to all of the other nodes in the cluster and applying it before proceeding to HSM-enable any other node. Note that if the first node that is HSM-enabled has a read-write peer node, then the read-write peer will not be able to decrypt the replicated information from the HSM-enabled node until the bundle is copied and applied successfully to the read-write peer. This could result in data loss if the bundle is not immediately successfully created and applied to the read-write peer, even if the first node that is HSM-enabled is reverse-migrated afterwards.

After you HSM-enable the first node in the cluster, use the following steps to create the bundle on the HSM-enabled node and copy and apply it on all other nodes in the cluster before you proceed to HSM-enable any other node.

Related Topics

- [Configuring an HSM for a Multi-Master Cluster Starting with Single Node \(Recommended\)](#)
Oracle recommends that to use an HSM with a multi-master cluster, you start with a single HSM-enabled node and add additional HSM-enabled nodes using the node induction process.

2.3.3.2 Step 1: Create and Copy the Bundle after HSM-Enabling the First Node

After HSM-enabling the first node in the multi-master cluster, you must create a bundle and copy it to the other nodes in the cluster.

You must HSM-enable the first node in the cluster similar to how you would HSM-enable a standalone Oracle Key Vault deployment, but with the additional steps in this section.

1. Log in to the Oracle Key Vault management console as a user who has the System Administrator role.
2. Click the **System** tab.
3. On the left side of the System page, click **Hardware Secure Module**.
4. On the HSM-enabled node, click **Create Bundle** on the HSM page.
5. In the Create Bundle dialog box, do the following:

- a. In the **HSM Credential** field, enter the HSM credential.
 - b. In the **Recovery Passphrase** field, enter the recovery passphrase.
 - c. Click the **Create Bundle** button.
6. Log in to the HSM-enabled node through SSH as user `support`.

```
$ ssh support@hsm_enabled_node
```

7. Switch to the `root` user.

```
support$ su root
```

8. To copy the bundle to the `/usr/local/okv/hsm` location on each of the other nodes using the IP address, use SCP.

Ensure that you perform this step using the IP address of all other nodes in the cluster.

```
root# scp /usr/local/okv/hsm/hsmbundle support@ip_address:/tmp
```

Related Topics

- [HSM-Enabling in a Standalone Oracle Key Vault Deployment](#)
You can use the Oracle Key Vault management console to HSM-enable Oracle Key Vault, which configures additional protection for the TDE master encryption key.

2.3.3.3 Step 2: Configure the Remaining Nodes

After you configure the first node, you are ready to install the bundle on the remaining nodes.

Complete this procedure as soon as possible after you have HSM-enabled the first node and copied the bundle to all other nodes.

1. Log in to each node in the cluster using the IP address (except the original HSM-enabled node):

```
$ ssh support@ip_address
```

2. On each node, switch to the `root` user.

```
support$ su root
```

3. Perform the following steps on each node:

```
root# cp /tmp/hsmbundle /usr/local/okv/hsm/  
root# chown oracle:oinstall /usr/local/okv/hsm/hsmbundle
```

4. On each node except the original HSM-enabled node, click **Apply Bundle** on the **HSM** page, and then follow these steps:
 - a. In the **Recovery Passphrase** field, enter the recovery passphrase.
 - b. Click the **Apply Bundle** button.

You must apply the bundle immediately on all nodes before you reverse-migrate the original HSM-enabled node.

5. Proceed to HSM-enable each of the remaining nodes in the cluster.
6. After you have HSM-enabled all nodes and verified the replication between all nodes, remove the `hmsbundle` file from all of the nodes.

2.4 Backup and Restore Operations in an HSM-Enabled Oracle Key Vault Instance

You can back up and restore an HSM-enabled Oracle Key Vault instance.

- [Backup Operations in an HSM-Enabled Oracle Key Vault Instance](#)
The steps to back up Oracle Key Vault data in an HSM-enabled instance are the same as the steps used to back up an instance that has not been HSM-enabled.
- [Restore Operations in an HSM-Enabled Oracle Key Vault Instance](#)
Backups taken from an HSM-enabled Oracle Key Vault instance can only be restored onto a standalone Oracle Key Vault server with access to the same Root of Trust key that was in use when the backup was taken.

2.4.1 Backup Operations in an HSM-Enabled Oracle Key Vault Instance

The steps to back up Oracle Key Vault data in an HSM-enabled instance are the same as the steps used to back up an instance that has not been HSM-enabled.

You can use the Oracle Key Vault management console to perform a backup operation.

Related Topics

- *Oracle Key Vault Administrator's Guide*

2.4.2 Restore Operations in an HSM-Enabled Oracle Key Vault Instance

Backups taken from an HSM-enabled Oracle Key Vault instance can only be restored onto a standalone Oracle Key Vault server with access to the same Root of Trust key that was in use when the backup was taken.

Before you restore a backup onto a system, you must ensure that the system can access both the HSM and the Root of Trust (RoT) that was used to make the backup. You must therefore have installed the HSM client software on the Oracle Key Vault server and enrolled the Oracle Key Vault as a client of the HSM before proceeding with this step. If the backup was taken on an HSM-enabled cluster node, then when you restore the backup to a standalone server, you must ensure that the server has access to the same HSM and RoT as the node on which the backup was taken.

1. Log into the Oracle Key Vault management console as a user with the System Administrator role.

The Oracle Key Vault Home page appears.

2. Click the **System** tab.

The Status page appears.

3. Click **Hardware Security Module** in the left sidebar.

The **Hardware Security Module** page appears. On restore, the **Status** is disabled first, then enabled after the restore completes.

4. Click **Set Credential**.

The **Prepare for HSM Restore** screen appears.

5. Enter the HSM credential two times: first in **HSM Credential** and second in **Re-enter HSM Credential**.

Consult the documentation that came with your HSM for this credential. The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. The HSM-credential if you use an Operator Card Set is the Operator Card Set password. If you use a Softcard, then the password is the Softcard password.

6. If the backup you are restoring was taken while Oracle Key Vault was HSM-enabled and given a specific token to use, select **Use Token Label** and enter the token label of the token that Oracle Key Vault was using when the backup was taken.
7. Click **Set Credential**.

▲ Caution:

If a credential has already successfully been set either via the Set Credential or Initialize operations, if you set an incorrect credential for the HSM, the previous credential, token label, and vendor will continue to be stored and used. If a credential has not been set previously and the Set Credential operation fails, the incorrect credential, token label, and vendor are not stored.

The HSM credential will be stored in the system. It must be stored on the system so that it can be used to perform a backup restore operation because it is not stored in backup itself.

8. If you are using nCipher, then run the following command as user `oracle`:

```
oracle$ /opt/nfast/bin/rfs-sync --update
```

This command is needed for an nCipher backup restore to complete successfully.

9. In the Oracle Key Vault management console, go to the **Restore** page and then restore the backup.

Related Topics

- *Oracle Key Vault Administrator's Guide*

2.5 Reverse Migration Operation

Reverse migrating an HSM-enabled Oracle Key Vault server reverts the Key Vault server to using the recovery passphrase to protect the TDE wallet.

This operation is necessary if you no longer want to use the HSM to protect the TDE wallet password (for example, if the HSM must be decommissioned).

- [Reverse Migrating a Standalone Deployment](#)
You can reverse migrate a standalone deployment by using the Oracle Key Vault management console.
- [Reverse Migrating a Primary-Standby Deployment](#)
To reverse migrate a primary-standby deployment, use both the Oracle Key Vault management console and the command line.
- [Reverse Migrating a Multi-Master Cluster](#)
You can reverse migrate a multi-master cluster by using the Oracle Key Vault management console.

2.5.1 Reverse Migrating a Standalone Deployment

You can reverse migrate a standalone deployment by using the Oracle Key Vault management console.

1. Log into the Oracle Key Vault management console as a user with the System Administrator role.
The Oracle Key Vault **Home** page appears.
2. Click the **System** tab.
The **Status** page appears.
3. Click **Hardware Security Module** in the left sidebar.
The **Hardware Security Module** page appears.
4. Click **Reverse Migrate**.
The **HSM Reverse Migrate** screen is displayed.

On the **HSM Reverse Migrate** screen, enter the following details:

- Enter the HSM credential in the **HSM Credential** field. Consult the HSM documentation for this credential. The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. For Utimaco, the credential is the PIN that was initialized when the token was configured.
- Enter the old recovery passphrase in the **Old Recovery Passphrase** field.
- Enter the new recovery passphrase in the **New Recovery Passphrase** and **Re-enter New Recovery Passphrase** fields. If you do not want to change the recovery passphrase, then enter the same recovery passphrase in the **New Recovery Passphrase** and **Re-enter New Recovery Passphrase** fields as the one you entered in **Old Recovery Passphrase**.

5. Click **Reverse Migrate**

The **Hardware Security Module** page appears. The red downward arrow indicates the **Status**.

2.5.2 Reverse Migrating a Primary-Standby Deployment

To reverse migrate a primary-standby deployment, use both the Oracle Key Vault management console and the command line.

1. Log into the Oracle Key Vault management console as a user with the System Administrator role.

The Oracle Key Vault **Home** page appears.

2. Click the **System** tab.

The **Status** page appears.

3. Click **Hardware Security Module** in the left sidebar.

The **Hardware Security Module** page appears.

4. Click **Reverse Migrate**.

The **HSM Reverse Migrate** screen is displayed.

On the **HSM Reverse Migrate** screen, enter the following details:

- Enter the HSM credential in the **HSM Credential** field. Consult the documentation that came with your HSM for this credential. The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. For Utimaco, the credential is the PIN that was initialized when the token was configured.
- Enter the old recovery passphrase in the **Old Recovery Passphrase** field.
- Enter the new recovery passphrase in the **New Recovery Passphrase** and **Re-enter New Recovery Passphrase** fields. If you do not want to change the recovery passphrase, then enter the same recovery passphrase in the **New Recovery Passphrase** and re-enter the **New Recovery Passphrase** fields as the one you entered in **Old Recovery Passphrase**.

5. Click **Reverse Migrate**

The **Hardware Security Module** page appears. The red downward arrow indicates the **Status**.

6. On the standby server, log in to the Oracle Key Vault Server through SSH as user support, then switch user (su) to root.

```
$ ssh support@okv_standby_instance
support$ su root
```

7. Modify the okv_security.conf file.

```
root# vi /usr/local/okv/etc/okv_security.conf
```

- Delete the line `HSM_PROVIDER="provider_value"`.
- Change the value of the parameter `HSM_ENABLED` to "0".

Save and quit by entering the following sequence of characters in the vi file: :wq!

8. On the standby server, remove the following files:

```
root# cd /usr/local/okv/hsm/wallet
root# rm -f cwallet.sso encdepwd
root# cd /usr/local/okv/hsm/restore
root# rm -f cwallet.sso ewallet.p12
root# cd /mnt/okvram
root# rm -f cwallet.sso ewallet.p12
root# cd /mnt/okvram/restore
root# rm -f cwallet.sso ewallet.p12
```

```
root# cd /usr/local/okv/tde
root# rm -f cwallet.sso
```

9. Switch user (su) to oracle:

```
root# su oracle
```

10. Run the following command:

```
oracle$ /var/lib/oracle/dbfw/bin/orapki wallet create -wallet /usr/
local/okv/tde -auto_login
```

11. Enter the new recovery passphrase that you specified in Step 4.

The primary-standby deployment is successfully reverse migrated.

2.5.3 Reverse Migrating a Multi-Master Cluster

You can reverse migrate a multi-master cluster by using the Oracle Key Vault management console.

1. Log into the Oracle Key Vault management console as a user with the System Administrator role.

The Oracle Key Vault **Home** page appears.

2. Click the **System** tab.


The **Status** page appears.

3. Click **Hardware Security Module** in the left sidebar.

The **Hardware Security Module** page appears.

4. Click **Reverse Migrate**.

The **HSM Reverse Migrate** dialog box is displayed.



The screenshot shows a dialog box titled "HSM Reverse Migrate". It contains two input fields: "HSM Credential" and "Recovery Passphrase". There are two buttons at the top right: "Cancel" and "Reverse Migrate".

In the **HSM Reverse Migrate** dialog box, enter the following details:

- Enter the HSM credential. Consult the documentation that came with your HSM for this credential. The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. For Utimaco, the credential is the PIN that was initialized when the token was configured.
 - Enter the recovery passphrase.
5. Click **Reverse Migrate**

The **Hardware Security Module** page appears. The red downward arrow indicates the **Status**.

3

Upgrade Considerations When Using HSMs in Oracle Key Vault

When you upgrade an Oracle Key Vault deployment that has HSMs, you should consider factors such as the release being upgraded from, nCipher, and tokens.

- [Upgrades from Oracle Key Vault Release 12.2](#)
Upgrading from a standalone or a primary-standby Oracle Key Vault release 12.2 environment has special considerations for HSMs.
- [Upgrade Considerations for nCipher](#)
When you upgrade while HSM-enabled and using an nCipher HSM, you must remake hardserver changes and consider changes to overriding security assurances.
- [Using a Token Label After Upgrading Oracle Key Vault without Reverse-Migrating](#)
Starting in release 18.4, Oracle Key Vault can use a token label when you choose a slot while connecting to an HSM.

3.1 Upgrades from Oracle Key Vault Release 12.2

Upgrading from a standalone or a primary-standby Oracle Key Vault release 12.2 environment has special considerations for HSMs.

- [Upgrading from an Oracle Key Vault Release 12.2 Standalone Deployment](#)
You can upgrade from an Oracle Key Vault standalone deployment by reverse-migrating before the upgrade, and after the upgrade completes, re-HSM-enabling Oracle Key Vault.
- [Upgrading from an Oracle Key Vault Release 12.2 Primary-Standby Deployment](#)
You can upgrade from an Oracle Key Vault release 12.2 primary-standby deployment by reverse-migrating before the upgrade, and after the upgrade completes, re-HSM-enabling Oracle Key Vault.

3.1.1 Upgrading from an Oracle Key Vault Release 12.2 Standalone Deployment

You can upgrade from an Oracle Key Vault standalone deployment by reverse-migrating before the upgrade, and after the upgrade completes, re-HSM-enabling Oracle Key Vault.

1. Make a one-time backup of the Oracle Key Vault server to a remote backup destination.
2. Make a copy of the `/mnt/okvram/cwallet.sso` wallet file.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
root# /bin/cp /mnt/okvram/cwallet.sso /var/lib/oracle/cwallet_hsm_upgrade.sso
```

3. Reverse migrate so that Oracle Key Vault is no longer using an HSM as the RoT.
You can verify the success of this operation by checking the audit record in the audit trail.
If this step fails despite using the correct HSM credential and recovery passphrase, then do not continue with the rest of these steps. Contact Oracle Support.
4. Make another one-time backup of the Oracle Key Vault server to a remote backup destination.
5. Proceed with the rest of the upgrade steps as described in *Oracle Key Vault Administrator's Guide* for a standalone Oracle Key Vault server, including taking a one-time backup after the upgrade completes.
6. After the upgrade successfully completes, optionally HSM-enable your Oracle Key Vault server.
7. Remove the copied wallet in Step 2.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
root# /bin/rm /var/lib/oracle/cwallet_hsm_upgrade.sso
```

Related Topics

- [HSM-Enabling in a Standalone Oracle Key Vault Deployment](#)
You can use the Oracle Key Vault management console to HSM-enable Oracle Key Vault, which configures additional protection for the TDE master encryption key.
- [Backup Operations in an HSM-Enabled Oracle Key Vault Instance](#)
The steps to back up Oracle Key Vault data in an HSM-enabled instance are the same as the steps used to back up an instance that has not been HSM-enabled.
- [Reverse Migrating a Standalone Deployment](#)
You can reverse migrate a standalone deployment by using the Oracle Key Vault management console.
- *Oracle Key Vault Administrator's Guide*

3.1.2 Upgrading from an Oracle Key Vault Release 12.2 Primary-Standby Deployment

You can upgrade from an Oracle Key Vault release 12.2 primary-standby deployment by reverse-migrating before the upgrade, and after the upgrade completes, re-HSM-enabling Oracle Key Vault.

1. On the current primary, make a one-time backup of the Oracle Key Vault server to a remote backup destination.
2. On the current primary, make a copy of the `/mnt/okvram/cwallet.sso` wallet file.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
root# /bin/cp /mnt/okvram/cwallet.sso /var/lib/oracle/cwallet_hsm_upgrade.sso
```

3. Unpair the primary and the standby servers.
 - a. Log in to the primary server's management console as a user with the System Administrator role.

- b. Select the **System** tab, then select **Primary-Standby** from the left side bar.
- c. Click **Unpair**.

The unpair operation takes about 10 minutes to complete. After the unpair operation is complete, the standby will no longer be usable.

- 4. Reverse migrate so that Oracle Key Vault is no longer using an HSM as the RoT.

You can verify the success of this operation by checking the audit record in the audit trail.

If this step fails despite using the correct HSM credential and recovery passphrase, then do not continue with the rest of these steps. Contact Oracle Support.

- 5. Make another one-time backup of the Oracle Key Vault server to a remote backup destination.
- 6. Proceed with the rest of the upgrade steps as described in *Oracle Key Vault Administrator's Guide* for a primary-standby Oracle Key Vault server, including taking a one-time backup after the upgrade completes.
- 7. After the upgrade successfully completes, optionally HSM-enable a new primary-standby configuration using the upgraded Oracle Key Vault server as the primary and a fresh installation of the same version as the standby.
- 8. Remove the copied wallet in Step 2.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
root# /bin/rm /var/lib/oracle/cwallet_hsm_upgrade.sso
```

Related Topics

- [Backup Operations in an HSM-Enabled Oracle Key Vault Instance](#)
The steps to back up Oracle Key Vault data in an HSM-enabled instance are the same as the steps used to back up an instance that has not been HSM-enabled.
- [Reverse Migrating a Standalone Deployment](#)
You can reverse migrate a standalone deployment by using the Oracle Key Vault management console.
- *Oracle Key Vault Administrator's Guide*
- [HSM-Enabling in a Primary-Standby Oracle Key Vault Deployment](#)
In an Oracle Key Vault primary-standby deployment, you must perform the HSM-enabling tasks separately on the Oracle Key Vault servers that will become primary and standby servers.

3.2 Upgrade Considerations for nCipher

When you upgrade while HSM-enabled and using an nCipher HSM, you must remake hardware changes and consider changes to overriding security assurances.

- [Remaking Hardware Changes While Upgrading Oracle Key Vault](#)
Because HSM configurations can vary, it is your responsibility to run test upgrades on non-production environments to ensure that the upgrade will work with your HSM configuration.

- [Overriding Security Assurances for the Oracle Key Vault Upgrade](#)
You can configure how the Oracle Key Vault security assurance attributes are set for future initialization operations.

3.2.1 Remaking Hardserver Changes While Upgrading Oracle Key Vault

Because HSM configurations can vary, it is your responsibility to run test upgrades on non-production environments to ensure that the upgrade will work with your HSM configuration.

1. Connect to the Oracle Key Vault server as the `root` user.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
```

2. Execute the steps to upgrade as described in *Oracle Key Vault Administrator's Guide*, up to and including the command where you run the following command:

```
root# /usr/bin/ruby /images/upgrade.rb --confirm
```

3. After running `/usr/bin/ruby /images/upgrade.rb --confirm` but before you execute the reboot operation, execute the following commands:

```
root# usermod -a -G nfast oracle
root# cd /etc/rc.d/rc5.d
root# mv S50nc_hardserver S40nc_hardserver
root# cd /etc/rc.d/rc3.d
root# mv S50nc_hardserver S41nc_hardserver
```

4. Continue with the upgrade process as described in *Oracle Key Vault Administrator's Guide*.

Related Topics

- [Oracle Key Vault Administrator's Guide](#)

3.2.2 Overriding Security Assurances for the Oracle Key Vault Upgrade

You can configure how the Oracle Key Vault security assurance attributes are set for future initialization operations.

As of Oracle Key Vault release 18.4.0.0.0, the Root of Trust (RoT) key that is created will have its `CKA_EXTRACTABLE` attribute set to `CK_FALSE` by default. However, in release 18.3.0.0.0 and earlier, `CKA_EXTRACTABLE` was set to `CK_TRUE`. This meant that the file `/opt/nfast/cknfastrc` used to require the following additional line:

```
CKNFAST_OVERRIDE_SECURITY_ASSURANCES=explicitness;tokenkeys;longterm
```

If you are upgrading Oracle Key Vault from release 18.3.0.0.0 or earlier, then these parameters will continue to be needed until you have reverse-migrated and re-initialized, which will create a new RoT key with the `CKA_EXTRACTABLE` attribute set to `CK_FALSE`. If you prefer that future initialize operations continue have `CKA_EXTRACTABLE` set to `CK_TRUE` in release 18.4.0.0.0 and later, then perform the following steps before initializing.

1. Connect to the Oracle Key Vault server as the `root` user.

```
$ ssh support@Oracle_Key_Vault_server_IP_address
support$ su - root
```

2. Open the file `okv_security.conf`:

```
root# vi /usr/local/okv/etc/okv_security.conf
```

3. Set the `HSM_KEY_EXTRACTABLE` parameter in `okv_security.conf` as follows:

```
HSM_KEY_EXTRACTABLE="1"
```

4. Save and exit the `okv_security.conf` file.

```
:wq
```

5. Open the `/opt/nfast/cknfastrc` file.

```
root# vi /opt/nfast/cknfastrc
```

6. Add the following line to `/opt/nfast/cknfastrc`:

```
CKNFAST_OVERRIDE_SECURITY_ASSURANCES=explicitness;tokenkeys;longterm
```


Future initialize operations on this Oracle Key Vault server will now create Root of Trust keys with the `CKA_EXTRACTABLE` attribute set to `CK_TRUE`.

3.3 Using a Token Label After Upgrading Oracle Key Vault without Reverse-Migrating

Starting in release 18.4, Oracle Key Vault can use a token label when you choose a slot while connecting to an HSM.

If you are upgrading an HSM-enabled Oracle Key Vault from a previous version, then you can begin using a token label after successfully upgrading without reverse-migrating.

1. Perform the upgrade to Oracle Key Vault release 18.4 or later.
2. Locate the token label of the token that Oracle Key Vault is currently using.
 - a. Log into the Oracle Key Vault management console as a user who has the System Administrator role.
 - b. Select the **System** tab, and then click **Hardware Security Module** in the left sidebar. Navigate to the Hardware Security Module page. For example, the token label in the following example is `myPartition1`:



- c. Select the **Set Credential** button.
- d. In the Prepare for HSM Restore dialog box, enter the HSM credential in the **HSM Credential** and **Re-enter HSM Credential** fields, and the recovery passphrase that you are currently using in the **Recovery Passphrase** field. Check the **Use Token Label** check box and enter the token label that you

found (for example, `myPartition1`) in the **Token Label** field. Then click **Set Credential**.

If this operation is successful, then Oracle Key Vault will begin to use the given token label when choosing a slot. If the operation fails, then your settings (token label, vendor, and HSM credential) are returned to what they were previously.

After this operation completes, if the green status arrow changes to a red arrow, this means that you have entered the wrong HSM credential, token label, vendor, or some combination of the three, and Oracle Key Vault was unable to revert the values to what they were previously. Oracle recommends that you try another set credential operation using the former HSM credential, token label, and vendor settings and do not restart Oracle Key Vault until the status arrow is again green. For more information about why the status arrow is red, check the most recent log files under the `/var/okv/log/hsm` directory.

4

Support Guidance

The support guidance provides information about troubleshooting and vendor specific notes.

- [General Troubleshooting](#)
Oracle Key Vault provides general troubleshooting help. Vendor-specific notes cover vendor-specific troubleshooting.
- [Vendor Specific Notes for SafeNet](#)
Oracle Key Vault supports Oracle Key Vault integration with SafeNet Luna SA Hardware Security Modules from Thales version 7000, but does not support Host Trust Link (HTL) for SafeNet Luna HSM.
- [Vendor Specific Notes for nCipher](#)
You can integrate Oracle Key Vault release 12.2 BP 3 and later with the HSM from nCipher nShield Connect 6000+.
- [Vendor Specific Notes for Utimaco](#)
Oracle Key Vault supports Oracle Key Vault integration with Utimaco SecurityServer 4.31.1.

4.1 General Troubleshooting

Oracle Key Vault provides general troubleshooting help. Vendor-specific notes cover vendor-specific troubleshooting.

- [Trace Files for Diagnosing Issues](#)
Oracle Key Vault provides trace files so that you can better diagnose issues that may arise.
- [HSM Alert](#)
Oracle Key Vault provides an alert mechanism that periodically monitors the HSM configuration to check for Root of Trust key availability and file health.
- [Could Not Get Slot for HSM Error](#)
The Could Not Get Slot for HSM error indicates that Oracle Key Vault could not get a slot from the HSM.
- [Could Not Load PKCS#11 Library Error](#)
The Could Not Load PKCS#11 Library error indicates that Oracle Key Vault could not load the PKCS#11 library.
- [Oracle Key Vault Management Console Does Not Start After Restarting HSM-Enabled Oracle Key Vault Server](#)
The Oracle Key Vault management console may not appear after you restart the HSM-enabled Oracle Key Vault server.
- [Primary-Standby Errors](#)
The `okv_security.conf` file contains settings that can help you diagnose primary-standby errors.

- [Errors from HSM-Enabled Oracle Key Vault Backups](#)
You can use the `cwallet.sso` file to diagnose HSM-enabled Oracle Key Vault backup errors.
- [Restoring an HSM-Enabled Backup](#)
Before you restore a backup that was taken on an HSM-enabled Oracle Key Vault, ensure that you have set the same HSM credential and token label that were used when the backup was taken.

4.1.1 Trace Files for Diagnosing Issues

Oracle Key Vault provides trace files so that you can better diagnose issues that may arise.

Use these trace files to more finely diagnose issues when you attempt hardware security module operations. These trace files are located in the `/var/okv/log/hsm/` directory on the Oracle Key Vault server. To see the most recently failed operation, you can sort the trace files by their last modified time. For example, `ls -ltr /var/okv/log/hsm` lists the most recently modified trace files at the bottom of the list.

4.1.2 HSM Alert

Oracle Key Vault provides an alert mechanism that periodically monitors the HSM configuration to check for Root of Trust key availability and file health.

When an Oracle Key Vault server is HSM-enabled, Oracle Key Vault contacts the HSM every five minutes (or whatever you have set the monitoring interval to on the Configure Alerts page) to ensure that the Root of Trust key is available and the TDE wallet password can be decrypted. When a problem in the HSM configuration arises (for example, the HSM cannot be reached or if there are conflicting keys in the HSM with the same ID), then the up arrow on the **Hardware Security Module** tab switches to a down arrow and an alert is raised. The down arrow signifies that the HSM is not configured or the HSM configuration has a problem. When an alert has been raised, the following error message appears: HSM configuration error. Please refer to the HSM Alert section in the Oracle Key Vault Root of Trust HSM Configuration Guide.

If this alert appears, then follow these steps:

1. Log in as root as follows:

```
$ ssh support@okv_instance_ip_address
support$ su - root
```

2. Back up the SSO wallet. For example:

```
root# cp /mnt/okvram/cwallet.sso /var/lib/oracle/cwallet_hsm_backup.sso
```

3. Diagnose the source of the alert.

The following `verify` command should show why the alert was raised. The `ls -ltrh` command shows the most recent log file at the bottom of the output.

```
root# su - oracle
oracle$ /usr/local/okv/hsm/bin/hsmclient verify
oracle$ cd /var/okv/log/hsm
oracle$ ls -ltrh
```

4. If you cannot resolve this problem, then contact Oracle Support.

4.1.3 Could Not Get Slot for HSM Error

The `Could Not Get Slot for HSM` error indicates that Oracle Key Vault could not get a slot from the HSM.

Consult the most recent trace files for more details. Possible causes include providing an invalid or nonexistent token label and the HSM failing to return a list of slots.

4.1.4 Could Not Load PKCS#11 Library Error

The `Could Not Load PKCS#11 Library` error indicates that Oracle Key Vault could not load the PKCS#11 library.

Possible reasons for this error could be due to file permission issues or failing to properly deploy the HSM client software on Oracle Key Vault. More details can be found in recent trace files. Oracle looks for the PKCS#11 library at the following locations, depending on the vendor:

- For Safenet, `/usr/safenet/lunaclient/lib/libCryptoki2_64.so`
- For nCipher, `/opt/nfast/toolkits/pkcs11/libcknfast.so`
- For Utimaco, `/opt/utimaco/lib/libcs_pkcs11_R2.so`

4.1.5 Oracle Key Vault Management Console Does Not Start After Restarting HSM-Enabled Oracle Key Vault Server

The Oracle Key Vault management console may not appear after you restart the HSM-enabled Oracle Key Vault server.

If this happens, then log into the Oracle Key Vault server using SSH as user `support` and try manually opening the wallet as follows:

```
$ ssh support@okv_instance_ip_address
support$ su root
root# su oracle
oracle$ cd /usr/local/okv/hsm/bin
oracle$ ./hsmclient open_wallet
```

If the `open_wallet` command succeeds, the database will open and the management console will appear, unless there is another non-HSM problem. If the command does not succeed, then check the recent log files under `/var/okv/log/hsm` and check for vendor-specific instructions.

4.1.6 Primary-Standby Errors

The `okv_security.conf` file contains settings that can help you diagnose primary-standby errors.

1. Check that the files have been transported to the standby server.

Execute the command `ls -l` as root on the standby server:

```
root# ls -l /usr/local/okv/hsm/wallet
-rw----- 1 oracle oinstall 324 May 16 22:57 cwallet.sso
-rw----- 1 oracle oinstall 176 May 16 22:57 enctdepwd
root# ls -l /usr/local/okv/hsm/restore
-rw----- 1 oracle oinstall 320 May 16 22:57 ewallet.p12
```

You should see `cwallet.sso` and `enctdepwd` in the `/usr/local/okv/hsm/wallet` directory and `ewallet.p12` in the `/usr/local/okv/hsm/restore` directory.

2. Check that the mode is set to HSM on the standby server:

Open the file `okv_security.conf` as root on the standby server:

```
root# cat /usr/local/okv/etc/okv_security.conf
Look for the line:
HSM_ENABLED="1"
```

You should see the number within double quotes.

3. Check the vendor-specific instructions.

4.1.7 Errors from HSM-Enabled Oracle Key Vault Backups

You can use the `cwallet.sso` file to diagnose HSM-enabled Oracle Key Vault backup errors.

You should check that the `pre_restore` command has been run on the target as follows:

Execute the command `ls -l` as root on the Oracle Key Vault server to which you are restoring the backup:

```
root# ls -l /usr/local/okv/hsm/wallet
-rw----- 1 oracle oinstall 324 May 16 22:57 cwallet.sso
```

You should see the wallet file `cwallet.sso`, which indicates that the credential has successfully been set and stored on Oracle Key Vault.

You should also check that you have followed the instructions from the HSM vendor. In addition, check the most recent log files generated by the recent backup restore, which are in the `/var/okv/log/db` directory.

4.1.8 Restoring an HSM-Enabled Backup

Before you restore a backup that was taken on an HSM-enabled Oracle Key Vault, ensure that you have set the same HSM credential and token label that were used when the backup was taken.

The HSM credential for SafeNet is the SafeNet partition password. For nCipher, the credential is the password that is associated with the Operator Card Set or Softcard. For Utimaco, the credential is the PIN that was initialized when the token was configured.

When using the Set Credential operation, if you enter an incorrect credential or token label, or if Oracle Key Vault is unable to connect to the HSM, then the operation will not succeed and the credential, token label, and vendor provided will not be stored. Ensure that Oracle Key Vault has been enrolled as a client of the HSM and then ensure that the correct credential and token label are entered such that Oracle Key Vault will be able to access the same Root of Trust key that was in use when the backup was taken.

For more information about enrolling Oracle Key Vault as a client of the HSM, see [Enrolling Oracle Key Vault as a Client of the HSM](#).

4.2 Vendor Specific Notes for SafeNet

Oracle Key Vault supports Oracle Key Vault integration with SafeNet Luna SA Hardware Security Modules from Thales version 7000, but does not support Host Trust Link (HTL) for SafeNet Luna HSM.

- [Installing the HSM Client Software on the Oracle Key Vault Server for SafeNet](#)
You must use the SafeNet client version 6.2 for Linux x64 for the installation.
- [HSM Credential for SafeNet](#)
The HSM credential is the SafeNet partition password.
- [Token Label for SafeNet](#)
The token label for SafeNet is the name of the partition.
- [Enrolling Oracle Key Vault as a Client of a SafeNet HSM](#)
To perform the enrollment, you use the Oracle Key Vault management console and the command-line interface.
- [HSM Provider Value for SafeNet](#)
For SafeNet, the provider value is 1.
- [HSM Vendor Specific Checks for SafeNet](#)
You should check the SafeNet vendor-specific settings.

4.2.1 Installing the HSM Client Software on the Oracle Key Vault Server for SafeNet

You must use the SafeNet client version 6.2 for Linux x64 for the installation.

1. Obtain the SafeNet client software package, version 6.2 for Linux x64.
2. Transport the SafeNet client software package to the Oracle Key Vault machine. Oracle recommends using SCP. For example, assuming the SafeNet client software packages is called `safenet.tar`:

```
$ scp safenet.tar support@okv_instance_ip_address:/tmp
```

3. Install the SafeNet client software on Oracle Key Vault.
4. Log in to the Oracle Key Vault Server through SSH as user `support`, and switch user (`su`) to `root`:

```
$ ssh support@okv_instance_ip_address
support$ su root
root# cd /usr/local/okv/hsm
```

```
root# cp /tmp/safenet.tar /usr/local/okv/hsm
root# tar -xvf safenet.tar
root# cd 64
root# ./install.sh
```

5. Accept the SafeNet license by typing `y` at the prompt.
6. Install the Luna SA by entering `l, n, i` at the successive prompts.
This installs the SafeNet software in the directory `/usr/safenet/lunaclient`.
7. Delete the `safenet.tar` file from `/tmp` directory.

```
root# rm -f /tmp/safenet.tar
```

4.2.2 HSM Credential for SafeNet

The HSM credential is the SafeNet partition password.

If you are using SafeNet as your HSM, then you can use the SafeNet `assignPassword` command to assign a password for a partition. However, do not do this when a partition is currently in use by an Oracle Key Vault server, because Oracle Key Vault will no longer be able to access the Root of Trust key as its stored credential will no longer be correct.

4.2.3 Token Label for SafeNet

The token label for SafeNet is the name of the partition.

4.2.4 Enrolling Oracle Key Vault as a Client of a SafeNet HSM

To perform the enrollment, you use the Oracle Key Vault management console and the command-line interface.

1. Log in to the Oracle Key Vault management console as a user who has the System Administrator role.
2. Set up the DNS servers.
When enrolling Oracle Key Vault as a client of a SafeNet HSM, if the HSM will be registered using a host name, you should first set up DNS using the Oracle Key Vault the management console. To access the DNS settings, select the **System** tab, and then from the left menu, select **System Settings**.

You must configure the DNS servers on each Oracle Key Vault server that you plan to register as a client of the HSM. In a primary-standby environment, configure the DNS servers on both primary and standby server before pairing. For a multi-master cluster, configure DNS on each node in the cluster that will be registered as a client of the HSM.

3. Exchange certificates between Oracle Key Vault and the SafeNet Luna SA HSM.
Log in to the Oracle Key Vault Server through SSH as user `support`, and switch user (`su`) to `root`:

```
$ ssh support@okv_instance_ip_address
support$ su root
```

```

root# cd /usr/safenet/lunaclient/bin
root# scp admin@hsm_hostname:server.pem .
root# ./vtl addServer -n hsm_hostname -c server.pem
root# ./vtl createCert -n okv_hostname
root# scp /usr/safenet/lunaclient/cert/client/okv_hostname.pem
admin@hsm_hostname:

```

You must enter the HSM administrative password when using SCP with the HSM.

4. Register Oracle Key Vault as a client of the Luna SA.

This assumes that you have a partition set up on the SafeNet Luna SA HSM. You can use any client name that is not yet taken. Oracle recommends using a descriptive name that will identify the Oracle Key Vault instance.

Access the HSM administrative console by using SSH to `admin@hsm_hostname` and providing the administrative password:

```

$ client register -client client_name -hostname okv_hostname
$ client hostip map -c client_name -i okv_ip_address
$ client assignPartition -client client_name -partition partition_name

```

5. Verify the enrollment as follows:

Log in to Oracle Key Vault as the support user using SSH:

```

$ ssh support@okv_instance_ip_address
support$ su root
root# cd /usr/safenet/lunaclient/bin
root# ./vtl verify

```

The following output appears:

The following Luna SA Slots/Partitions were found:

Slot	Serial #	Label
====	=====	=====
1	serial_number	partition_name

4.2.5 HSM Provider Value for SafeNet

For SafeNet, the provider value is 1.

If you are setting this value manually for a primary-standby configuration, then set `HSM_PROVIDER="1"` in the `okv_security.conf` file. For more information about enabling HSM in a primary-standby deployment, see [Enabling HSM in a High Availability Deployment](#).

4.2.6 HSM Vendor Specific Checks for SafeNet

You should check the SafeNet vendor-specific settings.

You can verify the connection to the HSM for every Oracle Key Vault server as follows:

Log in to the Oracle Key Vault server as user `support` using SSH:

```
$ ssh support@okv_instance_ip_address
support$ su root
root# cd /usr/safenet/lunaclient/bin
root# ./vtl verify
```

The following output appears when the HSM is set up properly:

The following Luna SA Slots/Partitions were found:

Slot	Serial #	Label
====	=====	=====
1	[serial #]	[partition name]

If you do not see this output, then it means that the HSM is not set up properly. You can diagnose further as follows:

1. Log into the Luna SA administrative console.
2. Type the command: `client show -client client_name`
3. Verify that the expected client exists and is assigned a partition.
4. If it does not exist, register the client with the command:
`client register -client client_name-hostname host_name`
5. If no partition is assigned, assign a partition with the command:
`client assignPartition -client client_name -partition partition_name`
6. Verify that all client IP addresses are mapped correctly. If entries are missing, run the command:
`client hostip map -c client_name -i ip_address`
7. Verify that Oracle Key Vault can reach the HSM using the `vtl verify` command:

```
$ su root
root# cd /usr/safenet/lunaclient/bin
root# ./vtl verify
```

The output should look similar to the following output:

The following Luna SA Slots/Partitions were found:

Slot	Serial #	Label
====	=====	=====
1	[serial #]	[partition name]

If the command fails, then it means that the Oracle Key Vault server is unable to contact the HSM. Check the vendor's other troubleshooting sections for instructions to restore `vtl verify` functionality. Contact your HSM administrator and confirm that Oracle Key Vault's access to the HSM has not been revoked. If you are unable to resolve the problem, then contact Oracle Support.

4.3 Vendor Specific Notes for nCipher

You can integrate Oracle Key Vault release 12.2 BP 3 and later with the HSM from nCipher nShield Connect 6000+.

- [Installing the HSM Client Software on the Oracle Key Vault Server for nCipher](#)
The nCipher HSM requires a separate non-HSM computer on the network to use as the remote file system.
- [HSM Credential for nCipher](#)
The HSM credential for nCipher is the password that is associated with the Operator Card Set or Softcard.
- [Token Label for nCipher](#)
The token label for nCipher is the name of the Operator Card Set or Softcard.
- [Enrolling Oracle Key Vault as a Client of an nCipher HSM](#)
You use both the nCipher user interface and the command line to enroll Oracle Key Vault as a client of an nCipher HSM.
- [HSM Provider Value for nCipher](#)
For nCipher, the provider value is 2.

4.3.1 Installing the HSM Client Software on the Oracle Key Vault Server for nCipher

The nCipher HSM requires a separate non-HSM computer on the network to use as the remote file system.

After setting up the remote file system, you can proceed with the following steps:

1. Log in to the Oracle Key Vault server as support user using SSH:

```
$ ssh support@okv_instance_ip_address
```

2. Switch to root:

```
support$ su root
```

3. Go to the `root` directory and create the directories `ctls`, `hwsp`, and `pkcs11`:

```
root# cd /root
root# mkdir ctls
root# mkdir hwsp
root# mkdir pkcs11
```

4. Transfer the nCipher software installation files using the Secure Copy (SCP) protocol as follows:

For example:

```
root# scp user@remote_file_system_computer:/source_directory/ncipher/nfast/ctls/agg.tar ctls
root# scp user@remote_file_system_computer:/source_directory/ncipher/nfast/hwsp/agg.tar hwsp
root# scp user@remote_file_system_computer:/source_directory/ncipher/nfast/pkcs11/user.tar pkcs11
```

5. Install these files as follows:

```
root# cd /
root# tar xvf /root/ctls/agg.tar
root# tar xvf /root/hwsp/agg.tar
root# tar xvf /root/pkcs11/user.tar
root# /opt/nfast/sbin/install
```

6. As root, perform additional edits on the Oracle Key Vault server:

```
root# usermod -a -G nfast oracle
root# cd /etc/rc.d/rc5.d
root# mv S50nc_hardserver S40nc_hardserver
root# cd /etc/rc.d/rc3.d
root# mv S50nc_hardserver S41nc_hardserver
```

7. Switch to user `oracle` and verify the installation:

```
root# su oracle
oracle$ PATH=/opt/nfast/bin:$PATH
oracle$ export PATH
oracle$ enquiry
```

The state should say `operational` in the output.

8. Restart Oracle Key Vault for the group change to take effect.

In the Oracle Key Vault management console, log in as a user with the System Administrator role. Select the **System** tab, and then select **System Settings**. Then click the **Reboot** button.

4.3.2 HSM Credential for nCipher

The HSM credential for nCipher is the password that is associated with the Operator Card Set or Softcard.

The HSM-credential if they use an Operator Card Set is the Operator Card Set password. If they use a Softcard, then the password is the Softcard password.

4.3.3 Token Label for nCipher

The token label for nCipher is the name of the Operator Card Set or Softcard.

4.3.4 Enrolling Oracle Key Vault as a Client of an nCipher HSM

You use both the nCipher user interface and the command line to enroll Oracle Key Vault as a client of an nCipher HSM.

1. Add the Oracle Key Vault server IP address to the client list on the HSM using the front panel. Select privileged on any port.
 - In a primary-standby environment, register both the primary server and the standby server to use the nCipher HSM.
 - In a multi-master cluster environment, register each Oracle Key Vault node that will use the nCipher HSM.
2. Switch to user `oracle`:

```
root# su oracle
oracle$ PATH=/opt/nfast/bin:$PATH
oracle$ export PATH
```

3. On the Oracle Key Vault server, enroll with the HSM :

```
oracle$ nethsmenroll hsm_ip_address hsm_esn hsm_keyhash
```

4. Configure the TCP sockets:

```
oracle$ config-serverstartup --enable-tcp --enable-privileged-tcp
```

5. Switch to root and restart the hardserver (nCipher client process that communicates with the HSM):

```
oracle$ su root
root# /opt/nfast/sbin/init.d-ncipher restart
```

6. On the remote file system computer, run the following command:

```
$ rfs-setup --gang-client --write-noauth okv_server_ip_address
```

7. On the Oracle Key Vault server as user oracle, run the following commands:

```
oracle$ rfs-sync --setup --no-authenticate remote_file_system_ip_address
oracle$ rfs-sync --update
```

8. Test PKCS#11 access as follows:

```
root# /opt/nfast/bin/ckcheckinst
```

A prompt appears listing the module. You can confirm or exit.

9. Create the config file /opt/nfast/cknfastrc as user root. Write the following lines to the file:

```
CKNFAST_NO_ACCELERATOR_SLOTS=1
CKNFAST_OVERRIDE_SECURITY_ASSURANCES=none
```

10. Perform the steps described in [HSM-Enabling in a Standalone Oracle Key Vault Deployment](#).

11. On the Oracle Key Vault server as user oracle run the command:

```
oracle$ /opt/nfast/bin/rfs-sync --commit
```

If you do not run this command after each HSM initialize operation, then the Root of Trust key may not be available for other operations such as restoring backups and setting up a primary-standby configuration.

4.3.5 HSM Provider Value for nCipher

For nCipher, the provider value is 2.

If you are setting this value manually for the primary-standby, then set `HSM_PROVIDER="2"`. For more information about enabling HSM in a primary-standby deployment, see [Enabling HSM in a High Availability Deployment](#).

4.4 Vendor Specific Notes for Utimaco

Oracle Key Vault supports Oracle Key Vault integration with Utimaco SecurityServer 4.31.1.

- [Installing the HSM Client Software on the Oracle Key Vault Server for Utimaco](#)
The setup files for Utimaco are provided in the `SecurityServerEvaluation-V4.31.1.0.zip` file from Utimaco.

- [HSM Credential for Utimaco](#)
The HSM credential for Utimaco is the PIN that was initialized when the token was configured.
- [Token Label for Utimaco](#)
The token label for Utimaco is the name of the token that was set up for the HSM.
- [HSM Provider Value for Utimaco](#)
For Utimaco, the provider value is 3.
- [HSM Vendor Specific Checks for Utimaco](#)
You should check the Utimaco vendor-specific settings.

4.4.1 Installing the HSM Client Software on the Oracle Key Vault Server for Utimaco

The setup files for Utimaco are provided in the `SecurityServerEvaluation-V4.31.1.0.zip` file from Utimaco.

1. Locate the necessary setup files provided in the `SecurityServerEvaluation-V4.31.1.0.zip` file from Utimaco.
2. After unzipping the Utimaco zip file, transport the necessary files to the Oracle Key Vault machine. Oracle recommends using SCP. For example:

```
$ scp <unzip directory>/Software/Linux/x86-64/Crypto_APIs/PKCS11_R2/sample/cs_pkcs11_R2.cfg support@okv_instance_ip_address:/tmp
$ scp <unzip directory>/Software/Linux/x86-64/Crypto_APIs/PKCS11_R2/lib/libcs_pkcs11_R2.so support@okv_instance_ip_address:/tmp
$ scp <unzip directory>/Software/Linux/x86-64/Crypto_APIs/PKCS11_R2/bin/plltool2 support@okv_instance_ip_address:/tmp
$ scp <unzip directory>/Software/Linux/x86-64/Crypto_APIs/CXI/bin/cxitool support@okv_instance_ip_address:/tmp
$ scp <unzip directory>/Software/Linux/x86-64/Administration/csadm support@okv_instance_ip_address:/tmp
```

3. Login to the Oracle Key Vault server as user `support`, and switch user (`su`) to `root`:

```
$ ssh support@okv_instance_ip_address
support$ su - root
```

4. Create the appropriate directories for the Utimaco files:

```
root# mkdir -p /opt/utimaco/lib
root# mkdir /opt/utimaco/bin
root# mkdir /etc/utimaco
```

5. Move the Utimaco files to the correct directories:

```
root# mv /tmp/cs_pkcs11_R2.cfg /etc/utimaco
root# mv /tmp/plltool2 /opt/utimaco/bin
root# mv /tmp/cxitool /opt/utimaco/bin
root# mv /tmp/csadm /opt/utimaco/bin
root# mv /tmp/libcs_pkcs11_R2.so /opt/utimaco/lib
```

6. Change the configuration file permissions:

```
root# /bin/chmod 640 /etc/utimaco/cs_pkcs11_R2.cfg
root# /bin/chown oracle:oinstall /etc/utimaco/cs_pkcs11_R2.cfg
```

7. Change the executable file permissions:

```
root# /bin/chmod 550 /opt/utimaco/bin/*
root# /bin/chown oracle:oinstall /opt/utimaco/bin/*
```

8. Change the library file permissions:

```
root# /bin/chmod 440 /opt/utimaco/lib/libcs_pkcs11_R2.so
root# /bin/chown oracle:oinstall /opt/utimaco/lib/libcs_pkcs11_R2.so
```

9. Modify the configuration file /etc/utimaco/cs_pkcs11_R2.so so that **Device is set to the Utimaco HSM's IP address.**

```
Device = utimaco_ip_address
```

If you are testing with an Utimaco HSM simulator, the line should be in the format:

```
Device = 3001@utimaco_ip_address
```

It is not recommended that you use the simulator in a production environment.

10. To verify that you have set up your Utimaco HSM and the client files correctly, you can use p11tool2. The p11tool2 command call can be used to verify that the PKCS11 token has been configured:

```
root# /opt/utimaco/bin/p11tool2 GetSlotInfo
```

The output should look similar to the following output:

```
CK_SLOT_INFO (slot ID: 0x00000000):

  slotDescription      33303031 4031302e 3234302e 3131382e |
3001@10.240.118.|
                        32333120 2d20534c 4f545f30 30303020 |231 -
SLOT_0000 |
                        20202020 20202020 20202020 20202020
|
                        20202020 20202020 20202020 20202020
|
                        20202020 20202020 20202020 20202020

  manufacturerID      5574696d 61636f20 49532047 6d624820 |Utimaco IS
GmbH |
                        20202020 20202020 20202020 20202020
|
                        20202020 20202020 20202020 20202020

  flags: 0x00000005
    CKF_TOKEN_PRESENT : CK_TRUE
    CKF_REMOVABLE_DEVICE : CK_FALSE
```

```

CKF_HW_SLOT          : CK_TRUE

hardwareVersion       : 5.01
firmwareVersion       : 2.03

```

11. The `csadm` command call can be used to confirm that the PKCS11 users have been defined:

```
root# /opt/utimaco/bin/csadm Dev=utimaco_ip_address ListUsers
```

The output should look similar to the following output:

Name	Permission	Mechanism	Attributes
ADMIN	22000000	RSA sign	Z[0]
SO_0000	00000200	HMAC passwd	Z[0]A[CXI_GROUP=SLOT_0000]
USR_0000	00000002	HMAC passwd	Z[0]A[CXI_GROUP=SLOT_0000]

4.4.2 HSM Credential for Utimaco

The HSM credential for Utimaco is the PIN that was initialized when the token was configured.

See the Utimaco documentation for more details.

4.4.3 Token Label for Utimaco

The token label for Utimaco is the name of the token that was set up for the HSM.

4.4.4 HSM Provider Value for Utimaco

For Utimaco, the provider value is 3.

If you are setting this value manually for primary-standby, set `HSM_PROVIDER="3"` in the `okv_security.conf` file. For more information about enabling HSM in a primary-standby deployment, see [Enabling HSM in a High Availability Deployment](#).

4.4.5 HSM Vendor Specific Checks for Utimaco

You should check the Utimaco vendor-specific settings.

In addition to the `p11tool2 GetSlotInfo` and `csadm ListUsers` commands, you can also check to see that a key was created after completing the HSM Initialize operation. Note that more keys may be created after subsequent HSM initialize commands.

```
root# /opt/utimaco/bin/p11tool2 LoginUser=<HSM Credential> ListObjects
```

The output should look similar to the following output:

```
CKO_DATA:
```

```
+ 1.1
  CKA_LABEL                                = OKV 18.1 HSM Key Number

CKO_SECRET_KEY:

+ 2.1
  CKA_KEY_TYPE                            = CKK_AES
  CKA_SENSITIVE                           = CK_TRUE
  CKA_EXTRACTABLE                         = CK_TRUE
  CKA_LABEL                              = OKV 18.1 HSM Root Key
  CKA_ID                                  = 0x00000001 ( )
```