

# Oracle® Fusion Middleware

## WebLogic Scripting Tool Command Reference for Oracle Traffic Director



12c (12.2.1.3.0)

E80571-02

August 2018

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Fusion Middleware WebLogic Scripting Tool Command Reference for Oracle Traffic Director, 12c (12.2.1.3.0)

E80571-02

Copyright © 2016, 2018, Oracle and/or its affiliates. All rights reserved.

Primary Author: Trupthi N.T, Contributors: Amit Gupta, Nanda Kishore, Isvaran Krishnamurthy

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

## Preface

---

Audience	xi
Documentation Accessibility	xi
Related Documents	xi
Conventions	xi

## 1 Overview of the WebLogic Scripting Tool for Oracle Traffic Director

---

1.1	Changes from Release 11g	1-1
1.2	Usage Modes	1-1
1.2.1	Interactive Mode	1-1
1.2.2	Script Mode	1-2
1.2.3	Embedded Mode	1-2
1.3	Offline Commands	1-3
1.3.1	Offline Provisioning	1-3
1.3.2	Monitoring	1-3
1.3.3	SNMP Runtime Management	1-3
1.3.4	Failover Runtime Management	1-4
1.4	Custom WLST Command Usage	1-4
1.4.1	Syntax	1-4
1.4.2	Use with WLST	1-4
1.4.3	Arguments	1-4
1.4.4	Return Values	1-4
1.4.5	Error Messages	1-4
1.4.6	Unable to Unset/Disable the URI Mapping on a Route	1-5
1.5	List of Commands	1-5
1.5.1	Provisioning	1-5
1.5.1.1	Collocated Domain	1-5
1.5.1.2	Standalone Domain	1-5
1.5.2	Instance Management	1-5
1.5.3	Configuration Deployment	1-5
1.5.4	Configuration Management	1-6
1.5.4.1	Configuration	1-6

1.5.4.2	Setting/Tuning	1-6
1.5.5	Virtual Server Management	1-7
1.5.5.1	Configuration	1-7
1.5.5.2	Setting/Tuning	1-7
1.5.6	TCP Load Balancer Management	1-8
1.5.7	Server Pool Management	1-8
1.5.7.1	Server Pool	1-8
1.5.7.2	Health Check	1-8
1.5.7.3	Origin Server	1-8
1.5.7.4	Maintenance	1-9
1.5.8	Listener Management	1-9
1.5.8.1	HTTP	1-9
1.5.8.2	TCP	1-9
1.5.9	SSL Management	1-9
1.5.9.1	Certificate Management	1-9
1.5.9.2	SSL Settings	1-10
1.5.9.3	Ciphers	1-10
1.5.10	Rules Management	1-11
1.5.10.1	Routes	1-11
1.5.10.2	Proxy Cache Rules	1-11
1.5.10.3	Request Limit Rules	1-11
1.5.10.4	Compression Rules	1-12
1.5.10.5	Content Rules	1-12
1.5.11	Web Application Firewall (WAF) Management	1-12
1.5.11.1	Configuration	1-12
1.5.11.2	Ruleset File Management	1-12
1.5.12	Monitoring	1-13
1.5.12.1	Runtime Statistics	1-13
1.5.12.2	Setting/Tuning	1-13
1.5.12.3	SNMP Configuration	1-13
1.5.12.4	SNMP Runtime Management	1-13
1.5.13	Logging Configuration	1-13
1.5.14	Failover Management	1-14
1.5.14.1	Configuration	1-14
1.5.14.2	Runtime Management	1-14
1.5.15	Events	1-14
1.5.16	Multi-tenancy (with WebLogic Server MT)	1-15
1.5.17	Service Management	1-15

## 2 Oracle Traffic Director WLST Commands

---

2.1	activate	2-1
2.2	deleteKeyStoreEntry	2-2
2.3	displayLogs	2-3
2.4	displayMetricTables	2-5
2.5	enableOverwriteComponentChanges	2-6
2.6	exportKeyStoreCertificate	2-8
2.7	exportKeyStoreCertificateRequest	2-9
2.8	generateKeyPair	2-10
2.9	getKeyStoreCertificates	2-11
2.10	help	2-11
2.11	importKeyStoreCertificate	2-12
2.12	listExpiringCertificates	2-13
2.13	listKeyStores	2-14
2.14	listKeyStoreAliases	2-14
2.15	otd_addFailoverInstance	2-15
2.16	otd_blockProxyInfo	2-16
2.17	otd_copyConfiguration	2-17
2.18	otd_copyVirtualServer	2-18
2.19	otd_createCacheRule	2-18
2.20	otd_createCompressionRule	2-19
2.21	otd_createConfiguration	2-20
2.22	otd_createContentRule	2-21
2.23	otd_createErrorPage	2-22
2.24	otd_createEvent	2-23
2.25	otd_createEventSubscription	2-24
2.26	otd_createFailoverGroup	2-24
2.27	otd_createHttpListener	2-26
2.28	otd_createInstance	2-28
2.29	otd_createMimeType	2-29
2.30	otd_createOriginServer	2-29
2.31	otd_createOriginServerPool	2-30
2.32	otd_createRequestLimit	2-31
2.33	otd_createRoute	2-32
2.34	otd_createService	2-33
2.35	otd_createStandaloneDomain	2-34
2.36	otd_createStandaloneInstance	2-35
2.37	otd_createTcpListener	2-36
2.38	otd_createTcpProxy	2-37
2.39	otd_createConfigurationVariable	2-38

2.40	otd_createVirtualServer	2-39
2.41	otd_createVirtualServerVariable	2-40
2.42	otd_deleteCacheRule	2-41
2.43	otd_deleteCompressionRule	2-41
2.44	otd_deleteConfigFile	2-42
2.45	otd_deleteConfiguration	2-42
2.46	otd_deleteConfigurationWebappFirewallRulesetFile	2-43
2.47	otd_deleteContentRule	2-44
2.48	otd_deleteCrl	2-44
2.49	otd_deleteErrorPage	2-45
2.50	otd_deleteEvent	2-46
2.51	otd_deleteEventSubscription	2-46
2.52	otd_deleteFailoverGroup	2-47
2.53	otd_deleteHttpListener	2-47
2.54	otd_deleteInstance	2-48
2.55	otd_deleteMimeType	2-49
2.56	otd_deleteOriginServer	2-49
2.57	otd_deleteOriginServerPool	2-50
2.58	otd_deleteRequestLimit	2-51
2.59	otd_deleteRoute	2-51
2.60	otd_deleteService	2-52
2.61	otd_deleteStandaloneInstance	2-53
2.62	otd_deleteTcpListener	2-53
2.63	otd_deleteTcpProxy	2-54
2.64	otd_deleteConfigurationVariable	2-54
2.65	otd_deleteVirtualServer	2-55
2.66	otd_deleteVirtualServerVariable	2-56
2.67	otd_deleteVirtualServerWebappFirewallRulesetFile	2-56
2.68	otd_disableOriginServerPoolMaintenance	2-57
2.69	otd_disablePerfDump	2-57
2.70	otd_disableRequestLimitEvents	2-58
2.71	otd_disableRouteAuth	2-59
2.72	otd_disableRouteBandwidthLimit	2-59
2.73	otd_disableStatsXml	2-60
2.74	otd_disableStatusListener	2-61
2.75	otd_disableVirtualServerAccessLog	2-61
2.76	otd_disableWebAppFirewall	2-62
2.77	otd_disableVirtualServerRequestBandwidthLimit	2-62
2.78	otd_disableVirtualServerResponseBandwidthLimit	2-63
2.79	otd_enableOriginServerPoolMaintenance	2-63
2.80	otd_enablePerfDump	2-64

2.81	otd_enableRouteAuth	2-65
2.82	otd_enableRouteBandwidthLimit	2-65
2.83	otd_enableRequestLimitEvents	2-66
2.84	otd_enableStatsXml	2-67
2.85	otd_enableStatusListener	2-68
2.86	otd_enableWebAppFirewall	2-68
2.87	otd_enableVirtualServerAccessLog	2-69
2.88	otd_enableVirtualServerRequestBandwidthLimit	2-70
2.89	otd_enableVirtualServerResponseBandwidthLimit	2-71
2.90	otd_exportKeyStore	2-72
2.91	otd_forwardProxyInfo	2-72
2.92	otd_getAccessLogBufferProperties	2-74
2.93	otd_getCacheProperties	2-75
2.94	otd_getCacheRuleProperties	2-75
2.95	otd_getCompressionRuleProperties	2-76
2.96	otd_getConfigFile	2-76
2.97	otd_getConfigurationAccessLogProperties	2-77
2.98	otd_getConfigurationCrlProperties	2-78
2.99	otd_getConfigurationProperties	2-78
2.100	otd_getContentRuleProperties	2-79
2.101	otd_getDnsCacheProperties	2-80
2.102	otd_getDnsProperties	2-80
2.103	otd_getEventProperties	2-81
2.104	otd_getEventSubscriptionProperties	2-81
2.105	otd_getFileCacheProperties	2-82
2.106	otd_getFailoverGroupProperties	2-82
2.107	otd_getHealthCheckProperties	2-83
2.108	otd_getHttpListenerProperties	2-84
2.109	otd_getHttpListenerSslProperties	2-85
2.110	otd_getHttpProperties	2-85
2.111	otd_getHttpThreadPoolProperties	2-86
2.112	otd_getKeepaliveProperties	2-86
2.113	otd_getLogProperties	2-87
2.114	otd_getOriginServerPoolMaintenanceProperties	2-88
2.115	otd_getOriginServerPoolProperties	2-88
2.116	otd_getOriginServerProperties	2-89
2.117	otd_getOriginServerPoolSslProperties	2-90
2.118	otd_getPartitionAccessLogProperties	2-90
2.119	otd_getPerfDump	2-91
2.120	otd_getPerfDumpProperties	2-92
2.121	otd_getRequestLimitProperties	2-92

2.122	otd_getRouteAuthProperties	2-93
2.123	otd_getRouteBandwidthLimitProperties	2-94
2.124	otd_getRouteProperties	2-95
2.125	otd_getSnmpProperties	2-95
2.126	otd_getSslSessionCacheProperties	2-96
2.127	otd_getStatsProperties	2-96
2.128	otd_getStatsXml	2-97
2.129	otd_getStatsXmlProperties	2-98
2.130	otd_getStatusListenerProperties	2-98
2.131	otd_getStatusListenerSslProperties	2-99
2.132	otd_getTcpAccessLogProperties	2-99
2.133	otd_getTcpListenerProperties	2-100
2.134	otd_getTcpListenerSslProperties	2-100
2.135	otd_getTcpProxyProperties	2-101
2.136	otd_getTcpThreadPoolProperties	2-102
2.137	otd_getVirtualServerAccessLogProperties	2-102
2.138	otd_getVirtualServerRequestBandwidthLimitProperties	2-103
2.139	otd_getVirtualServerResponseBandwidthLimitProperties	2-104
2.140	otd_getVirtualServerProperties	2-105
2.141	otd_getVirtualServerSslProperties	2-105
2.142	otd_getWebappFirewallProperties	2-106
2.143	otd_installConfigurationWebappFirewallRulesetFile	2-106
2.144	otd_installCrl	2-107
2.145	otd_installVirtualServerWebappFirewallRulesetFile	2-108
2.146	otd_listCacheRules	2-108
2.147	otd_listCertificates	2-109
2.148	otd_listCompressionRules	2-110
2.149	otd_listConfigFiles	2-110
2.150	otd_listConfigurations	2-111
2.151	otd_listConfigurationWebappFirewallRulesetFiles	2-111
2.152	otd_listContentRules	2-112
2.153	otd_listCrls	2-112
2.154	otd_listErrorPages	2-113
2.155	otd_listEvents	2-113
2.156	otd_listEventSubscriptions	2-114
2.157	otd_listFailoverGroups	2-114
2.158	otd_listFailoverInstances	2-115
2.159	otd_listHttpListeners	2-116
2.160	otd_listInstances	2-116
2.161	otd_listMimeType	2-117
2.162	otd_listOriginServers	2-117



2.163	otd_listOriginServerPools	2-118
2.164	otd_listPartitions	2-119
2.165	otd_listProxyInfo	2-119
2.166	otd_listRequestLimits	2-120
2.167	otd_listResourceGroups	2-120
2.168	otd_listRoutes	2-121
2.169	otd_listServices	2-122
2.170	otd_listTcpListeners	2-122
2.171	otd_listTcpProxies	2-123
2.172	otd_listConfigurationVariables	2-123
2.173	otd_listVirtualServers	2-124
2.174	otd_listVirtualServerVariables	2-124
2.175	otd_listVirtualServerWebappFirewallRulesetFiles	2-125
2.176	otd_removeFailoverInstance	2-126
2.177	otd_rotateLog	2-126
2.178	otd_saveConfigFile	2-127
2.179	otd_setAccessLogBufferProperties	2-128
2.180	otd_setCacheProperties	2-129
2.181	otd_setCacheRuleProperties	2-130
2.182	otd_setCompressionRuleProperties	2-131
2.183	otd_setConfigurationAccessLogProperties	2-132
2.184	otd_setConfigurationCrIProperties	2-133
2.185	otd_setConfigurationProperties	2-134
2.186	otd_setContentRuleProperties	2-135
2.187	otd_setDnsCacheProperties	2-136
2.188	otd_setDnsProperties	2-137
2.189	otd_setEventProperties	2-137
2.190	otd_setEventSubscriptionProperties	2-139
2.191	otd_setFailoverInstanceOrder	2-139
2.192	otd_setFileCacheProperties	2-140
2.193	otd_setHealthCheckProperties	2-142
2.194	otd_setHttpListenerProperties	2-143
2.195	otd_setHttpProperties	2-145
2.196	otd_setHttpListenerSslProperties	2-147
2.197	otd_setHttpThreadPoolProperties	2-148
2.198	otd_setKeepaliveProperties	2-149
2.199	otd_setLogProperties	2-150
2.200	otd_setOriginServerPoolSslProperties	2-152
2.201	otd_setOriginServerPoolProperties	2-153
2.202	otd_setOriginServerProperties	2-154
2.203	otd_setPartitionAccessLogProperties	2-155

2.204	otd_setRequestLimitProperties	2-156
2.205	otd_setRouteProperties	2-157
2.206	otd_setSnmpProperties	2-160
2.207	otd_setSslSessionCacheProperties	2-160
2.208	otd_setStatsProperties	2-161
2.209	otd_setStatusListenerSslProperties	2-162
2.210	otd_setTcpAccessLogProperties	2-163
2.211	otd_setTcpListenerProperties	2-163
2.212	otd_setTcpListenerSslProperties	2-165
2.213	otd_setTcpProxyProperties	2-166
2.214	otd_setTcpThreadPoolProperties	2-168
2.215	otd_setVirtualServerProperties	2-169
2.216	otd_setVirtualServerSslProperties	2-170
2.217	otd_setWalletPassword	2-171
2.218	otd_setWebappFirewallProperties	2-172
2.219	otd_startFailover	2-173
2.220	otd_startSnmpSubAgent	2-173
2.221	otd_stopFailover	2-174
2.222	otd_stopSnmpSubAgent	2-175
2.223	otd_toggleFailoverGroupPrimary	2-175
2.224	pullComponentChanges	2-176
2.225	resync/resyncAll	2-177
2.226	showComponentChanges	2-178
2.227	softRestart	2-179
2.228	start	2-180
2.229	state	2-180
2.230	stop	2-181
2.231	stopEdit	2-181
2.232	undo	2-182

# Preface

This document provides information about custom WLST commands that can be used to manage Oracle Traffic Director.

## Audience

This book is intended for Oracle Traffic Director administrators. This book assumes you are familiar with the following topics:

- Installing software
- Issuing commands in a terminal window
- Oracle WebLogic Server administrative tasks

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Related Documents

See the following documents, which are available on the Oracle Technology Network:

- *Administering Oracle Traffic Director*
- *Configuration File Reference for Oracle Traffic Director*
- *Installing Oracle Traffic Director*
- *Using WebLogic Server MT*

## Conventions

The following text conventions are used in this document:

<b>Convention</b>	<b>Meaning</b>
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

# 1

## Overview of the WebLogic Scripting Tool for Oracle Traffic Director

The WebLogic Scripting Tool (WLST) is a command-line scripting environment that you can use to create, manage, and monitor Oracle Traffic Director configurations and instances. WLST is based on the Java scripting interpreter, Jython. In addition to supporting standard Jython features such as local variables, conditional variables, and flow control statements, WLST provides a set of scripting functions (commands) that are specific to Oracle Traffic Director. You can invoke the WLST by executing the `wlst.sh`, as follows:

```
cd ORACLE_HOME/oracle_common/common/bin
./wlst.sh
```

`ORACLE_HOME` is the Oracle Home directory you specified at installation.

This guide defines all the custom WLST commands supported for configuring and administering Oracle Traffic Director.

### 1.1 Changes from Release 11g

Oracle Traffic Director administration is now built on a Common Administration Model (CAM). CAM includes system components such as, Oracle HTTP Server, and Oracle Traffic Director in the WebLogic domain. An Oracle Traffic Director Administration Server is no longer required. You must install Oracle WebLogic Server, create an Oracle WebLogic domain and use Oracle WebLogic Administration Server to manage Oracle Traffic Director.

WLST is now the equivalent of the Oracle Traffic Director `tadm` command line in Release 11g. You can only run the commands in script mode and not in standalone mode. The commands are implemented as WLST custom command functions, they are not hyphenated and follow the pattern 'otd\_MixedCaseCommandName'. For example, the `create-config` command in Release 11g is the `otd_createConfiguration` command.

### 1.2 Usage Modes

You can use the following techniques to invoke Oracle Traffic Director custom commands. For more information on using WLST in these modes, see *Interactive Mode*, *Script Mode*, and *Embedded Mode* in *Understand WebLogic Scripting Tool Guide*.

#### 1.2.1 Interactive Mode

In the interactive mode, the WLST scripting shell maintains a persistent connection with an instance of WebLogic Server. You can enter an Oracle Traffic Director command and view the response at the command line prompt.

```
# Launch wlst.sh
<oracle_home>/otd/common/bin/wlst.sh

# Connect to WLS admin server
> connect('weblogic', 'welcome1','t3://localhost:7001')

# Execute an OTD command - list existing configurations
> otd_listConfigurations()
['origin-server-1', 'test', 'origin-server-2', 'origin-server-3']

# Execute another command - get http properties of configuration 'test'
> props={'configuration': 'test'}
> ret = otd_getHttpProperties(props)
> print ret
{'ecid': 'true', 'unchunk-timeout': '60', 'discard-misquoted-cookies': 'true', 'max-
request-headers': '64', 'favicon': 'true',
'request-body-timeout': '-1', 'request-header-buffer-size': '8192', 'etag': 'true',
'max-unchunk-size': '8192', 'io-timeout': '30',
'body-buffer-size': '1024', 'output-buffer-size': '8192', 'websocket-strict-
upgrade': 'false', 'strict-request-headers': 'false',
'request-header-timeout': '30', 'server-header': None}
```

## 1.2.2 Script Mode

Scripts invoke a sequence of WLST commands without requiring interactive input, much like a shell script. Scripts contain WLST commands in a text file with a `.py` file extension.

## 1.2.3 Embedded Mode

In embedded mode, the WLST interpreter can be instantiated in Java code and used to run WLST commands and scripts. To run Oracle Traffic Director commands in embedded mode, you must extend the environment to include Oracle Traffic Director commands and libraries as follows:

1. Extend the Java classpath to include `<oracle_home>/otd/lib/admin.jar`.
2. Set the `weblogic.wlstHome` Java system property to point to `<oracle_home>/otd/common/wlst`.

For example, `-Dweblogic.wlstHome=<oracle_home>/otd/common/wlst`

3. Write a Java program to invoke Oracle Traffic Director commands:

```
package oracle.otd.wlst;

import weblogic.management.scripting.utils.WLSTInterpreter;
import org.python.util.InteractiveInterpreter;

public class WLSTClient
{
    public static void main(String[] args)
    {
        InteractiveInterpreter interpreter = new WLSTInterpreter();
        interpreter.exec("connect('weblogic', 'weblogic1','t3://localhost:
1894')");
        interpreter.exec("print otd_listConfigurations()");
    }
}
```

## 1.3 Offline Commands

The following Oracle Traffic Director WLST commands can be executed in offline mode directly on the host where the Oracle Traffic Director instance/admin server is configured.

### 1.3.1 Offline Provisioning

After creating and extending the domain with Oracle Traffic Director domain template, use the following offline commands to create and delete Oracle Traffic Director configurations and instances on the administration server. These commands do not require the administration server to be running. Run these commands on the host where the administration server resides.

As these are offline commands, you need not execute `activate` for changes to be applied. Ensure that there is no open edit session while running these commands as these would manipulate the `config-store` directly and the changes will not be applied in the edit session unless the administration server is restarted.

- [otd\\_createConfiguration](#)
- [otd\\_deleteConfiguration](#)
- [otd\\_listConfigurations](#)
- [otd\\_createInstance](#)
- [otd\\_deleteInstance](#)
- [otd\\_listInstances](#)

 **Note:**

You cannot invoke the above commands in offline mode until a domain has been read using `readDomain`. Make sure to update the domain using `updateDomain` after the command for changes to be applied.

### 1.3.2 Monitoring

The following commands can be used for monitoring the statistics pertaining to an instance by executing the commands directly on the host where the OTD instance resides.

- [otd\\_getStatsXml](#)
- [otd\\_getPerfDump](#)

### 1.3.3 SNMP Runtime Management

The following commands can be used to start/stop SNMP sub-agent by executing the commands directly on the host corresponding to the machine.

- [otd\\_startSnmpSubAgent](#)

- [otd\\_stopSnmpSubAgent](#)

## 1.3.4 Failover Runtime Management

The following commands can be executed to start/stop failover on the instance by executing the commands directly on the host where the OTD instance resides:

- [otd\\_startFailover](#)
- [otd\\_stopFailover](#)

## 1.4 Custom WLST Command Usage

All Oracle Traffic Director custom WLST commands are implemented as Jython functions with options (if any) passed as function arguments.

### 1.4.1 Syntax

```
> <otd_custom_command>(props) or <otd_custom_command>()
```

### 1.4.2 Use with WLST

Unless specified otherwise, the commands can only be executed online where the connection to a running server is needed. If mentioned as Offline, the command can be executed directly on the host where the Oracle Traffic Director instances are to be configured.

While specifying the path in WLST commands in a Microsoft Windows system, ensure that the path is provided with double backslash only. For example, `C:\\newline`.

### 1.4.3 Arguments

The commands either take no argument or a python dictionary as an argument. All the properties are passed to the command in python dictionary as name-value pairs with both name and the value being strings.

### 1.4.4 Return Values

Unless specified otherwise, all the getter commands (`otd_getX`) return a python dictionary with properties as name (string)-value (string) pairs, setters (`otd_setX`) and create/delete do not return any value while list methods (`otd_listX`) return a list of python dictionaries of name (string)-value (string) pairs

### 1.4.5 Error Messages

In case of an error, all the commands throw a `WLSTException` with an exception message ID in the format 'OTD-XXXXX', and a description. For example:

```
WLSTException: OTD-67853 Object does not exist:  
oracle.otd.admin:type=Configuration,configuration=test1
```



## 1.4.6 Unable to Unset/Disable the URI Mapping on a Route

To unset a value for any property, ensure that you enter "None". Leaving an empty string does not unset a property.

## 1.5 List of Commands

This section contains the functional list of WLST commands that are used in Oracle Fusion Middleware. Using this section you can look for specific commands based on the functional role of Oracle Fusion Middleware.

### 1.5.1 Provisioning

Commands for provisioning a collocated or standalone domain.

#### 1.5.1.1 Collocated Domain

The following commands are for provisioning a collocated domain:

- [otd\\_createConfiguration](#)
- [otd\\_deleteConfiguration](#)
- [otd\\_listConfigurations](#)
- [otd\\_createInstance](#)
- [otd\\_deleteInstance](#)
- [otd\\_listInstances](#)

#### 1.5.1.2 Standalone Domain

The following commands are for provisioning a standalone domain.

- [otd\\_createStandaloneDomain](#)
- [otd\\_createStandaloneInstance](#)
- [otd\\_deleteStandaloneInstance](#)

### 1.5.2 Instance Management

The following are instance management commands:

- [start](#)
- [stop](#)
- [state](#)
- [softRestart](#)
- [otd\\_rotateLog](#)

### 1.5.3 Configuration Deployment

The following are configuration deployment commands:

- activate
- undo
- stopEdit
- showComponentChanges
- pullComponentChanges
- resync/resyncAll
- enableOverwriteComponentChanges

## 1.5.4 Configuration Management

Commands for configuration management.

### 1.5.4.1 Configuration

The following are configuration commands:

- otd\_copyConfiguration
- otd\_listConfigFiles
- otd\_getConfigFile
- otd\_saveConfigFile
- otd\_deleteConfigFile

### 1.5.4.2 Setting/Tuning

The following are setting/tuning commands:

- otd\_setConfigurationProperties
- otd\_getConfigurationProperties
- otd\_setHttpProperties
- otd\_getHttpProperties
- otd\_setKeepaliveProperties
- otd\_getKeepaliveProperties
- otd\_setHttpThreadPoolProperties
- otd\_getHttpThreadPoolProperties
- otd\_setTcpThreadPoolProperties
- otd\_getTcpThreadPoolProperties
- otd\_setDnsProperties
- otd\_getDnsProperties
- otd\_setDnsCacheProperties
- otd\_getDnsCacheProperties
- otd\_setSslSessionCacheProperties
- otd\_getSslSessionCacheProperties

- [otd\\_setFileCacheProperties](#)
- [otd\\_getFileCacheProperties](#)
- [otd\\_createConfigurationVariable](#)
- [otd\\_deleteConfigurationVariable](#)
- [otd\\_listConfigurationVariables](#)
- [otd\\_setCacheProperties](#)
- [otd\\_getCacheProperties](#)
- [otd\\_setConfigurationCrlProperties](#)
- [otd\\_getConfigurationCrlProperties](#)
- [otd\\_installCrl](#)
- [otd\\_deleteCrl](#)
- [otd\\_listCrls](#)
- [otd\\_createMimeType](#)
- [otd\\_deleteMimeType](#)
- [otd\\_listMimeType](#)

## 1.5.5 Virtual Server Management

Commands for management of virtual server configuration and properties.

### 1.5.5.1 Configuration

The following are configuration commands:

- [otd\\_createVirtualServer](#)
- [otd\\_deleteVirtualServer](#)
- [otd\\_listVirtualServers](#)
- [otd\\_listVirtualServers](#)

### 1.5.5.2 Setting/Tuning

The following are setting/tuning commands:

- [otd\\_setVirtualServerProperties](#)
- [otd\\_getVirtualServerProperties](#)
- [otd\\_createErrorPage](#)
- [otd\\_deleteErrorPage](#)
- [otd\\_listErrorPages](#)
- [otd\\_createVirtualServerVariable](#)
- [otd\\_deleteVirtualServerVariable](#)
- [otd\\_listVirtualServerVariables](#)
- [otd\\_disableVirtualServerResponseBandwidthLimit](#)

- [otd\\_enableVirtualServerResponseBandwidthLimit](#)
- [otd\\_getVirtualServerRequestBandwidthLimitProperties](#)
- [otd\\_disableVirtualServerRequestBandwidthLimit](#)
- [otd\\_enableVirtualServerRequestBandwidthLimit](#)
- [otd\\_getVirtualServerRequestBandwidthLimitProperties](#)

## 1.5.6 TCP Load Balancer Management

The following are commands for TCP load balancer management:

- [otd\\_createTcpProxy](#)
- [otd\\_deleteTcpProxy](#)
- [otd\\_listTcpProxies](#)
- [otd\\_setTcpProxyProperties](#)
- [otd\\_getTcpProxyProperties](#)

## 1.5.7 Server Pool Management

Commands for server pool management.

### 1.5.7.1 Server Pool

The following are server pool management commands:

- [otd\\_createOriginServerPool](#)
- [otd\\_deleteOriginServerPool](#)
- [otd\\_listOriginServerPools](#)
- [otd\\_getOriginServerPoolProperties](#)

### 1.5.7.2 Health Check

The following are health check commands:

- [otd\\_getHealthCheckProperties](#)
- [otd\\_setHealthCheckProperties](#)

### 1.5.7.3 Origin Server

The following are origin server commands:

- [otd\\_createOriginServer](#)
- [otd\\_deleteOriginServer](#)
- [otd\\_listOriginServers](#)
- [otd\\_setOriginServerProperties](#)
- [otd\\_getOriginServerProperties](#)

## 1.5.7.4 Maintenance

The following are maintenance commands:

- [otd\\_enableOriginServerPoolMaintenance](#)
- [otd\\_disableOriginServerPoolMaintenance](#)
- [otd\\_getOriginServerPoolMaintenanceProperties](#)

## 1.5.8 Listener Management

Commands for managing listeners.

### 1.5.8.1 HTTP

The following are HTTP listener commands:

- [otd\\_createHttpListener](#)
- [otd\\_deleteHttpListener](#)
- [otd\\_listHttpListeners](#)
- [otd\\_setHttpListenerProperties](#)
- [otd\\_getHttpListenerProperties](#)

### 1.5.8.2 TCP

The following are TCP listener commands:

- [otd\\_createTcpListener](#)
- [otd\\_deleteTcpListener](#)
- [otd\\_listTcpListeners](#)
- [otd\\_setTcpListenerProperties](#)
- [otd\\_getTcpListenerProperties](#)

## 1.5.9 SSL Management

Commands for managing SSL.

### 1.5.9.1 Certificate Management

The following are certificate management commands:

- [listKeyStores](#)
- [generateKeyPair](#)
- [listKeyStoreAliases](#)
- [getKeyStoreCertificates](#)
- [exportKeyStoreCertificateRequest](#)
- [importKeyStoreCertificate](#)

- [exportKeyStoreCertificate](#)
- [listExpiringCertificates](#)
- [deleteKeyStoreEntry](#)
- [otd\\_setWalletPassword](#)
- [otd\\_exportKeyStore](#)
- [otd\\_listCertificates](#)

### 1.5.9.2 SSL Settings

The following are commands for SSL settings:

- [otd\\_setVirtualServerSslProperties](#)
- [otd\\_getVirtualServerSslProperties](#)
- [otd\\_setHttpListenerSslProperties](#)
- [otd\\_getHttpListenerSslProperties](#)
- [otd\\_setTcpListenerSslProperties](#)
- [otd\\_getTcpListenerSslProperties](#)
- [otd\\_setOriginServerPoolSslProperties](#)
- [otd\\_getOriginServerPoolSslProperties](#)

### 1.5.9.3 Ciphers

The following are the ciphers supported by the server.

- TLS\_RSA\_WITH\_AES\_128\_CBC\_SHA
- TLS\_RSA\_WITH\_AES\_128\_CBC\_SHA256
- TLS\_RSA\_WITH\_AES\_256\_CBC\_SHA256
- TLS\_RSA\_WITH\_AES\_128\_GCM\_SHA256
- TLS\_RSA\_WITH\_AES\_256\_GCM\_SHA384
- TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_CBC\_SHA256
- TLS\_ECDHE\_ECDSA\_WITH\_AES\_256\_CBC\_SHA384
- TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_GCM\_SHA256
- TLS\_ECDHE\_ECDSA\_WITH\_AES\_256\_GCM\_SHA384
- TLS\_ECDHE\_RSA\_WITH\_AES\_128\_CBC\_SHA256
- TLS\_ECDHE\_RSA\_WITH\_AES\_256\_CBC\_SHA384
- TLS\_ECDHE\_RSA\_WITH\_AES\_128\_GCM\_SHA256
- TLS\_ECDHE\_RSA\_WITH\_AES\_256\_GCM\_SHA384

The following ciphers are disabled by default and are now deprecated.

- TLS\_ECDHE\_RSA\_WITH\_AES\_128\_CBC\_SHA
- TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_CBC\_SHA
- TLS\_ECDHE\_RSA\_WITH\_AES\_256\_CBC\_SHA

- `TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA`
- `TLS_RSA_WITH_AES_256_CBC_SHA`
- `TLS_ECDHE_RSA_WITH_3DES_EDE_CBC_SHA`
- `TLS_ECDHE_ECDSA_WITH_3DES_EDE_CBC_SHA`
- `SSL_RSA_WITH_3DES_EDE_CBC_SHA`

## 1.5.10 Rules Management

Commands for rules management.

### 1.5.10.1 Routes

The following are routes commands:

- `otd_createRoute`
- `otd_deleteRoute`
- `otd_listRoutes`
- `otd_setRouteProperties`
- `otd_getRouteProperties`
- `otd_enableRouteAuth`
- `otd_disableRouteAuth`
- `otd_listProxyInfo`
- `otd_forwardProxyInfo`
- `otd_blockProxyInfo`
- `otd_enableRouteBandwidthLimit`
- `otd_disableRouteBandwidthLimit`
- `otd_getRouteBandwidthLimitProperties`

### 1.5.10.2 Proxy Cache Rules

The following are proxy cache rules commands:

- `otd_createCacheRule`
- `otd_deleteCacheRule`
- `otd_listCacheRules`
- `otd_setCacheRuleProperties`
- `otd_getCacheRuleProperties`

### 1.5.10.3 Request Limit Rules

The following are request limit rules commands:

- `otd_createRequestLimit`
- `otd_deleteRequestLimit`

- [otd\\_listRequestLimits](#)
- [otd\\_setRequestLimitProperties](#)
- [otd\\_getRequestLimitProperties](#)

#### 1.5.10.4 Compression Rules

The following are compression rules commands:

- [otd\\_createCompressionRule](#)
- [otd\\_deleteCompressionRule](#)
- [otd\\_listCompressionRules](#)
- [otd\\_setCompressionRuleProperties](#)
- [otd\\_getCompressionRuleProperties](#)

#### 1.5.10.5 Content Rules

The following are content rules commands:

- [otd\\_createContentRule](#)
- [otd\\_deleteContentRule](#)
- [otd\\_listContentRules](#)
- [otd\\_setContentRuleProperties](#)
- [otd\\_getContentRuleProperties](#)

### 1.5.11 Web Application Firewall (WAF) Management

Commands for Web Application Firewall (WAF) management.

#### 1.5.11.1 Configuration

The following are setting/tuning commands:

- [otd\\_enableWebAppFirewall](#)
- [otd\\_disableWebAppFirewall](#)
- [otd\\_setWebappFirewallProperties](#)
- [otd\\_getWebappFirewallProperties](#)

#### 1.5.11.2 Ruleset File Management

The following are setting/tuning commands:

- [otd\\_installConfigurationWebappFirewallRulesetFile](#)
- [otd\\_installVirtualServerWebappFirewallRulesetFile](#)
- [otd\\_deleteConfigurationWebappFirewallRulesetFile](#)
- [otd\\_deleteVirtualServerWebappFirewallRulesetFile](#)
- [otd\\_listConfigurationWebappFirewallRulesetFiles](#)



- [otd\\_listVirtualServerWebappFirewallRulesetFiles](#)

## 1.5.12 Monitoring

Commands for monitoring.

### 1.5.12.1 Runtime Statistics

The following are commands for displaying runtime statistics:

- [otd\\_getStatsXml](#)
- [otd\\_getPerfDump](#)
- [displayMetricTables](#)

### 1.5.12.2 Setting/Tuning

The following are commands for setting/tuning monitoring settings:

- [otd\\_enableStatsXml](#)
- [otd\\_enableStatsXml](#)
- [otd\\_getStatsXmlProperties](#)
- [otd\\_enablePerfDump](#)
- [otd\\_disablePerfDump](#)
- [otd\\_getPerfDumpProperties](#)
- [otd\\_setStatsProperties](#)
- [otd\\_getStatsProperties](#)

### 1.5.12.3 SNMP Configuration

The following are commands for SNMP configuration:

- [otd\\_setSnmpProperties](#)
- [otd\\_getSnmpProperties](#)

### 1.5.12.4 SNMP Runtime Management

The following are commands for SNMP runtime management:

- [otd\\_startSnmpSubAgent](#)
- [otd\\_stopSnmpSubAgent](#)

## 1.5.13 Logging Configuration

The following are logging configuration commands:

- [otd\\_setLogProperties](#)
- [otd\\_getLogProperties](#)
- [otd\\_setAccessLogBufferProperties](#)

- `otd_getAccessLogBufferProperties`
- `otd_setConfigurationAccessLogProperties`
- `otd_getConfigurationAccessLogProperties`
- `otd_enableVirtualServerAccessLog`
- `otd_disableVirtualServerAccessLog`
- `otd_getVirtualServerAccessLogProperties`
- `otd_setTcpAccessLogProperties`
- `otd_getTcpAccessLogProperties`
- `displayLogs`

## 1.5.14 Failover Management

The following are failover management commands:

### 1.5.14.1 Configuration

The following are configuration commands:

- `otd_addFailoverInstance`
- `otd_createFailoverGroup`
- `otd_deleteFailoverGroup`
- `otd_getFailoverGroupProperties`
- `otd_toggleFailoverGroupPrimary`
- `otd_listFailoverGroups`
- `otd_removeFailoverInstance`
- `otd_listFailoverInstances`
- `otd_setFailoverInstanceOrder`

### 1.5.14.2 Runtime Management

The following are runtime management commands:

- `otd_startFailover`
- `otd_stopFailover`

## 1.5.15 Events

The following are events commands:

- `otd_createEvent`
- `otd_deleteEvent`
- `otd_listEvents`
- `otd_getEventProperties`
- `otd_setEventProperties`

## 1.5.16 Multi-tenancy (with WebLogic Server MT)

Commands for use with Oracle Traffic Director in a WebLogic Server MT environment.

- [otd\\_listPartitions](#)
- [otd\\_listResourceGroups](#)
- [otd\\_getPartitionAccessLogProperties](#)
- [otd\\_setPartitionAccessLogProperties](#)

## 1.5.17 Service Management

Commands used for creating or deleting operating system services for Oracle Traffic Director instances.

- [otd\\_createService](#)
- [otd\\_deleteService](#)
- [otd\\_listServices](#)

# 2

## Oracle Traffic Director WLST Commands

This chapter lists and describes the WebLogic Scripting Tool (WLST) commands and their options for Oracle Traffic Director in alphabetical order.

### 2.1 activate

#### Description

Activates changes saved during the current editing session but not yet deployed. This command prints a message if a server restart is required for the changes that are being activated.

The activate command returns the latest `ActivationTask` MBean which reflects the state of changes that a user is currently making or has made recently. You can then invoke methods to get information about the latest Configuration Manager activate task in progress or just completed. In the event of an error, the command returns a `WLSTException`.

Use this command to deploy the configuration changes to the instances. Note that this command will deploy only the changes done after starting an edit session by executing the command `startEdit`. Also, the effect of this command is not limited to Oracle Traffic Director. All the changes done after starting an edit session to the various other components and managed servers will also be deployed.

#### Syntax

```
activate([timeout], [block])
```

Argument	Definition
<code>timeout</code>	Optional. Time (in milliseconds) that WLST waits for the activation of configuration changes to complete before canceling the operation. A value of -1 indicates that the operation will not time out. This argument defaults to 300,000 ms (or 5 minutes).
<code>block</code>	Optional. Boolean value specifying whether WLST should block user interaction until the command completes. This argument defaults to <code>false</code> , indicating that user interaction is not blocked. In this case, WLST returns control to the user after issuing the command and assigns the task MBean associated with the current task to a variable that you can use to check its status. If you are importing WLST as a Jython module, as described in <i>Importing WLST as a Jython Module in Understanding the WebLogic Scripting Tool</i> , <code>block</code> is always set to <code>true</code> .

#### Example

The following example activates the changes made during the current edit session that have been saved to disk, but that have not yet been activated. WLST waits for 100,000 ms for the activation to complete, and 200,000 ms before the activation is stopped.

```
wls:/mydomain/edit !> activate(200000, block='true')
Activating all your changes, this may take a while ...
The edit lock associated with this edit session is released once the activation is
completed.
Action completed.
wls:/mydomain/edit>
```

**See Also**

[help](#), [otd\\_createConfiguration](#), [otd\\_listConfigurations](#), [otd\\_deleteConfiguration](#),  
[otd\\_copyConfiguration](#), [otd\\_listConfigFiles](#), [otd\\_getConfigFile](#), [otd\\_saveConfigFile](#)

## 2.2 deleteKeyStoreEntry

**Description**

Deletes a certificate or trusted certificate from the keystore using its alias.

**Syntax**

```
deleteKeyStoreEntry(appStripe='stripe', name='keystore',
password='password', alias='alias', keypassword='keypassword')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>alias</i>	Specifies the alias of the entry to be deleted.
<i>keypassword</i>	Specifies the key password of the entry to be deleted.

**Example**

This example deletes a keystore entry denoted by alias `mycert`.

```
svc = getOpssService("KeyStoreService")
svc.deleteKeyStoreEntry(appStripe='OTD', name='myconfig', password='',
alias='mycert', keypassword='')
```

**See Also**

[help](#), [exportKeyStoreCertificateRequest](#), [otd\\_listCertificates](#),  
[importKeyStoreCertificate](#), [getKeyStoreCertificates](#), [generateKeyPair](#). Also see  
`deleteKeyStoreEntry` in *Infrastructure Security WLST Command Reference*.

## 2.3 displayLogs

### Description

Use this command to view the contents of Oracle Traffic Director log files, the access log, tcp access log and error log. The access log records information about requests to and responses from the server.

The command returns a value only when the returnData option is set to true. By default it will not return any data. The return value depends on the option used.

### Syntax

```
displayLogs([searchString,][options])
```

Argument	Definition
searchString	<p>An optional search string. Only messages that contain the given string (case-insensitive) will be returned.</p> <p>Note that the displayLogs command can read logs in multiple formats and it converts the messages to ODL format. The search will be performed in the native format, if possible. Otherwise, it may be performed in the message contents, and it may exclude mark-up. Therefore you should avoid using mark-up characters in the search string.</p>
target	<p>Optional. The name of a WebLogic Server instance, or a system component.</p> <p>For a system component, the syntax for the target is:</p> <pre>sc:component-name</pre> <p>In connected mode, the default target is the WebLogic domain. In disconnected mode, there is no default; the target option is required.</p>
oracleInstance	Optional. Defines the path to the ORACLE_INSTANCE or WebLogic domain home. The command is executed in disconnected mode when you use this parameter.
log	Optional. A log file path. The command will read messages from the given log file. If the log file path is not given, the command will read all logs associated with the given target.
last	Optional. An integer value. Restricts the search to messages logged within the last minutes. The value can have a suffix <i>s</i> (second), <i>m</i> (minute), <i>h</i> (hour), or <i>d</i> (day) to specify a different time unit. (For example, last='2h' will be interpreted as the last 2 hours).
tail	Optional. An integer value. Restrict the search to the last <i>n</i> messages from each log file and limits the number of messages displayed to <i>n</i> .
pattern	<p>Optional. A regular expression pattern. Only messages that contain the given pattern are returned. Using the pattern option is similar to using the searchString argument, except that you can use a regular expression.</p> <p>The regular expression pattern search is case sensitive (unless you explicitly turn on case-insensitive flags in the pattern). The pattern must follow java.util.regex syntax.</p>
ecid	Optional. A string or string sequence containing one or more Execution Context ID (ECID) values to be used as a filter for log messages.

Argument	Definition
component	Optional. A string or string sequence containing one or more component ID values to be used as a filter for log messages.
module	Optional. A string or string sequence containing one or more module ID values to be used as a filter for log messages.
type	Optional. A string or string sequence containing one or more message type values to be used as a filter for log messages.
app	Optional. A string or string sequence containing one or more application values to be used as a filter for log messages.
query	<p>Optional. A string that specifies an expression used to filter the contents of log messages.</p> <p>A simple expression has the form:</p> <p><i>field-name operator value</i></p> <p>where <i>field-name</i> is a log record field name and <i>operator</i> is an appropriate operator for the field type (for example, you can specify equals, startsWith, contains or matches for string fields).</p> <p>A field name is either one of the standard ODL attribute names (such as COMPONENT_ID, MSG_TYPE, MSG_TEXT, and SUPPL_DETAIL), or the name of a supplemental attribute (application specific), prefixed by SUPPL_ATTR. (For example, SUPPL_ATTR.myAttribute).</p> <p>A few common supplemental attributes can be used without the prefix. For example, you can use APP to filter by application name.</p> <p>You can combine multiple simple expressions using the boolean operators and, or and not to create complex expressions, and you can use parenthesis for grouping expressions.</p> <p>See <i>Administering Oracle Fusion Middleware</i> for a detailed description of the query syntax.</p>
groupBy	Optional. A string list. When the groupBy option is used, the output is a count of log messages, grouped by the attributes defined in the string list.
orderBy	<p>Optional. A string list that defines the sort order for the result. The values are log message attribute names. The name may be extended with an optional suffix :asc or :desc to specify ascending or descending sorting. The default sort order is ascending.</p> <p>By default, the result is sorted by time.</p>
returnData	Optional. A Jython boolean value (0 or 1). If the value is true the command will return data (for example, to be used in a script). The default value is false, which means that the command only displays the data but does not return any data.
format	Optional. A string defined the output format. Valid values are ODL-Text, ODL-XML, ODL-complete and simple. The default format is ODL-Text.
exportFile	Optional. The name of a file to where the command output is written. By default, the output is written to standard output.
follow (f)	Optional. Puts the command in "follow" mode so that it continues to read the logs and display messages as new messages are added to the logs (similar to the UNIX tail -f command). The command will not return when the f option is used. This option is currently not supported with system components.

**Example**

```
displayLogs(target="sc:otd_test_varunam.in.example.com")
```

**See Also**

[help](#), [displayLogs](#), [otd\\_getAccessLogBufferProperties](#),  
[otd\\_enableVirtualServerAccessLog](#), [otd\\_disableVirtualServerAccessLog](#), [displayLogs](#),  
[otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

## 2.4 displayMetricTables

**Description**

This WLST command can be used to display runtime statistics about a server instance.

**Syntax**

```
displayMetricTables([metricTable_1] [, metricTable_2], [...] [, servers] [, variables])
```

Argument	Definition
metricTable_n	<p>Optional. Specifies a list of metric tables. By default, this argument displays all available metrics. The metric table name can contain special characters for simple pattern matching. The character '?' matches any single character. The character '*' matches zero or more characters.</p> <p>You specify the metric table name. You can specify multiple metric table names in a comma-separated list.</p> <p>These are the same names output by the WLST command <code>displayMetricTableNames</code>.</p>
servers	<p>Optional. Specifies the servers from which to retrieve metrics. Valid values are a list of WebLogic Server instance names and system component names.</p> <p>To specify one server, use the following syntax:</p> <pre>servers='servername'</pre> <p>To specify multiple servers, use one of the following syntax options:</p> <pre>servers=['servername1', 'servername2', ...] servers=('servername1', 'servername2', ...)</pre> <p>If this argument is not specified, the command returns the list of metric tables for all WebLogic servers and system components.</p> <p>For system components, such as Oracle HTTP Server, use the following format:</p> <pre>servers=['component_name], servertime='component_type')</pre>



Argument	Definition
variables	<p>Optional. Defines the metric aggregation parameters. Valid values are a set of name-value pairs. It uses the following syntax:</p> <pre>variables={name1:value1, name2:value2, ...}</pre> <p>The specific name-value pairs depend on the aggregated metric tables. Each aggregated metric table has its specific set of variable names.</p>

### Example

Note that at least a single Oracle Traffic Director instance needs to be running for the following examples to work correctly.

```
# View metrics for all OTD instances
displayMetricTables('OTD_*')

# View origin server metrics for all instances
displayMetricTables('OTD_OriginServer')

# Get list of metric tables for a specific instance
displayMetricTableNames(servers='/OTD/otd_test_myserver.example.com')

# View all metrics for a specific instance
displayMetricTables(servers='/OTD/otd_test_myserver.example.com')

# View instance metrics for a specific instance
displayMetricTables('OTD_Instance', servers='/OTD/otd_test_myserver.example.com')
```

### See Also

[help](#), [otd\\_createOriginServer](#), [otd\\_deleteOriginServer](#), [otd\\_listOriginServers](#), [otd\\_setOriginServerProperties](#)

## 2.5 enableOverwriteComponentChanges

### Description

Executing this command before `activate` lets the `activate` call overwrite the local configuration file modifications on instances with their corresponding server versions.

An `activate` call would fail if there are any local configuration file modifications on the instance. In such a case, you would want to either discard the changes on the instance or pull the changes from the instance to the config store by executing `pullComponentChanges`. In either case, you should execute the command `enableOverwriteComponentChanges` before `activate` such that the `activate` call would not fail because of the local modifications on the instance.

#### Note:

This command can only be executed from an open edit session. See [resync/resyncAll](#) for overriding instance changes outside of an open edit session.

## Syntax

```
enableOverwriteComponentChanges()
```

## Example

```
props={'configuration': 'test', 'name': 'var_foo', 'value': 'bar'}
otd_createVariable(props)

activate()
weblogic.management.provider.UpdateException: [Management:141191]The prepare phase
of the configuration update failed with an exception.
Caused by: weblogic.nodemanager.NMException: Received error message from Node
Manager Server:
[ChangeList validation failed for transaction '3033897627106602' with cause:
OTD-67807 Validation failed for instance 'otd_test.example.com':
The instance configuration has been locally modified. The following changes can
either be discarded on the next activate using 'enableOverwriteComponentChanges' or
pulled into the current configuration using 'pullComponentChanges'.
Modified files: config/server.xml,config/test-obj.conf,config/obj.conf

# Scenario 1: Pull the changes on instance to config store and call
enableOverwriteComponentChanges and activate.

showComponentChanges("otd_test.example.com")
component otd_test.example.com changes on machine example.com:
edit OTD/test/config/obj.conf 2014.12.01-16:20:50 1970.01.01-05:29:59
edit OTD/test/config/test-obj.conf 2014.12.01-16:20:50 1970.01.01-05:29:59
edit OTD/test/config/server.xml 2014.12.01-16:50:27 2014.12.01-16:49:44

pullComponentChanges("otd_test.example.com")
pull component otd_test.example.com changes on machine in.example.com:
edit OTD/test/config/obj.conf
edit OTD/test/config/test-obj.conf
edit OTD/test/config/server.xml

enableOverwriteComponentChanges()
activate()
Activating all your changes, this may take a while ...
The edit lock associated with this edit session is released once the activation is
completed.
Activation completed

# Scenario 2: Discard the changes on the instance and override them with changes
from the current edit session

showComponentChanges("otd_test.example.com")
component otd_test.example.com changes on machine example.com:
edit OTD/test/config/obj.conf 2014.12.01-16:55:29 1970.01.01-05:29:59
edit OTD/test/config/test-obj.conf 2014.12.01-16:55:29 1970.01.01-05:29:59
edit OTD/test/config/server.xml 2014.12.01-16:55:29 2014.12.01-16:58:23

enableOverwriteComponentChanges()
activate()
Activating all your changes, this may take a while ...
The edit lock associated with this edit session is released
once the activation is completed.
Activation completed
```

**See Also**

[help](#), [pullComponentChanges](#), [resync/resyncAll](#), [showComponentChanges](#), [stopEdit](#), [undo](#)

## 2.6 exportKeyStoreCertificate

**Description**

Exports a certificate, trusted certificate or certificate chain.

**Syntax**

```
exportKeyStoreCertificate(appStripe='stripe', name='keystore', password='password',  
alias='alias', keypassword='keypassword',  
type='entrytype', filepath='absolute_file_path')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>alias</i>	Specifies the alias of the entry to be exported
<i>keypassword</i>	Specifies the key password.
<i>type</i>	Specifies the type of keystore entry to be exported. Valid values are 'Certificate', 'TrustedCertificate' or 'CertificateChain'.
<i>filepath</i>	Specifies the absolute path of the file where certificate, trusted certificate or certificate chain is exported.

**Example**

```
svc = getOpssService("KeyStoreService")  
svc.exportKeyStoreCertificate(appStripe='OTD', name='myconfig', password='',  
alias='mycert', keypassword='', type='Certificate', filepath='/scratch/cert.txt')
```

**See Also**

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificate](#) in *Infrastructure Security WLST Command Reference*.

## 2.7 exportKeyStoreCertificateRequest

### Description

Generate a certificate signing request for a key pair and saves it to a file. This Base64-encoded certificate request can be submitted to a third-party Certificate Authority (CA) which will verify the sender, sign and return the signed certificate.

### Syntax

```
exportKeyStoreCertificateRequest(appStripe='stripe', name='keystore',
password='password', alias='alias', keypassword='keypassword',
filepath='absolute_file_path')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>alias</i>	Specifies the entry's alias name.
<i>keypassword</i>	Specifies the key password.
<i>filepath</i>	Specifies the absolute path of the file where certificate request is exported.

### Example

```
svc = getOpssService("KeyStoreService")

# generate a key pair with the proper DN
svc.generateKeyPair(appStripe='OTD', name='myconfig', password='', alias='mycert',
keypassword='', dn='CN=test.example.com, OU=Webtier, O=\'Company Name\',
ST=California, C=US', keysize='1024')

# generate the CSR and put it in to a text file
svc.exportKeyStoreCertificateRequest(appStripe='OTD', name='myconfig', password='',
alias='mycert', keypassword='', filepath='/scratch/certreq.crt')
```

### See Also

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificateRequest](#) in *Infrastructure Security WLST Command Reference*.

## 2.8 generateKeyPair

### Description

Use this command to generate a key pair in a keystore and wrap it in a demo CA-signed certificate. This command is the equivalent of creating a self-signed certificate in Release 11g. You can use this key pair to generate a certificate signing request (CSR) using `exportKeyStoreCertificateRequest` which you can submit to a third-party Certificate Authority (CA) for signing.

### Syntax

```
generateKeyPair(appStripe='stripe', name='keystore', password='password',
dn='distinguishedname', keysize='keysize', alias='alias',
keypassword='keypassword')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>dn</i>	Specifies the distinguished name of the certificate wrapping the key pair.
<i>keysize</i>	Specifies the key size.
<i>alias</i>	Specifies the alias of the key pair entry.
<i>keypassword</i>	Specifies the key password.
<i>ext_san</i>	subject alternate name extension

### Example

```
svc = getOpssService("KeyStoreService")
svc.generateKeyPair(appStripe='OTD', name='myconfig', password='', alias='mycert',
keypassword='', dn='CN=test.example.com, OU=Webtier, O=\'Company Name\',
ST=California, C=US', keysize='1024', ext_san="DNS:www.b.com,DNS:www.c.com")
```

### See Also

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificateRequest](#), [generateKeyPair](#) in *Infrastructure Security WLST Command Reference*.

## 2.9 getKeyStoreCertificates

### Description

Use this command to view the certificate properties including subject, issuer, issue date, and expiry date.

### Syntax

```
getKeyStoreCertificates(appStripe='stripe', name='keystore',
password='password', alias='alias', keypassword='keypassword')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>alias</i>	Specifies the alias of the certificate, trusted certificate or certificate chain to be displayed.
<i>keypassword</i>	Specifies the key password.

### Example

```
svc = getOpssService("KeyStoreService")
svc.getKeyStoreCertificates(appStripe='OTD', name='myconfig', password='',
alias='mycert')
```

### See Also

[help](#), [importKeyStoreCertificate](#), [deleteKeyStoreEntry](#), [otd\\_listCertificates](#), [generateKeyPair](#), [exportKeyStoreCertificateRequest](#), [getKeyStoreCertificates](#) in *Infrastructure Security WLST Command Reference*.

## 2.10 help

### Description

Lists all available Oracle Traffic Director custom WLST commands, or lists help for a particular command.

### Syntax

To list all available Oracle Traffic Director custom WLST commands:

```
help('otd')
```

To list help for a particular command:

```
help('<otd_custom_command>')
```

### Example

```
help('otd_createConfiguration')
```

## 2.11 importKeyStoreCertificate

### Description

Imports a CA signed or trusted certificate into the keystore.

Once a CSR is submitted to a CA for signing, the CA signs the request and typically sends the certificate as a Base-64 encoded string. You should import this certificate as type `CertificateChain` along with any Intermediate and Root CA certificates using the same alias as that of the key pair that was used to generate the certificate request.

Once you have downloaded your certificate from your CA, you can download any Intermediate and Root certificates from your CA's website, open a text editor and paste the entire body of each certificate into one text file in the following order: Primary Certificate > Intermediate Certificate > Root Certificate.

The file should appear as follows when finished:

```
-----BEGIN CERTIFICATE-----
(Server SSL certificate)
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
(Intermediate certificate)
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
(Root certificate)
-----END CERTIFICATE-----
```

### Syntax

```
importKeyStoreCertificate(appStripe='stripe', name='keystore',
password='password', alias='alias', keypassword='keypassword',
type='entrytype', filepath='absolute_file_path')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>alias</i>	Specifies the alias of the entry to be imported.
<i>keypassword</i>	Specifies the key password of the newly imported entry.

Argument	Definition
<i>type</i>	Specifies the type of keystore entry to be imported. Valid values are 'Certificate', 'TrustedCertificate' or 'CertificateChain'.
<i>filepath</i>	Specifies the absolute path of the file from where certificate, trusted certificate or certificate chain is imported.

### Example

```
svc = getOpssService("KeyStoreService")

# generate a key pair with the proper DN
svc.generateKeyPair(appStripe='OTD', name='myconfig', password='', alias='mycert',
keypassword='', dn='CN=test.example.com, OU=Webtier, O=\'Company Name\',
ST=California, C=US', keysize='1024')

# generate the CSR and put it in to a text file
svc.exportKeyStoreCertificateRequest(appStripe='OTD', name='myconfig', password='',
alias='mycert', keypassword='', filepath='/scratch/certreq.crt')

# Submit the CSR to a CA who can sign the certificate and import signed cert into #
the keystore using the same alias as the key pair. Note that the file being #
imported should contain the CA cert along with the server cert and should be
# imported as type 'CertificateChain'
svc.importKeyStoreCertificate(appStripe='OTD', name='myconfig', password='',
alias='mycert', keypassword='', type='CertificateChain', filepath='/scratch/
certsign.pem')

# Any CA cert can be imported into the keystore as a trusted cert
svc.importKeyStoreCertificate(appStripe='OTD', name='myconfig', password='',
alias='ca-cert', keypassword='', type='TrustedCertificate', filepath='/scratch/
cacert.crt')
```

### See Also

[help](#), [exportKeyStoreCertificateRequest](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [generateKeyPair](#), [importKeyStoreCertificate](#) in *Infrastructure Security WLST Command Reference*.

## 2.12 listExpiringCertificates

### Description

List certificates expiring in a specified period.

### Syntax

```
listExpiringCertificates(days='days', autorenew=true|false)
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>days</i>	Specifies that the list should only include certificates within this many days from expiration.



Argument	Definition
<i>autorenew</i>	Specifies true for automatically renewing expiring certificates, false for only listing them.

**Example**

```
svc = getOpssService("KeyStoreService")
svc.listExpiringCertificates(days='365', autorenew=false)
```

**See Also**

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificateRequest](#), [listExpiringCertificates](#) in *Infrastructure Security WLST Command Reference*.

## 2.13 listKeyStores

**Description**

List all the keystores in a stripe. In the case of Oracle Traffic Director, a permission-protected keystore is created at the same time as the configuration and also has the same name as the configuration. Hence the keystore names returned by `listKeyStores` will typically match the configuration names.

**Syntax**

```
listKeyStores(appStripe='stripe')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe whose keystores are listed.

**Example**

```
svc = getOpssService("KeyStoreService")
svc.listKeyStores(appStripe='OTD')
```

**See Also**

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificateRequest](#), [listKeyStores](#) in *Infrastructure Security WLST Command Reference*.

## 2.14 listKeyStoreAliases

**Description**

List aliases in a keystore. Any certificate that is generated or imported into the keystore will be listed by its alias.

### Syntax

```
listKeyStoreAliases(appStripe='stripe', name='keystore', password='password',
type='entrytype')
```

Argument	Definition
<i>svc</i>	Specifies the service command object obtained through a call to <code>getOpssService()</code> .
<i>appStripe</i>	Specifies the name of the stripe where the keystore resides.
<i>name</i>	Specifies the name of the keystore.
<i>password</i>	Specifies the keystore password.
<i>type</i>	Specifies the type of entry for which aliases are listed. Valid values are 'Certificate', 'TrustedCertificate', 'SecretKey' or '*'.

### Example

```
svc = getOpssService("KeyStoreService")

# List all certificates
svc.listKeyStoreAliases(appStripe='OTD', name='myconfig', password='', type='*')

# List all user certificates (both SSL server and client)
svc.listKeyStoreAliases(appStripe='OTD', name='myconfig', password='',
type='Certificate')

# List only Trusted CA certificates
svc.listKeyStoreAliases(appStripe='OTD', name='myconfig', password='',
type='TrustedCertificate')
```

### See Also

[help](#), [importKeyStoreCertificate](#), [otd\\_listCertificates](#), [deleteKeyStoreEntry](#), [getKeyStoreCertificates](#), [exportKeyStoreCertificateRequest](#), `listKeyStoreAliases` in *Infrastructure Security WLST Command Reference*.

## 2.15 otd\_addFailoverInstance

### Description

Use this command to add a failover instance. This command is valid only for active-active failover type. You can add a maximum of 254 instances in a failover group.

### Syntax

```
otd_addFailoverInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-ip	Virtual IP that uniquely identifies the failure group.	Mandatory.
instance	Name of the instance.	Mandatory.
nic	A network interface, upon which the VIP must be managed.	Mandatory.

### Example 2-1 Example

```
props = {}
props['configuration'] = 'ha'
props['virtual-ip'] = '10.128.67.44'
props['instance'] = '1.example.com'
props['nic'] = 'eth0'
otd_addFailoverInstance(props)
```

### See Also

## 2.16 otd\_blockProxyInfo

### Description

Use this command to block the generation and forwarding of a particular proxy parameter to the origin server. The information about the proxy parameters and headers is described in [otd\\_forwardProxyInfo](#).

#### Note:

If the incoming request contains any of the headers corresponding to the proxy parameters, Oracle Traffic Director will pass-through the incoming request containing this header to the origin server.

### Syntax

```
otd_blockProxyInfo(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

Property	Description	Comments
route	Name of the route.	Mandatory.
param	Name of the proxy parameter to be blocked. Range of values: jroute, via, ip, cipher, proxy-agent, keysize, secret-keysize, ssl-id, issuer-dn, user-dn, auth-cert, xforwarded-for, cache-info, ssl.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['param'] = 'ssl'
otd_blockProxyInfo(props)
```

**See Also**

[help](#), [otd\\_listProxyInfo](#), [otd\\_forwardProxyInfo](#)

## 2.17 otd\_copyConfiguration

**Description**

Use this command to create a copy of an existing configuration.

**Syntax**

```
otd_copyConfiguration(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
source-configuration	Name of the configuration to be copied.	Mandatory.
dest-configuration	Name of the new configuration. Name should not contain spaces, invalid characters or non-ASCII characters.	Mandatory.

**Example**

```
props = {}
props['source-configuration'] = 'foo'
props['dest-configuration'] = 'bar'
otd_copyConfiguration(props)
```

**See Also**

[help](#), [otd\\_createConfiguration](#), [otd\\_deleteConfiguration](#), [otd\\_listConfigurations](#), [activate](#)

## 2.18 otd\_copyVirtualServer

### Description

Use this command to create a copy of an existing virtual server.

### Syntax

```
otd_copyVirtualServer(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>source-virtual-server</code>	Name of the virtual server to be copied.	Mandatory.
<code>dest-virtual-server</code>	Name of the new virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['source-virtual-server'] = 'bar'
props['dest-virtual-server'] = 'baz'
otd_copyVirtualServer(props)
```

### See Also

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#),  
[otd\\_deleteVirtualServer](#), [otd\\_getVirtualServerProperties](#), [otd\\_listVirtualServers](#)

## 2.19 otd\_createCacheRule

### Description

Use this command to create a cache rule with a set of initial values.

### Syntax

```
otd_createCacheRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

Property	Description	Comments
cache-rule	Name of the cache rule to be created. Only small letters are available. If the value contains capital letters, it will be changed to small letters without any notifications.	Mandatory.
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['cache-rule'] = 'cache-rule-1'
otd_createCacheRule(props)
```

**See Also**

[help](#), [otd\\_deleteCacheRule](#), [otd\\_getCacheProperties](#), [otd\\_getCacheRuleProperties](#), [otd\\_listCacheRules](#)

## 2.20 otd\_createCompressionRule

**Description**

Use this command to create a compression rule with an initial set of values.

**Syntax**

```
otd_createCompressionRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
compression-rule	Name of the compression rule to be created. Only small letters are available. If the value contains capital letters, it will be changed to small letters without any notifications.	Mandatory.
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
```

```
props['compression-rule'] = 'compression-rule-1'
otd_createCompressionRule(props)
```

### See Also

[help](#), [otd\\_deleteCompressionRule](#), [otd\\_setCompressionRuleProperties](#),  
[otd\\_listCompressionRules](#)

## 2.21 otd\_createConfiguration

A configuration is a collection of metadata to instantiate Oracle Traffic Director. You can create a new configuration that listens to HTTP and TCP traffic on a given port and front-ends a set of HTTP and TCP origin servers.

### Description

This command creates a default virtual server that handles HTTP traffic and a default TCP proxy that handles TCP traffic. In addition, it creates a default route and forwards all traffic to the origin server.

### Syntax

```
otd_createConfiguration(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>name</code>	Name of the configuration to be created. Name should not contain spaces, invalid characters or non-ASCII characters.	Mandatory.
<code>listener-port</code>	Listener port through which the server accepts requests. Range of values: port number should be an integer between 1 and 65535, both inclusive.	Mandatory.
<code>server-name</code>	Valid only if <code>origin-server-type</code> is <code>http</code> or <code>https</code> . The server name is used in any URLs that are generated automatically by the server and sent to the client. This server name should be the virtual host name or alias name if your server uses an alias. If a colon and port number are appended to the server name then that port is used in the generated URLs.	
<code>ip</code>	The server will bind to this Internet Protocol (IP) address for the default listener. Only traffic sent to this IP address will be serviced. * indicates that the server will listen on all IP addresses. Range of values: *, a hostname, or an IPV4/IPV6 address	
<code>origin-server-type</code>	Type of requests handled by the origin servers. Range of values: <code>http/https/tcp</code> Default: <code>http</code>	
<code>origin-server</code>	A back-end server to which Oracle Traffic Director forwards requests that it receives from clients, and from which it receives responses to client requests. The origin servers could, for example, be application servers like Oracle WebLogic Server, web servers, LDAP servers, and so on. This should be specified as a comma separated list of origin servers of the format <code>host:port</code> .	Multi-valued.

 **Note:**

You cannot invoke this command in offline mode until you have read a domain using `readDomain`. Make sure to update the domain using `updateDomain` after the command to apply the changes.

**Example****Online:**

```
# Online
props = {}
props['name'] = 'foo'
props['listener-port'] = '12345'
props['server-name'] = 'foo'
props['origin-server'] = 'vault.example.com:80'
otd_createConfiguration(props)
```

**Offline:**

```
# Offline
readDomain('/export/domains/otd_domain')
props = {}
props['name'] = 'foo'
props['listener-port'] = '12345'
props['server-name'] = 'foo'
props['origin-server'] = 'vault.example.com:80'
otd_createConfiguration(props)
updateDomain()
closeDomain()
```

**See Also**

[help](#), [otd\\_listConfigurations](#), [otd\\_deleteConfiguration](#), [otd\\_copyConfiguration](#), [otd\\_listConfigFiles](#), [otd\\_getConfigFile](#), [otd\\_saveConfigFile](#), [activate](#)

## 2.22 otd\_createContentRule

**Description**

Use this command to create a content rule.

**Syntax**

```
otd_createContentRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server for which the content rule is to be created.	Mandatory.



Property	Description	Comments
content-rule	Name of the content rule to be created. Only small letters are available. If the value contains capital letters, it will be changed to small letters without any notifications.	Mandatory. Name should be unique.
uri-prefix	URI prefix that has to be mapped to a directory.	Mandatory.
directory-path	Absolute server path and a valid directory for storing documents.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['uri-prefix'] = '/baz'
props['directory-path'] = '/qux'
props['content-rule'] = 'content-rule-1'
otd_createContentRule(props)
```

**See Also**

[help](#), [otd\\_getContentRuleProperties](#), [otd\\_listContentRules](#), [otd\\_deleteContentRule](#), [otd\\_setContentRuleProperties](#)

## 2.23 otd\_createErrorPage

**Description**

Use this command to create an error page corresponding to the specified error code.

**Syntax**

```
otd_createErrorPage(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
code	Error code for which you want to create an error page. Range of values: 400 - 599.	Mandatory.
error-page	Absolute path for which an error page is to be created.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
```

```

props['virtual-server'] = 'bar'
props['code'] = '408'
props['error-page'] = '/documents/otd'
otd_createErrorPage(props)

```

**See Also**

[help](#), [otd\\_deleteErrorPage](#), [otd\\_listErrorPages](#)

## 2.24 otd\_createEvent

**Description**

Use this command to create an event.

**Syntax**

```
otd_createEvent(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration for which the event is to be created.	Mandatory.
event	Name that uniquely identifies the event. Name can consist of one or more characters. Whitespace is not permitted.	Mandatory.
command	The command that the event executes. Range of values: the value can be restart, reconfig, rotate-log, rotate-access-log, and update-crl, or any executable command.	Mandatory.
time	Time, for example, 12:30, when this event is to be started. Range of values: the format of the time is hh:mm.	
month	Month at which this event should occur. Range of values: 1-12.	
day-of-month	Day of the month at which this event should occur. Range of values: 1-31.	
day-of-week	Day of the week at which this event should occur. Range of values: Sun, Mon, Tue, Wed, Thu, Fri, or Sat.	
interval	Time interval at which this event should occur. Range of values: an interval in seconds between 60 (1 minute) and 86400 (1 day), inclusive.	
enabled	Whether the event is enabled at runtime. Range of values: true or false. Default: true.	

**Example**

```

props = {}
props['configuration'] = 'foo'
props['event'] = 'event-1'
props['command'] = 'rotate-log'

```

```
props['time'] = '12:00'
otd_createEvent(props)
```

### See Also

[help](#), [otd\\_deleteEvent](#), [otd\\_listEvents](#), [otd\\_getEventProperties](#), [otd\\_setEventProperties](#)

## 2.25 otd\_createEventSubscription

### Description

Use this command to create an event subscription.

### Syntax

```
otd_createEventSubscription(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration for which the event subscription is to be created.	Mandatory.
event-subscription	User defined name for the event subscription.	Mandatory.
URL	Specifies the subscription URL. If this is configured, Oracle Traffic Director publishes the notification to this URL. Range of values: A valid HTTP URL.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['event-subscription'] = 'bar'
props['url'] = 'http://example.com:7777/subscriber'
otd_createEventSubscription(props)
```

### See Also

[help](#), [otd\\_deleteEventSubscription](#), [otd\\_getEventSubscriptionProperties](#), [otd\\_setEventSubscriptionProperties](#), [otd\\_listEventSubscriptions](#)

## 2.26 otd\_createFailoverGroup

### Description

Use this command to create a failover group consisting of two Oracle Traffic Director instances grouped by a unique virtual IP address (VIP), to provide high availability in active-passive mode. Requests are received at the specified VIP address and routed to the Oracle Traffic Director instance that is designated as the primary instance. If the primary instance is not reachable, requests are routed to the backup instance.

After creating the failover group, add the failover instance using the `otd_addFailoverInstance` command.

There can be a maximum of 255 failover groups, across configurations.

When creating a failover group, if the administration node process is running as `non-root` on the node where the instances are located, then you must run `otd_startFailover` on those nodes as a `root` user. This is to manually start the failover. If this command is not executed, failover is not started and there will be no high availability.

For information about how failover works in Oracle Traffic Director, see *Administering Oracle Traffic Director*.

### Syntax

```
otd_createFailoverGroup(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration for which the failover group is to be created.	Mandatory.
<code>virtual-ip</code>	The VIP for which we are creating a failover for. The VIP should belong to the same subnet as that of the nodes in the failover group, and must be accessible to clients. Range of values: host name or an IPv4/IPv6 address.	Mandatory.
<code>primary-instance</code>	An existing instance which is designated as the primary.	Mandatory.
<code>backup-instance</code>	An existing instance which is designated as the backup.	Mandatory.
<code>primary-nic</code>	A network interface, on the node where <code>primary-instance</code> is running, upon which the VIP must be managed.	Mandatory.
<code>backup-nic</code>	A network interface, on the node where <code>backup-instance</code> is running, upon which the VIP must be managed.	Mandatory.
<code>router-id</code>	A VRRP necessity, identifies the VRRP router group that are participating in failover for a VIP. The value should be unique across failover groups. If not specified, the default <code>router-id</code> will be a random number between 1 - 255. Range of values: positive integer, valid range is 1-255. Default: random number between 1 - 255	
<code>type</code>	Failover group type. Values: Active-passive, Active-active. Default value: Active-passive. Note: This property is valid on a Linux platform only.	

### Example

#### Creating an active-passive failover group

```
props = {}
props['configuration'] = 'ha'
props['virtual-ip'] = '192.0.2.1'
props['primary-instance'] = '1.example.com'
props['backup-instance'] = '2.example.com'
props['primary-nic'] = 'eth0'
```

```
props['backup-nic'] = 'eth0'
otd_createFailoverGroup(props)
```

### Creating an active-active failover group

```
props = {}
props['configuration'] = 'ha'
props['virtual-ip'] = '192.0.2.1'
props['failover-type'] = 'active-active'
otd_createFailoverGroup(props)
```

### See Also

[help](#), [otd\\_deleteFailoverGroup](#), [otd\\_getFailoverGroupProperties](#), [otd\\_toggleFailoverGroupPrimary](#), [otd\\_startFailover](#), [otd\\_stopFailover](#)

## 2.27 otd\_createHttpListener

### Description

Use this command to create a new HTTP listener socket with a set of initial values. All virtual servers have an HTTP listener specified. When a new request comes in, Oracle Fusion Middleware determines which virtual server to send it to, based on the configured HTTP listener.

### Syntax

```
otd_createHttpListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>http-listener</code>	Name that uniquely identifies the HTTP listener. Name can consist of one or more characters. Whitespace is not permitted.	Mandatory.
<code>port</code>	Port on which to listen. Range of values: port number between 1 and 65535, inclusive.	Mandatory.
<code>server-name</code>	Default server name. May include a scheme (for example, <code>http://</code> ) prefix and port (for example, <code>:80</code> ) suffix. Can be a hostname, fully qualified domain name, IP address, or a URL prefix that contains one. The URL prefix must not specify a path.	Mandatory.
<code>default-virtual-server-name</code>	Name of the virtual server that processes requests that did not match a host.	Mandatory.
<code>enabled</code>	Whether the listener is enabled at runtime. Range of values: true or false. Default: true.	
<code>ip</code>	IP address on which to listen. Range of values: *, a hostname, or an IP address.	

Property	Description	Comments
acceptor-threads	Number of threads dedicated to accepting connections received by this listener. Range of values: 1 - 128. Default: auto-tuned.	
blocking-io	Whether the server uses blocking IO. Range of values: true or false. Default: false.	
blocking-accept	Enables/Disables blocking of the server Listen Socket while retaining client end points as non blocking (useful when MaxProcs > 1). Range of values: true or false. Default: false.	
handle-protocol-mismatch	Range of values: true or false. Default: true.	
family	The socket family used to connect to the origin server. Range of values: default, inet, inet6, or inet-sdp Default: auto-tuned.	
listen-queue-size	Maximum size of the operating system listen queue backlog. Range of values: 1 - 1048576. Default: 128.	
receive-buffer-size	Size (in bytes) of the operating system socket receive buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	
send-buffer-size	Size (in bytes) of the operating system socket send buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	
max-requests-per-connection	Maximum number of keep-alive requests that will be handled per HTTP connection after which the keep-alive connection will be closed. 0 indicates no limit. Range of values: any positive Integer Default: 0.	
description	Description of the HTTP listener for the administrator's reference.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
props['port'] = '23456'
props['server-name'] = 'example.com'
props['default-virtual-server-name'] = 'bar'
otd_createHttpListener(props)
```

### See Also

[help](#), [otd\\_setHttpListenerProperties](#), [otd\\_listHttpListeners](#), [otd\\_deleteHttpListener](#)

## 2.28 otd\_createInstance

### Description

Use this command to create an instance of this configuration on the specified machine. Instance refers to the environment of an Oracle Fusion Middleware daemon, including its configuration, log files, and other runtime artifacts such as lock databases, caches, and temporary files.

### Syntax

```
otd_createInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>machine-name</code>	Name specified while creating the machine in the Oracle WebLogic Server console corresponding to the host name of the machine on which the Oracle Traffic Director instance is running.	Mandatory.

### Note:

When this command is executed in offline mode, the instance file artifacts are created only if the machine specified is on the same host as that of the admin server. Otherwise, the instance file artifacts will get created after the start of both admin server and node manager.

### Example

```
# Online
props = {}
props['configuration'] = 'foo'
props['machine-name'] = 'machine1'
otd_createInstance(props)

# Offline
readDomain('/export/domains/otd_domain')
props = {}
props['configuration'] = 'foo'
props['machine-name'] = 'machine1'
otd_createInstance(props)
updateDomain()
closeDomain()
```

### See Also

[help](#), [otd\\_deleteInstance](#), [otd\\_listInstances](#), [start](#), [stop](#), [softRestart](#)

## 2.29 otd\_createMimeType

### Description

Use this command to create a MIME type.

### Syntax

```
otd_createMimeType(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>content-type</code>	The content type of the MIME types.	Mandatory.
<code>extensions</code>	The file extension for the MIME value.	Mandatory. To define multiple file extensions, separate them by a comma (,)

### Example

```

props = {}
props['configuration'] = 'foo'
props['content-type'] = 'bar'
props['extensions'] = 'baz'
otd_createMimeType(props)

```

### See Also

[help](#), [otd\\_deleteMimeType](#), [otd\\_listMimeType](#)

## 2.30 otd\_createOriginServer

### Description

Use this command to create a origin pool server with a set of initial values to the existing origin server pool. The origin server defines a member of a server pool.

### Syntax

```
otd_createOriginServer(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.



Property	Description	Comments
origin-server-pool	Name of the origin server pool.	Mandatory.
host	IP address/Host name of this origin server. Range of values: hostname or IP address.	Mandatory.
port	Port number of this origin server. Range of values: port number between 1 and 65535, inclusive.	Mandatory.
weight	Load distribution weight for this origin server. Range of values: 1 - 1000. Default: 1	
backup	The parameter specifies if the origin server is a backup server. Range of values: true or false. Default: false.	
max-connections	The maximum number of concurrent connections to a server. Range of values: 0 - 20480. Default: 0.	
ramp-up-time	The time in seconds to ramp the sending rate up to the capacity of a newly up origin server. If the parameter is not specified, request rate accelerating will not be activated for the server. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 0.001.	

**Example**

```

props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['host'] = 'www.example.com'
props['port'] = '12345'
otd_createOriginServer(props)

```

**See Also**

[help](#), [otd\\_deleteOriginServer](#), [otd\\_listOriginServers](#), [otd\\_getOriginServerProperties](#), [otd\\_setOriginServerProperties](#)

## 2.31 otd\_createOriginServerPool

**Description**

Use this command to create a origin-server pool. The origin-server pool configures a pool of origin servers that are used for load balancing requests.

**Syntax**

```
otd_createOriginServerPool(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name by which this server pool is referenced. Name can consist of one or more characters, whitespace is not permitted.	Mandatory.
<code>origin-server</code>	Represents an origin server that belongs to this server pool. Multiple comma separated values can be specified.	Multi-valued.
<code>type</code>	Specifies the type of (requests handled by) every server in this server pool. Range of values: tcp, http, or https. Default: http.	
<code>family</code>	The socket family used to connect to servers in this pool. Range of values: default, inet, inet6, or inet-sdp. Default: auto-tuned.	
<code>load-distribution</code>	Algorithm that is used for load distribution of this server pool. Range of values: round-robin, least-connection-count, or least-response-time. Default: round-robin.	
<code>proxy-server</code>	Name of the proxy-server in the form of host:port.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['origin-server'] = 'www.example.com:12345'
otd_createOriginServerPool(props)
```

### See Also

[help](#), [otd\\_setOriginServerPoolProperties](#), [otd\\_getOriginServerPoolProperties](#), [otd\\_deleteOriginServerPool](#), [otd\\_listOriginServerPools](#)

## 2.32 otd\_createRequestLimit

### Description

Use this command to create a request limit rule with a set of initial values.

### Syntax

```
otd_createRequestLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
request-limit	Name of the request limit rule. Only small letters are available. If the value contains capital letters, it will be changed to small letters without any notifications.	Mandatory.
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	
max-rps	Maximum number of requests that the virtual server can receive per second.	
max-connections	Maximum number of concurrent matching connections.	
monitor-attribute	Request attribute to monitor.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['request-limit'] = 'request-limit-1'
props['max-connections'] = '2048'
otd_createRequestLimit(props)
```

**See Also**

[help](#), [otd\\_deleteRequestLimit](#), [otd\\_listRequestLimits](#), [otd\\_getRequestLimitProperties](#), [otd\\_setRequestLimitProperties](#)

## 2.33 otd\_createRoute

**Description**

Use this command to create a route with a set of initial values. Based on the condition specified while creating a route, the load balancing requests are routed to the specified origin-server pool. A default route is created when a virtual-server is created.

**Syntax**

```
otd_createRoute(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

Property	Description	Comments
route	Name of the route to be created. Only small letters are available. If the value contains capital letters, it will be changed to small letters without any notifications.	Mandatory.
origin-server-pool	Name of the origin server pool to which the load balancing requests must be routed.	Mandatory.
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	condition cannot be specified if uri-prefix is specified.
uri-prefix	A uri-prefix is a URI path with wildcard patterns. If a request URI matches with the uri-prefix then the rule will be executed.	uri-prefix can not be specified if condition is specified.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_createRoute(props)
```

### See Also

[help](#), [otd\\_deleteRoute](#), [otd\\_listRoutes](#), [otd\\_getRouteProperties](#), [otd\\_setRouteProperties](#)

## 2.34 otd\_createService

### Description

This command creates operating system service for the specified instance. This command should be executed as a privileged user on the machine on which the instance exists. By default, the name of the service would be the instance's name. If there exists a service already with the instance name, the service name will be suffixed with hash of instance-home. By default the service will be run as the user who owns the instance. The service can be run as a different user by modifying {SERVICE\_USER} variable in /etc/init.d/<instance\_name>

The service will not be created if an existing service is found for an instance.

### Syntax

```
otd_createService(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the directory that contains Oracle Traffic Director domain	Mandatory.

Property	Description	Comments
instance	Name of the Oracle Traffic Director instance.	Mandatory.

**Example**

```
props = {}
props['domain-home'] = '/export/domains/otd_domain'
props['instance'] = 'otd_foo_machine1'
otd_createService(props)
```

By default the service will not be restarted on machine's restart. This can be changed by the user by executing the following command manually.

```
$ chkconfig <service-name> on <run levels>
```

**See Also**

[otd\\_deleteService](#), [otd\\_listServices](#)

## 2.35 otd\_createStandaloneDomain

**Description**

Use this command to create an Oracle Traffic Director standalone domain at the given location.

This command can only be run in offline mode.

**Syntax**

```
otd_createStandaloneDomain(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the domain directory which should contain the Oracle Traffic Director standalone domain.	Mandatory.

**Example**

```
props = {}
props['domain-home'] = '/export/domains/otd_standalone'
otd_createStandaloneDomain(props)
```

**See Also**

[help](#), [otd\\_createStandaloneInstance](#), [otd\\_deleteStandaloneInstance](#)

## 2.36 otd\_createStandaloneInstance

### Description

Use this command to create an Oracle Traffic Director instance in an Oracle Traffic Director standalone domain.

This command can only be run in offline mode.

### Syntax

```
otd_createStandaloneInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>instance</code>	Name of the instance to be created.	Mandatory.
<code>domain-home</code>	Path to the domain directory which should contain the Oracle Traffic Director standalone domain.	Mandatory.
<code>listener-port</code>	Listener port through which the server accepts requests. Range of values: port number should be an integer between 1 and 65535, both inclusive.	Mandatory.
<code>server-name</code>	Valid only if <code>origin-server-type</code> is <code>http</code> or <code>https</code> . The server name is used in any URLs that are generated automatically by the server and sent to the client. This server name should be the virtual host name or alias name if your server uses an alias. If a colon and port number are appended to the server name then that port is used in the generated URLs.	
<code>ip</code>	The server will bind to this Internet Protocol (IP) address for the default listener. Only traffic sent to this IP address will be serviced. * indicates that the server will listen on all IP addresses. Range of values: *, a hostname, or an IPV4/IPV6 address.	
<code>origin-server-type</code>	Type of requests handled by the origin servers. Range of values: <code>http/https/tcp</code> . Default: <code>http</code> .	
<code>origin-server</code>	A back-end server to which Oracle Traffic Director forwards requests that it receives from clients, and from which it receives responses to client requests. The origin servers could, for example, be application servers like Oracle WebLogic Server, web servers, LDAP servers, and so on. Specified as a comma separated list of origin servers of the format <code>host:port</code> .	

### Example

```
props = {}
props['name'] = 'foo'
props['domain-home'] = '/export/domains/otd_standalone'
props['listener-port'] = '12345'
```

```
props['server-name'] = 'foo.bar'
otd_createStandaloneInstance(props)
```

### See Also

[help](#), [otd\\_createStandaloneDomain](#), [otd\\_deleteStandaloneInstance](#)

## 2.37 otd\_createTcpListener

### Description

Use this command to create a new TCP listener with a set of initial values. When a new request comes in, Oracle Traffic Director determines which TCP proxy to send it to, based on the configured TCP listener.

### Syntax

```
otd_createTcpListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>tcp-listener</code>	Name that uniquely identifies the listener. Name can consist of one or more characters. Whitespace is not permitted.	Mandatory.
<code>port</code>	Port on which to listen. Range of values: port number between 1 and 65535, inclusive.	Mandatory.
<code>tcp-proxy-name</code>	Name that identifies the exposed TCP service.	Mandatory.
<code>enabled</code>	Whether the instance is enabled. Range of values: true or false. Default: true.	
<code>ip</code>	IP address on which to listen. Range of values: hostname, or an IP address.	
<code>acceptor-threads</code>	Acceptor threads for this listening end point. Range of values: 1 - 128. Default: auto-tuned.	
<code>blocking-accept</code>	Enables/Disables blocking of the server Listen Socket while retaining client end points as non blocking (useful when <code>MaxProcs &gt; 1</code> ). Range of values: true or false. Default: false.	
<code>description</code>	Description of the TCP listener for the administrator's reference.	
<code>family</code>	Protocol family. Range of values: default, inet, inet6, or inet-sdp. Default: auto-tuned.	

Property	Description	Comments
listen-queue-size	Maximum size of the operating system listen queue backlog. Range of values: 1 - 1048576. Default: 128.	
receive-buffer-size	Size (in bytes) of the operating system socket receive buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	
send-buffer-size	Size (in bytes) of the operating system socket send buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
props['port'] = '34567'
props['tcp-proxy-name'] = 'tcp-proxy-1'
otd_createTcpListener(props)
```

### See Also

[help](#), [otd\\_deleteTcpListener](#), [otd\\_listTcpListeners](#), [otd\\_getTcpListenerProperties](#), [otd\\_setTcpListenerProperties](#)

## 2.38 otd\_createTcpProxy

### Description

Use this command to create a new TCP proxy with a set of initial values. A TCP proxy handles TCP requests through TCP listeners for traffic tunnelling to the listed origin servers. A TCP proxy can have several TCP listeners associated with it.

You can enable FTP support for a TCP proxy. This will enable the TCP proxy along with the TCP listeners referring to it to be used to front-end an FTP server.

### Syntax

```
otd_createTcpProxy(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-proxy	Name that uniquely identifies the exposed TCP service.	Mandatory.
origin-server-pool	Name of an existing server pool that provides the TCP service.	Mandatory.



Property	Description	Comments
enabled	Whether the TCP service is enabled. Range of values: true or false. Default: true.	
session-idle-timeout	Maximum timeout in seconds for load balancer to wait for receiving/sending data in the session. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive.	
protocol	If the protocol is 'ftp', the TCP proxy would have additional ftp properties that can be set/get using otd_setTcpProxyProperties/otd_getTcpProxyProperties. Range of values: *, ftp. Default value: *.	

When `otd_createTcpProxy` is executed with `protocol` as FTP, the FTP configuration is enabled for the TCP proxy with properties `ssl-termination`, `origin-explicit-fts` and `client-explicit-fts` as false, true and true respectively.

#### Example

```
props = {}
props['configuration'] = 'foo'
props['tcp-proxy'] = 'bar'
props['protocol'] = 'ftp'
props['origin-server-pool-name'] = 'tcp-origin-server-pool-1'
otd_createTcpProxy(props)
```

#### See Also

[help](#), [otd\\_deleteTcpProxy](#), [otd\\_listTcpProxies](#), [otd\\_getTcpProxyProperties](#), [otd\\_setTcpProxyProperties](#)

## 2.39 otd\_createConfigurationVariable

#### Description

Use this command to define a variable for use in expressions, log formats, and `obj.conf` parameters.

#### Syntax

```
otd_createConfigurationVariable(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
name	Variable name consisting of letters, numbers, and underscores. Variable names must not begin with a number.	Mandatory.

Property	Description	Comments
value	Value corresponding to a variable name.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['name'] = 'bar'
props['value'] = 'baz'
otd_createConfigurationVariable(props)
```

**See Also**

[help](#), [otd\\_deleteConfigurationVariable](#) , [otd\\_listVirtualServerVariables](#)

## 2.40 otd\_createVirtualServer

**Description**

Use this command to create a new virtual server with initial values defined.

**Syntax**

```
otd_createVirtualServer(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name that uniquely identifies the virtual server. Name can consist of one or more characters. Whitespace is not permitted.	Mandatory.
origin-server-pool	Name of the origin server pool for which a virtual-server is to be created.	Mandatory.
canonical-server-name	Canonical hostname of the virtual server (requests using a different hostname will be redirected to this hostname). Can be a Hostname, fully qualified domain name, IP address, or a URL prefix that contains one. The URL prefix must not specify a path.	
log-file	Log file for the virtual server.	
http-listener	Name of an HTTP listener associated with one or more of the virtual server's host hostnames. Multiple comma separated values can be specified.	Multi-valued.
host	Hostname of the virtual server services. Multiple comma separated values can be specified where each value can be a wildcard pattern that matches one or more hostnames.	Multi-valued. Mandatory if <code>http-listener</code> is set.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_createVirtualServer(props)
```

**See Also**

[help](#), [otd\\_setVirtualServerProperties](#), [otd\\_deleteVirtualServer](#),  
[otd\\_getVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#)

## 2.41 otd\_createVirtualServerVariable

**Description**

Use this command to create a variable at the virtual server level. You can use the variable in expressions, log formats, and `obj.conf` parameters.

**Syntax**

```
otd_createVirtualServerVariable(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server for which the variable is to be created.	Mandatory.
name	Variable name consisting of letters, numbers, and underscores. Variable names must not begin with a number.	Mandatory.
value	Value corresponding to the variable.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['name'] = 'baz'
props['value'] = 'qux'
otd_createVirtualServerVariable(props)
```

**See Also**

[help](#), [otd\\_deleteConfigurationVariable](#) , [otd\\_listVirtualServerVariables](#)

## 2.42 otd\_deleteCacheRule

### Description

Use this command to delete the cache rule with the specified name.

### Syntax

```
otd_deleteCacheRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>cache-rule</code>	Name of the cache rule to be deleted.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['cache-rule'] = 'cache-rule-1'
otd_deleteCacheRule(props)

```

### See Also

[help](#), [otd\\_createCacheRule](#), [otd\\_listCacheRules](#)

## 2.43 otd\_deleteCompressionRule

### Description

Use this command to delete the compression rule with the specified name.

### Syntax

```
otd_deleteCompressionRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>compression-rule</code>	Name of the compression rule to be deleted.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['compression-rule'] = 'compression-rule-1'
otd_deleteCompressionRule(props)

```

**See Also**

[help](#), [otd\\_createCompressionRule](#), [otd\\_getCompressionRuleProperties](#), [otd\\_listCompressionRules](#), [otd\\_setCompressionRuleProperties](#)

## 2.44 otd\_deleteConfigFile

**Description**

Use this command to delete an existing configuration file.

**Syntax**

```
otd_deleteConfigFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
config-file	Name of the configuration file to be deleted. This can be any existing configuration file except <code>server.xml</code> and object-files referred by virtual servers.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['config-file'] = 'bar.conf'
otd_deleteConfigFile(props)

```

**See Also**

[help](#), [otd\\_createConfiguration](#), [otd\\_listConfigurations](#), [activate](#), [otd\\_copyConfiguration](#), [otd\\_saveConfigFile](#), [otd\\_deleteConfiguration](#)

## 2.45 otd\_deleteConfiguration

**Description**

Use this command to delete the configuration if it does not have any instances associated with it.

**Syntax**

```
otd_deleteConfiguration(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>name</code>	Name of the configuration to be deleted.	Mandatory.
<code>domain-home</code>	Path to the directory which contains an Oracle Traffic Director domain.	Mandatory for Offline, not valid for Online.

### Example

```
# Online
props = {}
props['name'] = 'foo'
otd_deleteConfiguration(props)

# Offline
readDomain('/export/domains/otd_domain')
props = {}
props['name'] = 'foo'
otd_deleteConfiguration(props)
updateDomain()
closeDomain()
```

### See Also

[help](#), [otd\\_createConfiguration](#), [otd\\_listConfigurations](#), [activate](#), [otd\\_copyConfiguration](#), [otd\\_saveConfigFile](#), [otd\\_getConfigFile](#)

## 2.46 otd\_deleteConfigurationWebappFirewallRulesetFile

### Description

Use this command to delete a ruleset file for a web application firewall installed at the configuration level.

### Syntax

```
otd_deleteConfigurationWebappFirewallRulesetFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>ruleset-file</code>	Name of the ruleset file that needs to be deleted.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['ruleset-file'] = 'bar.conf'
otd_deleteConfigurationWebappFirewallRulesetFile(props)
```

**See Also**

[help](#), [otd\\_installVirtualServerWebappFirewallRulesetFile](#),  
[otd\\_listVirtualServerWebappFirewallRulesetFiles](#)

## 2.47 otd\_deleteContentRule

**Description**

Use this command to delete a content rule.

**Syntax**

```
otd_deleteContentRule(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
content-rule	Name of the content rule to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['content-rule'] = 'content-rule-1'
otd_deleteContentRule(props)
```

**See Also**

[help](#), [otd\\_getContentRuleProperties](#), [otd\\_listContentRules](#), [otd\\_createContentRule](#) ,  
[otd\\_setContentRuleProperties](#)

## 2.48 otd\_deleteCrl

**Description**

Use this command to delete a certificate revocation list (CRL).

**Syntax**

```
otd_deleteCrl(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
issuer	Name of the CRL issuer.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['issuer'] = 'CN=GlobalSign ServerSign CA,OU=ServerSign CA,O=GlobalSign nv-sa,C=BE'
otd_deleteCrl(props)
```

**See Also**

[help](#), [otd\\_installCrl](#), [otd\\_listCrls](#)

## 2.49 otd\_deleteErrorPage

**Description**

Use this command to delete the error page corresponding to the specified error code.

**Syntax**

```
otd_deleteErrorPage(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
code	Error code for which the error page is to be deleted. Range of values: 400 - 599.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['code'] = '408'
otd_deleteErrorPage(props)
```

**See Also**

[help](#), [otd\\_createErrorPage](#), [otd\\_listErrorPages](#)



## 2.50 otd\_deleteEvent

### Description

Use this command to delete a scheduled event.

### Syntax

```
otd_deleteEvent(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>event</code>	Name that uniquely identifies the event.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['event'] = 'event-1'
otd_deleteEvent(props)
```

### See Also

[help](#), [otd\\_createEvent](#), [otd\\_listEvents](#), [otd\\_getEventProperties](#), [otd\\_setEventProperties](#)

## 2.51 otd\_deleteEventSubscription

### Description

Use this command to delete an event subscription.

### Syntax

```
otd_deleteEventSubscription(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>event-subscription</code>	User defined name for the event subscription.	Mandatory.

### Example 2-2 Example

```
props = {}
props['configuration'] = 'foo'
```

```
props['event-subscription'] = 'bar'
otd_deleteEventSubscription(props)
```

## 2.52 otd\_deleteFailoverGroup

### Description

Use this command to delete the specified failover group. To change the VIP or any property of a failover group, you should delete the failover group and create it afresh.

When deleting a failover group, if the administration node process is running as non-root on the node where the instances are located and if at least one failover group is still available, then you must run [otd\\_startFailover](#) on those nodes as a root user. This is to manually restart the failover. On the other hand, after deleting a failover group, if no other failover groups are available for the corresponding instances, then [otd\\_stopFailover](#) must be executed to stop the failover. If you do not execute either [otd\\_startFailover](#) or [otd\\_stopFailover](#), then the VIP associated with the deleted failover group will continue to be available.

### Syntax

```
otd_deleteFailoverGroup(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-ip	The VIP for the failover group to be deleted.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-ip'] = '10.128.10.10'
otd_deleteFailoverGroup(props)
```

### See Also

[help](#), [otd\\_createFailoverGroup](#), [otd\\_toggleFailoverGroupPrimary](#), [otd\\_getFailoverGroupProperties](#), [otd\\_startFailover](#), [otd\\_stopFailover](#)

## 2.53 otd\_deleteHttpListener

### Description

Use this command to delete an HTTP listener socket with the specified name.

### Syntax

```
otd_deleteHttpListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
http-listener	Name of the HTTP listener to be deleted.	Mandatory.
force	Enables the forced deletion of the HTTP listener. Default: false.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
otd_deleteHttpListener(props)
```

**See Also**

[help](#), [otd\\_createHttpListener](#), [otd\\_setHttpListenerProperties](#),  
[otd\\_setHttpListenerProperties](#), [otd\\_listHttpListeners](#)

## 2.54 otd\_deleteInstance

**Description**

Use this command to delete the specified instance.

**Syntax**

```
otd_deleteInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration to which the instance belongs to.	Mandatory.
instance	Name of the instance to be deleted.	Mandatory.

**Note:**

When this command is executed in offline mode, the instance file artifacts are deleted only if the machine specified is on the same host as that of the admin server. Otherwise, the instance file artifacts will get deleted after the start of both admin server and node manager.

**Example**

```
# Online
props = {}
```

```

props['configuration'] = 'foo'
props['instance'] = 'otd_foo_machine1'
otd_deleteInstance(props)

# Offline
readDomain('/export/.../domains/otd_domain')
props = {}
props['configuration'] = 'foo'
props['instance'] = 'otd_foo_machine1'
otd_deleteInstance(props)
updateDomain()
closeDomain()

```

**See Also**

[help](#), [otd\\_createInstance](#), [otd\\_listInstances](#), [start](#), [stop](#), [softRestart](#)

## 2.55 otd\_deleteMimeType

**Description**

Use this command to delete a MIME type.

**Syntax**

```
otd_deleteMimeType(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
content-type	The content type of the MIME types.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['content-type'] = 'bar'
otd_deleteMimeType(props)

```

**See Also**

[help](#), [otd\\_createMimeType](#), [otd\\_listMimeType](#)

## 2.56 otd\_deleteOriginServer

**Description**

Use this command to delete an origin server with the specified host and port.

**Syntax**

```
otd_deleteOriginServer(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name of the origin server pool.	Mandatory.
<code>host</code>	IP address/Host name of the origin server to be deleted.	Mandatory.
<code>port</code>	Port number of the origin server to be deleted.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['host'] = 'www.example.com'
props['port'] = '12345'
otd_deleteOriginServer(props)
```

### See Also

[help](#), [otd\\_deleteOriginServer](#), [otd\\_listOriginServers](#), [otd\\_getOriginServerProperties](#), [otd\\_setOriginServerProperties](#)

## 2.57 otd\_deleteOriginServerPool

### Description

Use this command to delete the origin-server pool with the specified name.

### Syntax

```
otd_deleteOriginServerPool(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name of the origin server pool to be deleted.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_deleteOriginServerPool(props)
```

**See Also**

[help](#), [otd\\_listOriginServerPools](#), [otd\\_deleteOriginServerPool](#),  
[otd\\_getOriginServerPoolProperties](#), [otd\\_setOriginServerPoolProperties](#)

## 2.58 otd\_deleteRequestLimit

**Description**

Use this command to delete the request limit with the specified name.

**Syntax**

```
otd_deleteRequestLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
request-limit	Name of the request limit rule.	Mandatory.

**Example**

```
props = {}  
props['configuration'] = 'foo'  
props['virtual-server'] = 'bar'  
props['request-limit'] = 'request-limit-1'  
otd_deleteRequestLimit(props)
```

**See Also**

[help](#), [otd\\_createRequestLimit](#), [otd\\_listRequestLimits](#), [otd\\_getRequestLimitProperties](#),  
[otd\\_setRequestLimitProperties](#)

## 2.59 otd\_deleteRoute

**Description**

Use this command to delete the route with the specified name.

**Syntax**

```
otd_deleteRoute(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
otd_deleteRoute(props)
```

**See Also**

[help](#), [otd\\_createRoute](#), [otd\\_listRoutes](#), [otd\\_getRouteProperties](#), [otd\\_setRouteProperties](#)

## 2.60 otd\_deleteService

**Description**

This command removes the operating system service for the specified instance if it exists. This command should be executed as a privileged user on the machine on which the instance exists.

**Syntax**

```
otd_deleteService(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the directory that contains Oracle Traffic Director domain.	Mandatory.
instance	Name of the Oracle Traffic Director instance.	Mandatory.

**Example 2-3 Example Title**

```
props = {}
props['domain-home'] = '/export/domains/otd_domain'
props['instance'] = 'otd_foo_machine1'
otd_deleteService(props)
```

**See Also**

[otd\\_createService](#), [otd\\_listServices](#)

## 2.61 otd\_deleteStandaloneInstance

### Description

Use this command to delete an Oracle Traffic Director instance with the specified name in an Oracle Traffic Director standalone domain.

This command can only be run in offline mode.

### Syntax

```
otd_deleteStandaloneInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
instance	Name of the instance to be deleted.	Mandatory.
domain-home	Path to the domain directory which should contain the Oracle Traffic Director standalone domain.	Mandatory.

### Example

```

props = {}
props['instance'] = 'foo'
props['domain-home'] = '/export/domains/otd_standalone'
otd_deleteStandaloneInstance(props)

```

### See Also

[help](#), [otd\\_createStandaloneDomain](#), [otd\\_createStandaloneInstance](#)

## 2.62 otd\_deleteTcpListener

### Description

Use this command to delete the TCP listener with the specified name.

### Syntax

```
otd_deleteTcpListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-listener	Name of the TCP listener to be deleted.	Mandatory.



**Example**

```
props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
otd_deleteTcpListener(props)
```

**See Also**

[help](#), [otd\\_createTcpListener](#), [otd\\_listTcpListeners](#), [otd\\_getTcpListenerProperties](#), [otd\\_setTcpListenerProperties](#)

## 2.63 otd\_deleteTcpProxy

**Description**

Use this command to delete the TCP proxy with the specified name.

**Syntax**

```
otd_deleteTcpProxy(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-proxy	Name of the TCP proxy to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['tcp-proxy'] = 'bar'
otd_deleteTcpProxy(props)
```

**See Also**

[help](#), [otd\\_createTcpProxy](#), [otd\\_listTcpProxies](#), [otd\\_getTcpProxyProperties](#), [otd\\_setTcpProxyProperties](#)

## 2.64 otd\_deleteConfigurationVariable

**Description**

Use this command to delete a variable defined at the configuration level.

**Syntax**

```
otd_deleteConfigurationVariable(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
name	Name of the variable to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['name'] = 'bar'
otd_deleteConfigurationVariable(props)
```

**See Also**

[help](#), [otd\\_createConfigurationVariable](#) , [otd\\_listVirtualServerVariables](#)

## 2.65 otd\_deleteVirtualServer

**Description**

Use this command to delete the virtual server with the specified name.

**Syntax**

```
otd_deleteVirtualServer(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_deleteVirtualServer(props)
```

**See Also**

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#),  
[otd\\_getVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#)

## 2.66 otd\_deleteVirtualServerVariable

### Description

Use this command to delete the variable with the specified name defined at the virtual server level.

### Syntax

```
otd_deleteVirtualServerVariable(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
name	Name of the variable to be deleted.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['name'] = 'baz'
otd_deleteVirtualServerVariable(props)
```

### See Also

[help](#), [otd\\_createConfigurationVariable](#), [otd\\_listVirtualServerVariables](#)

## 2.67 otd\_deleteVirtualServerWebappFirewallRulesetFile

### Description

Use this command to delete a ruleset file for a web application firewall installed at the virtual server level.

### Syntax

```
otd_deleteVirtualServerWebappFirewallRulesetFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

Property	Description	Comments
ruleset-filename	Name of the ruleset file that needs to be deleted.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['ruleset-file'] = 'baz.conf'
otd_deleteVirtualServerWebappFirewallRulesetFile(props)
```

**See Also**

[help, otd\\_installVirtualServerWebappFirewallRulesetFile](#),  
[otd\\_listVirtualServerWebappFirewallRulesetFiles](#)

## 2.68 otd\_disableOriginServerPoolMaintenance

**Description**

Use this command to disable maintenance for the origin server pool.

**Syntax**

```
otd_disableOriginServerPoolMaintenance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_disableOriginServerPoolMaintenance(props)
```

**See Also**

[help, otd\\_enableOriginServerPoolMaintenance](#),  
[otd\\_getOriginServerPoolMaintenanceProperties](#)

## 2.69 otd\_disablePerfDump

**Description**

Use this command to disable access to `perfdump` output through a URI.

**Syntax**

```
otd_disablePerfDump(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_disablePerfDump(props)
```

**See Also**

[help](#), [otd\\_enablePerfDump](#), [otd\\_getPerfDumpProperties](#)

## 2.70 otd\_disableRequestLimitEvents

**Description**

Use this command to disable events for a specific request limit.

**Syntax**

```
otd_disableRequestLimitEvents(props)
```

The argument 'props' is a dictionary that must contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
request-limit	Name of the request-limit to be disabled.	Mandatory.

**Example 2-4 Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['request-limit'] = 'request-limit-1'
otd_disableRequestLimitEvents(props)
```

## 2.71 otd\_disableRouteAuth

### Description

Use this command to disable the route authentication.

### Syntax

```
otd_disableRouteAuth(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route'
otd_disableRouteAuth(props)

```

### See Also

[help](#), [otd\\_enableRouteAuth](#)

## 2.72 otd\_disableRouteBandwidthLimit

### Description

Use this command to disable bandwidth limiting at the route level.

### Syntax

```
otd_disableRouteBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.

Property	Description	Comments
type	Type of bandwidth limiting to be disabled. Range of values: request or response.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['type'] = 'request'
otd_disableRouteBandwidthLimit(props)
```

**See Also**

[help](#), [otd\\_enableRouteBandwidthLimit](#),  
[otd\\_getVirtualServerRequestBandwidthLimitProperties](#)

## 2.73 otd\_disableStatsXml

**Description**

Use this command to disable access to virtual server statistics in XML format through a URI.

**Syntax**

```
otd_disableStatsXml(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_disableStatsXml(props)
```

**See Also**

[help](#), [otd\\_getStatsXml](#), [otd\\_getStatsXmlProperties](#), [otd\\_enableStatsXml](#)

## 2.74 otd\_disableStatusListener

### Description

Use this command to disable Status Listener of an instance.

### Syntax

```
otd_disableStatusListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example 2-5 Example

```

props = {}
props['configuration'] = 'foo'
otd_disableStatusListener(props)

```

## 2.75 otd\_disableVirtualServerAccessLog

### Description

Use this command to disable the access log for a virtual server.

### Syntax

```
otd_disableVirtualServerAccessLog(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_disableVirtualServerAccessLog(props)

```

### See Also

[help](#), [otd\\_enableVirtualServerAccessLog](#), [otd\\_getVirtualServerAccessLogProperties](#)



## 2.76 otd\_disableWebAppFirewall

### Description

Use this command to disable the web application firewall for the virtual server.

### Syntax

```
otd_disableWebAppFirewall(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_disableWebappFirewall(props)
```

### See Also

[help](#), [otd\\_enableWebAppFirewall](#), [otd\\_getWebappFirewallProperties](#)

## 2.77 otd\_disableVirtualServerRequestBandwidthLimit

### Description

Use this command to disable request bandwidth limiting at the virtual server level.

### Syntax

```
otd_disableVirtualServerRequestBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
```

```
props['virtual-server'] = 'bar'
otd_disableVirtualServerRequestBandwidthLimit(props)
```

**See Also**

[help](#), [otd\\_enableVirtualServerRequestBandwidthLimit](#),  
[otd\\_getVirtualServerRequestBandwidthLimitProperties](#)

## 2.78 otd\_disableVirtualServerResponseBandwidthLimit

**Description**

Use this command to disable response bandwidth limiting at the virtual server level.

**Syntax**

```
otd_disableVirtualServerResponseBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_disableVirtualServerResponseBandwidthLimit(props)
```

**See Also**

[help](#), [otd\\_enableVirtualServerResponseBandwidthLimit](#),  
[otd\\_getVirtualServerRequestBandwidthLimitProperties](#)

## 2.79 otd\_enableOriginServerPoolMaintenance

**Description**

Use this command to enable the maintenance for an origin-server-pool.

**Syntax**

```
otd_enableOriginServerPoolMaintenance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

Property	Description	Comments
origin-server-pool	Name of the origin server pool.	Mandatory.
response-code	Specifies the response code of the request when it lands on a maintenance enabled origin server pool. When this is not configured, its implicit value will be 200 if response-file is specified, else it will be 503.	response-code 200 is not allowed if response-file is not configured.
response-file	Absolute path of an HTML file to send to the client when the request lands on a maintenance enabled origin server pool.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['response-code'] = '503'
otd_enableOriginServerPoolMaintenance(props)
```

**See Also**

[help](#), [otd\\_disableOriginServerPoolMaintenance](#),  
[otd\\_getOriginServerPoolMaintenanceProperties](#)

## 2.80 otd\_enablePerfDump

**Description**

Enables access to `perfdump` output through a URI. The `perfdump` utility collects the Oracle Traffic Director performance data and displays it in ASCII format. This utility allows you to monitor a greater variety of statistics. With `perfdump`, the statistics are unified. Rather than monitoring a single process, statistics are multiplied by the number of processes. This gives you a more accurate view of the server performance.

**Syntax**

```
otd_enablePerfDump(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
uri	The URI at which the <code>perfdump</code> report should be available. Default: <code>./perf</code> .	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
```

```
props['virtual-server'] = 'bar'
otd_enablePerfDump(props)
```

**See Also**

[help](#), [otd\\_getPerfDump](#), [otd\\_getPerfDumpProperties](#), [otd\\_disablePerfDump](#)

## 2.81 otd\_enableRouteAuth

**Description**

Use this command to enable the route authentication.

**Syntax**

```
otd_enableRouteAuth(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.
auth-user	Specifies the authenticated user.	Mandatory.
auth-password	Specifies the password for the user.	Mandatory.
auth-header	Specifies the name of the authentication header. Default is Authorization.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['auth-user'] = 'baz'
props['auth-password'] = 'qux'
otd_enableRouteAuth(props)
```

**See Also**

[help](#), [otd\\_disableRouteAuth](#)

## 2.82 otd\_enableRouteBandwidthLimit

**Description**

Use this command to enable bandwidth limiting at the route level.

## Syntax

```
otd_enableRouteBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server for which bandwidth limit is to be enabled.	Mandatory.
<code>route</code>	Name of the route for which bandwidth limit is to be enabled.	Mandatory.
<code>type</code>	Type of bandwidth limiting is to be applied. Range of values: request or response.	Mandatory.
<code>max-bps-per-monitor</code>	Value in bytes/sec for maximum request bandwidth for the entire bucket. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>max-bps-per-connection</code>	Value in bytes/sec for maximum request bandwidth per connection. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>timeout</code>	Value in second. Request is aborted when it had to wait in the queue for this much time. Default: 60.	
<code>monitor</code>	Name of bucket to which the request belongs to. Default: \$ip if type is "response".	
<code>error-code</code>	HTTP error code that is returned when request is aborted. Range of value: 400-599. Default: 503.	

## Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['type'] = 'request'
props['max-bps-per-monitor'] = '512'
otd_enableRouteBandwidthLimit(props)

```

## See Also

[help](#), [otd\\_disableRouteBandwidthLimit](#), [otd\\_getWebappFirewallProperties](#)

## 2.83 otd\_enableRequestLimitEvents

### Description

Use this command to enable events for a specified request limit.

**Syntax**

otd\_enableRequestLimitEvents(props)

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
request-limit	Name of the request limit to be enabled.	Mandatory.
event-notification-interval	Time interval (in seconds). A notification message will be sent to subscribers once every interval and will include information on all monitors that exceeded the request limit that was configured for them. Range: An interval in seconds between 1 and 32767, inclusive	Mandatory.

**Example 2-6 Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['request-limit'] = 'request-limit-1'
props['event-notification-interval'] = '60'
otd_enableRequestLimitEvents(props)
```

## 2.84 otd\_enableStatsXml

**Description**

Use this command to enable access to virtual server statistics in XML format through a URI.

**Syntax**

otd\_enableStatsXml(props)

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
uri	The URI at which the statistics report in XML format should be available. Default: /stats-xml.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_enableStatsXml(props)
```

**See Also**

[help](#), [otd\\_getStatsXml](#), [otd\\_getStatsXmlProperties](#), [otd\\_disableStatsXml](#)

## 2.85 otd\_enableStatusListener

**Description**

Use this command to enable listeners for status check requests. In addition, use this command to change the properties of an enabled Status Listener.

**Syntax**

```
otd_enableStatusListener(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
port	Port on which to listen. Range of values: port number 1 and 65535, inclusive.	Mandatory.
ip	IP address on which to listen. Range of values: hostname, or an IP address.	
family	Protocol family. Range of values: default, inet, or inet6. Default: default	

**Example 2-7 Example**

```
props = {}
props['configuration'] = 'foo'
props['port'] = '12345'
otd_enableStatusListener(props)
```

## 2.86 otd\_enableWebAppFirewall

**Description**

Use this command to enable the web application firewall for a specific virtual server.

**Syntax**

```
otd_enableWebAppFirewall(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_enableWebappFirewall(props)
```

### See Also

[help](#), [otd\\_disableWebAppFirewall](#), [otd\\_getWebappFirewallProperties](#)

## 2.87 otd\_enableVirtualServerAccessLog

### Description

Use this command to enable the access log for a virtual server.

### Syntax

```
otd_VirtualServerAccessLog(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>log-file</code>	Path to the file where access logs for this configuration will be stored. Default: <code>\$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/access.log</code>	
<code>format</code>	A format is a string that can be used to customize the format and the fields that are logged in the access log. Default: <code>%Ses-&gt;client.ip% - %Req-&gt;vars.auth-user% %SYSDATE% "%Req-&gt;reqpb.clf-request%" %Req-&gt;srvhdrs.clf-status% %Req-&gt;srvhdrs.content-length% %Req-&gt;vars.ecid% %Req-&gt;vars.origin-server%</code>	
<code>log-ip</code>	Whether to log the IP of the client into the access log. Range of values: true or false. Default: false.	



**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['log-file'] = 'logs/access.log'
otd_enableVirtualServerAccessLog(props)
```

**See Also**

[help](#), [otd\\_getVirtualServerAccessLogProperties](#), [otd\\_disableVirtualServerAccessLog](#)

## 2.88 otd\_enableVirtualServerRequestBandwidthLimit

**Description**

Use this command to enable request bandwidth limiting at the virtual server level.

**Syntax**

```
otd_enableVirtualServerRequestBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server for which bandwidth limit is to be enabled.	Mandatory.
<code>max-bps-per-monitor</code>	Value in bytes/sec for maximum request bandwidth for the entire bucket. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>max-bps-per-connection</code>	Value in bytes/sec for maximum request bandwidth per connection. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>timeout</code>	Value in second. Request is aborted when it had to wait in the queue for this much time. Default: 60.	
<code>monitor</code>	Name of bucket to which the request belongs to. Default: \$ip if type is "response".	
<code>error-code</code>	HTTP error code that is returned when request is aborted. Range of value: 400-599. Default: 503.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['max-bps-per-monitor'] = '1024'
otd_enableVirtualServerRequestBandwidthLimit(props)
```

**See Also**

[help](#), [otd\\_disableVirtualServerRequestBandwidthLimit](#),  
[otd\\_getWebappFirewallProperties](#)

## 2.89 [otd\\_enableVirtualServerResponseBandwidthLimit](#)

**Description**

Use this command to enable response bandwidth limiting at the virtual server level.

**Syntax**

```
otd_enableVirtualServerResponseBandwidthLimit(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server for which bandwidth limit is to be enabled.	Mandatory.
<code>max-bps-per-monitor</code>	Value in bytes/sec for maximum request bandwidth for the entire bucket. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>max-bps-per-connection</code>	Value in bytes/sec for maximum request bandwidth per connection. Default: 0.	Setting it to 0 means no bandwidth limiting is done.
<code>timeout</code>	Value in second. Request is aborted when it had to wait in the queue for this much time. Default: 60.	
<code>monitor</code>	Name of bucket to which the request belongs to. Default: \$ip if type is "response".	
<code>error-code</code>	HTTP error code that is returned when request is aborted. Range of value: 400-599. Default: 503.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['max-bps-per-monitor'] = '1024'
otd_enableVirtualServerResponseBandwidthLimit(props)
```

**See Also**

[help](#), [otd\\_disableVirtualServerRequestBandwidthLimit](#),  
[otd\\_getWebappFirewallProperties](#)

## 2.90 otd\_exportKeyStore

### Description

Use this command to export all the certificates within a keystore into an Oracle wallet which will be placed in the `config` directory of the configuration. If wallet password is set then the exported wallet is a password protected wallet (ewallet.p12), otherwise it is an auto login only wallet (cwallet.sso).

### Syntax

```
otd_exportKeyStore(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_exportKeyStore(props)
```

### See Also

[help](#), [exportKeyStoreCertificateRequest](#), [deleteKeyStoreEntry](#), [importKeyStoreCertificate](#), [getKeyStoreCertificates](#), [generateKeyPair](#)

## 2.91 otd\_forwardProxyInfo

### Description

Use this command to forward the proxy information. Information about a particular proxy parameter is generated and forwarded to the origin server using a HTTP header. Note that the HTTP header used by default is different depending on whether or not the origin server is Oracle WebLogic Server.

Parameter Name	Description	Default HTTP Header for WLS	Default HTTP Header for non-WLS
<code>jroute</code>	Information about request routing used by the <code>set-origin-server</code> function and some Servlet containers to implement session stickiness.	Proxy-jroute	Proxy-jroute
<code>via</code>	Proxy servers and protocol versions that were involved in routing a request.	Via	Via
<code>ip</code>	Client's actual IP address.	WL-proxy-client-ip	Client-ip
<code>xforwarded-for</code>	Used to keep track of the originating client IP connecting through a proxy.	X-forwarded-for	X-forwarded-for

Parameter Name	Description	Default HTTP Header for WLS	Default HTTP Header for non-WLS
proxy-agent	Proxy server product name and version.	Proxy-agent	Proxy-agent
cache-info	Client cache hits.	Cache-info	Cache-info
ssl	A value of true/false indicating whether the client connection was over SSL	WI-proxy-ssl	Proxy-ssl
cipher	Client's SSL/TLS cipher suite.	Proxy-cipher	Proxy-cipher
keysize	Client's SSL/TLS key size.	WI-Proxy-client-keysize	Proxy-keysize
secret-keysize	Size of the client's SSL/TLS secret key.	WI-proxy-client-secretkeysize	Proxy-secret-keysize
ssl-id	Client's SSL/TLS session ID.	Proxy-ssl-id	Proxy-ssl-id
auth-cert	Client's SSL/TLS certificate in X.509 format.	WI-proxy-client-cert	Proxy-auth-cert
user-dn	Distinguished name of the subject of the client's SSL/TLS certificate.	Proxy-user-dn	Proxy-user-dn
issuer-dn	Distinguished name of the issuer of the client's SSL/TLS certificate.	Proxy-issuer-dn	Proxy-issuer-dn

### Syntax

```
otd_forwardProxyInfo(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.
param	Name of the proxy parameter to be blocked. Range of values: jroute, via, ip, cipher, proxy-agent, keysize, secret-keysize, ssl-id, issuer-dn, user-dn, auth-cert, xforwarded-for, cache-info, ssl.	Mandatory.
header	Name of the HTTP header used to send the proxy parameter to the origin server. Default: the default HTTP header corresponding to the specified proxy parameter.	Mandatory.

 **Note:**

If an incoming request includes the specified header, Oracle Traffic Director will replace the header from the request that is forwarded to the origin server with the generated header.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['param'] = 'via'
otd_forwardProxyInfo(props)
```

**See Also**

[help](#), [otd\\_listProxyInfo](#), [otd\\_blockProxyInfo](#)

## 2.92 otd\_getAccessLogBufferProperties

**Description**

Use this command to view the access-log buffer properties. The properties that this command returns are described in [otd\\_setAccessLogBufferProperties](#).

**Syntax**

```
otd_getAccessLogBufferProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getAccessLogBufferProperties(props)
```

**See Also**

[help](#), [otd\\_setAccessLogBufferProperties](#), [otd\\_enableVirtualServerAccessLog](#), [otd\\_disableVirtualServerAccessLog](#), [displayLogs](#), [otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

## 2.93 otd\_getCacheProperties

### Description

Use this command to view the cache properties. The properties that this command returns are described in [otd\\_setCacheProperties](#).

### Syntax

```
otd_getCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_getCacheProperties(props)
```

### See Also

[help](#), [otd\\_setCacheProperties](#)

## 2.94 otd\_getCacheRuleProperties

### Description

Use this command to view the cache rule properties. The properties that this command returns are described in [otd\\_setCacheRuleProperties](#).

### Syntax

```
otd_getCacheRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
cache-rule	Name of the cache rule.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
```

```

props['virtual-server'] = 'bar'
props['cache-rule'] = 'cache-rule-1'
otd_getCacheRuleProperties(props)

```

**See Also**

[help](#), [otd\\_setCacheProperties](#), [otd\\_setCacheRuleProperties](#)

## 2.95 otd\_getCompressionRuleProperties

**Description**

Use this command to view compression rule properties. The properties that this command returns are described in [otd\\_setCompressionRuleProperties](#).

**Syntax**

```
otd_getCompressionRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
compression-rule	Name of the compression rule.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['compression-rule'] = 'compression-rule-1'
otd_getCompressionRuleProperties(props)

```

**See Also**

[help](#), [otd\\_createCompressionRule](#), [otd\\_deleteCompressionRule](#), [otd\\_listCompressionRules](#), [otd\\_setCompressionRuleProperties](#)

## 2.96 otd\_getConfigFile

**Description**

Use this command to view the contents of a configuration file.

**Syntax**

```
otd_getConfigFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
config-file	Name of the configuration file that needs to be fetched.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['config-file'] = 'foo-obj.conf'
otd_getConfigFile(props)
```

### See Also

[help](#), [otd\\_createConfiguration](#), [otd\\_listConfigurations](#), [activate](#), [otd\\_copyConfiguration](#), [otd\\_saveConfigFile](#), [otd\\_deleteConfiguration](#)

## 2.97 otd\_getConfigurationAccessLogProperties

### Description

Use this command to view these access-log properties for a configuration:

Property	Description
file	Path to the file where access logs for this configuration will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/access.log
format	A format is a string that can be used to customize the format and the fields that are logged in the access log. Default: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%
default-access-log-format	Default format for the access log entries: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%

### Syntax

```
otd_getConfigurationAccessLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.



**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getConfigurationAccessLogProperties(props)
```

**See Also**

[help](#), [otd\\_setConfigurationAccessLogProperties](#), [displayLogs](#), [otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

## 2.98 otd\_getConfigurationCrlProperties

**Description**

Use this command to view the certificate revocation list (CRL) properties. The properties that this command returns are described in [otd\\_setConfigurationCrlProperties](#).

**Syntax**

```
otd_getConfigurationCrlProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getConfigurationCrlProperties(props)
```

**See Also**

[help](#), [otd\\_setConfigurationCrlProperties](#)

## 2.99 otd\_getConfigurationProperties

**Description**

Use this command to view the configuration properties. The properties that this command returns are described in [otd\\_setConfigurationProperties](#).

**Syntax**

```
otd_getConfigurationProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getConfigurationProperties(props)
```

**See Also**

[help](#), [otd\\_setConfigurationProperties](#)

## 2.100 otd\_getContentRuleProperties

**Description**

Use this command to view the content rule properties. The properties that this command returns are described in [otd\\_setContentRuleProperties](#).

**Syntax**

```
otd_getContentRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
content-rule	Name of the content rule.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['content-rule'] = 'content-rule-1'
otd_getContentRuleProperties(props)
```

**See Also**

[help](#), [otd\\_setContentRuleProperties](#), [otd\\_listContentRules](#)

## 2.101 otd\_getDnsCacheProperties

### Description

Use this command to view the Domain Name Server (DNS) cache properties. The properties that this command returns are described in [otd\\_setDnsCacheProperties](#).

### Syntax

```
otd_getDnsCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

### Example

```
props = {}  
props['configuration'] = 'foo'  
otd_getDnsCacheProperties(props)
```

### See Also

[help](#), [otd\\_setDnsCacheProperties](#)

## 2.102 otd\_getDnsProperties

### Description

Use this command to view the Domain Name Server (DNS) properties. DNS associates a standard IP address such as, 192.0.3.11, with host names such as, www.example.com. The properties that this command returns are described in [otd\\_setDnsProperties](#).

### Syntax

```
otd_getDnsProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

### Example

```
props = {}  
props['configuration'] = 'foo'  
otd_getDnsProperties(props)
```

**See Also**[help](#), [otd\\_setDnsProperties](#)

## 2.103 otd\_getEventProperties

**Description**

Use this command to get the event properties. The properties that this command returns are described in [otd\\_setEventProperties](#).

**Syntax**

```
otd_getEventProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
event	Name of the event.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['event'] = 'bar'
otd_getEventProperties(props)

```

**See Also**[help](#), [otd\\_deleteEvent](#), [otd\\_listEvents](#), [otd\\_setEventProperties](#)

## 2.104 otd\_getEventSubscriptionProperties

**Description**

Use this command to get the event subscription properties.

**Syntax**

```
otd_getEventSubscriptionProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
event-subscription	User defined name of the event subscription.	Mandatory.

**Example 2-8 Example**

```

props = {}
props['configuration'] = 'foo'
props['event-subscription'] = 'bar'
otd_getEventSubscriptionProperties(props)

```

## 2.105 otd\_getFileCacheProperties

**Description**

Use this command to view the file cache properties. The properties that this command returns are described in [otd\\_setFileCacheProperties](#).

**Syntax**

```
otd_getFileCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
otd_getFileCacheProperties(props)

```

**See Also**

[help](#), [otd\\_setFileCacheProperties](#)

## 2.106 otd\_getFailoverGroupProperties

**Description**

Use this command to view the following properties of a failover group:

Property	Description	Comments
virtual-ip	The VIP for which we are creating a failover for. The VIP should belong to the same subnet as that of the nodes in the failover group, and must be accessible to clients. Range of values: host name or an IPv4/IPv6 address.	Mandatory.
primary-instance	An existing instance which is designated as the primary.	Mandatory.
backup-instance	An existing instance which is designated as the backup.	Mandatory.
primary-nic	A network interface, on the node where primary-instance is running, upon which the VIP must be managed.	Mandatory.

Property	Description	Comments
backup-nic	A network interface, on the node where backup-instance is running, upon which the VIP must be managed.	Mandatory.
router-id	A VRRP necessity, identifies the VRRP router group that are participating in failover for a VIP. The value should be unique across failover groups. Range of values: positive integer, valid range is 1-255. Default: random number between 1 - 255	

This command lists the following additional property.

Property	Description	Comments
type	Failover group type.	

### Syntax

```
otd_getFailoverGroupProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration for which the failover group is to be created.	Mandatory.
virtual-ip	Virtual IP that uniquely identifies the failover group.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-ip'] = '192.0.2.1'
otd_getFailoverGroupProperties(props)
```

### See Also

[help](#), [otd\\_deleteFailoverGroup](#), [otd\\_createFailoverGroup](#),  
[otd\\_toggleFailoverGroupPrimary](#)

## 2.107 otd\_getHealthCheckProperties

### Description

Use this command to view the health-check properties. The properties that this command returns are described in [otd\\_setHealthCheckProperties](#).

### Syntax

```
otd_getHealthCheckProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_getHealthCheckProperties(props)
```

**See Also**

[help, otd\\_setHealthCheckProperties](#)

## 2.108 otd\_getHttpListenerProperties

**Description**

Use this command to view the HTTP listener properties. The properties that this command returns are described in [otd\\_setHttpListenerProperties](#).

**Syntax**

```
otd_getHttpListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
http-listener	Name of the HTTP listener.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
otd_getHttpListenerProperties(props)
```

**See Also**

[help, otd\\_createHttpListener, otd\\_setHttpListenerProperties, otd\\_listHttpListeners, otd\\_deleteHttpListener](#)

## 2.109 otd\_getHttpListenerSslProperties

### Description

Use this command to view the Secure Sockets Layer (SSL) properties for an HTTP listener. SSL is a software library establishing a secure connection between the client and server. SSL is used to implement HTTPS, the secure version of HTTP.

The properties that this command returns are described in [otd\\_setHttpListenerSslProperties](#).

### Syntax

```
otd_getHttpListenerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
http-listener	Name of the HTTP listener.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
otd_getHttpListenerSslProperties(props)

```

### See Also

[help](#), [otd\\_setHttpListenerSslProperties](#)

## 2.110 otd\_getHttpProperties

### Description

Use this command to view the HTTP properties. The properties that this command returns are described in [otd\\_setHttpProperties](#).

### Syntax

```
otd_getHttpProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.



**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getHttpProperties(props)
```

**See Also**

[help, otd\\_setHttpProperties](#)

## 2.111 otd\_getHttpThreadPoolProperties

**Description**

Use this command to view the thread-pool properties. You can use thread pools to allocate a certain number of threads to a specific service. By defining a pool with the maximum number of threads as 1, only one request is allowed to the specified service function. The properties that this command returns are described in [otd\\_setHttpThreadPoolProperties](#).

**Syntax**

```
otd_getHttpThreadPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getHttpThreadPoolProperties(props)
```

**See Also**

[help, otd\\_setHttpThreadPoolProperties](#)

## 2.112 otd\_getKeepaliveProperties

**Description**

Use this command to view the keep-alive properties. The keep-alive or HTTP/1.1 persistent connection handling subsystem in Oracle Traffic Director is designed to be scalable. If the configuration does not conform as required, the performance can be less than optimal if the workload is not persistent (that is, HTTP/1.0 without the KeepAlive header), or for a lightly loaded system that is primarily servicing keep-alive connections. The properties that this command returns are described in [otd\\_setKeepaliveProperties](#).

**Syntax**

```
otd_getKeepAliveProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getKeepaliveProperties(props)
```

**See Also**

[help](#), [otd\\_setKeepaliveProperties](#)

## 2.113 otd\_getLogProperties

**Description**

Use this command to view the log properties. The properties that this command returns are described in [otd\\_setLogProperties](#).

**Syntax**

```
otd_getLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getLogProperties(props)
```

**See Also**

[help](#), [otd\\_setLogProperties](#)

## 2.114 otd\_getOriginServerPoolMaintenanceProperties

### Description

Use this command to view the maintenance properties for the origin server pool. The properties that this command returns are described in [otd\\_enableOriginServerPoolMaintenance](#).

### Syntax

```
otd_getOriginServerPoolMaintenanceProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name of the origin server pool.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_getOriginServerPoolMaintenanceProperties(props)
```

### See Also

[help](#), [otd\\_disableOriginServerPoolMaintenance](#),  
[otd\\_enableOriginServerPoolMaintenance](#)

## 2.115 otd\_getOriginServerPoolProperties

### Description

Use this command to view the origin-server pool properties. The properties that this command returns are described in [otd\\_setOriginServerPoolProperties](#).

### Syntax

```
otd_getOriginServerPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name of the origin server pool.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_getOriginServerPoolProperties(props)
```

**See Also**

[help](#), [otd\\_createOriginServerPool](#), [otd\\_deleteOriginServerPool](#),  
[otd\\_listOriginServerPools](#), [otd\\_setOriginServerPoolProperties](#)

## 2.116 otd\_getOriginServerProperties

**Description**

Use this command to view origin server properties. The properties that this command returns are described in [otd\\_setOriginServerPoolProperties](#).

**Syntax**

```
otd_getOriginServerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.
host	IP address/host name of the origin server.	Mandatory.
port	Port number of the origin server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['host'] = 'www.example.com'
props['port'] = '12345'
otd_getOriginServerProperties(props)
```

**See Also**

[help](#), [otd\\_createOriginServer](#), [otd\\_deleteOriginServer](#), [otd\\_listOriginServers](#),  
[otd\\_setOriginServerProperties](#)

## 2.117 otd\_getOriginServerPoolSslProperties

### Description

Use this command to view the SSL properties of the origin server. The properties that this command returns are described in [otd\\_setOriginServerPoolSslProperties](#).

### Syntax

```
otd_getOriginServerPoolSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_getOriginServerPoolSslProperties(props)
```

### See Also

[help, otd\\_setOriginServerPoolSslProperties](#)

## 2.118 otd\_getPartitionAccessLogProperties

### Description

Use this command to view these access-log properties for a partition:

Property	Description
log-file	Path to the file where access logs for the partition will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/\$PARTITION_NAME.log
format	A format is a string that can be used to customize the format and the fields that are logged in the partition access log. Default: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%
default-access-log-format	Default format for the partition access log entries: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%

### Syntax

```
otd_getPartitionAccessLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration. This must be the name of the configuration that is specified while registering the Oracle Traffic Director runtime with the Lifecycle Manager.	Mandatory.
<code>partition</code>	Name of the partition.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'mt'
props['partition'] = 'WLSPartition'
otd_getPartitionAccessLogProperties(props)
```

### See Also

[help](#), [otd\\_listPartitions](#), [otd\\_setPartitionAccessLogProperties](#)

## 2.119 otd\_getPerfDump

### Description

Use this command to view the runtime statistics for various subsystems as a text report on the browser.

### Syntax

```
otd_getPerfDump(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>instance-name</code>	Name of the instance.	Mandatory.
<code>domain-home</code>	Path to the directory which contains the Oracle Traffic Director domain	Mandatory for Offline, not valid for Online.

### Example

```
# Online
props = {}
props['instance-name'] = 'otd_abcl23.example.com'
otd_getPerfDump(props)

# Offline
props = {}
props['domain-home'] = '/export/domains/otd_domain'
```

```
props['instance-name'] = 'otd_abcl23.example.com'
otd_getPerfDump(props)
```

**See Also**

[help](#), [otd\\_getPerfDumpProperties](#), [otd\\_enablePerfDump](#), [otd\\_disablePerfDump](#)

## 2.120 otd\_getPerfDumpProperties

**Description**

Use this command to get the following `perfdump` properties:

Property	Description	Comments
enabled	Whether <code>perfdump</code> is enabled. Default is false.	Mandatory.
uri	The URI at which the <code>perfdump</code> report should be available. Default: <code>/.perf</code> .	Mandatory.

**Syntax**

```
otd_getPerfDumpProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getPerfDumpProperties(props)
```

**See Also**

[help](#), [otd\\_getPerfDump](#), [otd\\_enablePerfDump](#), [otd\\_disablePerfDump](#)

## 2.121 otd\_getRequestLimitProperties

**Description**

Use this command to view the request-limit properties. The properties that this command returns are described in [otd\\_setRequestLimitProperties](#).

**Syntax**

```
otd_getRequestLimitProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>request-limit</code>	Name of the request limit rule.	Mandatory.
<code>event-notification-interval</code>	Time interval (in seconds). A notification message will be sent to subscribers once every interval and will include information on all monitors that exceeded the request limit that was configured for them.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['request-limit'] = 'request-limit-1'
otd_getRequestLimitProperties(props)
```

### See Also

[help](#), [otd\\_listRequestLimits](#), [otd\\_deleteRequestLimit](#), [otd\\_createRequestLimit](#), [otd\\_setRequestLimitProperties](#)

## 2.122 otd\_getRouteAuthProperties

### Description

Use this command to view the following route authentication properties:

Property	Description	Comments
<code>auth-user</code>	Specifies the authenticated user.	Mandatory.
<code>auth-header</code>	Specifies the name of the authentication header. Default is Authorization.	

### Syntax

```
otd_getRouteAuthProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.



Property	Description	Comments
route	Name of the route.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
otd_getRouteAuthProperties(props)
```

**See Also**

[help](#), [otd\\_disableRouteAuth](#), [otd\\_enableRouteAuth](#) , [otd\\_disableRouteAuth](#)

## 2.123 otd\_getRouteBandwidthLimitProperties

**Description**

Use this command to get bandwidth limiting properties at the route level.

**Syntax**

```
otd_getRouteBandwidthLimitProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.
type	Type of bandwidth limiting. Range of values: request or response.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['type'] = 'request'
otd_getRouteBandwidthLimitProperties(props)
```

**See Also**

[help](#), [otd\\_enableRouteBandwidthLimit](#), [otd\\_disableRouteBandwidthLimit](#)

## 2.124 otd\_getRouteProperties

### Description

Use this command to view route properties. The properties that this command returns are described in [otd\\_setRouteProperties](#).

### Syntax

```
otd_getRouteProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.

### Example

```
props = {}  
props['configuration'] = 'foo'  
props['virtual-server'] = 'bar'  
props['route'] = 'route-1'  
otd_getRouteProperties(props)
```

### See Also

[help](#), [otd\\_createRoute](#), [otd\\_listRoutes](#), [otd\\_setRouteProperties](#), [otd\\_deleteRoute](#)

## 2.125 otd\_getSnmpProperties

### Description

Use this command to view the Simple Network Management Protocol (SNMP) properties. The properties that this command returns are described in [otd\\_setSnmpProperties](#).

### Syntax

```
otd_getSnmpProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getSnmpProperties(props)
```

**See Also**

[help](#), [otd\\_stopSnmpSubAgent](#), [otd\\_startSnmpSubAgent](#), [otd\\_setSnmpProperties](#)

## 2.126 otd\_getSslSessionCacheProperties

**Description**

Use this command to view the properties that are currently defined for caching SSL session data. The properties that this command returns are described in [otd\\_setSslSessionCacheProperties](#).

**Syntax**

```
otd_getSslSessionCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getSslSessionCacheProperties(props)
```

**See Also**

[help](#), [otd\\_setSslSessionCacheProperties](#)

## 2.127 otd\_getStatsProperties

**Description**

Use this command to view properties of the statistics collection subsystem. The properties that this command returns are described in [otd\\_setStatsProperties](#).

**Syntax**

```
otd_getStatsProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getStatsProperties(props)
```

**See Also**

[help](#), [otd\\_setStatsProperties](#)

## 2.128 otd\_getStatsXml

**Description**

Use this command to view runtime statistics for various subsystems in XML format.

**Syntax**

```
otd_getStatsXml(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
instance	Name of the instance.	Mandatory.
domain-home	Path to the directory which contains the Oracle Traffic Director domain.	Mandatory for Offline, not valid for Online.

**Example**

Online syntax:

```
props = {}
props['instance'] = 'otd_foo_machine1'
otd_getStatsXml(props)
```

Offline syntax:

```
props = {}
props['domain-home'] = '/export/domains/otd_domain'
props['instance'] = 'otd_foo_machine1'
otd_getStatsXml(props)
```

**See Also**

[help](#), [otd\\_getStatsXmlProperties](#), [otd\\_enableStatsXml](#), [otd\\_disableStatsXml](#)

## 2.129 otd\_getStatsXmlProperties

### Description

Use this command to view these properties defined for gathering and reporting statistical data in XML format:

Property	Description	Default
enabled	Whether access to virtual-server statistics in XML format through a URI is enabled.	false
url	The URI at which the statistics report in XML format should be available.	/stats-xml

### Syntax

```
otd_getStatsXmlProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getStatsXmlProperties(props)
```

### See Also

[help](#), [otd\\_enableStatsXml](#), [otd\\_disableStatsXml](#)

## 2.130 otd\_getStatusListenerProperties

### Description

Use this command to view the Status Listener properties.

### Syntax

```
otd_getStatusListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example 2-9 Example**

```
props = {}
props['configuration'] = 'foo'
otd_getStatusListenerProperties(props)
```

## 2.131 otd\_getStatusListenerSslProperties

**Description**

Use this command to view the SSL properties of a Status Listener.

**Syntax**

```
otd_getStatusListenerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example 2-10 Example**

```
props = {}
props['configuration'] = 'foo'
otd_getStatusListenerSslProperties(props)
```

## 2.132 otd\_getTcpAccessLogProperties

**Description**

Use this command to view these properties of the TCP access log. The properties that this command returns are described in [otd\\_setTcpAccessLogProperties](#).

Property	Description
file	Path to the file where the access log for this configuration will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/tcp-access.log

**Syntax**

```
otd_getTcpAccessLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getTcpAccessLogProperties(props)
```

**See Also**

[help](#), [otd\\_setTcpAccessLogProperties](#)

## 2.133 otd\_getTcpListenerProperties

**Description**

Use this command to view the properties of the TCP listener. The properties that this command returns are described in [otd\\_setTcpListenerProperties](#).

**Syntax**

```
otd_getTcpListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-listener	Name of the TCP listener.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
otd_getTcpListenerProperties(props)
```

**See Also**

[help](#), [otd\\_createTcpListener](#), [otd\\_deleteTcpListener](#), [otd\\_listTcpListeners](#), [otd\\_setTcpListenerProperties](#)

## 2.134 otd\_getTcpListenerSslProperties

**Description**

Use this command to view the Secure Sockets Layer (SSL) properties for a TCP listener. SSL is a software library establishing a secure connection between the client and server. SSL is used to implement HTTPS, the secure version of HTTP.

The properties that this command returns are described in [otd\\_setTcpListenerSslProperties](#).

### Syntax

```
otd_getTcpListenerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-listener	Name of the TCP listener.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
otd_getTcpListenerSslProperties(props)
```

### See Also

[help](#), [otd\\_setTcpListenerSslProperties](#)

## 2.135 otd\_getTcpProxyProperties

### Description

Use this command to view the properties of the TCP proxy.

### Syntax

```
otd_getTcpProxyProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-proxy	Name that uniquely identifies the exposed TCP service.	Mandatory.

The properties that this command returns are described in [otd\\_setTcpProxyProperties](#).

### Example

```
props = {}
props['configuration'] = 'foo'
props['tcp-proxy'] = 'bar'
otd_getTcpProxyProperties(props)
```



**See Also**

[help](#), [otd\\_createTcpProxy](#), [otd\\_deleteTcpProxy](#), [otd\\_listTcpProxies](#), [otd\\_setTcpProxyProperties](#)

## 2.136 otd\_getTcpThreadPoolProperties

**Description**

Use this command to view the properties of the TCP thread pool. The properties that this command returns are described in [otd\\_setTcpThreadPoolProperties](#).

**Syntax**

```
otd_getTcpThreadPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_getTcpThreadPoolProperties(props)
```

**See Also**

[help](#), [otd\\_setTcpThreadPoolProperties](#)

## 2.137 otd\_getVirtualServerAccessLogProperties

**Description**

Use this command to view the following access-log properties:

Property	Description
enabled	Whether the server writes to this access log. Range of values: true or false. Default: true.
file	Path to the file where access logs for this configuration will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/access.log
format	A format is a string that can be used to customize the format and the fields that are logged in the access log. Default: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%

Property	Description
log-ip	Whether to log the IP of the client into the access log. Range of values: true or false. Default: false.
default-access-log-format	Default format for the access log entries: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%

**Syntax**

```
otd_getVirtualServerAccessLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getVirtualServerAccessLogProperties(props)
```

**See Also**

[help](#), [otd\\_enableVirtualServerAccessLog](#), [otd\\_disableVirtualServerAccessLog](#), [displayLogs](#), [otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

## 2.138

# otd\_getVirtualServerRequestBandwidthLimitProperties

**Description**

Use this command to get request bandwidth limiting properties at the virtual server level.

**Syntax**

```
otd_getVirtualServerRequestBandwidthLimitProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

Property	Description	Comments
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getVirtualServerRequestBandwidthLimitProperties(props)
```

**See Also**

[help](#), [otd\\_enableVirtualServerRequestBandwidthLimit](#),  
[otd\\_disableVirtualServerRequestBandwidthLimit](#)

## 2.139

# otd\_getVirtualServerResponseBandwidthLimitProperties

**Description**

Use this command to get response bandwidth limiting properties at the virtual server level.

**Syntax**

```
otd_getVirtualServerResponseBandwidthLimitProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getVirtualServerBandwidthLimitProperties(props)
```

**See Also**

[help](#), [otd\\_enableVirtualServerResponseBandwidthLimit](#),  
[otd\\_disableVirtualServerResponseBandwidthLimit](#)

## 2.140 otd\_getVirtualServerProperties

### Description

Use this command to view the properties of a virtual server. The properties that this command returns are described in [otd\\_setVirtualServerProperties](#).

### Syntax

```
otd_getVirtualServerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getVirtualServerProperties(props)

```

### See Also

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#), [otd\\_deleteVirtualServer](#)

## 2.141 otd\_getVirtualServerSslProperties

### Description

Use this command to get the SSL properties for a virtual server. The properties that this command returns are documented in [otd\\_setVirtualServerSslProperties](#).

### Syntax

```
otd_getVirtualServerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getVirtualServerSslProperties(props)
```

**See Also**

[help](#), [otd\\_setVirtualServerSslProperties](#)

## 2.142 otd\_getWebappFirewallProperties

**Description**

Use this command to view the properties of a web application firewall. The properties that this command returns are described in [otd\\_setWebappFirewallProperties](#).

**Syntax**

```
otd_getWebappFirewallProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_getWebappFirewallProperties(props)
```

**See Also**

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#), [otd\\_deleteVirtualServer](#), [otd\\_getVirtualServerProperties](#)

## 2.143 otd\_installConfigurationWebappFirewallRulesetFile

**Description**

Use this command to upload a file containing Web Application Firewall (WAF) rules into the server configuration directory. These rules will apply server-wide across all virtual servers.

**Syntax**

```
otd_installConfigurationWebappFirewallRulesetFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>file-path</code>	The full path of the ruleset file to be installed.	Mandatory.
<code>file-on-server</code>	Whether the file to be installed is available on the administration server host. Default is false.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['file-path'] = '/export/bar.conf'
otd_installConfigurationWebappFirewallRulesetFile(props)
```

### See Also

[help, otd\\_deleteVirtualServerWebappFirewallRulesetFile](#),  
[otd\\_listVirtualServerWebappFirewallRulesetFiles](#)

## 2.144 otd\_installCrl

### Description

Use this command to install a certificate revocation list (CRL) issued by a Certificate Authority (CA) into the server configuration directory. A CRL lists all certificates that either client or server users should no longer trust.

### Syntax

```
otd_installCrl(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>file-path</code>	Specify the full path of the CRL file that you want to install.	Mandatory.
<code>file-on-server</code>	If you specify this option, the CRL file is available on the administration server computer. If you do not specify this option, the CRL file is assumed to be available on the client machine and will be uploaded to the server.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['file-path'] = '/export/ServerSign.crl'
otd_installCrl(props)
```

**See Also**

[help](#), [otd\\_listCrls](#), [otd\\_deleteCrl](#)

## 2.145 otd\_installVirtualServerWebappFirewallRulesetFile

**Description**

Use this command to upload the web application firewall ruleset files into the server configuration directory. These rules will apply only to requests handled by the specified virtual server.

**Syntax**

```
otd_installVirtualServerWebappFirewallRulesetFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>file-path</code>	The full path of the ruleset file to be installed. This file should be available on the administration server host.	Mandatory.
<code>file-on-server</code>	Whether the file to be installed is available on the administration server host. Default is false.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['file-path'] = '/export/rulesets/baz.conf'
otd_installVirtualServerWebappFirewallRulesetFile(props)
```

**See Also**

[help](#), [otd\\_deleteVirtualServerWebappFirewallRulesetFile](#),  
[otd\\_listVirtualServerWebappFirewallRulesetFiles](#)

## 2.146 otd\_listCacheRules

**Description**

Use this command to view a list of caching rules defined for the specified virtual server.

**Syntax**

```
otd_listCacheRules(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

This command returns a list of strings each representing the name of a cache rule.

#### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listCacheRules(props)
```

#### See Also

[help](#), [otd\\_createCacheRule](#), [otd\\_deleteCacheRule](#), [otd\\_setCacheRuleProperties](#)

## 2.147 otd\_listCertificates

#### Description

Use this command to list all the certificates of type 'Certificate' present in the keystore.

#### Syntax

```
otd_listCertificates(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

This command returns a list of maps, each map representing one certificate with properties `alias`, `subject`, `issuer`, `serial-number` and `key-type`.

#### Example

```
props = {}
props['configuration'] = 'foo'
otd_listCertificates(props)
```

#### See Also

[help](#), [exportKeyStoreCertificateRequest](#), [deleteKeyStoreEntry](#), [importKeyStoreCertificate](#), [getKeyStoreCertificates](#), [generateKeyPair](#)



## 2.148 otd\_listCompressionRules

### Description

Use this command to list compression rules defined for the specified virtual server.

### Syntax

```
otd_listCompressionRules(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

This command returns a list of strings each representing the name of a compression rule.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listCompressionRules(props)
```

### See Also

[help](#), [otd\\_createCompressionRule](#), [otd\\_deleteCompressionRule](#), [otd\\_setCompressionRuleProperties](#), [otd\\_getCompressionRuleProperties](#)

## 2.149 otd\_listConfigFiles

### Description

Use this command to list configuration files pertaining to the specified configuration.

### Syntax

```
otd_listConfigFiles(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of a configuration file.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listConfigFiles(props)
```

**See Also**

[help](#), [otd\\_createConfiguration](#), [activate](#), [otd\\_copyConfiguration](#), [otd\\_saveConfigFile](#), [otd\\_deleteConfiguration](#), [otd\\_getConfigFile](#), [otd\\_listConfigurations](#)

## 2.150 otd\_listConfigurations

**Description**

Use this command to return a list of strings each representing the name of an existing configuration.

**Syntax**

```
otd_listConfigurations()
```

**Example**

```
# Online
otd_listConfigurations()

# Offline
readDomain('/export/domains/otd_domain')
otd_listConfigurations()
closeDomain()
```

**See Also**

[help](#), [otd\\_createConfiguration](#), [activate](#), [otd\\_copyConfiguration](#), [otd\\_saveConfigFile](#), [otd\\_deleteConfiguration](#), [otd\\_getConfigFile](#), [otd\\_listConfigFiles](#)

## 2.151 otd\_listConfigurationWebappFirewallRulesetFiles

**Description**

Use this command to list all web application firewall rulesets defined for a configuration.

**Syntax**

```
otd_listConfigurationWebappFirewallRulesetFiles(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of a web application ruleset file.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_listConfigurationWebappFirewallRulesetFiles(props)
```

### See Also

[help](#), [otd\\_installVirtualServerWebappFirewallRulesetFile](#),  
[otd\\_listVirtualServerWebappFirewallRulesetFiles](#),  
[otd\\_deleteVirtualServerWebappFirewallRulesetFile](#)

## 2.152 otd\_listContentRules

### Description

Use this command to list the content rules.

### Syntax

```
otd_listContentRules(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listContentRules(props)
```

### See Also

[help](#), [otd\\_getContentRuleProperties](#), [otd\\_setContentRuleProperties](#),  
[otd\\_createContentRule](#) , [otd\\_deleteContentRule](#)

## 2.153 otd\_listCrls

### Description

Use this command to list all installed certificate revocation lists (CRLs).

### Syntax

```
otd_listCrls(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.

#### Example

```
props = {}
props['configuration'] = 'foo'
otd_listCrIs(props)
```

#### See Also

[help](#), [otd\\_installCrI](#), [otd\\_deleteCrI](#)

## 2.154 otd\_listErrorPages

#### Description

Use this command to list all the error pages and their corresponding error codes.

#### Syntax

```
otd_listErrorPages(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

#### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listErrorPages(props)
```

#### See Also

[help](#), [otd\\_createErrorPage](#), [otd\\_deleteErrorPage](#)

## 2.155 otd\_listEvents

#### Description

Use this command to list all scheduled events for a configuration.

#### Syntax

```
otd_listEvents(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_listEvents(props)
```

### See Also

[help](#), [otd\\_createEvent](#), [otd\\_deleteEvent](#), [otd\\_getEventProperties](#), [otd\\_setEventProperties](#)

## 2.156 otd\_listEventSubscriptions

### Description

Use this command to view a list of subscribed event subscriptions.

### Syntax

```
otd_listEventSubscriptions(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	

### Example 2-11 Example

```
props = {}
props['configuration'] = 'foo'
otd_listEventSubscriptions(props)
```

### See Also

[help](#), [otd\\_createEventSubscription](#), [otd\\_deleteEventSubscription](#), [otd\\_getEventSubscriptionProperties](#), [otd\\_listEventSubscriptions](#)

## 2.157 otd\_listFailoverGroups

### Description

Use this command to return a list of strings each representing the `virtual-ip` of an existing failover group.

### Syntax

```
otd_listFailoverGroups(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_listFailoverGroups(props)
```

### See Also

[help](#), [otd\\_createFailoverGroup](#), [otd\\_deleteFailoverGroup](#),  
[otd\\_getFailoverGroupProperties](#), [otd\\_toggleFailoverGroupPrimary](#)

## 2.158 otd\_listFailoverInstances

### Description

Use this command to list all the instances present in an active-active failover group type. This command returns a list of maps, each map representing one instance with properties instance and NIC.

### Syntax

```
otd_listFailoverInstances(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-ip	Virtual IP that uniquely identifies the failure group.	Mandatory.

### Example 2-12 Example

To list failover groups, see the following example with the below details.

Configuration: ha

Instance: 1.example.com

Virtual IP address: 10.128.67.44

```
props = {}
props['configuration'] = 'ha'
props['virtual-ip'] = '10.128.67.44'
props['instance'] = '1.example.com'
otd_listFailoverInstances(props)
```

## 2.159 otd\_listHttpListeners

### Description

Use this command to list the names of the HTTP listeners defined for the configuration.

### Syntax

```
otd_listHttpListeners(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of an HTTP listener.

### Example

```
props = {}
props['configuration'] = 'foo'
otd_listHttpListeners(props)
```

### See Also

[help](#), [otd\\_createHttpListener](#), [otd\\_setHttpListenerProperties](#), [otd\\_setHttpListenerProperties](#), [otd\\_deleteHttpListener](#)

## 2.160 otd\_listInstances

### Description

Use this command to list all instances of this configuration.

### Syntax

```
otd_listInstances(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of an instance.

### Example

```
#Online
props = {}
```

```

props['configuration'] = 'foo'
otd_listInstances(props)

#Offline
readDomain('/export/domains/otd_domain')
props = {}
props['configuration'] = 'foo'
otd_listInstances(props)
closeDomain()

```

**See Also**

[help](#), [otd\\_createInstance](#), [otd\\_deleteInstance](#), [start](#), [stop](#), [softRestart](#)

## 2.161 otd\_listMimeTypes

**Description**

Use this command to list MIME types.

**Syntax**

```
otd_listMimeTypes(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
otd_listMimeTypes(props)

```

**See Also**

[help](#), [otd\\_createMimeType](#), [otd\\_deleteMimeType](#)

## 2.162 otd\_listOriginServers

**Description**

Use this command to view a list of origin-servers defined in a pool.

**Syntax**

```
otd_listOriginServers(props)
```

The argument `props` is a dictionary that can contain the following properties, in addition to the properties described in [otd\\_createOriginServer](#):



Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
otd_listOriginServers(props)
```

**See Also**

[help](#), [otd\\_createOriginServer](#), [otd\\_deleteOriginServer](#), [otd\\_getOriginServerProperties](#), [otd\\_setOriginServerProperties](#)

## 2.163 otd\_listOriginServerPools

**Description**

Use this command to list origin-server pools defined for a configuration.

**Syntax**

```
otd_listOriginServerPools(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

The command returns a list of strings each representing the name of an origin server pool.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listOriginServerPools(props)
```

**See Also**

[help](#), [otd\\_getOriginServerPoolProperties](#), [otd\\_setOriginServerPoolProperties](#), [otd\\_deleteOriginServerPool](#), [otd\\_createOriginServerPool](#)

## 2.164 otd\_listPartitions

### Description

Use this command to list all the Oracle Traffic Director partitions in a given configuration. The Oracle Traffic Director partition name should be same as the WLS partition name that it front-ends. In that case, it lists all the WLS partitions that are front-ended by Oracle Traffic Director.

### Syntax

```
otd_listPartitions(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration. This must be the name of the configuration that is specified while registering the Oracle Traffic Director runtime with the Lifecycle Manager.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'mt'
otd_listPartitions(props)
```

### See Also

[help](#), [otd\\_listResourceGroups](#), [otd\\_getPartitionAccessLogProperties](#), [otd\\_setPartitionAccessLogProperties](#)

## 2.165 otd\_listProxyInfo

### Description

Use this command to list the information about the proxy parameters configured for the route.

### Syntax

```
otd_listProxyInfo(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>route</code>	Name of the route.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
otd_listProxyInfo(props)
```

**See Also**

[help](#), [otd\\_blockProxyInfo](#), [otd\\_forwardProxyInfo](#)

## 2.166 otd\_listRequestLimits

**Description**

Use this command to list the request limit conditions defined for a virtual server.

**Syntax**

```
otd_listRequestLimits(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

This command returns a list of strings each representing the name of a request limit

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listRequestLimits(props)
```

**See Also**

[help](#), [otd\\_getRequestLimitProperties](#), [otd\\_setRequestLimitProperties](#),  
[otd\\_deleteRequestLimit](#), [otd\\_createRequestLimit](#)

## 2.167 otd\_listResourceGroups

**Description**

Provides information about all the `resource-groups` that exist under a given partition. The `resource-group` information contains the information about all the `virtual-targets` that the `resource-group` is targeted to. The `virtual-target` information in turn includes the `virtual-target` name and the corresponding Oracle Traffic Director artifacts information such as `route` name, `virtual-server` name and `origin-server-pool` name.

**Syntax**

```
otd_listResourceGroups(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration. This must be the name of the configuration that is specified while registering the Oracle Traffic Director runtime with the Lifecycle Manager.	Mandatory.
partition	Name of the partition.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'mt'
props['partition'] = 'WLSPartition'
otd_listResourceGroups(props)
```

**See Also**

[help](#), [otd\\_listPartitions](#), [otd\\_getPartitionAccessLogProperties](#), [otd\\_setPartitionAccessLogProperties](#)

## 2.168 otd\_listRoutes

**Description**

Use this command to list the rules defined for a virtual server.

**Syntax**

```
otd_listRoutes(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

This command returns a list of strings each representing the name of a route.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listRoutes(props)
```

**See Also**

[help](#), [otd\\_createRoute](#), [otd\\_deleteRoute](#), [otd\\_getRouteProperties](#), [otd\\_setRouteProperties](#)

## 2.169 otd\_listServices

**Description**

This command lists the operating system services corresponding to the Oracle Traffic Director instances that exist on the machine where the command is executed. The command returns a list of python dictionaries of name (string) - value (string) pairs where each dictionary contains the properties mentioned below.

**Syntax**

```
otd_listServices(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the directory that contains Oracle Traffic Director domain.	Mandatory.

**Example 2-13 Example Title**

```
props = {}
props['domain-home'] = '/export/domains/otd_domain'
otd_listServices(props)
```

**See Also**

[otd\\_deleteService](#), [otd\\_createService](#)

## 2.170 otd\_listTcpListeners

**Description**

Use this command to list all the TCP listeners.

**Syntax**

```
otd_listTcpListeners(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of a TCP listener.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listTcpListeners(props)
```

**See Also**

[help](#), [otd\\_createTcpListener](#), [otd\\_deleteTcpListener](#), [otd\\_getTcpListenerProperties](#), [otd\\_setTcpListenerProperties](#)

## 2.171 otd\_listTcpProxies

**Description**

Use this command to list all the TCP proxies.

**Syntax**

```
otd_listTcpProxies(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of a TCP proxy.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listTcpProxies(props)
```

**See Also**

[help](#), [otd\\_createTcpProxy](#), [otd\\_deleteTcpProxy](#), [otd\\_getTcpProxyProperties](#), [otd\\_setTcpProxyProperties](#)

## 2.172 otd\_listConfigurationVariables

**Description**

Use this command to list all the variables defined at the configuration level.

**Syntax**

```
otd_listConfigurationVariables(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listConfigurationVariables(props)
```

**See Also**

[help](#), [otd\\_createConfigurationVariable](#) , [otd\\_deleteConfigurationVariable](#)

## 2.173 otd\_listVirtualServers

**Description**

Use this command to list all virtual-servers defined for a configuration.

**Syntax**

```
otd_listVirtualServers(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

This command returns a list of strings each representing the name of a virtual server.

**Example**

```
props = {}
props['configuration'] = 'foo'
otd_listVirtualServers(props)
```

**See Also**

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#),  
[otd\\_getVirtualServerProperties](#), [otd\\_deleteVirtualServer](#), [otd\\_copyVirtualServer](#)

## 2.174 otd\_listVirtualServerVariables

**Description**

Use this command to list all variables defined at the configuration level.

**Syntax**

```
otd_listVirtualServerVariables(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listVirtualServerVariables(props)
```

### See Also

[help](#), [otd\\_createVirtualServerVariable](#), [otd\\_deleteVirtualServerVariable](#)

## 2.175 otd\_listVirtualServerWebappFirewallRulesetFiles

### Description

Use this command to list all web application firewall rulesets defined for a virtual server.

### Syntax

```
otd_listVirtualServerWebappFirewallRulesetFiles(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

This command returns a list of strings each representing the name of a web application ruleset file.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
otd_listVirtualServerWebappFirewallRulesetFiles(props)
```

### See Also

[help](#), [otd\\_installVirtualServerWebappFirewallRulesetFile](#), [otd\\_deleteVirtualServerWebappFirewallRulesetFile](#)



## 2.176 otd\_removeFailoverInstance

### Description

Use this command to remove a failover instance. This command is valid only for the active-active failover type.

### Syntax

```
otd_removeFailoverInstance(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-ip	Virtual IP that uniquely identifies the failure group.	Mandatory.
instance	An instance which is part of this failover group.	Mandatory.

### Example 2-14 Example

Configuration: ha

Instance: 1.example.com

Virtual IP address: 10.128.67.44

```
props = {}  
props['configuration'] = 'ha'  
props['virtual-ip'] = '10.128.67.44'  
props['instance'] = '1.example.com'  
otd_removeFailoverInstance(props)
```

### See Also

help, otd\_addFailoverInstance,otd\_setFailoverInstanceOrder

## 2.177 otd\_rotateLog

### Description

Use this command to rotate the server log and access log files. The server saves the old log files and marks the saved files with a name that includes the date and time when they were saved.

#### Note:

Ensure that you are connected to the Administration Server while running this command.

**Syntax**

```
otd_rotateLog(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>instance-name</code>	Name of the node whose logs are to be rotated.	Mandatory.

**Example**

```
props = {}
props['instance-name'] = 'otd_foo_machine1'
otd_rotateLog(props)
```

**See Also**

[help](#)

## 2.178 otd\_saveConfigFile

**Description**

Use this command to upload changes to an existing configuration file or create a new one.

**Syntax**

```
otd_saveConfigFile(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>file-path</code>	Absolute path to the local file to be uploaded to the configuration directory.	Mandatory.
<code>config-file</code>	Name of the configuration file.	

**Example**

```
props = {}
props['configuration'] = 'foo'
props['file-path'] = '/export/config_files/foo-obj.conf'
otd_saveConfigFile(props)
```

**See Also**

[help](#), [otd\\_createConfiguration](#), [otd\\_listConfigurations](#), [otd\\_deleteConfiguration](#), [otd\\_copyConfiguration](#), [otd\\_listConfigFiles](#), [otd\\_getConfigFile](#), [activate](#)

## 2.179 otd\_setAccessLogBufferProperties

### Description

Use this command to set the following properties of the access-log buffer.

Property	Description
enabled	Whether the system buffers access log updates. Range of values: true or false. Default: true.
buffer-size	Size (in bytes) of individual access log buffers. Range of values: 4096 - 1048576. Default: 8192.
direct-io	Indicates whether the file system should cache access-log writes. Range of values: true or false. The default value, false, indicates that the file system should cache access log writes. Setting the value to true indicates that the file system should not cache access log writes. The setting is purely advisory; either the server or the operating system may choose to ignore it.
max-buffers	Maximum number of access log buffers per server. Range of values: 1 - 65536. Default: 1000.
max-buffers-per-file	Maximum number of access log buffers per access log file. Range of values: 1 - 128. Default: auto-tuned.
max-age	Maximum amount of time to buffer a given access log entry. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 1.

### Syntax

```
otd_setAccessLogBufferProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['max-buffers'] = '2000'
otd_setAccessLogBufferProperties(props)
```

**See Also**

[help](#), [otd\\_getAccessLogBufferProperties](#), [otd\\_enableVirtualServerAccessLog](#), [otd\\_disableVirtualServerAccessLog](#), [displayLogs](#), [otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

## 2.180 otd\_setCacheProperties

**Description**

Use this command to define or change the following caching properties for a configuration:

Property	Description
enabled	Defines if caching is enabled or not. Range of values: true or false. Default: true.
max-entries	Maximum number of objects for which to cache content. Range of values: 1 - 1073741824. Default: 1024.
replacement	Cache entry replacement algorithm. Range of values: lru, lfu, or false. Default: lru.
max-heap-object-size	Maximum size of response (single entry) (in bytes) to cache on the heap. If HTTP response object is bigger than max-heap-object-size, it will not be cached. Range of values: maximum size in bytes between 0 and 2147483647, inclusive. -1 indicates that there is no maximum size. Default: 524288.
max-heap-size	Maximum amount (in bytes) of heap to use for caching response objects. It should not be more than available memory or process address space. Range of values: maximum amount of address space in bytes between 0 and 1099511627776, inclusive. Default: 10485760.

**Syntax**

```
otd_setCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
```

```
props['max-heap-space'] = '20971520'
otd_setCacheProperties(props)
```

**See Also**

[help](#), [otd\\_getCacheProperties](#)

## 2.181 otd\_setCacheRuleProperties

**Description**

Use this command to set the following cache rule properties:

Property	Description	Comments
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	
enabled	Specifies whether the caching rule is enabled.	
max-reload-interval	Specifies the maximum time (in seconds) allowed between consecutive up-to-date checks. Range of values: any positive Integer. Default: 3600.	
min-reload-time	Specifies the minimum time (in seconds) allowed between consecutive up-to-date checks of a cached document. Range of values: any positive Integer. Default: 0.	
last-modified-factor	Represents the factor used in estimating the expiry time, which defines how long a document will be up-to-date based on time it was last modified. This property is used only when the explicit age of the document is not available. Range of values: any positive Integer. Default: 0.	
min-object-size	The maximum size, in bytes, of any document to be cached. This setting enables users to limit the maximum size of cached documents, so that no single document can take too much space. This value cannot exceed the value of <code>max-heap-object-size</code> . Range of values: any positive Integer. Default: 0.	
max-object-size	Specifies the minimum size (in bytes) of any document to be cached. Range of values: any positive Integer.	
query-maxlen	Specifies the number of characters in the query string. If this property is set to 0, URIs with query strings are not cached. Range of values: any positive Integer. Default: 0.	

Property	Description	Comments
compression	If this property value is set to true, the document is compressed before storing in the cache Range of values: true or false. Default: false.	
cache-https-response	If this property value is set to true, responses from the HTTPS servers are also cached. Range of values: true or false. Default: false.	

### Syntax

```
otd_setCacheRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
cache-rule	Name of the cache rule.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['cache-rule'] = 'cache-rule-1'
props['min-object-size'] = '512'
otd_setCacheRuleProperties(props)
```

### See Also

[help](#), [otd\\_setCacheProperties](#), [otd\\_getCacheRuleProperties](#)

## 2.182 otd\_setCompressionRuleProperties

### Description

Use this command to set or change the following properties of a compression rule for a virtual server:

Property	Description	Comments
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	

Property	Description	Comments
insert-vary-header	Select to insert a vary:Accept-encoding header. Range of values: true or false. Default: true.	
compression-level	Specifies the compression level for the virtual server. Specifying 1 yields better speed and specifying 9 yields best compression. Range of values: 1 - 9. Default: auto-tuned.	
fragment-size	Specifies the memory fragment size (in bytes) that is used by the compression library to control the compression rate. Range of values: any positive Integer. Default: 8192.	

### Syntax

```
otd_setCompressionRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
compression-rule	Name of the compression rule.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['compression-rule'] = 'compression-rule-1'
props['compression-level'] = '8'
otd_setCompressionRuleProperties(props)
```

### See Also

[help](#), [otd\\_createCompressionRule](#), [otd\\_deleteCompressionRule](#), [otd\\_listCompressionRules](#), [otd\\_getCompressionRuleProperties](#)

## 2.183 otd\_setConfigurationAccessLogProperties

### Description

Use this command to set access-log properties for a configuration.

## Syntax

```
otd_setConfigurationAccessLogProperties
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>log-file</code>	Path to the file where access log for this configuration will be stored. Default: <code>\$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/access.log</code> .	
<code>format</code>	A format is a string that can be used to customize the format and the fields that are logged in the access log. Default: <code>%Ses-&gt;client.ip% - %Req-&gt;vars.auth-user% %SYSDATE% "%Req-&gt;reqpb.clf-request%" %Req-&gt;srvhdrs.clf-status% %Req-&gt;srvhdrs.content-length% %Req-&gt;vars.ecid% %Req-&gt;vars.origin-server%</code>	

## Example

```
props = {}
props['configuration'] = 'foo'
props['log-file'] = 'logs/access.log'
otd_setConfigurationAccessLogProperties(props)
```

## See Also

[help](#), [otd\\_enableVirtualServerAccessLog](#), [otd\\_disableVirtualServerAccessLog](#), [displayLogs](#), [otd\\_getLogProperties](#), [otd\\_setLogProperties](#), [otd\\_rotateLog](#)

# 2.184 otd\_setConfigurationCrlProperties

## Description

Use this command to define or change the following certificate revocation list (CRL) properties for a configuration:

Property	Description
<code>enabled</code>	Specifies whether the properties are enabled. Range of values: true or false. Default: true.
<code>crl-cache-size</code>	Size of CRL cache. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 52428800.
<code>crl-path</code>	Directory that contains dynamically updated CRL files. Range of values: pathname. Default: <code>crl</code> .



**Syntax**

```
otd_setConfigurationCrlProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['crl-cache-size'] = '104857600'
otd_setConfigurationCrlProperties(props)
```

**See Also**

[help](#), [otd\\_getConfigurationCrlProperties](#)

## 2.185 otd\_setConfigurationProperties

**Description**

Use this command to set the following configuration properties.

Property	Description	Comments
temp-path	Any valid directory where the server stores its temporary files.	not supported on windows
webapp-firewall-ruleset	Wildcard pattern that matches one or more path names or a path to a file containing Web Application Firewall(WAF) rules/configurations. Multiple values (separated by commas) can also be specified.	Multi-valued.
default-language	An IANA language tag specifying the default language for messages displayed to administrators and content served to clients.	
negotiate-client-language	Whether the server attempts to use the Accept-language HTTP header to negotiate the content language with clients. Range of values: true or false. Default: false.	
fips	Turns on FIPS-140 mode of operation for security library. Range of values: true or false. Default: false.	
max-fd	Sets the maximum value of file descriptor availability. Default: 2097152.	

**Syntax**

```
otd_setConfigurationProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['webapp-firewall-ruleset'] = 'rulesets'
otd_setConfigurationProperties(props)
```

### See Also

[help](#), [otd\\_getConfigurationProperties](#)

## 2.186 otd\_setContentRuleProperties

### Description

Use this command to set content rule properties.

### Syntax

```
otd_setContentRuleProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
content-rule	Name of the content rule.	Mandatory.
uri-prefix	URI prefix that has to be mapped to a directory.	
directory-path	Absolute server path and a valid directory for storing documents.	
index-files	Index files are a list of welcome files or startup pages. Default: index.html,index.htm.	
default-content-type	The type of the default content that you want to edit. Default: text/plain.	
allow-directory-listing	Enable directory listing for a directory that does not have a welcome page. Range of values: true or false. Default: false.	

**Example**

```

props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['content-rule'] = 'content-rule-1'
props['index-files'] = 'home.htm'
otd_setContentRuleProperties(props)

```

**See Also**

[help](#), [otd\\_getContentRuleProperties](#), [otd\\_listContentRules](#), [otd\\_createContentRule](#) ,  
[otd\\_deleteContentRule](#)

## 2.187 otd\_setDnsCacheProperties

**Description**

Use this command to set the following Domain Name Server (DNS) cache properties:

Property	Description
enabled	Defines whether the server caches DNS lookup results. Range of values: true or false. Default: true.
max-age	Maximum amount of time (in seconds) to cache a DNS lookup result. Range of values: an interval in seconds between 0.001 (1 millisecond) and 604800 (1 week), inclusive. Default: 120.
max-entries	Maximum number of DNS lookup results to cache. Range of values: 1 - 1048576. Default: 1024.

**Syntax**

```
otd_setDnsCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['max-age'] = '240'
otd_setDnsCacheProperties(props)

```

**See Also**

[help](#), [otd\\_getDnsCacheProperties](#)

## 2.188 otd\_setDnsProperties

### Description

Use this command to set the following Domain Name Server (DNS) lookup properties for a configuration:

Property	Description
enabled	Defines whether the server does DNS lookups. Range of values: true or false. Default: true.
async	Whether the server uses its own asynchronous DNS resolver instead of the operating system's synchronous resolver. Range of values: true or false. Default: false.
timeout	Timeout (in seconds) for asynchronous DNS lookups. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 12.

### Syntax

```
otd_setDnsProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['async'] = 'true'
props['timeout'] = '24'
otd_setDnsProperties(props)
```

### See Also

[help](#), [otd\\_getDnsProperties](#), [otd\\_setDnsCacheProperties](#), [otd\\_getDnsCacheProperties](#)

## 2.189 otd\_setEventProperties

### Description

Use this command to set the event properties.

Property	Description	Comments
command	The command that the event executes. Range of values: the value can be restart, reconfig, rotate-log, rotate-access-log, and update-crl, or any executable command.	
day-of-month	Day of the month at which this event should occur. Range of values: 1-31.	
day-of-week	Day of the week at which this event should occur. Range of values: Sun, Mon, Tue, Wed, Thu, Fri, or Sat.	
enabled	Whether the event is enabled at runtime. Range of values: true or false. Default: true.	
interval	Time interval at which this event should occur. Range of values: an interval in seconds between 60 (1 minute) and 86400 (1 day), inclusive.	
month	Month at which this event should occur. Range of values: 1-12.	
time	Time, for example, 12:30, when this event is to be started. Range of values: the format of the time is hh:mm.	

### Syntax

```
otd_setEventProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
event	Name of the event.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['event'] = 'bar'
props['time'] = '10:24'
otd_setEventProperties(props)
```

### See Also

[help](#), [otd\\_deleteEvent](#), [otd\\_listEvents](#), [otd\\_getEventProperties](#)

## 2.190 otd\_setEventSubscriptionProperties

### Description

Use this command to set the event subscription properties.

### Syntax

```
otd_setEventSubscriptionProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>event-subscription</code>	User defined name of the event subscription.	Mandatory.
<code>enabled</code>	Indicates whether the even-subscription is enabled/disabled. Range of values: true or false	
<code>url</code>	Specifies the subscription URL. If this is configured, Oracle Traffic Director publishes the notifications to this URL. Range: A Valid HTTP URL.	

### Example 2-15 Example

```

props = {}
props['configuration'] = 'foo'
props['event-subscription'] = 'bar'
props['enabled'] = 'false'
otd_setEventSubscriptionProperties(props)

```

### See Also

`help,otd_createEventSubscription,otd_deleteEventSubscription,otd_getEventSubscriptionProperties,otd_listEventSubscriptions`

## 2.191 otd\_setFailoverInstanceOrder

### Description

Use this command to change the failover instance order. This command is valid only for the active-active failover type.

### Syntax

```
otd_setFailoverInstanceOrder(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-ip	Virtual IP that uniquely identifies the failure group.	Mandatory.
instances	List of instances in the order in which failover must happen.	Mandatory.

**Example 2-16 Example**

```

props = {}
props['configuration'] = 'ha'
props['virtual-ip'] = '10.128.67.44'
props['instances'] = '1.example.com,2.example.com'
otd_setFailoverInstanceOrder(props)

```

**See Also**

otd\_addFailoverInstance,otd\_removeFailoverInstance,otd\_listFailoverInstances

## 2.192 otd\_setFileCacheProperties

**Description**

Sets file cache properties.

**Syntax**

```
otd_setFileCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description
configuration	Name of the configuration.
enabled	Indicates whether the server caches the file content and meta information. Default: true
max-age	The maximum amount of time (in seconds) to cache the file content and/or meta information. Range of values: the range of values is 0.001-3600. Default: 30.
max-entries	The maximum number of paths for which the file content and/or meta information should be cached. Range of values: 1 - 1073741824 Default: 1024.
max-open-files	The maximum number of file descriptors the file cache will keep open. Range of values: 1 - 1073741824.

---

Property	Description
sendfile	Indicates whether the server will attempt to use the operating system's <code>sendfile</code> , <code>sendfilev</code> , <code>send_file</code> , or <code>TransmitFile</code> system call. The default value is true on Windows and false on other platforms.
copy-files	Indicates whether the server copies the cached files to a temporary directory. The default value is true on Windows and false on other platforms.
copy-path	The name of the temporary directory that the server uses when <code>copy-files</code> is true.
replacement	The cache entry replacement algorithm. The values can be <code>false</code> , <code>lru</code> , or <code>lfu</code> . Default: <code>lru</code> .
cache-content	Indicates whether the server caches the file content. Default: <code>true</code>
max-heap-file-size	The maximum size (in bytes) of files to cache on the heap. Range of values: 0-2147483647. Default: 524288.
max-heap-space	The maximum amount (in bytes) of heap to use for caching files. Range of values: 0-9223372036854775807. Default: 10485760.
max-mmap-file-size	The maximum size (in bytes) of files to mmap. Range of values: 0-2147483647. Default: 0.
max-mmap-space	The maximum amount (in bytes) of mmap address space to use for caching files. Range of values: 0-9223372036854775807. Default: 0.
buffer-size	Size of the input/output buffer used on cache misses. Range of values: 512-1048576. Default: 8192.
sendfile-size	A hint to send the file in chunks of at most this value Range of values: 0-2147483647. Default: 0.

---

### Example

```
props = {}  
props['configuration'] = 'foo'  
props['max-age'] = '1200'  
otd_setFileCacheProperties(props)
```

### See Also

[help, otd\\_getFileCacheProperties](#)



## 2.193 otd\_setHealthCheckProperties

### Description

Use this command to set the following health-check properties for an origin server pool:

Property	Description
protocol	Health check mechanism. Range of values: http, tcp or command Default: origin server pool type
interval	The time interval in seconds between two health check pings. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 30
timeout	The timeout value in seconds for a ping request or connection. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 5
failover-threshold	The number of consecutive failures for marking a server down. Range of values: 1 - 256 Default: 3
request-method	The method used in HTTP ping requests. Range of values: OPTIONS or GET Default: OPTIONS
request-uri	The URI to use for HTTP health check request. Range of values: URI (virtual directory) that begins with /. Default: /
response-code-match	A modified regular expression to specify what response status codes are acceptable for a healthy origin server. The expression is a union of 3-character patterns that contain only digits or 'x', where 'x' stands for any digit. For example, the following 3 expressions are valid: 200, 2xx or 304, 1xx or 2xx or 3xx or 4xx. If the parameter is not specified, all codes except 5xx server errors are considered acceptable.
response-body-match	A regular expression used to match the HTTP response body in order to determine if the server is healthy. The origin server will be marked UP if the ping response matches the regular expression (if this parameter is specified) and the response status code is not a 5xx server error (if this parameter is not specified). If response body match is enabled, request method should be set to GET.
response-body-match-size	The maximum length of response body to be matched. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 2048.
dynamic-server-discovery	Indicates whether the server caches the file content. Range of values: true or false. Default: false.
command	The full path of the external health check executable.
use-object-file	Indicates whether object file processing is done for health-check-requests. Range of values: true or false. Default: true.

### Syntax

```
otd_setHealthCheckProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>origin-server-pool</code>	Name of the origin server pool.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['response-body-match-size'] = '4096'
otd_setHealthCheckProperties(props)

```

### See Also

[help](#), [otd\\_getHealthCheckProperties](#)

## 2.194 otd\_setHttpListenerProperties

### Description

Use this command to set the following HTTP listener properties:

Property	Description	Comments
<code>enabled</code>	Whether the listener is enabled at runtime. Range of values: true or false. Default: true.	
<code>ip</code>	IP address on which to listen. Range of values: *, a hostname, or an IP address.	
<code>port</code>	Port on which to listen. Range of values: port number between 1 and 65535, inclusive.	
<code>acceptor-threads</code>	Number of threads dedicated to accepting connections received by this listener. Range of values: 1 - 128. Default: auto-tuned.	
<code>server-name</code>	Default server name. May include a scheme (for example, <code>http://</code> ) prefix and port (for example, <code>:80</code> ) suffix . Can be a hostname, fully qualified domain name, IP address, or a URL prefix that contains one. The URL prefix must not specify a path.	

Property	Description	Comments
blocking-io	Whether the server uses blocking IO. Range of values: true or false. Default: false.	
blocking-accept	Enables/Disables blocking of the server Listen Socket while retaining client end points as non blocking (useful when MaxProcs > 1). Range of values: true or false. Default: false.	
handle-protocol-mismatch	Range of values: true or false. Default: true.	
family	The socket family used to connect to the origin server. Range of values: default, inet, inet6, or inet-sdp Default: auto-tuned.	
listen-queue-size	Maximum size of the operating system listen queue backlog. Range of values: 1 - 1048576. Default: 128.	
receive-buffer-size	Size (in bytes) of the operating system socket receive buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	
send-buffer-size	Size (in bytes) of the operating system socket send buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.	
max-requests-per-connection	Maximum number of keep-alive requests that will be handled per HTTP connection after which the keep-alive connection will be closed. -1 indicates no limit. Range of values: 1-, any positive Integer Default: -1.	
default-virtual-server-name	Name of the virtual server that processes requests that did not match a host.	
description	Description of the HTTP listener for the administrator's reference.	

### Syntax

```
otd_setHttpListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory
http-listener	Name that uniquely identifies the HTTP listener.	Mandatory

**Example**

```

props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
props['max-requests-per-connection'] = '1024'
otd_setHttpListenerProperties(props)

```

**See Also**

[help](#), [otd\\_createHttpListener](#), [otd\\_getHttpListenerProperties](#), [otd\\_listHttpListeners](#), [otd\\_deleteHttpListener](#)

## 2.195 otd\_setHttpProperties

**Description**

Use this command to set the following HTTP properties for a configuration:

Property	Description
server-header	Specifies the server header information such as server software and version. Default: Oracle-Traffic-Director/<version>
etag	Indicates if the server includes an Etag header field in its responses. Range of values: true or false. Default: true.
request-header-buffer-size	Size (in bytes) of buffer used to read HTTP request header. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 8192.
strict-request-headers	Whether the server rejects certain malformed HTTP request headers Range of values: true or false. Default: false.
websocket-strict-upgrade	Enables/Disables the strict RFC 6455 adherence during the WebSocket upgrade request. Range of values: true or false. Default: false.
discard-misquoted-cookies	Whether to discard misquoted cookies. Range of values: true or false. Default: true.
max-request-headers	Maximum number of header fields to allow in an HTTP request header. Range of values: 1 - 512. Default: 64.
body-buffer-size	Defines the maximum size of the request body content that OTD will expose via the \$body variable in obj.conf. Range of values: size in bytes between 0 and 2147483647, inclusive Default: 1024.
output-buffer-size	Size (in bytes) of buffer used to buffer HTTP responses. Range of values: size in bytes between 0 and 2147483647, inclusive Default: 8192.

Property	Description
max-unchunk-size	Maximum size (in bytes) of a chunked HTTP request body the server will unchunk. Range of values: size in bytes between 0 and 2147483647, inclusive Default: 8192.
unchunk-timeout	Maximum time (in seconds) the server will spend waiting for a chunked HTTP request body to arrive. Range of values: an interval in seconds between 0 and 3600 (1 hour), inclusive. -1 indicates no timeout. Default: 60.
io-timeout	Maximum time (in seconds) server will wait for an individual packet. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 30.
request-body-timeout	Maximum time (in seconds) server will wait for the complete HTTP request body. Range of values: an interval in seconds between 0 and 604800 (1 week), inclusive. -1 indicates no timeout. Default: -1.
request-header-timeout	Maximum time (in seconds) server will wait for the complete HTTP request header. Range of values: an interval in seconds between 0 and 3600 (1 hour), inclusive. -1 indicates no timeout. Default: 30.
favicon	Whether the server replies to requests for favicon.ico with its own built in icon file. Range of values: true or false. Default: true.
ecid	Whether the server generates/propagates Execution Context and logs it with its error log. Range of values: true or false. Default: true.

### Syntax

```
otd_setHttpProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set as described above):

Property	Description	Comments
configuration	Name of the configuration.	

### Example

```
props = {}
props['configuration'] = 'foo'
props['unchunk-timeout'] = '120'
otd_setHttpProperties(props)
```

### See Also

[help, otd\\_getHttpProperties](#)

## 2.196 otd\_setHttpListenerSslProperties

### Description

Use this command to set the SSL properties for a listener. SSL is a software library establishing a secure connection between the client and server. SSL is used to implement HTTPS, the secure version of HTTP. You can set the following properties:

Property	Description
enabled	Whether SSL/TLS is enabled at runtime. Range of values: true or false. Default: true.
client-auth	Client certificate authentication method. Range of values: one of required, optional, or false. Default: false.
client-auth-timeout	Timeout (in seconds) after which client authentication handshake fails. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 60.
max-client-auth-data	Maximum amount of application-level data to buffer during a client authentication handshake. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 1048576.
tls10	Whether TLS 1.0 connections are accepted. Range of values: true or false. Default: false.
tls11	Whether TLS 1.1 connections are accepted. Range of values: true or false. Default: true.
tls12	Whether TLS 1.2 connections are accepted. Range of values: true or false. Default: true.
ciphers	Comma separated list of ciphers that must be enabled. Range of values: one (or) more ciphers that are supported. For a list of supported ciphers, see <a href="#">Ciphers</a> . Default: all supported ciphers are enabled by default.
override-cipher-order	Whether cipher order should be overridden. Setting this flag to true will make OTD select the cipher suites in the order specified in server.xml instead of the order specified in the client's ClientHello message. Range of values: true or false. Default: false.
supported-ciphers	List of supported ciphers. This is a read-only property. Range of values: for a list of supported ciphers, see <a href="#">Ciphers</a> . Default: N.A.
server-cert-alias	Comma separated list of server certificate aliases present in the keystore. Maximum of one RSA server certificate alias and one EC server certificate alias.

 **Note:**

The command `otd_setHttpListenerSslProperties` will enable ssl implicitly if `server-cert-alias` is set for the first time. It will enable ssl, even though `ssl=enabled` is not explicitly set.

**Syntax**

```
otd_setHttpListenerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory
<code>http-listener</code>	Name of the HTTP listener.	Mandatory

**Example**

```
props = {}
props['configuration'] = 'foo'
props['http-listener'] = 'http-listener-1'
props['tls10'] = 'false'
otd_setHttpListenerSslProperties(props)
```

**See Also**

[help](#), [otd\\_getTcpListenerSslProperties](#)

## 2.197 otd\_setHttpThreadPoolProperties

**Description**

Use this command to set the thread-pool properties for a configuration. The `min-threads` and `max-threads` properties configure the threads used to process HTTP requests. You can use thread pools to allocate a certain number of threads to a specific service. By defining a pool with the maximum number of threads as 1, only one request is allowed to the specified service function.

You can set the following properties:

Property	Description
<code>enabled</code>	Whether the thread pool is enabled or not. Range of values: true or false. Default: true.

Property	Description
queue-size	Maximum number of concurrent HTTP connections that can be queued waiting for processing. Range of values: 1 - 1048576. Default: auto-tuned.
min-threads	Minimum number of HTTP request processing threads. Range of values: 1 - 20480. Default: auto-tuned.
max-threads	Maximum number of HTTP request processing threads. Range of values: 1 - 20480. Default: auto-tuned.
stack-size	Stack size (in bytes) for HTTP request processing threads. Range of values: stack size in bytes between 8192 and 268435456, inclusive. 0 indicates that the platform-specific default stack size should be used. Default: 262144.

### Syntax

```
otd_setThreadPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory

### Example

```
props = {}
props['configuration'] = 'foo'
props['stack-size'] = '8192'
otd_setThreadPoolProperties(props)
```

### See Also

[help, otd\\_getThreadPoolProperties](#)

## 2.198 otd\_setKeepaliveProperties

### Description

Sets the following keep-alive subsystem properties:

Property	Description
enabled	Whether the server supports keep-alive connections. Range of values: true or false. Default: true.



Property	Description
threads	Number of keep-alive subsystem threads. Range of values: 1 - 256. Default: auto-tuned.
max-connections	Maximum number of concurrent keep-alive connections the server will support. Range of values: 1 - 1048576. Default: auto-tuned.
timeout	Timeout (in seconds) after which inactive keep-alive connection may be closed. Range of values: an interval in seconds between 0.001 (1 millisecond) and 3600 (1 hour), inclusive. -1 indicates no timeout. Default: 30.
poll-interval	Interval (in seconds) between polls. Range of values: an interval in seconds between 0.001 and 1, inclusive. Default: 0.001.

### Syntax

```
otd_setKeepaliveProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory

### Example

```
props = {}
props['configuration'] = 'foo'
props['threads'] = '128'
otd_setKeepaliveProperties(props)
```

### See Also

[help](#), [otd\\_getKeepaliveProperties](#)

## 2.199 otd\_setLogProperties

### Description

Use this command to set the following log properties:

Property	Description
log-stdout	Whether the server logs data that applications write to stdout. Range of values: true or false. Default: true.

Property	Description
log-stderr	Whether the server logs data that applications write to stderr. Range of values: true or false. Default: true.
log-virtual-server-name	Whether the server includes the virtual server name in log messages. Range of values: true or false. Default: false.
create-console	(Windows only) Whether the server creates a console window. Range of values: true or false. Default: false.
log-to-console	Whether the server writes log messages to the console. Range of values: true or false. Default: true.
log-to-syslog	Whether the server writes log messages to syslog (Unix) or the Event Viewer (Windows). Range of values: true or false. Default: false.
archive-command	Command executed after the server rotates a log file. The file name of the log file, after rotation, is passed as an argument to the archive command.
log-level	Log verbosity for the server as a whole. Range of values: valid log levels are INCIDENT_ERROR:1, ERROR:1, ERROR:16, ERROR:32, WARNING:1, NOTIFICATION:1, TRACE:1, TRACE:16, and TRACE:32. TRACE:32 (finest) is the most verbose while INCIDENT_ERROR:1 (catastrophe) is the least verbose. Default: NOTIFICATION:1.
log-file	Log file for the server as a whole. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/server.log.

### Syntax

```
otd_setLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory

### Example

```
props = {}
props['configuration'] = 'foo'
props['log-level'] = 'TRACE:32'
otd_setLogProperties(props)
```

### See Also

[help](#), [otd\\_getLogProperties](#), [displayLogs](#)

## 2.200 otd\_setOriginServerPoolSslProperties

### Description

Use this command to set the SSL properties of the origin server pool.

Property	Description
enabled	Whether SSL/TLS is enabled at runtime. Range of values: true or false. Default: true.
tls10	Whether TLS 1.0 connections are accepted. Range of values: true or false. Default: false.
tls11	Whether TLS 1.1 connections are accepted. Range of values: true or false. Default: true.
tls12	Whether TLS 1.2 connections are accepted. Range of values: true or false. Default: true.
validate-server-cert	Only applies to outgoing connections. Validate SSL certificate hostname on/off flag. Range of values: true or false. Default: true.
ciphers	Comma separated list of ciphers that must be enabled. Range of values: one (or) more ciphers that are supported. For a list of supported ciphers, see <a href="#">Ciphers</a> . Default: all supported ciphers are enabled by default.
supported-ciphers	List of supported ciphers. This is a read-only property. Range of values: for a list of supported ciphers, see <a href="#">Ciphers</a> . Default: n/a
client-cert-alias	A valid client certificate alias present in the keystore. Maximum of one RSA server certificate alias and one EC server certificate alias.

### Syntax

```
otd_setOriginServerPoolSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory
origin-server-pool	Name of the origin server pool.	Mandatory

**Example**

```
props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['tls10'] = 'false'
otd_setOriginServerPoolSslProperties(props)
```

**See Also**[help](#)

## 2.201 otd\_setOriginServerPoolProperties

**Description**

Use this command to set the following origin-server pool properties:

Property	Description	Comments
family	The socket family used to connect to servers in this pool. Range of values: default, inet, inet6, or inet-sdp. Default: auto-tuned.	
load-distribution	Algorithm that is used for load distribution of this server pool. Range of values: round-robin, least-connection-count, or least-response-time. Default: least-connection-count.	
queue-timeout	Timeout (in seconds) for which the request waits in the queue for a connection to an origin-server. After the timeout, request is rejected. Range of values: 0.001 - 3600. Default: 30.	
proxy-server	Name of the proxy-server in the form of host:port.	

**Syntax**

```
otd_setOriginServerPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
origin-server-pool	Name of the origin server pool.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
```

```
props['origin-server-pool'] = 'origin-server-pool-1'
props['load-distribution'] = 'least-connection-count'
otd_setOriginServerPoolProperties(props)
```

**See Also**

[help](#), [otd\\_getOriginServerPoolProperties](#), [otd\\_listOriginServerPools](#), [otd\\_deleteOriginServerPool](#), [otd\\_createOriginServerPool](#)

## 2.202 otd\_setOriginServerProperties

**Description**

Use this command to set the following properties of an origin-server:

Property	Description
mode	Mode of this origin server. Range of values: enabled, disabled, draining. Default: enabled.
weight	Load distribution weight for this origin server. Range of values: 1 - 1000. Default: 1.
backup	The parameter specifies if the origin server is a backup server. Range of values: true or false. Default: false.
max-connections	The maximum number of concurrent connections to a server. -1 indicates that there is no maximum. Range of values: -1, 1 - 1048576. Default: -1.
ramp-up-time	The time in seconds to ramp the sending rate up to the capacity of a newly up origin server. If the parameter is not specified, request rate accelerating will not be activated for the server. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 0.001.
max-requests-per-connection	Maximum limit on times a connection to origin server can be reused for different requests. -1 indicates there is no limit. Range of values: -1, 1 - 2147483647. Default: -1.
max-request-bps	Total bandwidth limit in byte/second enforced on request. Range of values: 0 - 1099511627776. Default: 0.
max-response-bps	Total bandwidth limit in byte/second enforced on response. Range of values: 0 - 1099511627776. Default: 0.
bandwidth-queue-timeout	Request is aborted when it had to wait in the queue for bandwidth for this much time in second. Range of values: 0 - 86400. Default: 60.

### Syntax

```
otd_setOriginServerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties (in addition to the properties that can be set):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory
origin-server-pool	Name of the origin server pool.	Mandatory
host	IP address/Host name of the origin server.	Mandatory
port	Port number of the origin server.	Mandatory

### Example

```

props = {}
props['configuration'] = 'foo'
props['origin-server-pool'] = 'origin-server-pool-1'
props['host'] = 'www.example.com'
props['port'] = '12345'
props['ramp-up-time'] = '1200'
otd_setOriginServerProperties(props)

```

### See Also

[help](#), [otd\\_getOriginServerProperties](#), [otd\\_listOriginServers](#), [otd\\_deleteOriginServer](#), [otd\\_createOriginServer](#)

## 2.203 otd\_setPartitionAccessLogProperties

### Description

Use this command to set the access-log properties for a partition.

Property	Description
log-file	Path to the file where access logs for this partition will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/\$PARTITION_NAME.log
format	A format is a string that can be used to customize the format and the fields that are logged in the partition access log. Default: %Ses->client.ip% - %Req->vars.auth-user% %SYSDATE% "%Req->reqpb.clf-request%" %Req->srvhdrs.clf-status% %Req->srvhdrs.content-length% %Req->vars.ecid% %Req->vars.origin-server%

### Syntax

```
otd_setPartitionAccessLogProperties (props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
configuration	Name of the configuration. This must be the name of the configuration that is specified while registering the Oracle Traffic Director runtime with the Lifecycle Manager.	Mandatory.
partition	Name of the partition.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'mt'
props['partition'] = 'WLSPartition'
props['log-file'] = 'logs/WLSPartition.log'
otd_setPartitionAccessLogProperties(props)
```

**See Also**

[help](#), [otd\\_listPartitions](#), [otd\\_getPartitionAccessLogProperties](#)

## 2.204 otd\_setRequestLimitProperties

**Description**

Use this command to set the following request limit properties for a virtual server:

Property	Description	Comments
condition	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	
max-rps	Maximum number of requests that the virtual server can receive per second. Range of values: any positive Integer.	
max-connections	Maximum number of concurrent matching connections. Range of values: any positive Integer.	
queue-size	Maximum number of requests to be queued in the bucket. Range of values: any positive Integer. Default: 0.	
timeout	Request is aborted when it had to wait in the queue for this much time in second. Range of values: 1 - 86400. Default: 60.	
error-code	HTTP status code to return for blocked requests. Range of values: 400 - 599. Default: 503.	
monitor-attribute	Request attribute to monitor.	

**Syntax**

```
otd_setRequestLimitProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.
<code>request-limit</code>	Name of the request limit rule.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['request-limit'] = 'request-limit-1'
props['max-connections'] = '1024'
otd_setRequestLimitProperties(props)
```

### See Also

[help](#), [otd\\_getRequestLimitProperties](#), [otd\\_listRequestLimits](#), [otd\\_deleteRequestLimit](#), [otd\\_createRequestLimit](#)

## 2.205 otd\_setRouteProperties

### Description

Use this command to set the following route properties for a virtual server.

Property	Description	Comments
<code>condition</code>	A condition is an expression which if evaluates to true, will result in the rule being executed. Conditions are constructed from literals, variables, functions and operators.	<code>condition</code> cannot be set for the <code>uri-prefix</code> based routes.
<code>uri-prefix</code>	A <code>uri-prefix</code> is a URI path with wildcard patterns. If a request URI matches with the <code>uri-prefix</code> then the rule will be executed.	<code>uri-prefix</code> cannot be set for the <code>condition</code> based routes.
<code>origin-server-pool</code>	Name of the origin server pool for this route.	
<code>offline-check-interval</code>	Specifies the offline check interval.	
<code>server</code>	Specifies the server name.	
<code>sticky-cookie</code>	Name of the cookie that causes subsequent requests to stick to a particular origin server. Default: JSESSIONID.	



---

Property	Description	Comments
sticky-param	Name of a URI parameter to inspect for route information. When the URI parameter is present in a request URI and its value contains a colon :, followed by a route ID, the request will 'stick' to the origin server identified by that route ID. Default: jsessionid.	
route-header	Name of the HTTP request header that is used to communicate route IDs to the origin servers. Default: Proxy-jroute.	
route-cookie	Name of the cookie generated by the server when it encounters a sticky-cookie cookie in a response. The route-cookie parameter stores the route ID that enables the server to direct subsequent requests back to the same origin server. Default: ORA_OTD_JROUTE.	
rewrite-headers	List of HTTP request headers separated by commas.	
use-keep-alive	Whether the HTTP client can use existing persistent connections for all types of requests. Range of values: true of false. Default: true.	
keep-alive-timeout	Maximum number (in seconds) to retain persistent connectivity. Range of values: any positive Integer. Default: 29.	
timeout	Maximum number (in seconds) that a connection can be in a idle state. Range of values: any positive Integer. Default: 300.	
always-use-keep-alive	Whether the HTTP client can reuse existing connections for all types of requests. Range of values: true of false. Default: false.	
protocol	Specifies the HTTP protocol version.	
proxy-agent	Whether the proxy server product name and version has to be forwarded to the origin servers.	
from	URI prefix to map. The prefix must not contain trailing slashes.	
to	URL prefix to which the request should be mapped. The prefix must not contain trailing slashes.	
log-headers	If true, the HTTP request and response headers for all connections with origin servers will be logged in the server log file. Range of values: true or false. Default: false.	

---

Property	Description	Comments
websocket-upgrade-enabled	Specifies whether standard HTTP(S) connections should be upgraded to bi-directional, full-duplex WebSocket connections.  Range of values: true or false. Default: true.	
websocket-idle-timeout	The maximum number of seconds a connection can be idle. If no value is specified, then the timeout from the TCP connection thread pool (300 seconds) is used.  Range of values: -1 or 0 - 3600.	
buffer-size	The size of the buffer that is used by the server to store data before it is sent to the client.  Range of values: any positive Integer. Default: 16384.	
priority	The priority of the request.  Range of values: high, normal, low. Default: normal.	

### Syntax

```
otd_setRouteProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.
route	Name of the route.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['route'] = 'route-1'
props['websocket-idle-timeout'] = '1200'
otd_setRouteProperties(props)
```

### See Also

[help](#), [otd\\_getRouteProperties](#), [otd\\_listProxyInfo](#), [otd\\_forwardProxyInfo](#), [otd\\_blockProxyInfo](#), [otd\\_listRoutes](#), [otd\\_deleteRoute](#), [otd\\_createRoute](#)

## 2.206 otd\_setSnmpProperties

### Description

Use this command to enable and define these settings for the SNMP subagents.

Property	Description
enabled	Whether SNMP is enabled. Range of values: true or false. Default: true.
description	Description of the server, or unknown.
organization	Organization responsible for the server, or unknown.
location	Location of the server, or unknown.
contact	Contact information of the person responsible for the server, or unknown.

### Syntax

```
otd_setSnmpProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['organization'] = 'bar'
otd_setSnmpProperties(props)
```

### See Also

[help](#), [otd\\_getSnmpProperties](#), [otd\\_startSnmpSubAgent](#), [otd\\_stopSnmpSubAgent](#)

## 2.207 otd\_setSslSessionCacheProperties

### Description

Use this command to set the SSL session cache properties.

Property	Description
enabled	Whether the server caches SSL/TLS sessions. Range of values: true or false. Default: true.
max-entries	Maximum number of SSL/TLS sessions the server will cache. Range of values: 1 - 524288. Default: 10000.
max-ssl3-tls-session-age	Maximum amount of time to cache an TLS session. Range of values: 1 - 86400. Default: 86400.

### Syntax

```
otd_setSslSessionCacheProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['max-entries'] = '20000'
otd_setSslSessionCacheProperties(props)
```

### See Also

[help, otd\\_getSslSessionCacheProperties](#)

## 2.208 otd\_setStatsProperties

### Description

Use this command to set these properties of the statistics collection subsystem.

Property	Description
enabled	Whether the server collects statistics at runtime. Range of values: true or false. Default: true.
interval	Interval (in seconds) at which statistics are updated. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 5.

Property	Description
profiling	Whether performance buckets, used to track NSAPI function execution time, are enabled. Range of values: true or false. Default: true.

**Syntax**

```
otd_setStatsProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['interval'] = '10'
otd_setStatsProperties(props)
```

**See Also**

[help, otd\\_getStatsProperties](#)

## 2.209 otd\_setStatusListenerSslProperties

**Description**

Use this command to change the SSL properties of the Status Listener.

**Syntax**

```
otd_setStatusListenerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
enabled	Specifies if SSL is enabled for status listener. Values: True or false. Default: True	

### Example 2-17 Example

```
props = {}
props['configuration'] = 'foo'
props['enabled'] = 'false'
otd_setStatusListenerSslProperties(props)
```

#### See Also

[otd\\_enableStatusListener](#), [otd\\_disableStatusListener](#),  
[otd\\_getStatusListenerProperties](#), [otd\\_getStatusListenerSslProperties](#)

## 2.210 [otd\\_setTcpAccessLogProperties](#)

### Description

Use this command to set the properties of the TCP access log.

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
log-file	Path to the file where the TCP access log for this configuration will be stored. Default: \$DOMAIN_HOME/servers/\$INSTANCE_NAME/logs/tcp-access.log	

### Syntax

```
otd_setTcpAccessLogProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['log-file'] = 'logs/tcp-access.log'
otd_setTcpAccessLogProperties(props)
```

#### See Also

[help](#), [otd\\_getTcpAccessLogProperties](#)

## 2.211 [otd\\_setTcpListenerProperties](#)

### Description

Use this command to set the TCP listener properties.

Property	Description
port	Port on which to listen. Range of values: port number between 1 and 65535, inclusive.
ip	IP address on which to listen. Range of values: *, a hostname, or an IP address. Default: *.
acceptor-threads	Acceptor threads for this listening end point. Range of values: 1 - 128. Default: auto-tuned.
enabled	Whether the instance is enabled. Range of values: true or false. Default: true.
description	Description of the TCP listener for the administrator's reference.
family	Protocol family. Range of values: default, inet, inet6, or inet-sdp. Default: auto-tuned.
listen-queue-size	Maximum size of the operating system listen queue backlog. Range of values: 1 - 1048576. Default: 128.
receive-buffer-size	Size (in bytes) of the operating system socket receive buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.
send-buffer-size	Size (in bytes) of the operating system socket send buffer. Range of values: size in bytes between 0 and 2147483647, inclusive.
blocking-accept	Enables/Disables blocking of the server Listen Socket while retaining client end points as non blocking (useful when <code>MaxProcs &gt; 1</code> ). Range of values: true or false. Default: false.
tcp-proxy	Name that identifies the exposed TCP service. Name can consist of one or more characters, whitespace is not permitted.

### Syntax

```
otd_setTcpListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-listener	Name of the TCP listener.	Mandatory.

**Example**

```

props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
props['listen-queue-size'] = '256'
otd_setTcpListenerProperties(props)

```

**See Also**

[help](#), [otd\\_createTcpListener](#), [otd\\_deleteTcpListener](#), [otd\\_listTcpListeners](#), [otd\\_getTcpListenerProperties](#)

## 2.212 otd\_setTcpListenerSslProperties

**Description**

Use this command to set the Secure Sockets Layer (SSL) properties for a TCP listener:

Property	Description
enabled	Whether SSL/TLS is enabled at runtime. Range of values: true or false. Default: true.
client-auth	Client certificate authentication method. Range of values: one of required, optional, or false. Default: false.
client-auth-timeout	Timeout (in seconds) after which client authentication handshake fails. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 60.
max-client-auth-data	Maximum amount of application-level data to buffer during a client authentication handshake. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 1048576.
tls11	Whether TLS 1.1 connections are accepted. Range of values: true or false. Default: true.
tls12	Whether TLS 1.2 connections are accepted. Range of values: true or false. Default: true.
ciphers	Comma separated list of ciphers that must be enabled. Range of values: one (or) more ciphers that are supported. For a list of supported ciphers, see <a href="#">Ciphers</a> . Default: all supported ciphers are enabled by default.
override-cipher-order	Whether cipher order should be overridden. Setting this flag to true will make OTD select the cipher suites in the order specified in server.xml instead of the order specified in the client's ClientHello message. Range of values: true or false. Default: false.



Property	Description
supported-ciphers	List of supported ciphers. This is a read-only property. Range of values: for a list of supported ciphers, see <a href="#">Ciphers</a> . Default: N.A.
server-cert-alias	Comma separated list of server certificate aliases present in the keystore. Maximum of one RSA server certificate alias and one EC server certificate alias.

**Syntax**

```
otd_setTcpListenerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-listener	Name of the TCP listener.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['tcp-listener'] = 'tcp-listener-1'
props['tls10'] = 'false'
otd_setTcpListenerSslProperties(props)
```

**See Also**

[help](#), [otd\\_getTcpListenerSslProperties](#)

## 2.213 otd\_setTcpProxyProperties

**Description**

Use this command to set the following properties of the TCP proxy for a configuration:

In addition, use this command to set FTP configuration properties on the TCP proxy in addition to the existing TCP properties if the TCP proxy is created with the property protocol as FTP.

**Syntax**

```
otd_setTcpProxyProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set (as described above):

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
tcp-proxy	Name that uniquely identifies the exposed TCP service.	Mandatory.
enabled	Indicates whether the TCP service is enabled. Range of values: true or false.	
session-idle-timeout	Maximum timeout in seconds for load balancer to wait for receiving/sending data in the session. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive.	
origin-server-pool	Name of an existing server pool that provides the TCP service.	
protocol	If the protocol is FTP, the FTP configuration properties can be set/get on the TCP proxy. Default value: *	This is a <b>read-only</b> property.
client-explicit-ftp	Specifies if client-side SSL should be explicitly enabled. Default value: true	Valid only if protocol is ftp.
origin-explicit-ftp	Specifies if server-side SSL should be explicitly enabled. Default value: true	Valid only if protocol is ftp.
ssl-termination	Specifies if SSL should terminate at Oracle® Fusion Middleware. Default value: false	Valid only if protocol is ftp.
passive-port-min	Specifies the lower limit of port range for FTP passive connections. Default value: 1025	Valid only if protocol is ftp.
passive-port-max	Specifies the upper limit of port range for FTP passive connections. Default value: 65535	Valid only if protocol is ftp.
active-port-min	Specifies the lower limit of port range for FTP active connections. Default value: 1025	Valid only if protocol is ftp.
active-port-max	Specifies the upper limit of port range for FTP active connections. Default value: 65535	Valid only if protocol is ftp.

### Example

When `protocol` property is not FTP-enabled.

```
props = {}
props['configuration'] = 'foo'
props['tcp-proxy'] = 'bar'
props['session-idle-timeout'] = '1200'
otd_setTcpProxyProperties(props)
```

When `protocol` property is `ftp` for a TCP proxy and `client-side` SSL is enabled explicitly.

```

props = {}
props['configuration'] = 'foo'
props['tcp-proxy'] = 'bar'
props['client-explicit-https'] = 'true'
otd_setTcpProxyProperties(props)

```

**See Also**

[help](#), [otd\\_createTcpProxy](#), [otd\\_deleteTcpProxy](#), [otd\\_listTcpProxies](#), [otd\\_getTcpProxyProperties](#)

## 2.214 otd\_setTcpThreadPoolProperties

**Description**

Use this command to set the thread-pool properties of a configuration. The properties configure the threads used to proxy data for upgraded WebSocket connections and generic TCP connections. You can use TCP thread pools to allocate a certain number of threads to a specific service.

You can set the following properties:

Property	Description
enabled	Whether the pool is enabled or not. Range of values: true or false. Default: true.
threads	Number of threads in the proxy thread-pool. Range of values: 1 - 512. Default: auto-tuned.
max-connections	Maximum number of connection pairs the server will support. Range of values: 1 - 1048576. Default: auto-tuned.
timeout	Idle timeout (in seconds) after which connection pairs will be closed. Value will be overridden by the TCP or WebSocket subsystem. Range of values: an interval in seconds between 0.001 (1 millisecond) and 3600 (1 hour), inclusive. -1 indicates no timeout. Default: 300.
poll-interval	Interval (in seconds) between polls. Range of values: an interval in seconds between 0.001 and 1, inclusive. Default: 0.01.
buffer-size	Size of the buffer in bytes used for transferring data. Range of values: 512 - 1048576. Default: 16384.
stack-size	Stack size in bytes for each thread. Range of values: stack size in bytes between 8192 and 268435456, inclusive. 0 indicates that the platform-specific default stack size should be used. Default: 32768.

**Syntax**

```
otd_setTcpThreadPoolProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['stack-size'] = '8192'
otd_setTcpThreadPoolProperties(props)
```

### See Also

[help](#), [otd\\_getTcpThreadPoolProperties](#)

## 2.215 otd\_setVirtualServerProperties

### Description

Use this command to set the properties of a virtual-server.

Property	Description
enabled	Whether the virtual server is enabled at runtime. Range of values: true or false. Default: true.
canonical-server-name	Canonical hostname of the virtual server (requests using a different hostname will be redirected to this hostname). Can be a Hostname, fully qualified domain name, ip address, or a url prefix that contains one. the url prefix must not specify a path.
log-file	Log file for the virtual server.
http-listener-name	Name of an HTTP listener associated with one or more of the virtual server's host hostnames. Multiple comma separated values can be specified.
host	Hostname the virtual server services. Multiple comma separated values can be specified where each value can be a wildcard pattern that matches one or more hostnames.
default-language	An IANA language tag specifying the default language for messages displayed to administrators and content served to clients.
negotiate-client-language	Whether the server attempts to use the Accept-language HTTP header to negotiate the content language with clients. Range of values: true or false. Default: false.

### Syntax

```
otd_setVirtualServerProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to the properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

**Example**

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['http-listener-name'] = 'http-listener-1'
otd_setVirtualServerProperties(props)
```

**See Also**

[help](#), [otd\\_deleteVirtualServer](#), [otd\\_getVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#)

## 2.216 otd\_setVirtualServerSslProperties

**Description**

Use this command to set the SSL properties for a virtual server.

Property	Description
enabled	Whether SSL/TLS is enabled at runtime. Range of values: true or false. Default: true.
client-auth	Client certificate authentication method. Range of values: one of required, optional, or false. Default: false.
client-auth-timeout	Timeout (in seconds) after which client authentication handshake fails. Range of values: an interval in seconds between 0.001 and 3600 (1 hour), inclusive. Default: 60.
max-client-auth-data	Maximum amount of application-level data to buffer during a client authentication handshake. Range of values: size in bytes between 0 and 2147483647, inclusive. Default: 1048576.
tls10	Whether TLS 1.0 connections are accepted. Range of values: true or false. Default: false.
tls11	Whether TLS 1.1 connections are accepted. Range of values: true or false. Default: true.
tls12	Whether TLS 1.2 connections are accepted. Range of values: true or false. Default: true.

Property	Description
ciphers	Comma separated list of ciphers that must be enabled. Range of values: one (or) more ciphers that are supported. For a list of supported ciphers, see <a href="#">Ciphers</a> . Default: all supported ciphers are enabled by default.
override-cipher-order	Whether cipher order should be overridden. Setting this flag to true will make OTD select the cipher suites in the order specified in server.xml instead of the order specified in the client's ClientHello message. Range of values: true or false. Default: false.
supported-ciphers	List of supported ciphers. This is a read-only property. Range of values: for a list of supported ciphers, see <a href="#">Ciphers</a> . Default: N.A.
server-cert-alias	Comma separated list of server certificate aliases present in the keystore. Maximum of one RSA server certificate alias and one EC server certificate alias.

### Syntax

```
otd_setVirtualServerSslProperties(props)
```

The argument `props` is a dictionary that can contain the following properties in addition to those properties that can be set:

Property	Description	Comments
configuration	Name of the configuration.	Mandatory.
virtual-server	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['tls10'] = 'false'
otd_setVirtualServerSslProperties(props)
```

### See Also

[help](#), [otd\\_getVirtualServerSslProperties](#)

## 2.217 otd\_setWalletPassword

### Description

Sets the password on a wallet.

### Syntax

```
otd_setWalletPassword(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>password</code>	Password consisting of a minimum length of 8 characters and contain alphabetic characters combined with numbers or special characters.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['password'] = 'barBazqux#'
otd_setWalletPassword(props)
```

### See Also

[help](#), [exportKeyStoreCertificateRequest](#), [otd\\_listCertificates](#), [importKeyStoreCertificate](#), [getKeyStoreCertificates](#), [generateKeyPair](#)

## 2.218 otd\_setWebappFirewallProperties

### Description

Use this command to set the following properties of a web application firewall:

Property	Description	Comments
<code>ruleset</code>	Path to a file containing Web Application Firewall (WAF) rules/ configuration	Multi-valued.

### Syntax

```
otd_setWebappFirewallProperties(props)
```

The argument `props` is a dictionary that must contain the following keys in addition to the properties that can be set:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-server</code>	Name of the virtual server.	Mandatory.

### Example

```
props = {}
props['configuration'] = 'foo'
props['virtual-server'] = 'bar'
props['ruleset'] = 'rulesets'
otd_setWebappFirewallProperties(props)
```

**See Also**

[help](#), [otd\\_createVirtualServer](#), [otd\\_setVirtualServerProperties](#), [otd\\_listVirtualServers](#), [otd\\_copyVirtualServer](#), [otd\\_deleteVirtualServer](#), [otd\\_getVirtualServerProperties](#)

## 2.219 otd\_startFailover

**Description**

Use this command to start the failover daemon on the local machine. Since the failover daemon needs to run as root, you should execute this command should with `sudo` privileges on the host on which the primary/backup instance of the failover group is running to start the failover on the instance.

This command can only be run in offline mode.

**Syntax**

```
otd_startFailover(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the directory that contains the Oracle Traffic Director domain.	Mandatory.
instance-name	Name of the primary/backup Oracle Traffic Director instance which is part of the failover group.	Mandatory.
log-verbose	Whether keepalived should be started in verbose log level mode. Default: false.	

**Example**

```
props = {}
props['domain-home'] = '/export/domains/otd_domain'
props['instance-name'] = 'otd_abcl23.example.com'
otd_startFailover(props)
```

**See Also**

[help](#), [otd\\_createFailoverGroup](#), [otd\\_deleteFailoverGroup](#), [otd\\_toggleFailoverGroupPrimary](#), [otd\\_stopFailover](#)

## 2.220 otd\_startSnmpSubAgent

**Description**

Use this command to start the Oracle Traffic Director Simple Network Management Protocol (SNMP) sub-agent on the specified machine.

**Syntax**

```
otd_startSnmpSubAgent(props)
```



The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
machine-name	Name specified while creating the machine in the Oracle WebLogic Server console, corresponding to the host name of the machine on which the Oracle Traffic Director instance is running.	Mandatory for Online, not valid for Offline.
domain-home	Path to the directory that contains the Oracle Traffic Director domain.	Mandatory for Offline, not valid for Online.

### Example

```
# Online
props = {}
props['machine-name'] = 'abc123.example.com'
otd_startSnmpSubAgent(props)

# Offline
props = {}
props['domain-home'] = '/export/domains/otd_domain'
otd_startSnmpSubAgent(props)
```

### See Also

[help](#), [otd\\_stopSnmpSubAgent](#), [otd\\_setSnmpProperties](#), [otd\\_getSnmpProperties](#)

## 2.221 otd\_stopFailover

### Description

Use this command to stop the failover daemon on the local machine. Since the failover daemon needs to run as root, execute this command with `sudo` privileges on the host on which the primary/backup instance of the failover group is running to stop the failover on the instance.

This command can only be run in offline mode.

### Syntax

```
otd_stopFailover(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
domain-home	Path to the directory that contains the Oracle Traffic Director domain.	Mandatory.
instance	Name of the primary/backup Oracle Traffic Director instance which is part of the failover group.	Mandatory.

### Example

```
props = {}
props['domain-home'] = '/export/otd_domain'
props['instance'] = 'otd_abc123.example.com'
otd_stopFailover(props)
```

**See Also**

[help](#), [otd\\_createFailoverGroup](#), [otd\\_deleteFailoverGroup](#),  
[otd\\_toggleFailoverGroupPrimary](#), [otd\\_startFailover](#)

## 2.222 otd\_stopSnmpSubAgent

**Description**

Use this command to stop the Simple Network Management Protocol (SNMP) sub-agent on the specified machine.

**Syntax**

```
otd_stopSnmpSubAgent(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
machine-name	Name specified while creating the machine in the Oracle WebLogic Server console, corresponding to the host name of the machine on which the Oracle Traffic Director instance is running.	Mandatory for Online, not valid for Offline.
domain-home	Path to the directory that contains the Oracle Traffic Director domain.	Mandatory for Offline, not valid for Online.

**Example**

```
# Online
props = {}
props['machine-name'] = 'host.example.com'
otd_stopSnmpSubAgent(props)

# Offline
props = {}
props['domain-home'] = '/export/domains/otd_domain'
otd_stopSnmpSubAgent(props)
```

**See Also**

[help](#), [otd\\_startSnmpSubAgent](#), [otd\\_setSnmpProperties](#), [otd\\_getSnmpProperties](#)

## 2.223 otd\_toggleFailoverGroupPrimary

**Description**

Use this command to toggle the primary and backup instances in a failover group. This command is valid only when failover type is `active-passive`. If the failover is running already, you should execute the `stopFailover` and `startfailover` scripts on the hosts where the instances are running. This is to manually toggle the nodes. If this command is not executed, the instances will not be toggled. Also, when you execute [otd\\_getFailoverGroupProperties](#), the result will show the configured primary and the backup instances, which will not be the same as the runtime primary and backup instances.

### Syntax

```
otd_toggleFailoverGroupPrimary(props)
```

The argument `props` is a dictionary that can contain the following properties:

Property	Description	Comments
<code>configuration</code>	Name of the configuration.	Mandatory.
<code>virtual-ip</code>	Virtual IP that uniquely identifies the failover group.	Mandatory.

### Example

```

props = {}
props['configuration'] = 'foo'
props['virtual-ip'] = '192.0.2.1'
otd_toggleFailoverGroupPrimary(props)

```

### See Also

[help](#), [otd\\_deleteFailoverGroup](#), [otd\\_createFailoverGroup](#),  
[otd\\_getFailoverGroupProperties](#), [otd\\_startFailover](#), [otd\\_stopFailover](#)

## 2.224 pullComponentChanges

### Description

Pulls configuration files from a particular instance of the configuration to the config store in the admin server. The pulled configuration files overwrite their corresponding server versions and any pending changes (conflicting with the pulled configuration files) on the admin server are lost.

After executing this command, you must execute the command `enableOverwriteComponentChanges` before `activate`. Otherwise, `activate` will fail because of the local modifications on the instance.

#### Note:

This command can only be executed from an open edit session. You must execute the command `activate` for the pulled configuration changes to be deployed across all the instances of the configuration.

### Syntax

```
pullComponentChanges(<instance_name>)
```

The argument `<instance_name>` is the name of the instance and is mandatory.

### Example

```
startEdit()

pullComponentChanges('otd_test.example.com')
pull component otd_test.example.com changes on machine example.com:
add OTD/test/config/foo.conf
edit OTD/test/config/server.xml
edit OTD/test/config/test-obj.conf
remove OTD/test/config/obj.conf

activate()
```

### See Also

[help](#), [enableOverwriteComponentChanges](#), [resync/resyncAll](#),  
[showComponentChanges](#), [stopEdit](#), [undo](#)

## 2.225 resync/resyncAll

### Description

Over writes the modifications on an instance or all instances with their corresponding server versions from the admin server.

### Syntax

```
resync(<instance_name>) / resyncAll()
```

The argument <instance\_name> is the name of the instance and is mandatory.

#### Note:

This command cannot be executed from an open edit session. See [enableOverwriteComponentChanges](#) and [activate](#) for overriding instance changes within an open edit session.

### Example

```
# resync
showComponentChanges('otd_test.example.com')
add OTD/test/config/bar.conf 1970.01.01-05:30:00 2014.11.07-17:35:15
edit OTD/test/config/proxyvs.obj.conf 2014.11.07-17:36:49 1970.01.01-05:29:59
edit OTD/test/config/server.xml 2014.11.07-17:36:49 2014.11.07-17:37:22
remove OTD/test/config/test-obj.conf 2014.11.07-17:36:49 1970.01.01-05:30:00

resync('otd_test.example.com')

showComponentChanges('otd_test.example.com')
component otd_test.example.com changes on machine example.com: no change found.

# resyncAll
showComponentChanges()
component otd_test.example.com changes on machine example.com:
add OTD/test/config/baz.conf 1970.01.01-05:30:00 2014.11.07-17:42:57
```

```
component otd_origin-server-1.example.com changes on machine example.com:
add OTD/origin-server-1/config/bar.conf 1970.01.01-05:30:00 2014.11.07-17:43:34

resyncAll()

showComponentChanges()
component otd_test.example.com changes on machine example.com: no change found.
component otd_origin-server-1.example.com changes on machine example.com: no change
found.
```

### See Also

[help](#), [enableOverwriteComponentChanges](#), [pullComponentChanges](#),  
[showComponentChanges](#), [stopEdit](#), [undo](#)

## 2.226 showComponentChanges

### Description

Lists all the configuration file modifications on instances.

### Syntax

```
showComponentChanges(<instance_name>)
```

The argument `<instance_name>` is the name of the instance and is optional. If not specified, the command will display the modifications across all the instances.

#### Note:

Configuration changes in Oracle Traffic Director sometimes requires changes to multiple files such as `server.xml`, `obj.conf`, and `magnus.conf`. Hence configuration changes in Oracle Traffic Director should either be overridden or pulled with these files treated as a unit in order to avoid inconsistencies. As a result, even if one of these files is modified, all of them will be shown as modified since they are treated as a file unit.

### Example

```
showComponentChanges()
component otd_test.example.com changes on machine example.com: no change found.
component otd_origin-server-1.example.com changes on machine example.com: no change
found.
component otd_origin-server-2.example.com changes on machine example.com: no change
found.
component otd_origin-server-3.example.com changes on machine example.com: no change
found.

showComponentChanges('otd_test.example.com')
add OTD/test/config/foo.conf 1970.01.01-05:30:00 2014.11.07-17:06:30
edit OTD/test/config/server.xml 2014.11.06-19:48:15 2014.11.07-17:06:08
edit OTD/test/config/test-obj.conf 2014.11.06-16:59:32 1970.01.01-05:29:59
remove OTD/test/config/obj.conf 2014.11.06-19:48:15 1970.01.01-05:30:00
```

**See Also**

[help](#), [enableOverwriteComponentChanges](#), [pullComponentChanges](#), [resync/resyncAll](#), [stopEdit](#), [undo](#)

## 2.227 softRestart

**Description**

Use this WLST command to restart or reconfigure the instance

Reconfigure dynamically applies configuration changes on instances without a server restart. Only dynamically reconfigurable changes in the configuration take effect. Changes in the `user`, `temp-path`, `log`, `thread-pool`, `pkcs11`, `stats`, `dns`, `dns-cache`, `ssl-session-cache`, and `access-log-buffer` settings remain the same after a reconfiguration procedure is completed. A Restart-required exception will be thrown if there are any such changes that require restart when a reconfiguration is done.

 **Note:**

Ensure that you are connected to the Administration Server while running this command.

**Syntax**

```
softRestart(name, [block], [properties])
```

Argument	Definition
<i>name</i>	Name of the system component to restart.
<i>block</i>	Optional. Boolean value specifying whether WLST should block user interaction until the server is restarted.
<i>properties</i>	Optional. Properties value specifying properties to pass to the system component.

**Example**

Reconfiguring the instance:

```
props = java.util.Properties()
props.setProperty("MODE", "RECONFIG")
cmo.softRestart(props)
```

Restarting the instance:

```
cmo.softRestart(java.util.Properties())
```

**See Also**

[help](#), [otd\\_deleteInstance](#), [otd\\_listInstances](#), [start](#), [stop](#), [otd\\_createInstance](#)

## 2.228 start

### Description

Starts an instance.



#### Note:

Ensure that you are connected to the Administration Server while running this command.

### Syntax

```
start(name, [type])
```

Argument	Definition
<i>name</i>	Name of the system component to start.
<i>type</i>	Optional. <code>Type</code> , <code>Server</code> or <code>Cluster</code> . This argument defaults to <code>Server</code> . When starting a cluster, you must set this argument explicitly to <code>Cluster</code> , or the command will fail.

### Example

```
start('otd_foo_machine1')
```

### See Also

[help](#), [otd\\_deleteInstance](#), [otd\\_listInstances](#), [otd\\_createInstance](#), [stop](#), [softRestart](#)

## 2.229 state

### Description

Returns the state of an instance.



#### Note:

Ensure that you are connected to the Administration Server while running this command.

### Syntax

```
state(name, [type])
```

Argument	Definition
<i>name</i>	Name of the server, cluster, or system component for which you want to retrieve the current state.

Argument	Definition
<i>type</i>	Optional. Type is <code>Server</code> , <code>Cluster</code> , or <code>SystemComponent</code> . If not specified, WLST will look for a server, cluster, or system component with the specified name.

**Example**

```
state('otd_test.in.example.com')
```

**See Also**

[help](#)

## 2.230 stop

**Description**

Stops an instance.

 **Note:**

Ensure that you are connected to the Administration Server while running this command.

**Syntax**

```
stop(name, [type])
```

**Example**

```
stop('host.example.com', 'SystemComponent')
```

**See Also**

[help](#), [otd\\_deleteInstance](#), [otd\\_listInstances](#), [otd\\_createInstance](#), [stop](#), [softRestart](#)

## 2.231 stopEdit

**Description**

Stops the edit session, discards unsaved changes and releases the edit lock.

**Syntax**

```
stopEdit([defaultAnswer])
```

Argument	Definition
<i>defaultAnswer</i>	Optional. Default response, if you would prefer not to be prompted at the command line. Valid values are <code>y</code> and <code>n</code> . This argument defaults to null, and WLST prompts you for a response.



### Example

The following example stops the current editing session. WLST prompts for verification before canceling.

```
wls:/mydomain/edit !> stopEdit()
Sure you would like to stop your edit session? (y/n)
y
Edit session has been stopped successfully.
wls:/mydomain/edit>
```

### See Also

[help](#), [enableOverwriteComponentChanges](#), [pullComponentChanges](#), [resync/resyncAll](#), [showComponentChanges](#), [undo](#)

## 2.232 undo

### Description

This command reverts all unsaved (`undo()`) or unactivated (`undo('true')`) edits. This command does not release the edit session. The effect of this command is not limited to Oracle Traffic Director. All the changes done after starting an edit session to the various other components and managed servers will also be reverted.

### Syntax

```
undo([unactivatedChanges], [defaultAnswer])
```

Argument	Definition
<i>unactivatedChanges</i>	Optional. Boolean value specifying whether to undo all unactivated changes, including edits that have been saved to disk. This argument defaults to false, indicating that all edits since the last <code>save</code> operation are reverted.
<i>defaultAnswer</i>	Optional. Default response, if you would prefer not to be prompted at the command line. Valid values are <code>y</code> and <code>n</code> . This argument defaults to null, and WLST prompts you for a response.

### Example

The following example reverts all changes since the last save operation. WLST prompts for verification before reverting.

```
wls:/mydomain/edit !> undo()
Sure you would like to undo your changes? (y/n)
y
Discarded your in-memory changes successfully.
wls:/mydomain/edit>
```

The following example reverts all unactivated changes. WLST prompts for verification before reverting.

```
wls:/mydomain/edit !> undo('true')
Sure you would like to undo your changes? (y/n)
y
```

```
Discarded all your changes successfully.  
wls:/mydomain/edit>
```

**See Also**

[help](#), [enableOverwriteComponentChanges](#), [pullComponentChanges](#), [resync/resyncAll](#), [showComponentChanges](#), [stopEdit](#)