Oracle® Banking Virtual Account Management
Oracle FLEXCUBE Universal Banking Integration Guide

ORACLE®

Oracle Banking Virtual Account Management Oracle FLEXCUBE Universal Banking Integration Guide, Release 14.8.0.0.0

G29408-01

Contents

Preface

1   Integration Guide

Index

Preface

- [Purpose](#)
- [Audience](#)
- [Documentation Accessibility](#)
- [Diversity and Inclusion](#)
- [Related Resources](#)
- [Conventions](#)
- [Screenshot Disclaimer](#)
- [Acronyms and Abbreviations](#)

Purpose

This guide describes the systematic instruction to integrate Oracle Banking Virtual Account Management with Oracle FLEXCUBE Universal Banking and its specific maintenances.

Audience

This guide is primarily intended for the following user/user roles:

Table 1   Audience

Role	Function
Implementation and IT Staff	Implementation and maintenance of the software

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also

mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Related Resources

The related documents are as follows:

- *Oracle Banking Security Management System User Guide*
- *Oracle Banking Common Core User Guide*
- *Oracle Banking Getting Started User Guide*
- *Configuration User Guide*
- Common Core - Gateway User Guide

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
`monospace`	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Screenshot Disclaimer

Personal information used in the interface or documents are dummy and does not exist in the real world. It is only for reference purposes.

Acronyms and Abbreviations

The list of acronyms and abbreviations that are used in this guide are as follows:

Table 2   Acronyms and Abbreviations

Abbreviation	Description
DDA	Demand Deposit Account
ECA	External Credit Approval
GL	General Ledger

1

Integration Guide

This topic provides information on the integration of Oracle Banking Virtual Account Management with Oracle FLEXCUBE Universal Banking.

This topic contains the following subtopics:

- Maintenance for Oracle FLEXCUBE Universal Banking
  This topic describes the maintenance for Oracle FLEXCUBE Universal Banking.
- Structured Address Replication in Oracle FLEXCUBE Universal Banking Minicore
  This topic describes the structured address replication in Oracle FLEXCUBE Universal Banking minicore.
- Maintenance for Oracle Banking Virtual Account Management
  This topic describes the maintenance for Oracle Banking Virtual Account Management.

1.1 Maintenance for Oracle FLEXCUBE Universal Banking

This topic describes the maintenance for Oracle FLEXCUBE Universal Banking.

Specify **User ID** and **Password**, and login to **Oracle FLEXCUBE Universal Banking Home** screen.

Gateway setup should be done in Oracle FLEXCUBE Universal Banking for the particular source system by performing the below-listed maintenance.
Refer to **Common Core - Gateway User Guide** in Oracle FLEXCUBE Universal Banking for a detailed explanation.

Upload Source Maintenance
Maintain the source code for Oracle Banking Virtual Account Management in the **Upload Source Maintenance** screen.

1. On **Home** screen, specify **CODSORCE**, and click **Next** arrow.

   The **Upload Source Maintenance** screen displays.

   Figure 1-1   Upload Source Maintenance

   Upload Source Preferences Maintenance

Maintain the module code for IF, CA and ST modules in the **Upload Source Preferences Maintenance** screen.

2. On **Home** screen, specify **CODUPLDM**, and click **Next** arrow.

    The **Upload Source Preferences Maintenance** screen displays.

Figure 1-2   Upload Source Preferences Maintenance

External System Maintenance
Maintain the external system for Oracle Banking Virtual Account Management in the **External System Maintenance** screen.

3. On **Home** screen, specify **GWDETSYS**, and click **Next** arrow.

    The **External System Maintenance** screen displays.

Figure 1-3   External System Maintenance

External System Functions
Maintain the below functions and actions for Oracle Banking Virtual Account Management in the **External System Functions** screen.

Table 1-1   External System Functions - Parameter Setup

Function	Action
IFGEXACC	NEW
STQVALAC	VIEW
CAGECABL	NEW
CAGECABL	CLOSE

4. On **Home** screen, specify **GWDETFUN**, and click **Next** arrow.

   The **External System Functions** screen displays.

Figure 1-4   External System Functions

1.2 Structured Address Replication in Oracle FLEXCUBE Universal Banking Minicore

This topic describes the structured address replication in Oracle FLEXCUBE Universal Banking minicore.

Specify **User ID** and **Password**, and login to Oracle FLEXCUBE Universal Banking.

Gateway setup should be done in Oracle FLEXCUBE Universal Banking to replicate the Structured Address for a particular source system by performing maintenance in the below-mentioned screens, to use the web services exposed by Oracle FLEXCUBE Universal Banking Minicore for Structured Address so that we can push the data from Oracle Banking Virtual Account Management Common Core to Oracle FLEXCUBE Universal Banking Minicore. Refer to **Common Core - Gateway User Guide** in Oracle FLEXCUBE Universal Banking for a detailed explanation.

External System Functions Maintenance
Maintain the below functions and actions for Oracle Banking Virtual Account Management in the **External System Functions** screen.

1. On **Home** screen, specify **GWDETFUN**, and click **Next** arrow.

   The **External System Functions** screen displays.

Figure 1-5   External System Functions

2. Click **New** and click **Search** icon in the **Function** field.

    The **List of Values Function** screen displays.

Figure 1-6   List of Values Function

Table 1-2   External System Functions - Parameter Setup

Function	Action
STGACCAD	AUTHORIZE
STGACCAD	MODIFY
STGACCAD	OPEN
STGACCAD	CLOSE

3. Select the above Function Id, and click **OK** to save the record.

    Record will be saved and authorized successfully.

External System Function Summary
Maintain the External System Functions for the below function and actions.

External System: Oracle Banking Virtual Account Management

Function Id: STGACCAD

4. On **Home** screen, specify **GWSETFUN**, and click **Next** arrow.

The **External System Function Summary** screen displays.

Figure 1-7   External System Function Summary

1.3 Maintenance for Oracle Banking Virtual Account Management

This topic describes the maintenance for Oracle Banking Virtual Account Management.

Specify **User ID** and **Password**, and login to **Home** screen.

Refer to *Oracle Banking Common Core User Guide* and *Configuration User Guide* for a detailed explanation.

ECA System Maintenance
Maintain ECA system in common core for Oracle FLEXCUBE Universal Banking.

1. On **Home** screen, click **Core Maintenance**. Under **Core Maintenance**, click **ECA System**.

2. Under **ECA System**, click **Create ECA System**.

The **Create ECA System** screen displays.

Figure 1-8   Create ECA System

External Customer Maintenance

Common Core **External Customer** should replicate the Real Customer from Oracle FLEXCUBE Universal Banking. In addition, the source system should be maintained the same as the one created in the **ECA System Maintenance** screen.

3. On **Home** screen, click **Core Maintenance**. Under **Core Maintenance**, click **External Customer**.

4. Under **External Customer**, click **Create External Customer**.

   The **Create External Customer** screen displays.

Figure 1-9   Create External Customer

External Customer Account Maintenance

Common Core **External Account** should replicate the Real Account from Oracle FLEXCUBE Universal Banking. In addition, External Credit Approval System should be the source system maintained in the **ECA System Maintenance** screen.

5. On **Home** screen, click **Core Maintenance**. Under **Core Maintenance**, click **External Customer Account**.

6. Under **External Customer Account**, click **Create External Customer Account**.

   The **Create External Customer Account** screen displays.

Figure 1-10   Create External Customer Account

External Chart Account Maintenance
Common Core **External Chart** should replicate the GL value from Oracle FLEXCUBE Universal Banking. The GL should be present in the STTB_ACCOUNT table in Oracle FLEXCUBE Universal Banking.

7. On **Home** screen, click **Core Maintenance**. Under **Core Maintenance**, click **External Chart Account**.

8. Under **External Chart Account**, click **Create External Chart Account**.

    The **Create External Chart Account** screen displays.

Figure 1-11   Create External Chart Account

Transaction Code Maintenance
Maintain a valid transaction code from Oracle FLEXCUBE Universal Banking.

9. On **Home** screen, click **Core Maintenance**. Under **Core Maintenance**, click **Transaction Code**.

10. Under **Transaction Code**, click **Create Transaction Code**.

    The **Create Transaction Code** screen displays.

Figure 1-12   Create Transaction Code

**External DDA System Maintenance**
Maintain External DDA details, the offset GL, and EAC Required.

11. On **Home** screen, click **Virtual Account Management**. Under **Virtual Account Management**, click **Configuration**.

12. Under **Configuration**, click **External DDA System**.

13. Under **External DDA System**, click **Create External DDA System**.

    a. Search and Select the Default Offset GL maintained in Common Core External Chart.

    b. Select the toggle whether EAC is required or not.

The **Create External DDA System** screen displays.

Figure 1-13   Create External DDA System

Index