



# BEA WebLogic Integration™

## Writing Messages to the B2B Integration Log

## Copyright

Copyright © 2002 BEA Systems, Inc. All Rights Reserved.

## Restricted Rights Legend

This software and documentation is subject to and made available only pursuant to the terms of the BEA Systems License Agreement and may be used or copied only in accordance with the terms of that agreement. It is against the law to copy the software except as specifically allowed in the agreement. This document may not, in whole or in part, be copied photocopied, reproduced, translated, or reduced to any electronic medium or machine readable form without prior consent, in writing, from BEA Systems, Inc.

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the BEA Systems License Agreement and in subparagraph (c)(1) of the Commercial Computer Software-Restricted Rights Clause at FAR 52.227-19; subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013, subparagraph (d) of the Commercial Computer Software--Licensing clause at NASA FAR supplement 16-52.227-86; or their equivalent.

Information in this document is subject to change without notice and does not represent a commitment on the part of BEA Systems. THE SOFTWARE AND DOCUMENTATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. FURTHER, BEA Systems DOES NOT WARRANT, GUARANTEE, OR MAKE ANY REPRESENTATIONS REGARDING THE USE, OR THE RESULTS OF THE USE, OF THE SOFTWARE OR WRITTEN MATERIAL IN TERMS OF CORRECTNESS, ACCURACY, RELIABILITY, OR OTHERWISE.

## Trademarks or Service Marks

BEA, Jolt, Tuxedo, and WebLogic are registered trademarks of BEA Systems, Inc. BEA Builder, BEA Campaign Manager for WebLogic, BEA eLink, BEA Manager, BEA WebLogic Commerce Server, BEA WebLogic E-Business Platform, BEA WebLogic Enterprise, BEA WebLogic Express, BEA WebLogic Integration, BEA WebLogic Personalization Server, BEA WebLogic Portal, BEA WebLogic Server and How Business Becomes E-Business are trademarks of BEA Systems, Inc.

All other trademarks are the property of their respective companies.

## Writing Messages to the B2B Integration Log

<b>Part Number</b>	<b>Date</b>	<b>Software Version</b>
N/A	January 2002	2.1 Service Pack 1

---

# Contents

## About This Document

What You Need to Know .....	v
e-docs Web Site .....	vi
How to Print this Document .....	vi
Contact Us! .....	vi
Documentation Conventions .....	vii

## 1. Writing to the Log

About the Log .....	1-1
Log Files .....	1-1
Logging API .....	1-2
Severity Levels .....	1-2
Writing Messages to the Log .....	1-3
Importing the Logging Package .....	1-3
Writing a Log Message with an INFO Severity Level .....	1-3
Writing a Message with a Specific Severity Level .....	1-4

## Index



---

# About This Document

This document describes how to write messages to the B2B integration log.

## What You Need to Know

This document is intended primarily for:

- Business process designers who use the WebLogic Integration Studio to design workflows that can be integrated with the WebLogic Integration environment.
- Application developers who write Java applications that manage the exchange of business messages or monitor run-time statistics in the WebLogic Integration environment.
- System administrators who set up and administer WebLogic Integration applications.

---

# e-docs Web Site

The WebLogic Integration product documentation is available on the BEA e-docs Web site at <http://e-docs.bea.com>.

## How to Print this Document

You can print a copy of this document from a Web browser, one file at a time, by using the File→Print option on your Web browser.

A PDF version of this document is available from the WebLogic Integration documentation Home page, which is available on the documentation CD and on the e-docs Web site at <http://e-docs.bea.com>. You can open the PDF in Adobe Acrobat Reader and print the entire document, or a portion of it, in book format. To access the PDFs, open the WebLogic Integration documentation Home page, click the PDF Files button, and select the document you want to print.

If you do not have the Adobe Acrobat Reader installed, you can download it for free from the Adobe Web site at <http://www.adobe.com/>.

## Contact Us!

Your feedback on the WebLogic Integration documentation is important to us. Send us e-mail at [docsupport@bea.com](mailto:docsupport@bea.com) if you have questions or comments. Your comments will be reviewed directly by the BEA professionals who create and update the WebLogic Integration documentation.

In your e-mail message, please indicate which release of the product and documentation you are using.

If you have questions about this version of WebLogic Integration, or if you have problems installing and running WebLogic Integration, contact BEA Customer Support at <http://www.bea.com/support>. You can also contact Customer Support by using the contact information provided on the Customer Support Card, which is included in the product package.

When contacting Customer Support, be prepared to provide the following information:

- Your name, e-mail address, phone number, and fax number
- Your company name and company address
- Your machine type and authorization codes
- The name and version of the product you are using
- A description of the problem and the content of pertinent error messages

## Documentation Conventions

The following documentation conventions are used throughout this document.

<b>Convention</b>	<b>Item</b>
Ctrl+Tab	Indicates that you must press two or more keys simultaneously.
<i>italics</i>	Indicates emphasis or book titles.

---

<b>Convention</b>	<b>Item</b>
monospace text	<p>Indicates code samples, commands and their options, data structures and their members, data types, directories, and filenames and their extensions. Monospace text also indicates text that you must enter from the keyboard.</p> <p><i>Examples:</i></p> <pre>#include &lt;iostream.h&gt; void main ( ) the pointer psz chmod u+w * \tux\data\ap .doc tux.doc BITMAP float</pre>
<i>monospace</i> <i>italic</i> text	<p>Identifies variables in code.</p> <p><i>Example:</i></p> <pre>String expr</pre>
UPPERCASE TEXT	<p>Indicates device names, environment variables, and logical operators.</p> <p><i>Examples:</i></p> <pre>LPT1 SIGNON OR</pre>
{ }	<p>Indicates a set of choices in a syntax line. The braces themselves should never be typed.</p>
[ ]	<p>Indicates optional items in a syntax line. The brackets themselves should never be typed.</p> <p><i>Example:</i></p> <pre>buildobjclient [-v] [-o name] [-f file-list]... [-l file-list]...</pre>
	<p>Separates mutually exclusive choices in a syntax line. The symbol itself should never be typed.</p>

---

Convention	Item
...	<p>Indicates one of the following in a command line:</p> <ul style="list-style-type: none"><li>■ That an argument can be repeated several times in a command line</li><li>■ That the statement omits additional optional arguments</li><li>■ That you can enter additional parameters, values, or other information</li></ul> <p>The ellipsis itself should never be typed.</p> <p><i>Example:</i></p> <pre>buildobjclient [-v] [-o name] [-f file-list]... [-l file-list]...</pre>
.	<p>Indicates the omission of items from a code example or from a syntax line.</p> <p>The vertical ellipsis itself should never be typed.</p>

---



# 1 Writing to the Log

The following sections describe how to write messages to the B2B integration log:

- [About the Log](#)
- [Writing Messages to the Log](#)

## About the Log

The B2B engine uses the Logging API to write error, warning, and information messages to a log file.

## Log Files

Logged messages are written to the following locations:

- WebLogic Integration system log file (`b2b.log`) and the WebLogic Integration B2B Console (if it is running)
- WebLogic Server log file (`weblogic.log`) and the WebLogic Server Administration Console (if it is running)

The `b2b.log` system log file is created automatically when WebLogic Integration starts up. The size of this file is limited to 1MB. When this maximum is exceeded, the file is renamed with a numeric label (such as `b2b1.log`) and a new empty file is created.

## Logging API

The `com.bea.eci.logging` package contains the Logging API, which consists of the classes described in the following table.

**Table 1-1 Logging API**

Name	Description
<code>Log</code>	Defines severity levels for log messages.
<code>UserLog</code>	Represents a user log. Provides access to the log for users. The user log is defined as a user log output stream (with a <code>&lt;user&gt;</code> tag) in the system log.

For detailed information about these classes, see the *BEA WebLogic Integration Javadoc* on the WebLogic Integration documentation CD or in the `classdocs` subdirectory of your WebLogic Integration installation.

## Severity Levels

The `Log` class defines the severity levels described in the following table.

**Table 1-2 Severity Levels Defined in Log Class**

Level	Severity	Indicates an occurrence of . . .
1	FATAL	A fatal error; a system component failed abnormally due to the exception that was detected.
2	ERROR	A critical error; system stability is affected.
3	WARNING	A minor exception; normal operation or system stability may not be affected.
4	INFO	No exception or failure; indicates only a message reporting normal operations, not exception conditions. An example of such a message is logging the successful startup of the WebLogic Integration B2B Console.

# Writing Messages to the Log

WebLogic Integration applications can write messages to the log using the `log` method in the `UserLog` class. The `log` method records a message in the user log and does one of the following:

- Specifies the level of severity as `FATAL`, `ERROR`, `WARNING`, or `INFO`.
- Does not specify the level of severity, which then defaults to `INFO`.

In addition, applications can access the print stream to the user log using `UserLog.out`.

## Importing the Logging Package

To write to the log, WebLogic Integration applications must import the `com.bea.eci.logging` package, as shown in the following listing.

### **Listing 1-1 Importing the `com.bea.eci.logging` Package**

---

```
import com.bea.eci.logging.*;
```

---

## Writing a Log Message with an INFO Severity Level

To write a log message with an `INFO` severity level, an application can use the following version of the `log` method:

```
static void log(java.lang.String userMsg)
```

In the preceding line, `userMsg` is the message text to be logged.

# 1 Writing to the Log

---

When you use this version of the log method, the severity in the log defaults to `INFO`. The following listing shows how to write a log message with an `INFO` severity level.

## Listing 1-2 Writing an INFO Message to the Log

---

```
private static void debug(String msg){
    if (DEBUG)
        UserLog.log("***Partner1Servlet: "+msg);
}
```

---

## Writing a Message with a Specific Severity Level

To write a log message with a specific severity level, an application uses the following version of the `log` method:

```
static void log(int severity, java.lang.String userMsg)
```

In the preceding line:

- `severity` is the severity level (`FATAL`, `ERROR`, `WARNING`, or `INFO`).
- `userMsg` is the message text to be logged.

The following listing shows how to write a log message with a `WARNING` severity level.

## Listing 1-3 Writing a WARNING Message to the Log

---

```
private static void debug(String msg){
    if (DEBUG)
        UserLog.log(Log.WARNING, msg);
}

try {
} catch (Exception e) {
    debug("Partner1 exception errors");
    e.printStackTrace(UserLog.out);
}
```

---

---

# Index

- A**  
API, logging 1-2  
audience v
- C**  
com.bea.eci.logging package 1-2  
customer support contact information vi
- D**  
documentation, where to find it vi
- E**  
error levels 1-2  
ERROR severity level 1-2, 1-4
- F**  
FATAL severity level 1-2, 1-4
- I**  
importing packages 1-3  
INFO severity level 1-2, 1-3
- J**  
Java Classes  
    Log 1-2  
    UserLog 1-2
- L**  
Log Class 1-2  
log files 1-1  
Logging API 1-2
- P**  
packages, com.com.bea.eci.logging 1-2  
printing product documentation vi
- S**  
severity levels 1-2  
support, technical vii
- U**  
UserLog Class 1-2
- W**  
WARNING severity level 1-2, 1-4

