Oracle® Construction and Engineering Using the Oracle Primavera Unifier Adapter with Oracle Integration 3





Oracle Construction and Engineering Using the Oracle Primavera Unifier Adapter with Oracle Integration 3,

F78935 06

Copyright © 2023, 2025, Oracle and/or its affiliates.

Primary Author: Oracle Corporation

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Understand the Primavera Unifier Adapter	
Primavera Unifier Adapter Capabilities	1-1
Primavera Unifier Adapter Restrictions	1-1
What Application Version Is Supported?	1-2
Workflow to Create and Add a Primavera Unifier Adapter Connection to an Integration	1-2
Create a Primavera Unifier Adapter Connection	
Prerequisites for Creating a Connection	2-1
Create a Connection	2-1
Configure Connection Properties	2-3
Configure Connection Security	2-3
Test the Connection	2-3
Upload a Certificate to Connect with External Services	2-4
Add the Primavera Unifier Adapter Connection to an Integration	n
Basic Info Page	3-1
Trigger BP Selection Page	3-3
Invoke BP Selection Page	3-3
Summary Page	3-4



Preface

This guide describes how to configure this adapter as a connection in an integration in Oracle Integration.



The use of this adapter may differ depending on the features you have, or whether your instance was provisioned using Standard or Enterprise edition. These differences are noted throughout this guide.

Topics:

- Audience
- Documentation Accessibility
- Diversity and Inclusion
- Related Resources
- Conventions

Audience

This guide is intended for developers who want to use this adapter in integrations in Oracle Integration.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at https://www.oracle.com/corporate/accessibility/.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit https://support.oracle.com/portal/ or visit Oracle Accessibility Learning and Support if you are hearing impaired.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.



Related Resources

See these Oracle resources:

- Oracle Cloud at http://cloud.oracle.com
- Using Integrations in Oracle Integration 3
- Using the Oracle Mapper with Oracle Integration 3
- Oracle Integration documentation
- Oracle Primavera Unifier documentation

Conventions

The following text conventions are used in this document:

Convention	Meaning	
boldface	Boldface type indicates graphical user interface elements associated with action, or terms defined in text or the glossary.	
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.	
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.	



1

Understand the Primavera Unifier Adapter

Review the following topics to learn about the Oracle Primavera Unifier Adapter and how to use it as a connection in integrations in Oracle Integration. A typical workflow of adapter and integration tasks is also provided.

Topics:

- Primavera Unifier Adapter Capabilities
- Primavera Unifier Adapter Restrictions
- What Application Version Is Supported?
- · Workflow to Create and Add a Primavera Unifier Adapter Connection to an Integration

Primavera Unifier Adapter Capabilities

The Primavera Unifier Adapter enables you to set up a connection with Primavera Unifier. You can use this connection in integrations to connect with Unifier.

You can use the Unifier Adapter to fetch, create, or update a Business Process (BP) record (without attachments) in Unifier. It provides for an easy selection of the BP needed for integration. Based on the BP you select, the fields defined in the integration interface of that BP are available for mappings.

The Unifier Adapter provides trigger (inbound) and invoke (outbound) support. As a trigger, the adapter enables you to send the BP record data to Oracle Integration for further processing. As an invoke, the adapter enables you to create, update, and fetch records from and into Unifier.

The Unifier Adapter is one of many predefined adapters included with Oracle Integration. You can configure the Unifier Adapter as an invoke or trigger connection in an integration in Oracle Integration.

Primavera Unifier Adapter Restrictions

Note the following Primavera Unifier Adapter restrictions.

- The adapter does not support Business Process (BP) record data deletion in Unifier.
- The adapter supports synchronizing only one type of BP record at a time.



There are overall service limits for Oracle Integration. A service limit is the quota or allowance set on a resource. See Service Limits.

What Application Version Is Supported?

For information about which application version is supported by this adapter, see the Connectivity Certification Matrix.

Workflow to Create and Add a Primavera Unifier Adapter Connection to an Integration

You follow a very simple workflow to create a connection with an adapter and include the connection in an integration in Oracle Integration.

This table lists the workflow steps for both adapter tasks and overall integration tasks, and provides links to instructions for each step.

Step	Description	More Information
1	Access Oracle Integration.	Go to https://instance_URL/ic/home
2	Create the adapter connections for the applications you want to integrate. The connections can be reused in multiple integrations and are typically created by the administrator.	Create a Primavera Unifier Adapter Connection
3	Create the integration. When you do this, you add trigger (source) and invoke (target) connections to the integration.	Create Integrations in <i>Using Integrations</i> in <i>Oracle Integration 3</i> and Add the Primavera Unifier Adapter Connection to an Integration
4	Map data between the trigger connection data structure and the invoke connection data structure.	Map Data in Using Integrations in Oracle Integration 3
5	(Optional) Create lookups that map the different values used by those applications to identify the same type of object (such as gender codes or country codes).	Manage Lookups in Using Integrations in Oracle Integration 3
6	Activate the integration.	Activate an Integration in Using Integrations in Oracle Integration 3
7	Monitor the integration on the dashboard.	Monitor Integrations During Runtime in Using Integrations in Oracle Integration 3
8	Track payload fields in messages during runtime.	Assign Business Identifiers for Tracking Fields in Messages and Track Integration Instances in <i>Using Integrations in Oracle</i> <i>Integration 3</i>



Step	Description		More Information
9	Manage errors at the integration level, connection level, or specific integration instance level. Note:		Manage Errors in Using Integrations in Oracle Integration 3
		Visit My Oracle Support (MOS) if you have a technical issue and/or if you have a question about the Primavera Unifier Adapter that you cannot resolve using information on the Manage Errors page.	



2

Create a Primavera Unifier Adapter Connection

A connection is based on an adapter. You define connections to the specific cloud applications that you want to integrate.

Topics:

- Prerequisites for Creating a Connection
- Create a Connection
- Upload a Certificate to Connect with External Services

Prerequisites for Creating a Connection

You must satisfy the following prerequisites to create a connection with the Primavera Unifier Adapter:

- Create an account in Primavera Unifier: Purchase a subscription to Primavera Unifier.
 When you subscribe, you receive the Primavera Unifier instance URL for your region and administrator credentials.
- Set up an Integration User Account with Basic or OAuth Authentication Type: An integration user account is a generic user account used to manage integrations between Unifier and other applications. You must set up an integration account with a Basic or OAuth authentication type. See Setting Up Integration Users with Basic Authentication and Setting Up Integration Users with OAuth Authentication in the Oracle Primavera Unifier Integration Interface Guide for details.



Use a dedicated integration user account for all Primavera Unifier Adapter connections within Oracle Integration. Ensure that the integration user account has the *Admin > Get* permission and the *Get*, *Create*, *and Update Business Process (BP)* permissions if you intend to use the Primavera Unifier Adapter for performing GET, POST, and PUT operations on BPs.

Create a Connection

Before you can build an integration, you must create the connections to the applications with which you want to share data.



You can also create a connection in the integration canvas. See why working with projects is preferred.

To create a connection in Oracle Integration:

- 1. Decide where to start:
 - Work in a project (see why working with projects is preferred).
 - a. In the navigation pane, click **Projects**.
 - **b.** Select the project name.
 - c. Click Integrations 2.
 - d. In the **Connections** section, click **Add** if no connections currently exist or + if connections already exist. The Create connection panel opens.
 - Work outside a project.
 - a. In the navigation pane, click **Design**, then **Connections**.
 - **b.** Click **Create**. The Create connection panel opens.
- 2. Select the adapter to use for this connection. To find the adapter, scroll through the list, or enter a partial or full name in the **Search** field.
- 3. Enter the information that describes this connection.

Element	Description
Name	Enter a meaningful name to help others find your connection when they begin to create their own integrations.
Identifier	Automatically displays the name in capital letters that you entered in the Name field. If you modify the identifier name, don't include blank spaces (for example, SALES OPPORTUNITY).
Role	Select the role (direction) in which to use this connection.
	Note : Only the roles supported by the adapter you selected are displayed for selection. Some adapters support all role combinations (trigger, invoke, or trigger and invoke). Other adapters support fewer role combinations.
	When you select a role, only the connection properties and security policies appropriate to that role are displayed on the Connections page. If you select an adapter that supports both invoke and trigger, but select only one of those roles, you'll get an error when you try to drag the adapter into the section you didn't select.
	For example, assume you configure a connection for the Oracle Service Cloud (RightNow) Adapter as only an invoke . Dragging the adapter to a trigger section in the integration produces an error.
Keywords	Enter optional keywords (tags). You can search on the connection keywords on the Connections page.
Description	Enter an optional description of the connection.



Element	Description
Share with other projects	Note : This field only appears if you are creating a connection in a project.
	Select to make this connection publicly available in other projects. Connection sharing eliminates the need to create and maintain separate connections in different projects.
	When you configure an adapter connection in a different project, the Use a shared connection field is displayed at the top of the Connections page. If the connection you are configuring matches the same type and role as the publicly available connection, you can select that connection to reference (inherit) its resources.
	See Add and Share a Connection Across a Project.

Click Create.

Your connection is created. You're now ready to configure the connection properties, security policies, and (for some connections) access type.

- 5. Follow the steps to configure a connection. The connection property and connection security values are specific to each adapter. Your connection may also require configuration with an access type such as a private endpoint or an agent group.
- Test the connection.

Configure Connection Properties

Enter connection information so your application can process requests.

- Go to the Properties section.
- 2. In the Connection URL field, specify your Primavera Unifier URL.

Configure Connection Security

Configure security for your Primavera Unifier Adapter connection.

- Go to the Security section.
- 2. In the **User Name** field, enter the Primavera Unifier integration user account username.
- 3. In the Password field, enter the Primavera Unifier integration user account password.



The Unifier Adapter uses the username and password to obtain and refresh the OAuth token used to connect with Unifier.

Test the Connection

Test your connection to ensure that it's configured successfully.



 In the page title bar, click **Test**. What happens next depends on whether your adapter connection uses a Web Services Description Language (WSDL) file. Only some adapter connections use WSDLs.

If Your Connection	Then
Doesn't use a WSDL	The test starts automatically and validates the inputs you provided for the connection.
Uses a WSDL	A dialog prompts you to select the type of connection testing to perform:
	 Validate and Test: Performs a full validation of the WSDL, including processing of the imported schemas and WSDLs. Complete validation can take several minutes depending on the number of imported schemas and WSDLs. No requests are sent to the operations exposed in the WSDL.
	 Test: Connects to the WSDL URL and performs a syntax check on the WSDL. No requests are sent to the operations exposed in the WSDL.

- Wait for a message about the results of the connection test.
 - If the test was successful, then the connection is configured properly.
 - If the test failed, then edit the configuration details you entered. Check for typos and verify URLs and credentials. Continue to test until the connection is successful.
- 3. When complete, click **Save**.

Upload a Certificate to Connect with External Services

Certificates allow Oracle Integration to connect with external services. If the external service/ endpoint needs a specific certificate, request the certificate and then import it into Oracle Integration.

If you make an SSL connection in which the root certificate does not exist in Oracle Integration, an exception error is thrown. In that case, you must upload the appropriate certificate. A certificate enables Oracle Integration to connect with external services. If the external endpoint requires a specific certificate, request the certificate and then upload it into Oracle Integration.

- 1. Sign in to Oracle Integration.
- In the navigation pane, click Settings, then Certificates.
 All certificates currently uploaded to the trust store are displayed on the Certificates page.
- 3. Click **Filter** to filter by name, certificate expiration date, status, type, category, and installation method (user-installed or system-installed). Certificates installed by the system cannot be deleted.
- Click **Upload** at the top of the page.The Upload certificate panel is displayed.
- Enter an alias name and optional description.
- 6. In the **Type** field, select the certificate type. Each certificate type enables Oracle Integration to connect with external services.
 - Digital Signature
 - X.509 (SSL transport)
 - SAML (Authentication & Authorization)
 - PGP (Encryption & Decryption)



Signing key

Digital Signature

The digital signature security type is typically used with adapters created with the Rapid Adapter Builder. See Learn About the Rapid Adapter Builder in Oracle Integration in *Using the Rapid Adapter Builder with Oracle Integration 3*.

- Click Browse to select the digital certificate. The certificate must be an X509Certificate.
 This certificate provides inbound RSA signature validation. See RSA Signature Validation in Using the Rapid Adapter Builder with Oracle Integration 3.
- Click Upload.

X.509 (SSL transport)

- Select a certificate category.
 - a. Trust: Use this option to upload a trust certificate.
 - i. Click Browse, then select the trust file (for example, .cer or .crt) to upload.
 - b. Identity: Use this option to upload a certificate for two-way SSL communication.
 - i. Click **Browse**, then select the keystore file (.jks) to upload.
 - ii. Enter the comma-separated list of passwords corresponding to key aliases.



When an identity certificate file (.jks) contains more than one private key, all the private keys must have the same password. If the private keys are protected with different passwords, the private keys cannot be extracted from the keystore.

- iii. Enter the password of the keystore being imported.
- c. Click Upload.

SAML (Authentication & Authorization)

- Note that Message Protection is automatically selected as the only available certificate
 category and cannot be deselected. Use this option to upload a keystore certificate with
 SAML token support. Create, read, update, and delete (CRUD) operations are supported
 with this type of certificate.
- 2. Click Browse, then select the certificate file (.cer or .crt) to upload.
- 3. Click Upload.

PGP (Encryption & Decryption)

- Select a certificate category. Pretty Good Privacy (PGP) provides cryptographic privacy and authentication for communication. PGP is used for signing, encrypting, and decrypting files. You can select the private key to use for encryption or decryption when configuring the stage file action.
 - a. **Private**: Uses a private key of the target location to decrypt the file.
 - Click Browse, then select the PGP file to upload.
 - ii. Enter the PGP private key password.



- **b. Public**: Uses a public key of the target location to encrypt the file.
 - Click Browse, then select the PGP file to upload.
 - ii. In the ASCII-Armor Encryption Format field, select Yes or No.
 - Yes shows the format of the encrypted message in ASCII armor. ASCII armor is a binary-to-textual encoding converter. ASCII armor formats encrypted messaging in ASCII. This enables messages to be sent in a standard messaging format. This selection impacts the visibility of message content.
 - No causes the message to be sent in binary format.
 - iii. From the **Cipher Algorithm** list, select the algorithm to use. Symmetric-key algorithms for cryptography use the same cryptographic keys for both encryption of plain text and decryption of cipher text. The following supported cipher algorithms are FIPS-compliant:
 - AES128
 - AES192
 - AES256
 - TDES
- c. Click Upload.

Signing key

A signing key is a secret key used to establish trust between applications. Signing keys are used to sign ID tokens, access tokens, SAML assertions, and more. Using a private signing key, the token is digitally signed and the server verifies the authenticity of the token by using a public signing key. You must upload a signing key to use the OAuth Client Credentials using JWT Client Assertion and OAuth using JWT User Assertion security policies in REST Adapter invoke connections. Only PKCS1- and PKCS8-formatted files are supported.

- Select Public or Private.
- Click Browse to upload a key file.
 If you selected Private, and the private key is encrypted, a field for entering the private signing key password is displayed after key upload is complete.
- 3. Enter the private signing key password. If the private signing key is not encrypted, you are not required to enter a password.
- 4. Click Upload.



Add the Primavera Unifier Adapter Connection to an Integration

When you select and place the Primavera Unifier Adapter into the trigger or invoke area of an integration, the Adapter Endpoint Configuration Wizard opens. This wizard guides you through configuration of the Primavera Unifier Adapter endpoint properties.

The following wizard pages guide you through configuration of the Primavera Unifier Adapter as an invoke in an integration.

Topics:

- Basic Info Page
- Trigger BP Selection Page
- Invoke BP Selection Page
- Summary Page

Basic Info Page

You can enter a name and description on the Basic Info page of each adapter in your integration.

Element	Description	
What do you want to call your endpoint?	Provide a meaningful name so that others can understand the responsibilities of this connection. You can include English alphabetic characters, numbers, underscores, and hyphens in the name. You can't include the following characters:	
	• No blank spaces (for example, My Inbound Connection)	
	 No special characters (for example, #;83& or righ(t) now4) 	
	except underscores and hyphens	
	No multibyte characters	
What does this endpoint do?	Enter an optional description of the connection's responsibilities. For example:	
	This connection receives an inbound request to	
	synchronize account information with the cloud application.	
Select Level	Select the level within Unifier where you want to execute the service. You can select Company or Shell .	




Element

Description

What action do you want to perform on the endpoint?

Select the HTTP action you want to perform. Select **GET** to retrieve an existing record, **POST** to create a new record, and **PUT** to update an existing record.





Element		Description
	i O	
	n	
	p	
	а	
	g	
	е	

Trigger BP Selection Page

Select the Business Process (BP) record that you want to create in Unifier.

Element	Description
Select BP at Company/Shell Level	Select the BP record you want to create in Unifier.



Based on the BP you select, the fields defined in the integration interface of that BP are available for mappings.

Invoke BP Selection Page

Select the Business Process (BP) record you want to fetch.

Element	Description
Select BP at Company/Shell Level	Select the BP record you want to fetch from Unifier.



Based on the BP you select, the fields defined in the integration interface of that BP are available for mappings.



Summary Page

You can review the specified adapter configuration values on the Summary page.

Element	Description
Summary	Displays a summary of the configuration values you defined on previous pages of the wizard.
	The information that is displayed can vary by adapter. For some adapters, the selected business objects and operation name are displayed. For adapters for which a generated XSD file is provided, click the XSD link to view a read-only version of the file.
	To return to a previous page to update any values, click the appropriate tab in the left panel or click Go back .
	To cancel your configuration details, click Cancel.

