

Oracle® Banking Corporate Lending

GATEWAY Property File Creation



Release 14.8.1.0.0
G43298-01
October 2025

ORACLE®

Oracle Banking Corporate Lending GATEWAY Property File Creation, Release 14.8.1.0.0

G43298-01

Copyright © 2007, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Purpose	i
Acronyms and Abbreviations	i
Audience	ii
Critical Patches	ii
Conventions	ii
Diversity and Inclusion	ii
Documentation Accessibility	iii
Related Resources	iii
Screenshot Disclaimer	iii

1 Create Property File for Gateway Applications

1.1 Create Property Files	1
1.1.1 Gateway EJB Application	3
1.1.2 Gateway MDB Application	12
1.1.3 Gateway HTTP Servlet Application	21
1.1.4 Gateway Webservices Application	25
1.1.5 REST Services Application	34

Preface

This topic contains the following sub-topics:

- [Purpose](#)
- [Acronyms and Abbreviations](#)
- [Audience](#)
- [Critical Patches](#)
- [Conventions](#)
- [Diversity and Inclusion](#)
- [Documentation Accessibility](#)
- [Related Resources](#)
- [Screenshot Disclaimer](#)

Purpose

This guide explains the steps to create the property file for the gateway components through Enterprise Java Bean (EJB), Message Driven Beans (MDB), Web Services, and Servlet. This guide helps the user with the installation of Oracle Banking Application.

Acronyms and Abbreviations

The list of the acronyms and abbreviations used in this guide are as follows:

Table 1 Acronyms and Abbreviations

Abbreviation	Description
CSF	Credential Store Framework
EAR	Enterprise Archive
EJB	Enterprise Java Bean
FCUBS	Oracle FLEXCUBE Universal banking Solutions
GW	Gateway
JDBC	Java Database Connectivity
JNDI	Java Naming and Directory Interface
LDAP	Lightweight Directory Access Protocol
MDB	Message Driven Beans
MSAD	Microsoft Active Directory
SSO	Single sign-on

Audience

This manual is intended for the following User/User Roles:

Table 2 Audience

Role	Function
Administrator	Who controls the system and application parameters and ensures smooth functionality and flexibility of the banking application.
Implementation team	Implementation of Oracle Banking Corporate Lending Solution
Pre-sales team	Install Oracle Banking Corporate Lending for demo purpose
Bank personnel	Who installs Oracle Banking Corporate Lending

The user of this manual is expected to have basic understanding of Oracle Banking Application installation.

Critical Patches

Oracle advises customers to get all their security vulnerability information from the Oracle Critical Patch Update Advisory, which is available at [Critical Patches, Security Alerts and Bulletins](#). All critical patches should be applied in a timely manner to ensure effective security, as strongly recommended by [Oracle Software Security Assurance](#).

Conventions

The following text conventions are used in this document:

Table 3 Conventions

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <https://www.oracle.com/corporate/accessibility/>.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Related Resources

For more information on any related features, refer to the following documents:

- Oracle Banking Corporate Lending User Guides.
- Oracle Banking Corporate Lending Installation Guides.

Screenshot Disclaimer

Personal information used in the interface or documents is dummy and does not exist in the real world. It is only for reference purposes.

1

Create Property File for Gateway Applications

This topic contains the following sub-topic:

- [Create Property Files](#)
This topic explains systematic instructions to create the property file for the Gateway application.


1.1 Create Property Files

This topic explains systematic instructions to create the property file for the Gateway application.

1. Click the **FCUBSInstaller.bat** to launch launch **Oracle Banking Installer** from the **INSTALLER\SOFT\GUI** folder path.

The **Welcome To Oracle FLEXCUBE Universal Banking Installer** screen displays.

Figure 1-1 Welcome To Oracle Universal Banking Installer



2. On the **Welcome To Oracle FLEXCUBE Universal Banking Installer** screen, click **Browse**, and specify the **JDK Path** and **Oracle Home Path**.

- On the **Welcome To Oracle FLEXCUBE Universal Banking Installer** screen, select the **Property File Creation** option, and click **Next**.

The **Select One of the Components** screen displays.

Figure 1-2 Select One of the Components

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer **ORACLE INSTALLER**

Select one of the Components

Load Existing Property File

☐ INFRA ☐ Scheduler ☒ Gateway ☐ Switch Interface Installation

Select Oracle Product Processors

☒ Oracle FLEXCUBE Universal Banking

☐ Oracle FLEXCUBE Enterprise Limits and Collateral Management (CO-DEPLOY)

☐ Oracle Banking Payments

☐ Oracle Banking Corporate Lending ☐ Open Development Tool

☐ Oracle Banking Treasury ☐ Oracle FLEXCUBE Universal Banking for JAPAN

☐ Oracle Banking Trade Finance

Select Plugins to be Installed

Host Address ☐ Origination ☐ Scheduler

☐ Reports ☐ SIANET Adapter

☐ DMS ☐ Insulation ☐ External Adapter required

- Select the **Gateway** component, and click **Next**.

The **Environment Details** screen displays.

Figure 1-3 Environment Details

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer **ORACLE INSTALLER**

Provide Environment details.

EAR Name:

File Separator Style:

Application Server:

☐ OBMA PP Installed

Application Server Path:

Source Path:

Ear Destination Path:

Cookie-Name (JSESSION_ID):

5. Specify the **EAR Name**, **Application Server Path**, **Source Path**, and **EAR destination path**, and then click **Next**.

The **Gateway Property File Creation** screen displays.


- [Gateway EJB Application](#)
This topic explains systematic instructions to create a property file by choosing Gateway EJB as the application type.
- [Gateway MDB Application](#)
This topic provides systematic instructions to create a Property File by choosing Gateway MDB Application as the application type.
- [Gateway HTTP Servlet Application](#)
This topic explains systematic instructions to create a property file through the Gateway HTTP Servlet application type.
- [Gateway Webservices Application](#)
This topic explains systematic instructions to create a property file through the Gateway Webservices application type.
- [REST Services Application](#)
This topic explains systematic instructions to create a property file through the REST Services application.

1.1.1 Gateway EJB Application

This topic explains systematic instructions to create a property file by choosing Gateway EJB as the application type.

1. On the **Gateway Property File Creation** screen, select **Gateway EJB** application type.

Figure 1-4 Gateway Property File Creation



2. Click **Next**.
The **Multi Entity Names** screen displays.

Figure 1-5 Multi Entity Names

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

ORACLE
INSTALLER

Multi Entity Names

Provide Entity Names

MultiEntity Required ☒

S.No	Entity Name
1	

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-1 Multi Entity Names - Field Description

Field	Description
MultiEntity Required	Check the MultiEntity Required box to enable the multi-entity deployment. This will enable + and - for capturing the Entity Name .
+	Click + to add a new row for capturing the new entity name.
-	Select the entity name and click - for deletion of the existing entity name.
Entity Name	Enter the entity name as a single word. For example, ENTITY1

3. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-6 Property File Creation

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window with the 'Oracle Banking Installer' title bar. The main window has a header with the Oracle logo and 'INSTALLER'. The title of the screen is 'Property File Creation'. Below the title, a message states: 'Current screen provides an option for Enabling Single Sign on'. There are two input fields: 'SSO Required' with a checked checkbox, and 'SSO KEY' with a text box containing 'DN'. Below these, there is a section for 'Authentication details maintained external to FLEXCUBE'. It includes 'External Password Required' (unchecked checkbox), 'Authentication Type' (a dropdown menu showing 'MSAD'), and 'External User Login Required' (unchecked checkbox). A large text area at the bottom contains the following text: 'With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next.' Below this, there are three lines of text: 'MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.', 'External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.', and 'Authentication Type: LDAP/MSAD is the type of external server used for authentication.' At the bottom of the window, there are four buttons: 'Exit', 'Log', 'Back', and 'Next'.

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

Property File Creation

Current screen provides an option for Enabling Single Sign on

SSO Required ☒

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☐ Authentication Type

External User Login Required ☐

With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next.

MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.

External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

Authentication Type: LDAP/MSAD is the type of external server used for authentication.

Exit Log Back Next

Figure 1-7 Property File Creation -Authentication details

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

Property File Creation

Current screen provides an option for Enabling Single Sign on

SSO Required ☐

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☒ Authentication Type **MSAD**

External User Login Required ☒ **MSAD**

LDAP

With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next.

MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.

External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

Authentication Type: LDAP/MSAD is the type of external server used for authentication.

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-2 Property File Creation - Field Description

Field	Description
SSO Required	Check this box to enable single sign-on (SSO). If you check this box, specify the SSO Key .
SSO Key	Specify the SSO Key . If you have checked the box SSO Required , it is mandatory to specify the SSO key. If you have checked the box SSO Required , then the Installer will skip the following two screens and will directly navigate to the SSL screen shown below in this manual. If you have not checked the box SSO Required , then click Next .
External User Login Required	Check this box to enable user login using MSAD (Microsoft Active Directory)/LDAP (Lightweight Directory Access Protocol) user ID. Note: If you check this box, the user can log in with MSAD/LDAP server user ID as well as FCUBS user ID. If you do not check this box, the user can log in using Oracle FLEXCUBE Universal Banking User ID only.

Table 1-2 (Cont.) Property File Creation - Field Description

Field	Description
External Password Required	Check this box to allow user login using MSAD/LDAP password irrespective of the user ID. If you check this box, the user can log in using MSAD/LDAP server password only. The user ID can be one of the following: - MSAD/LDAP user ID - FCUBS user ID If you do not check this box, then the installer skips the following screen and directly navigates to the Modifying Gateway Properties screen.
Authentication Type	Select the authentication type. This is the type of external server that is used. Select one of the following options: MSAD (Microsoft Active Directory) LDAP (Lightweight Directory Access Protocol) The default option is MSAD , and this can be modified.

If you checked the boxes (External User Login Required and External Password Required, then the installer navigates to the following screen.

4. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-8 Property File Creation - LDAP Server Details

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window with the 'Oracle Banking Installer' title bar. The main window has a header with the Oracle logo and 'INSTALLER'. Below the header, the title 'Property File Creation' is displayed, followed by the subtitle 'LDAP Server Details for Gateway'. A table with 3 columns (No., Name, Value) contains the following data:

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.10.10.10:111
2	LDAP SSL ENABLED	☐
3	SECURITY AUTHENTICATIO...	Simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

At the bottom of the window, there are four buttons: 'Exit', 'Log', 'Back', and 'Next'.

For more information, refer to the fields description table.

Table 1-3 LDAP Server Details

Field	Description
LDAP Server URL	Specify the URL to access the LDAP server where the external user ID and password are maintained.
LDAP SSL Enabled	Check this box if the LDAP server is SSL enabled. If you check this box, then specify the SSL port also in the field LDAP SERVER URL. By default, this check box is unchecked. However, you can change this.
Security Authentication Type	Depending on the authentication mechanism supported by the LDAP server, select one of the following: • Simple • Strong Notes: • Different servers support different authentication mechanisms. • By default, the security authentication type is Simple. However, the user can change this.
Domain Name	Specify the domain name.
LDAP Server Timeout	Specify the LDAP server timeout in milliseconds. This must be a positive integer value. For example, you can specify 1000, 10000, or 5000. If it is zero or less, it indicates that no read timeout is specified. Then the wait for the response is infinite until it is received. By default, the LDAP server timeout is zero, However, you can change this.

5. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-9 Property File Creation

Property File Creation
Current screen provides an option for modifying the Gateway Properties

XSD Path: /Kernel11.1/GW_EJB/XSD/

Logger File: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path: /Kernel11.1/GW_EJB/log/

Security Key for Encryption: oraclefinancials

SMS Pool Name: jdbc/fcdevDSSMS

DataSource: FLEXTTEST.WORLD

☐ POSS DataSource ☒ OPSS CSF Available

POSS DataSource: FOSSTTEST.WORLD

Distributed Schema: No

MSG IN log Required: No

MSG OUT log Required: No

☐ Integration with CN Logger

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-4 Property File Creation - Field Description

Field	Description
XSD Path	Specify the path to the XSD file. The file name is not required. File separator must be <code>/</code> . There must be a <code>/</code> at the end. All the relevant XSD files must be manually copied to this location. For example, - For Windows - <code>D:\Kernel11.1\GW_EJB\XSD\</code> - For Linux - <code>/Kernel11.1/GW_EJB/XSD/</code>
Logger File	Specify the path to the gw_ejb_logger.properties file with the file name. The file must be manually copied to the specified location. For example, - For Windows - <code>D:\Kernel11.1\GW_EJB\config\gw_ejb_logger.properties</code> - For Linux - <code>/Kernel11.1/GW_EJB/config/gw_ejb_logger.properties</code>
Debug Path	Specify the path to the folder where the application creates the logs. There must be a <code>/</code> at the end. You need to manually create the folder structure. For example, - For Windows - <code>D:\Kernel11.1\GW_EJB\log\</code> - For Linux - <code>/Kernel11.1/GW_EJB/log/</code>


Table 1-4 (Cont.) Property File Creation - Field Description

Field	Description
Security Key for Encryption	Specify the security key for the encryption. Here, in this case, it is oraclefinancials .
SMS Pool Name	Specify SMS Pool name. Here, in this case, it is jdbc/fcjdevDSSMS .
DataSource	The JDBC data source is an object bound to the JNDI tree and provides database connectivity through a pool of JDBC connections.
POSS Datasource	Check this box if POSS is required. If you check this box, specify the POSS datasource name in the field below this.
OPSS CSF Available	Indicates whether OPSS-CSF is installed or not. Note: Select this only if Oracle Platform Security Services - Credential Store Framework (CSF) is installed as per the guidelines in the pre-requisite document. It is recommended that you install CSF for safeguarding application-specific security credentials.
Distributed Schema	- If the schema is distributed, select Yes. - If the schema is not distributed, select No.
MSG IN LOG Required	Select Yes or No from the drop-down.
MSG OUT LOG Required	Select Yes or No from the drop-down.

6. Click **Next**.

The **Property Installation** screen displays.

Figure 1-10 Property Installation



The property file will be created in a temporary folder.

7. Click **Property File** to view the created property file.
8. Click **Save** to save the created property file in the desired location.

1.1.2 Gateway MDB Application

This topic provides systematic instructions to create a Property File by choosing Gateway MDB Application as the application type.

1. On the **Gateway Property File Creation** screen, select **Gateway MDB** application type.


Figure 1-11 Gateway Property File Creation



2. Click **Next**.

The **Multi Entity Names** screen displays.

Figure 1-12 Multi Entity Names



For more information, refer to the fields description table.

Table 1-5 Multi Entity Names - Field Description

Field	Description
MultiEntity Required	Select the MultiEntity Required check box for enabling the multi-entity deployment. This will enable + and - for capturing the entity name.
+	Click + to add a new row for capturing the new entity name.
-	Select the entity name and click -, the deletion of the existing entity name will be done.
Entity Name	Specify the entity name as a single word. For example, ENTITY1

3. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-13 Property File Creation

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window with the 'Oracle Banking Installer' title bar. The main window has a header with the Oracle logo and 'INSTALLER'. The title of the current screen is 'Property File Creation'. Below the title, a message states: 'Current screen provides an option for Enabling Single Sign on'. The 'SSO Required' checkbox is checked, and the 'SSO KEY' field contains 'DN'. Below this, a section titled 'Authentication details maintained external to FLEXCUBE' contains three checkboxes: 'External Password Required' (unchecked), 'External User Login Required' (unchecked), and 'Authentication Type' (set to 'MSAD' in a dropdown menu). A large text area at the bottom contains the following text: 'With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next. MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID. External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID. Authentication Type: LDAP/MSAD is the type of external server used for authentication.' At the bottom of the window are four buttons: 'Exit', 'Log', 'Back', and 'Next'.

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

Property File Creation

Current screen provides an option for Enabling Single Sign on

SSO Required ☒

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☐ Authentication Type

External User Login Required ☐

With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next.

MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.

External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

Authentication Type: LDAP/MSAD is the type of external server used for authentication.

Exit Log Back Next

Figure 1-14 Property File Creation - Authentication Type

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

Property File Creation

Current screen provides an option for Enabling Single Sign on

SSO Required ☐

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☒ Authentication Type MSAD ▼

External User Login Required ☒ MSAD
LDAP

With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep the all options unchecked and Click on Next.

MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.

External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

Authentication Type: LDAP/MSAD is the type of external server used for authentication.

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-6 Property File Creation - Field Description

Field	Description
SSO Required	Select this box to enable single sign-on (SSO). If you check this box, specify the SSO Key.
SSO Key	Specify the SSO key. If you have checked the box SSO Required , it is mandatory to specify the SSO key. If you have not checked the box SSO Required , then the Installer will skip the following two screens and will directly navigate to the Modifying the Gateway properties screen.
External User Login Required	Check this box to enable user login using MSAD/LDAP user ID. By default, this check box is unchecked. However, you can change this. Note: If you check this box, the user can log in with MSAD/LDAP server user ID as well as using OBCL user ID. If you do not check this box, the user can login using OBCL user ID only.

Table 1-6 (Cont.) Property File Creation - Field Description

Field	Description
External Password Required	Check this box to allow user login using MSAD/LDAP password irrespective of the user ID. By default, this check box is unchecked. However, you can change this. Notes: - If you check this box, the user ID can be either MSAD/LDAP user ID or the FCUBS user ID, and the password can be MSAD/LDAP server password only. - If you do not check this box, then the installer skips the following screen and directly navigates to the Modifying Gateway Properties screen. The field Authentication Type is enabled if one of the check boxes (External Password Required or External User Login Required) is selected.
Authentication Type	Select the authentication type from the drop-down list. This is the type of external server that is used. Select one of the following options - MSAD (Microsoft Active Directory) LDAP (Lightweight Directory Access Protocol) The default option is MSAD. However, you can change this.

4. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-15 Property File Creation - LDAP Server Details

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

ORACLE
INSTALLER

Property File Creation

LDAP Server Details for Gateway

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.10.10.10:111
2	LDAP SSL ENABLED	☐
3	SECURITY AUTHENTICATIO...	Simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-7 LDAP server details.

Field	Description
LDAP Server URL	Specify the URL to access the LDAP server where the external user ID and password are maintained.
LDAP SSL Enabled	Check this box if the LDAP server is SSL enabled. If you check this box, then specify the SSL port also in the field LDAP SERVER URL . By default, this check box is unchecked. However, you can change this.
Security Authentication Type	Depending on the authentication mechanism supported by the LDAP server, select one of the following - • Simple • Strong Notes: • Different servers support different authentication mechanisms. • By default, the security authentication type is Simple, however, you can change this.
Domain Name	Specify the domain name.
LDAP Server Timeout	Specify the LDAP server timeout in milliseconds. This must be a positive integer value. For example, specify 1000, 10000 or 5000. If it is zero or less, it indicates that no read timeout is specified. Then the wait for the response infinite until it is received. By default, the LDAP server timeout is zero, however, you can change this.

5. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-16 Property File Creation

Property File Creation
Current screen provides an option for modifying the Gateway Properties

XSD Path: /Kernel11.1/GW_EJB/XSD/

Logger File: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path: /Kernel11.1/GW_EJB/log/

Security Key for Encryption: oraclefinancials

SMS Pool Name: jdbc/fcdevDSSMS

DataSource: FLEXTTEST.WORLD

☐ POSS DataSource ☒ OPSS CSF Available

POSS DataSource: FOSSTTEST.WORLD

Distributed Schema: No

MSG IN log Required: No

MSG OUT log Required: No

☐ Integration with CN Logger

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-8 Property File Creation - Field Description

Field	Description
XSD Path	Specify the path to the XSD file. The file name is not required. File separator must be <code>/</code> . There must be a <code>/</code> at the end. All the relevant XSD files must be manually copied to this location. For example, - For Windows - <code>D:\Kernel11.1\GW_MDB\XSD\</code> - For Linux - <code>/Kernel11.1/GW_MDB/XSD/</code>
Logger File	Specify the path to the gw_mdb_logger.properties file with the file name. The file must be manually copied to the specified location. For example, - For Windows - <code>D:\Kernel11.1\GW_MDB\config\gw_mdb_logger.properties</code> - For Linux - <code>/Kernel11.1/GW_MDB/config/gw_mdb_logger.properties</code>
Debug Path	Specify the path to the folder where the application creates the logs. There must be a <code>/</code> at the end. You need to manually create the folder structure. For example, - For Windows - <code>D:\Kernel11.1\GW_MDB\log\</code> - For Linux - <code>/Kernel11.1/GW_MDB/log/</code>

Table 1-8 (Cont.) Property File Creation - Field Description

Field	Description
Security Key for Encryption	Specify the security key for the encryption. Here, in this case, it is oraclefinancials .
SMS Pool Name	Specify SMS pool name. Here, in this case, it is jdbc/fcjdevDSSMS .
DataSource	The JDBC data source is an object bound to the JNDI tree and provides database connectivity through a pool of JDBC connections.
POSS Datasource	Select this checkbox if POSS is required. If you select this checkbox, specify the POSS Datasource name in the field below this.
OPSS CSF Available	Indicates whether OPSS-CSF is installed or not. Note: Select this only if Oracle Platform Security Services - Credential Store Framework (CSF) is installed as per the guidelines in the pre-requisite document. It is recommended that you install CSF for safeguarding application-specific security credentials.
Distributed Schema	- If the schema is distributed, select Yes. - If the schema is not distributed, select No.

6. Click **Next**.

The **Gateway Property File Creation** screen displays.

Figure 1-17 Gateway Property File Creation

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer ORACLE INSTALLER

Gateway Property File Creation
Current screen provides an option for modifying MDB Properties

No.	Name	Value
1	Request Queue	MDB_QUEUE
2	Response queue	MDB_QUEUE_RESPONSE
3	DL Queue	MDB_QUEUE_DLQ
4	Connection Factory	MDBQCF
5	Secure Queue	☐
6	Caller ID	
7	Caller Password	

Exit Log Back Next

For more information, refer to the fields description table.


Table 1-9 Gateway Property File Creation - Field Description

Field	Description
Request Queue	Specify the request queue. This is the point-to-point destination type used for asynchronous peer communication. For example, MDB_QUEUE
Response Queue	Specify the response queue name. For example, MDB_QUEUE_RESPONSE
DL Queue	Specify the dead letter queue name. For example, MDB_QUEUE_DLQ Refer to the <i>Resources To Be Created</i> guide for the creation of queues.
Connection Factory	Specify the connection configuration parameters to create connections for JMS clients. For example, MDBQCF
Secure Queue	Check this box if the Caller ID and Caller Password values have to be entered.

The Installer creates two files **gw_mdb_logger.properties** and **GW_MDB_Prop.properties** in the path provided to save the files.

7. Click **Next**.

The **Property Installation** screen displays.

Figure 1-18 Property Installation


8. Click **Property File** to view the created property file.
9. Click **Save** to save the created property file in the desired location.

1.1.3 Gateway HTTP Servlet Application

This topic explains systematic instructions to create a property file through the Gateway HTTP Servlet application type.

1. On the **Gateway Property File Creation** screen, select **Gateway HTTP Servlet** application type.

Figure 1-19 Gateway Property File Creation



2. Click **Next**.
The **Multi Entity Names** screen displays.

Figure 1-20 Multi Entity Names

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

ORACLE
INSTALLER

Multi Entity Names

Provide Entity Names

MultiEntity Required ☒

S.No	Entity Name
1	

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-10 Multi Entity Names - Field Description

Field	Description
MultiEntity Required	Select the MultiEntity Required checkbox for enabling the multi-entity deployment. After selecting this checkbox, +, - icons will be enabled for capturing the entity name.
+	Click + to add a new row for capturing the new entity name.
-	Select the entity name and click -, the deletion of the existing entity name will be done.
Entity Name	Enter the entity name as a single word. For example, ENTITY1

3. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-21 Property File Creation

Property File Creation
Current screen provides an option for modifying the Gateway Properties

XSD Path: /Kernel11.1/GW_EJB/XSD/

Logger File: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path: /Kernel11.1/GW_EJB/log/

Security Key for Encryption: oraclefinancials

SMS Pool Name: jdbc/fcjddevDSSMS

DataSource: FLEXTTEST.WORLD

☐ POSS DataSource ☒ OPSS CSF Available

POSS DataSource: FOSSTEST.WORLD

Distributed Schema: No

MSG IN log Required: No

MSG OUT log Required: No

☐ Integration with CN Logger

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-11 Property File Creation - Field Description

Field	Description
XSD Path	Specify the path to the XSD file. The file name is not required. File separator must be <code>/</code> . There must be a <code>/</code> at the end. All the relevant XSD files must be manually copied to this location. For example, - For Windows - <code>D:\Kernel11.1\GW_HTTP\XSD\</code> - For Linux - <code>/Kernel11.1/GW_HTTP/XSD/</code>
Logger File	Specify the path to the gw_http_logger.properties file with the file name. The file must be manually copied to the specified location. For example, - For Windows - <code>D:\Kernel11.1\GW_HTTP\config\gw_http_logger.properties</code> - For Linux - <code>/Kernel11.1/GW_HTTP/config/gw_http_logger.properties</code>
Debug Path	Specify the path to the folder where the application creates the logs. There must be a <code>/</code> at the end. You need to manually create the folder structure. For example, - For Windows - <code>D:\Kernel11.1\GW_HTTP\log\</code> - For Linux - <code>/Kernel11.1/GW_HTTP/log/</code>

Table 1-11 (Cont.) Property File Creation - Field Description


Field	Description
Security Key for Encryption	Specify the security key for the encryption. Here, in this case, it is oraclefinancials .
SMS Pool Name	Specify SMS Pool Name. Here, in this case, it is jdbc/fcjddevDSSMS .
DataSource	The JDBC data source is an object bound to the JNDI tree and provides database connectivity through a pool of JDBC connections.
POSS Datasource	Check this box if POSS is required. If you check this box, specify the POSS Datasource Name in the field below this.
OPSS Available	Indicates whether OPSS-CSF is installed or not. Note: Select this only if Oracle Platform Security Services - Credential Store Framework (CSF) is installed as per the guidelines in the pre-requisite document. It is recommended that you install CSF for safeguarding application-specific security credentials.
Distributed Schema	- If the schema is distributed, select Yes. - If the schema is not distributed, select No.

The Installer creates two files viz. **gw_http_logger.properties** and **GW_HTTP_Prop.properties** in the path provided to save the files.

4. Click **Next**.

The **Property Installation** screen displays.

Figure 1-22 Property Installation



The property file will be created in a temporary folder.

5. Click **Property File** to view the created property file.
6. Click **Save** to save the created property file in the desired location.

The property file will be created in a specified folder.


For Gateway EAR Building, refer to the *Installer EAR Building* user guide.

1.1.4 Gateway Webservices Application

This topic explains systematic instructions to create a property file through the Gateway Webservices application type.

1. On the **Gateway Property File Creation** screen, select **Gateway Webservices** application type.


Figure 1-23 Gateway Property File Creation



2. Click **Next**.

The **Multi Entity Names** screen displays.

Figure 1-24 Multi Entity Names



For more information, refer to the fields description table.

Table 1-12 Multi Entity Names - Field Description

Field	Description
MultiEntity Required	Select the MultiEntity Required checkbox for enabling the multi-entity deployment. After selecting this checkbox, the + and - icons will be enabled for capturing the entity name.
+	Click + to add a new row for capturing the new entity name.
-	Select the entity name and click -, the deletion of the existing entity name will be done.
Entity Name	Specify the entity name as a single word. For example, ENTITY1

3. Click **Next**.
The **Property File Creation** screen displays.

Figure 1-25 Property File Creation

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

Property File Creation
Current screen provides an option for Enabling Single Sign on

SSO Required ☒

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☐ Authentication Type

External User Login Required ☐

With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required, keep all options unchecked and Click on Next.

MSAD/LDAP User Login Required: User can login with MSAD/LDAP user ID as well as FCUBS user ID.

External Password Required: The user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

Authentication Type: LDAP/MSAD is the type of external server used for authentication.

Exit Log Back Next

Table 1-13 Property File Creation - Field Description

Field	Description
SSO Required	Select this checkbox to enable single sign-on (SSO). If you select this checkbox, you must specify the SSO Key.
SSO Key	Specify the SSO key. If you have checked the box SSO Required , it is mandatory to specify the SSO key. If you have checked the box SSO Required , then the installer will skip the following two screens and will directly navigate to the SSL screen shown below in this manual. If you have not checked the box SSO Required , then click Next . The following screen is displayed.
External User Login Required	Check this box to enable user login using MSAD/LDAP user ID. Note: If you check this box, the user can log in with MSAD/LDAP server user ID as well as OBCL user ID. If you do not check this box, the user can login using OBCL user ID only.

Table 1-13 (Cont.) Property File Creation - Field Description

Field	Description
External Password Required	Check this box to allow user login using MSAD/LDAP password irrespective of the user ID. If you check this box, the user can log in using MSAD/LDAP server password only. The user ID can be one of the following - - MSAD/LDAP user ID - FCUBS user ID If you do not check this box, then the installer skips the following screen and directly navigates to the Modifying Gateway Properties screen.
Authentication Type	Select the authentication type. This is the type of external server that is used. Select one of the following options - MSAD (Microsoft Active Directory) LDAP (Lightweight Directory Access Protocol) The default option is MSAD. However, it can be changed.

4. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-26 Property File Creation

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer ORACLE INSTALLER

Property File Creation
LDAP Server Details for Gateway

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.10.10.10:111
2	LDAP SSL ENABLED	☐
3	SECURITY AUTHENTICATIO...	Simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-14 LDAP server details.

Field	Description
LDAP Server URL	Specify the URL to access the LDAP server where the external user ID and password are maintained.
LDAP SSL Enabled	Check this box if the LDAP server is SSL enabled. If you check this box, then you need to specify the SSL port also in the field LDAP SERVER URL. By default, this check box is unchecked. However, you can change this.
Security Authentication Type	Depending on the authentication mechanism supported by the LDAP server, select one of the following - • Simple • Strong Notes: • Different servers support different authentication mechanisms. • By default, the security authentication type is Simple, however, you can change this.
Domain Name	Specify the domain name.
LDAP Server Timeout	Specify the LDAP server timeout in milliseconds. This must be a positive integer value. For example, specify 1000, 10000 or 5000. If it is zero or less, it indicates that no read timeout is specified. Then the wait for the response infinite until it is received. By default, the LDAP server timeout is zero, however, you can change this.

5. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-27 Property file Creation - Modify Gateway Properties

Property File Creation
Current screen provides an option for modifying the Gateway Properties

XSD Path: /Kernel11.1/GW_EJB/XSD/

Logger File: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path: /Kernel11.1/GW_EJB/log/

Security Key for Encryption: oraclefinancials

SMS Pool Name: jdbc/fcjddevDSSMS

DataSource: FLEXTTEST.WORLD

☐ POSS DataSource ☒ OPSS CSF Available

POSS DataSource: FOSSTTEST.WORLD

Distributed Schema: No

MSG IN log Required: No

MSG OUT log Required: No

☐ Integration with CN Logger

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-15 Property File Creation - Field Description

Field	Description
XSD Path	Specify the path to the XSD file. The file name is not required. File separator must be <i>/</i> . There must be a <i>/</i> at the end. All the relevant XSD files must be manually copied to this location. For example, - For Windows - <i>D:\Kernel11.1\GW_WS\XSD\</i> - For Linux - <i>/Kernel11.1/GW_WS/XSD/</i>
Logger File	Specify the path to the gw_ws_logger.properties file with the file name. The file must be manually copied to the specified location. For example, - For Windows - <i>D:\Kernel11.1\GW_WS\config\gw_ws_logger.properties</i> - For Linux - <i>/Kernel11.1/GW_WS/config/gw_ws_logger.properties</i>
Debug Path	Specify the path to the folder where the application creates the logs. There must be a <i>/</i> at the end. You need to manually create the folder structure. For example, - For Windows - <i>D:\Kernel11.1\GW_WS\log\</i> - For Linux - <i>/Kernel11.1/GW_WS/log/</i>

Table 1-15 (Cont.) Property File Creation - Field Description

Field	Description
Security Key for Encryption	Specify the security key for the encryption. Here, in this case, it is oraclefinancials .
SMS Pool Name	Specify SMS Pool Name. Here, in this case, it is jdbc/fcdevDSSMS .
DataSource	The JDBC data source is an object bound to the JNDI tree and provides database connectivity through a pool of JDBC connections.
POSS Datasource	Check this box if POSS is required. If you check this box, specify the POSS Datasource Name in the field below this.
OPSS CSF Available	Indicates whether OPSS-CSF is installed or not. Note: Select this only if Oracle Platform Security Services - Credential Store Framework (CSF) is installed as per the guidelines in the pre-requisite document. It is recommended that you install CSF for safeguarding application-specific security credentials.
Distributed Schema	- If the schema is distributed, select Yes. - If the schema is not distributed, select No.
MSG IN LOG Required	Select Yes or No from the drop-down.
MSG OUT LOG Required	Select Yes or No from the drop-down.

6. Click **Next**.

The **Property File Creation** screen displays.

Figure 1-28 Property File Creation

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer ORACLE INSTALLER

Property File Creation

Specify the EJB Application Name

EJB Application Name

Please remember the EJB Application name, the same name has to be used while deploying the EJB.

Exit Log Back Next

7. On the **Property File Creation** screen, specify the name of the EJB application deployed.
For example, GWEJB
8. Click **Next**.
The **Gateway Property File Creation** screen displays.

Figure 1-29 Gateway Property File Creation

Oracle FLEXCUBE Universal Installer

Oracle Banking Installer

ORACLE
INSTALLER

Gateway Property File Creation
Current screen provides an option for modifying WebServices Properties

No.	Name	Value
1	EJB JNDI Name	#com.ofss.fcubs.gw.ejb.GWEJBRemote
2	Application Server URL	http://10.10.10.10:7001
3	User Name	infra
4	Password	****
5	EJB Look Up	

Application Type: INTEGRATED

Application type can later be edited in env.properties

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-16 Gateway Property File Creation - Field Description

Field	Description
EJB JNDI Name	If you build the EJB application with the GWEJB name, this will create the name with which the EJB EAR file is built. If you select EJB Call Type as REMOTE , this will create <EJB_APPLICATION_NAME>#com.ofss.fcubs.gw.ejb.GWEJBRemote in GW_WS_Prop.properties file. For example, Weblogic/ : GWEJB #com.ofss.fcubs.gw.ejb.GWEJBRemote
Application Server URL	Specify the URL of the application server where the web service application is hosted. For example, Weblogic: t3://10.10.10.10:7001


Table 1-16 (Cont.) Gateway Property File Creation - Field Description

Field	Description
User Name	Specify the user name to access the application server where the EJB application is deployed. For example, INFRA
Password	Specify the password for the user name.
EJB Look Up	Specify the EJB look up type from the drop-down list. The options are LOCAL/REMOTE .
Application Type	Specify the application type from the drop-down list. Notes: - If the Application Type is INTEGRATED then the EJB Look Up should be selected as LOCAL. - If the Application Type is INDIVIDUAL then the EJB Look Up should be selected as REMOTE, and EJB should configure in any server. (REMOTE only works with the combination of EJB and GWWS). - The Installer creates two files viz. gw_ws_logger.properties and GW_WS_Prop.properties in the path provided to save the files.

9. Click **Next**.

The **Property Installation** screen displays.

Figure 1-30 Property Installation



The property file will be created in a temporary folder.

10. Click **Property File** to view the created property file.
11. Click **Save** to save the created property file in the desired location.

The property file will be created in a temporary folder.


For Gateway EAR Building, refer to the *Installer EAR Building* document.

1.1.5 REST Services Application

This topic explains systematic instructions to create a property file through the REST Services application.

1. On the **Gateway Property File Creation** screen, select **REST Services (Applicable to UBS 14.1 and above versions)** application type.

Figure 1-31 REST Services_Gateway Property File Creation



2. Click **Next**.

The **SMS Schema Details** screen displays.

Figure 1-32 SMS Schema Details

Name	Value
Username	installer
Password	••••••••
Service Name	testdb
IP Address	10.10.10.10
Port	1521
TNS Connect Descriptor	testdb

Test Connection

Exit Log Back Next

3. Specify the valid **Username**, **Password**, **Service Name** **IP Address**, **Port**, and **TNS Connect Descriptor**, and then click **Test Connection**.

The successful test connection will enable the **Next** button.

4. Click **Next**.

The **Property File Creation** screen displays.

5. On the **Property File Creation** screen, specify the fields.

Figure 1-33 Property File Creation

Oracle Banking Installer

Property File Creation
Current screen provides an option for modifying the Gateway Properties

XSD Path: /Kernel11.1/GW_EJB/XSD/

Logger File: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path: /Kernel11.1/GW_EJB/log/

Security Key for Encryption: oraclefinancials

SMS Pool Name: jdbc/fcdevDSSMS

DataSource: FLEXTEST.WORLD

☐ POSS DataSource ☒ OPSS CSF Available

POSS DataSource: FOSSTEST.WORLD

Distributed Schema: No

MSG IN log Required: No

MSG OUT log Required: No

☐ Integration with CN Logger

Exit Log Back Next

For more information, refer to the fields description table.

Table 1-17 Property File Creation - File Description

Field	Description
XSD Path	Specify the XSD path.
Logger File	Specify logger property file path.
Debug Path	Specify the path where debugs are to be written.
Security Key for Encryption	Specify the security key for the encryption. Here specify oraclefinancialsolutions .
SMS Pool Name	Specify valid pool name. This field displays the default value jdbc/fcdevDSSMS .
DataSource	The JDBC data source is an object bound to the JNDI tree and provides database connectivity through a pool of JDBC connections.
POSS DataSource	Check this box if POSS is required.
OPSS CSF Available	This check box indicates whether OPSS-CSF is installed or not.
POSS DataSource	If the POSS DataSource box is checked, specify the POSS Datasource Name in this field.
Distributed Schema	Select either Yes or No from the drop-down list.
MSG IN Log Required	Select either Yes or No from the drop-down list.
MSG OUT Log Required	Select either Yes or No from the drop-down list.

Table 1-17 (Cont.) Property File Creation - File Description

Field	Description
Integration with CN Logger	Check this box for the Integration with CN Logger.

6. Click **Next** to Specify REST Services information.
The **RESTServices Properties** screen displays.

Figure 1-34 RESTServices Properties

For more information, refer to the fields description table.

Table 1-18 REST Services Properties

Field	Description
REST Services Logger File	Specify logger property file path.
REST Services Debug Path	Specify the path where debugs are to be written.
REST Services Security Key for Encryption	Specify the security key for the encryption. In this case, it is oraclefinancialsolutions .
REST Services Msg Schema Pool Name	Specify a valid pool name. This field displays the default value as jdbc/fcdevDSSMS .


Table 1-18 (Cont.) REST Services Properties

Field	Description
Authentication Scheme	Select Authentication Scheme from the drop-down list. OAUTH FLEXCUBE For the FLEXCUBE authentication scheme, REST Client ID , REST Client Secret , and Access Token URL are disabled. The same has to be specified if OAUTH is selected.
CTX factory	Specify valid CTX factory information.
Provider URL	Specify the URL with the valid port number.
Security Principal	Specify the security principal user name.
Security Credentials	Specify the security principal password.
JNDI Name	In this field, JNDI Name is defaulted based on the application server selected.

7. Click **Next**.

The **Property Installation** screen displays.

Figure 1-35 Property Installation



8. Click **Property File** to view the created property file.
9. Click **Save** to save the created property file in the desired location.

The property file will be created in a temporary folder.