Oracle Linux Oracle VirtIO Drivers for Microsoft Windows for Use With KVM





Oracle Linux Oracle VirtlO Drivers for Microsoft Windows for Use With KVM,

F54847-11

Copyright © 2020, 2025, Oracle and/or its affiliates.

Contents

Documentation License	V	
Conventions	V	
Documentation Accessibility	V	
Access to Oracle Support for Accessibility	\	
Diversity and Inclusion	١	
About Oracle VirtIO Drivers for Microsoft Windows		
Supported Releases, Operating Systems, and Configuration Limits	1-2	
Supported Environments	1-2	
Supported Guest Operating Systems	1-2	
Virtual Machine Configuration	1-3	
Microsoft Windows Compatibility Signing	1-3	
Discontinued Platforms	1-3	
Downloading the Oracle VirtIO Drivers for Microsoft Windows		
Installing the Oracle VirtIO Drivers for Microsoft Windows		
Installing the Oracle VirtlO Drivers for Microsoft Windows on Existing Microsoft Windows quests	3-1	
Configuring Policies for Device Installation	3-1	
Installing Oracle VirtIO Drivers for Microsoft Windows	3-2	
Installing the Oracle Virtlo Drivers for Microsoft Windows During Microsoft Windows Guest	0.2	
	3-3	



4

- 5 Silently Installing or Upgrading the Oracle VirtIO Drivers for Microsoft Windows
- 6 Uninstalling the Oracle VirtIO Drivers for Microsoft Windows
- 7 Known Limitations and Workarounds

Preface

Oracle Linux: Oracle VirtIO Drivers for Microsoft Windows for Use With KVM describes how to install, use, and troubleshoot the Oracle VirtIO Drivers for Microsoft Windows. These instructions are intended for users and administrators of guests that are running the Microsoft Windows operating system in virtualized environments, where KVM is the hypervisor.

Documentation License

The content in this document is licensed under the Creative Commons Attribution—Share Alike 4.0 (CC-BY-SA) license. In accordance with CC-BY-SA, if you distribute this content or an adaptation of it, you must provide attribution to Oracle and retain the original copyright notices.

Conventions

The following text conventions are used in this document:

Convention	Meaning	
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.	
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.	
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.	

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at https://www.oracle.com/corporate/accessibility/.

Access to Oracle Support for Accessibility

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit https://www.oracle.com/corporate/accessibility/learning-support.html#support-tab.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners,



we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.



1

About Oracle VirtIO Drivers for Microsoft Windows

The Oracle VirtIO Drivers for Microsoft Windows are paravirtualized drivers for Microsoft Windows guests that run on KVM hypervisors; these drivers improve performance for network and block (disk) devices on Microsoft Windows guests and resolve common issues.

Features in 2.3

The Oracle VirtIO Drivers for Microsoft Windows 2.3 provides new support for **Microsoft Windows Server 2025**.

Features in 2.2

The Oracle VirtIO Drivers for Microsoft Windows 2.2 provides:

- New features
 - Support for the VirtlO balloon driver which allows the host to reclaim memory from the guest.
 - Change in ISO driver folder layout to allow the installer to automatically load the correct driver, detect the virtual disks and resume installation.
- Bug fix VirtIO installer and service updated to support:
 - non-KVM to KVM migration for Windows guests that are PC and Q35 machine types
 - installing and upgrading VirtlO drivers for PCI and PCIe devices

Features in 2.1.0

The Oracle VirtIO Drivers for Microsoft Windows 2.1.0 provides:

- An updated installer which includes better messaging and improved workflows for unsupported platforms.
- Support for the VirtIO GPU driver that drives the VirtIO VGA display device designed for virtual machines. VirtIO GPU supports system power state S3. You can suspend and wake up the Windows system that uses the VirtIO VGA device.
- Bug fixes for the VirtIO storage and network drivers.

Features in 2.0.1

Release 2.0.1 of the Oracle VirtIO Drivers for Microsoft Windows fixes an issue that caused migration failure when changing from non-KVM environments, such as VMWare or Hyper-V, to KVM environments, such as Oracle Cloud Infrastructure.

Features in 2.0

The primary focus in release 2.0 of the Oracle VirtlO Drivers for Microsoft Windows is an improvement in network and block performance. Also, a significant number of bugs are resolved in this update and the codebase aligns more closely to the upstream release of these

drivers. The update also facilitates the coexistence of third-party vendor drivers that previously resulted in conflicts and issues.

Supported Releases, Operating Systems, and Configuration Limits

The following information pertains to the Oracle Linux and Oracle Cloud Infrastructure releases that are supported with the Oracle VirtlO Drivers for Microsoft Windows, in addition to the supported operating systems for each version of the Oracle VirtlO Drivers for Microsoft Windows.

Information about Microsoft Windows compatibility signing and details on tested and recommended configuration limits for the Oracle VirtlO Drivers for Microsoft Windows is also provided.

Supported Environments

The Oracle VirtIO Drivers for Microsoft Windows Release 2.3 are supported on the following environments and platforms:

- Oracle Cloud Infrastructure
- Oracle Linux 10.0
- Oracle Linux 9.6
- Oracle Linux 8.10
- Oracle Linux 7.9

Supported Guest Operating Systems

The following supported Microsoft Windows operating systems for guest virtual machines that run on KVM have been tested with Oracle VirtIO Drivers for Microsoft Windows:

- Microsoft Windows Server 2025
- Microsoft Windows Server 2022
- Microsoft Windows Server 2019
- Microsoft Windows Server 2016
- Microsoft Windows 11
- Microsoft Windows 10 (64-bit only)



For information about the supported Microsoft Windows operating systems for the Oracle VirtIO Drivers for Microsoft Windows in the Oracle Cloud Infrastructure environment, see Bring your own image.



Virtual Machine Configuration

Virtual machine configuration for the Oracle VirtlO Drivers for Microsoft Windows complies with shape configurations for virtual machines in the Oracle Cloud Infrastructure environment. For more information, see: https://www.oracle.com/cloud/compute/virtual-machines/.

Microsoft Windows Compatibility Signing

The following Microsoft Windows operating systems have been signed and certified for Oracle VirtIO Drivers for Microsoft Windows. Oracle has also tested the drivers to ensure they work as expected.

- Microsoft Windows Server 2025
- Microsoft Windows Server 2022
- Microsoft Windows Server 2019
- Microsoft Windows Server 2016
- Microsoft Windows 11
- Microsoft Windows 10 (64-bit only)

Additional information on the certifications can be found at the Windows Server Catalog.

Discontinued Platforms

The following Windows platforms have reached the end of their product life cycle with Microsoft and are no longer supported or included in the VirtlO drivers:

- Microsoft Windows Server 2012
- Microsoft Windows Server 2012 R2
- Microsoft Windows Server 2008 R2
- Microsoft Windows Server 2008 SP2
- Microsoft Windows Server 2008
- Microsoft Windows Server 2003 R2
- Microsoft Windows Server 2003
- Microsoft Windows 2000
- Microsoft Windows NT 4.0
- Microsoft Windows 8
- Microsoft Windows 8.1
- Microsoft Windows 7
- Microsoft Windows 7 SP1
- Microsoft Windows Vista
- Microsoft Windows XP



Downloading the Oracle VirtIO Drivers for Microsoft Windows

Before you can install the Oracle VirtlO Drivers for Microsoft Windows you must download them from Oracle Software Delivery Cloud or My Oracle Support (MOS).

To download the Oracle VirtlO Drivers for Microsoft Windows from Oracle Software Delivery Cloud:

- 1. Navigate to https://edelivery.oracle.com and log in.
- 2. Search for Oracle Linux.
- Select one of the following:
 - DLP: Oracle Linux 10.0.0.0 (Oracle Linux)
 - DLP: Oracle Linux 9.6.0.0.0 (Oracle Linux)
 - DLP: Oracle Linux 8.10.0.0.0 (Oracle Linux)
 - DLP: Oracle Linux 7.9.0.0.0 (Oracle Linux)
- Click Continue.
- In the Platforms / Languages column, select Microsoft Windows x64 (64 bit) in the list and then click Continue.
- 6. Review and accept the Oracle License Agreement and then click Continue.
- Click the file name that has the description: Oracle VirtlO Drivers for Microsoft Windows, Version 2.3, and save it to your system.

To download the Oracle VirtIO Drivers for Microsoft Windows from MOS:

- 1. From the MOS home page, click the **Patches & Updates** tab.
- 2. From the **Patch Search** options, enter 27637937 in the **Patch Name or Number** field and then click **Search**. Don't select any of the **Platform** options.
- In the search results table, click the 27637937 Patch Name that corresponds to the Oracle VirtlO Drivers for Microsoft Windows, Version 2.3, which is shown in the Description field.
- From the Patch Details page, click Download.
 - The File Download window opens.
- 5. Click the link for the zip file and save it to your system.

Installing the Oracle VirtIO Drivers for Microsoft Windows

Installing the Oracle VirtIO Drivers for Microsoft Windows involves configuring Microsoft Windows policies, running the installation program, and then verifying the installation.

Installing the Oracle VirtIO Drivers for Microsoft Windows on Existing Microsoft Windows guests

To install the Oracle VirtIO Drivers for Microsoft Windows on existing Microsoft Windows guests, perform the following procedures.

Configuring Policies for Device Installation

Configure Microsoft Windows policies to allow the installation of the Oracle VirtlO Drivers for Microsoft Windows, if these policies are not already configured. This task prevents the following error from occurring during an installation:

The installation of this device is forbidden by system policy. Contact your system administrator.

To configure policies for installation:

- Open the Microsoft Windows virtual machine on which you want to install the Oracle VirtIO Drivers for Microsoft Windows.
- 2. From the Start menu, select Run.
- 3. Enter gpedit.msc and then click **OK**.

The Local Group Policy Editor is displayed.

- 4. From the Console Tree, display the list of device installation restrictions (Device Installation Restrictions) as follows:
 - Expand Computer Configuration, and then expand Administrative Templates.
 - b. Expand **System**, and then expand **Device Installation**.
 - c. Select Device Installation Restrictions.
- 5. Edit the policy settings so that no device installation restrictions are configured.

Alternatively, review each policy setting to determine the correct configuration for your business needs.

- 6. Close the Local Group Policy Editor.
- Restart the Microsoft Windows virtual machine.

When you are finished configuring the policy settings for device installation, you can proceed with the installation of the Oracle VirtIO Drivers for Microsoft Windows.

Installing Oracle VirtIO Drivers for Microsoft Windows

Before You Begin

Do the following before you start the installation process:

- Obtain the Oracle VirtIO Drivers for Microsoft Windows from Oracle Software Delivery Cloud or MOS. See Downloading the Oracle VirtIO Drivers for Microsoft Windows.
- Review the list of supported Microsoft Windows operating systems and any prerequisite hotfixes. See Supported Guest Operating Systems.
- Configure system policies to allow the installation. See Configuring Policies for Device Installation.



If you are migrating Microsoft Windows guests from OCI Classic to OCI, the installer copies the Oracle VirtlO Drivers for Microsoft Windows files, installs the drivers on the guest, and configures the guest to support migration from OCI Classic to OCI.

You can install the Oracle VirtIO Drivers for Microsoft Windows by using the GUI installation program or by performing a silent installation. Use the graphical installation program if you are installing a single instance of the Oracle VirtIO Drivers for Microsoft Windows. If you plan to silently install multiple instances of the Oracle VirtIO Drivers for Microsoft Windows, you must run the GUI installation program in a command line window on at least one Microsoft Windows guest to create a response file. You can then use the response file to perform all subsequent installations silently.

To install the Oracle VirtIO Drivers for Microsoft Windows:

- Copy the Oracle VirtIO Drivers for Microsoft Windows installation program Setup.exe to the guest.
- 2. Start the installation by running **Setup.exe** in one of the following ways:
 - To perform a single installation, double-click Setup.exe to start the Oracle VirtIO Drivers for Microsoft Windows installer.
 - To record a response file for automated installations on multiple systems:
 - a. Open a command line window.
 - b. Navigate to the directory where the **Setup.exe** file is located.
 - c. Run Setup.exe -r to start the Oracle VirtlO Drivers for Microsoft Windows installer and create a response file for silent installations.
- If prompted, select Yes in the User Account Control dialog to allow the Oracle VirtIO Drivers for Microsoft Windows installer to proceed.

The **Welcome** window is displayed.

4. Click Next.

The **Start to install Oracle VirtlO Drivers for Microsoft Windows Release 2.3** window is displayed with information about your selection.

Click Install to start the installation.



The installer copies the Oracle VirtIO Drivers for Microsoft Windows files and installs the drivers on the guest.

6. After the installation completes, click **Finish**.

The virtual machine is restarted.



If you are migrating Windows guests from OCI Classic to Oracle Cloud Infrastructure, shut down the Windows guest VM in the OCI Classic environment and then start the Windows guest VM in the OCI environment.

The Oracle VirtIO Drivers for Microsoft Windows are installed in the following directory:

C:\Program Files (x86)\Oracle Corporation\Oracle Windows VirtIO Drivers

If you used the -r option in the command line, the installation program creates a response file in the C:\Windows directory. You then use the response file, setup.iss, to perform silent installations on other Microsoft Windows guests. See Silently Installing or Upgrading the Oracle VirtlO Drivers for Microsoft Windows.

Installing the Oracle VirtIO Drivers for Microsoft Windows During Microsoft Windows Guest Installation

Before You Begin

Do the following before you start the installation process:

- Obtain the Oracle VirtIO Drivers for Microsoft Windows from Oracle Software Delivery Cloud or MOS. See Downloading the Oracle VirtIO Drivers for Microsoft Windows.
- Review the list of supported Microsoft Windows operating systems and any prerequisite hotfixes. See Supported Guest Operating Systems.

To install the Oracle VirtIO Drivers for Microsoft Windows during the installation of a Microsoft Windows guest, do the following:

- Create the virtual machine, but do not start it.
- Attach the Oracle VirtIO Drivers for Microsoft Windows ISO file to the virtual machine as an emulated IDE device. You can find the winvirtio.iso file in the Oracle VirtIO Drivers for Microsoft Windows zip file you downloaded.

Ensure that the Microsoft Windows guest installation ISO is attached to the virtual machine as the first IDE device. The Oracle VirtIO Drivers for Microsoft Windows ISO file is typically the second IDE device.

- 3. Start the virtual machine and begin the Microsoft Windows installation process.
- 4. When the disk or partition screen displays, follow the prompts to browse and load drivers.
- Navigate to the appropriate driver location on the Oracle VirtlO Drivers for Microsoft Windows ISO file and then select them.

The contents of the Oracle VirtlO Drivers for Microsoft Windows ISO file are as follows:



```
# File that automatically runs the installation program.
autorun.inf
fwcfg
               # Directory that contains the license file for fwcfg null drivers.
               # The main graphical installation program.
Setup.exe
               # Directory that contains the license file for NetKVM drivers.
NetKVM
                # Directory that contains the license file for pypanic drivers.
pvpanic
viogpu
                # Directory that contains the license file for viogpu drivers.
vioscsi
               # Directory that contains the license file for vioscsi drivers.
vioserial
                # Directory that contains the license file for vioserial drivers.
viostor
               # Directory that contains the license file for viostor drivers.
balloon
                # Directory that contains the license file for balloon drivers.
vio
                # Base directory for drivers.
vio/Common
                # Fwcfg null drivers for all Windows versions.
vio/Win10
                # Drivers for Windows 10, Windows Server 2016, Windows Server 2019
and Windows Server 2022.
vio/Win10/amd64 # 64-bit drivers.
vio/Win11
                # Drivers for Windows 11 and Windows Server 2025.
vio/Win11/amd64 # 64-bit drivers.
```

6. Repeat the preceding step to install other drivers as necessary and then continue with the Microsoft Windows installation process.

After you install the Microsoft Windows guest, you must configure Microsoft Windows policies. See Supported Guest Operating Systems.




Upgrading the Oracle VirtIO Drivers for Microsoft Windows

You can upgrade an existing installation of the Oracle VirtlO Drivers for Microsoft Windows by using the GUI installation program or by performing a silent upgrade. Use the graphical installation program if you are upgrading a single instance of the Oracle VirtlO Drivers for Microsoft Windows. If you plan to silently upgrade multiple instances of the Oracle VirtlO Drivers for Microsoft Windows, you must run the graphical installation program in a command line window on at least one Microsoft Windows guest to create a response file. You can then use the response file to perform all subsequent upgrades silently.

To upgrade the Oracle VirtIO Drivers for Microsoft Windows:

- 1. Copy the Oracle VirtlO Drivers for Microsoft Windows installation program, Setup.exe, to the guest.
- 2. Do one of the following:
 - Double-click Setup.exe to begin the upgrade.
 - Open a command line window and then do the following:
 - a. Navigate to the directory where the Setup. exe file is located.
 - b. Run the Setup.exe -r command to begin the upgrade and create a response file for silent installations.
- If prompted, select Yes in the User Account Control dialog to allow the Oracle VirtIO
 Drivers for Microsoft Windows installer to proceed.
 Oracle VirtIO Drivers for Microsoft Windows user account control dialog



The initial upgrade window is displayed.

Click Next to start the upgrade.

The installation program then copies new versions of the Oracle VirtlO Drivers for Microsoft Windows to the system and updates the installed drivers. The **Update Complete** window is displayed.

5. Click **Yes, I want to restart the system now** and then click **Finish** to restart the virtual machine.

If you used the -r option in the command line, the installation program creates a response file in the C:\Windows directory. You then use the response file, setup.iss, to perform silent upgrades on other Microsoft Windows guests. See Silently Installing or Upgrading the Oracle VirtlO Drivers for Microsoft Windows.



Silently Installing or Upgrading the Oracle VirtIO Drivers for Microsoft Windows

You can use a response file that you create with the graphical installation program to silently install or upgrade the Oracle VirtIO Drivers for Microsoft Windows. The response file provides the prompts that the installation program requires to successfully install or upgrade the Oracle VirtIO Drivers for Microsoft Windows.

Important:

Oracle VirtlO Drivers for Microsoft Windows must be signed by Microsoft to perform a silent installation or upgrade. See Microsoft Windows Compatibility Signing.

To install or upgrade the Oracle VirtlO Drivers for Microsoft Windows silently:

- Complete at least one installation or upgrade of the Oracle VirtIO Drivers for Microsoft Windows by using the GUI installation program to create a response file. See Installing Oracle VirtIO Drivers for Microsoft Windows or Upgrading the Oracle VirtIO Drivers for Microsoft Windows.
- 2. Locate the response file, setup.iss, in the C:\Windows directory on the file system of the computer where you ran the graphical installation program.
- 3. Copy setup.iss to the same directory as the Oracle VirtlO Drivers for Microsoft Windows installation program. Alternatively you can specify the location of the response file at the command line.
- 4. Open a command line window.
- 5. Run the Setup.exe -s command to silently install or upgrade the Oracle VirtlO Drivers for Microsoft Windows with the response file.

You can include the following options at the command line:

- -f1c:path\to\setup.iss to specify the location of setup.iss.
 - For example, Setup.exe -s -f1c:\Users\Username\setup.iss.
- -f2c:path\to\setup.log to specify the location of setup.log. By default, log files are written to the C:\Windows directory, for example, Setup.exe -s f2c:\Users\Username\setup.log.

Uninstalling the Oracle VirtIO Drivers for Microsoft Windows

You can uninstall the Oracle VirtlO Drivers for Microsoft Windows through the Microsoft Windows control panel or by running the installation program that you used to install the Oracle VirtlO Drivers for Microsoft Windows.

To uninstall through the Microsoft Windows control panel:

- 1. Open the control panel and navigate to the **Uninstall or change a program** section.
 - Note that the name of this section might be different, depending on your version of Microsoft Windows.
- 2. Locate, then select the Oracle VirtlO Drivers for Microsoft Windows.
- 3. Right-click the Uninstall option.
 - The installation program starts and prompts you to confirm the uninstallation.
- **4.** Select **Yes** when prompted to remove the application.
 - The installation program removes the Oracle VirtlO Drivers for Microsoft Windows and deletes the binaries from your system.
- When prompted, select Yes, restart the system and then click Finish to complete the uninstallation.

To uninstall with the installation program:

- 1. Double-click Setup. exe to start the Oracle VirtIO Drivers for Microsoft Windows installer.
 - The installation program starts and prompts you to modify the current installation. You are able to select either **Repair** or **Remove**.
- 2. Select Remove and then click Next.
- 3. Select **Yes** from the pop-up dialog.
 - The installation program removes the Oracle VirtlO Drivers for Microsoft Windows and deletes the binaries from your system.
- **4.** When prompted, select **Yes, restart the system** and then click **Finish** to complete the uninstallation.

7

Known Limitations and Workarounds

The are no known limitations and workarounds.

